

CIAB Remote Desktop System

(v5 - Oct 2021)

by Brian Mullan (bmullan.mail@gmail.com)

CIAB - "Cloud in a Box"

The file "install-ciab.zip" includes all of the installation Bash Scripts and associated files required to create an LXD container based CIAB Remote Desktop System.

CIAB will create 2 LXD containers:

- ciab-cn1 which will have an installer's choice of Desktop Envrionment installed in it
- ciab-guac will have Guacamole, Tomcat9, PostgreSQL, and NGINX installed via Docker in ciab-guac. We create the LXD "ciab-guac" container with an command option to "enable container "nesting". This is why we are able to install Docker "inside" the LXD "ciab-guac"

container

Once installation is complete you can access both Guacamole & the ciab-cn1 based Desktop using any HTML5 Web Browser.

We configure *Guacamole/NGINX* etc with a **"self-signed"** certificate to allow support for using HTTPS. This means the connection **from** a User **to** the Remote Desktop is **encrypted**.

Steps to Install CIAB Remote Desktop

- 1) Copy the install-ciab.zip to the (local/remote) (Cloud, VM, server etc) you want to create the CIAB System
- 2) Unzip *install-ciab.zip*
- 3) Execute ciab-pre-install.sh
- 4) Execute install-ciab.sh

NOTE: When Step 4 completes...

- a) both of the CIAB LXD containers (ciab-guac and ciab-cn1) will have been created
- b) a "working" installation directory /opt/ciab/ will have been created in each container
- c) additional configuration scripts specific to setting up software specific to the function of each LXD container
- -- scripts to install Docker, Guacamole, Tomcat9, PostgreSQL, NGINX in the ciab-guac LXD container
- -- scripts to install a Desktop Environment and a User Acct for the person doing the CIAB installation into the *ciab-cn1* container.

Setup & Configure the ciab-cn1 container

- 1) Access the ciab-cn1 container:
 - \$ lxc exec ciab-cn1 bash
- 2) Create a User Account for yourself (substitute your own UserID for "UserName" in the following steps)
 - root@ciab-cn1:~# adduser UserName

Answer all the questions re Password etc.

3) Make your UserName Account both "sudo" and "adm" privileged

```
root@ciab-cn1:~# adduser UserName sudo
root@ciab-cn1:~# adduser UserName adm
```

- 4) Change the ownership of everything in /opt/ciab to UserName:UserName
 - root@ciab-cn1:~# chown R UserName:UserName /opt/ciab
- 5) Make sure file permissions make sense for the installation
 - root@ciab-cn1:~# chmod -R 766 /opt/ciab/
- 6) change to the Install Directory
 - cd /opt/ciab
- 6.1) Become your UserName user

```
root@ciab-cn1:~# su UserName
UserName@ciab-cn1: ~$
```

NOTE:


CIAB installation scripts should be executed as a "normal" User ... **do not** use **sudo**. The Scripts will prompt for you to enter your password when required to use Sudo to do something!

6.2) Begin the ciab-cn1 installation/setup by executing:

UserName@ciab-cn1:/opt/ciab\$./setup-ciab-cn1.sh

During the installation into the **ciab-cn1** container you will be presented with the following menu where you can choose which

Desktop Environment you want to install:



You should pick just one of the variety of Desktop Environments available

- Kubuntu (re KDE)
- Lubuntu (re LXDE)
- Ubuntu Budgie
- Ubuntu Gnome
- Ubuntu MATE
- Xubuntu (re XFCE)

NOTE: You can also select to install some of the other services listed as well... if you choose!

Setup & Configure the ciab-guac container

\$ lxc exec ciab-guac bash

2) Create a User Account for yourself (substitute your own UserID for "UserName" in the following steps

```
root@ciab-guac:~# adduser UserName
```

Answer all the questions re Password etc.

3) Make your UserName Account both "sudo" and "adm" privileged

```
root@ciab-guac:~# adduser UserName sudo
root@ciab-guac:~# adduser UserName adm
```

4) Change the ownership of everything in /opt/ciab to UserName:UserName

```
root@ciab-guac:~# chown - R UserName:UserName /opt/ciab
```

5) Make sure file permissions make sense for the installation

```
root@ciab-guac:~# chmod -R 766 /opt/ciab/
```

6) change to the Install Directory

```
cd /opt/ciab
```

6.1) Become your UserName user

```
root@ciab-guac:~# su UserName
UserName@ciab-guac: ~$
```

NOTE:

CIAB installation scripts should be executed as "normal" User ... **do not** use **sudo**. The Scripts will prompt for you to enter your password when required to use Sudo to do something!

6.2) Begin the ciab-guac installation/setup by executing:

```
UserName@ciab-guac:/opt/ciab$ ./setup-ciab-guac.sh
```

This will install Docker and Docker-compose into the ciab-guac LXD container,

Then Docker-Compose is used to to install/setup **the Dockerized Guacamole**, Tomcat9, PostgreSQL, NGINX for CIAB.

Post Installation

At this point you should exit back to the LXD "Host" and restart both ciab-cn1 and ciab-guac so just type "exit" until you are back at your Server/VM's terminal Prompt.

Then execute:

\$ lxc restart ciab-cn1

\$ lxc restart ciab-guac

You can now use an HTML5 Web Browser to access Guacamole and configure a new "Connection" configuration for accessing ciab-cn1

You (the Admin) must first access Guacamole first to setup a Guacamole "connection" to ciab-cn1's using its IP address (10.x.x.x):

Point your web browser to:

HTTPS://ip_addr_of_Server-VM-Cloud-Instance

This HTTPS traffic will be sent to Port 443 (re HTTPS) on the Server/VM/Cloud-Instance.

CIAB forwards anything on the incoming to the Server/VM/Cloud-Instance on Port 443 to Port 443 on the *ciab-guac* Container. In *ciab-guac* NGINX is listening on Port 443 and will forward again that Traffic to Port 8443 for the Guacamole Daemon (*guacd*) to process.

First you will see the Guacamole Login Screen!

Enter *guacadmin* and *guacadmin*



You should see...

RECENT CONNECTIONS	guacadmin 🕶	
--------------------	-------------	--

No recent connections.

ALL CONNECTIONS	Q Filter
-----------------	----------


Click on "Guacadmin" in the upper right of the screen and a Drop Down Menu will appear.

On that menu...

Click on Settings

You will see the Guacamole Configuration editor's Main Menu:

Click on **Connections**



Configure a "new" Guacamole "Connection" for the ciab-cn1 Desktop Container.

Configure a "connection" for the *ciab-cn1* container running our CIAB Remote Desktop *using the following example*.

Make sure to substitute the IP of your ciab-cn1 container (_re 10.x.x.x something) for the Hostname instead of the "IP of ciab-cn1" in the example.

EDIT CON	NECTION
Name: Location:	CN1 ROOT
Protocol:	RDP v
CONCURR	ENCY LIMITS
	number of connections:
LOAD BAL	ANCING
Connection Use for failo	
GUACAMO	DLE PROXY PARAMETERS (GUACD)
Hostname:	
Port: Encryption:	
PARAMET	ERS

Network

Hostname:	ip-of-ciab-cn1		
Port:	3389	\$	

Authentication



Remote Desktop Gateway



Basic Settings

Dusic octangs			
Initial program:			
Client name:			
Keyboard layout:	US English	(Qwerty)	
Time zone:	America	∨ New York	~
Administrator cons	ole:		
1000			
Display			
Width:		\$	
Height:		•	
Resolution (DPI):		•	
Color depth:	True color (32-bit		
Resize method:	True cotor (32 bit	., .	
Read-only:			
,			
Clipboard			
Disable copying fro	m romoto doskto	n. 🗆	
Disable pasting from		p: [
Disable pasting nor	ii ciiciic.		
Device Redirection	n		
Support audio in co	nsole:		
Disable audio:			
Enable audio input	(microphone):		
Enable printing:			
Redirected printer	name:		
Enable drive:		✓	
Drive name:		ciab_drive	
Disable file downloa	ad:		
Disable file upload:			
Drive path:		/home/\${GUAC_USERNAME}	
Automatically creat	e drive:	✓	
Static channel name	es:	rdpdr	
Performance			
Enable wallpaper:		П	
Enable theming:			
Enable font smooth	ing (ClearType):		
Enable full-window			
Enable desktop con			
Enable menu anima			
Disable bitmap cacl	ning:		
Disable off-screen of	aching:		
Disable glyph cachin	ng:		

RemoteApp Working directory: Preconnection PDU / Hyper-V RDP source ID: Preconnection BLOB (VM ID): Load Balancing Load balance info/cookie: **Screen Recording** Recording path: Recording name: Exclude graphics/streams: Include key events: Automatically create recording path: SFTP Enable SFTP: Hostname: Port: Public host key (Base64): Username: Password: Private key: File browser root directory: Default upload directory: SFTP keepalive interval: Disable file download: Disable file upload: Wake-on-LAN (WoL) Send WoL packet: MAC address of the remote host: Broadcast address for WoL packet: Host boot wait time:

Remember to Click Save!

NOTE: the Use of "squirrely* braces in several of the above "fields".

the **\${GUAC_USERNAME}** will allow Guacamole to pass the current User's Guacamole ID as the XRDP Login User ID.

the **\${GUAC_USERNAME}** will allow Guacamole to pass the current User's Guacamole Password as the XRDP Login User's Password

This helps automate login so the CIAB User only has to enter their Login UserID and Login Password once.

NOTE: In Guacamole-speak the above are called Parameter Tokens

Configure a "new" Guacamole "User" for CIAB.

From the Guacamole main menu Click on *Users* and create a NEW User *wth the following example* **substituting** *your UserID on the* **ciab-cn1** *container as the* **UserName**; in place of the examples "YourID".

EDIT USER				≜ guacadmin →
Username: Password: Re-enter Password	YourID			
PROFILE				
Full name: Email address: Organization: Role:	/our name			
ACCOUNT REST	RICTIONS			
Login disabled: Password expired: Allow access after: Do not allow access Enable account aft Disable account aft User time zone:	ss after::			
PERMISSIONS				
Administer system Create new users: Create new user g Create new conne Create new conne Create new sharin Change own passy	roups: ctions: ction groups: g profiles:			
CONNECTIONS				Q Filter
Current Connection	ns All Connections			
□ ☑ CN1		Save	Cancel	
Remember	to Click Save!			

IMPORTANT NOTE

When creating **YOUR** Guacamole User ID...

Remember to check ALL of the *Permissions* so that you will have Guacamole Admin capabilities in the future.

Other future Users you create usually only have 1 or 2 of these checked!

Time to Rock & Roll

Logout of Guacamole by again Clicking on Guacadmin in the upper right and selecting Logoff

Then log back in using your new CIAB User ID and Password_

Troubleshooting Tips

1) RDP uses Port 3389 so make sure that Port is open on the LXD *ciab-cn1* container.

Make sure that Ports 443 are Open on the LXD Host and in the LXD ciab-guac container to permit HTTPS access.

2) When you access your ciab-cn1 Desktop, if you have no audio then open a Terminal on that Desktop and do the following:

\$ pulseaudio -k

This will kill & immediately restart the Pulseaudio Daemon for that UserID only. Audio should then work.

NOTE: the CIAB installation should have alread added the above command to the system /etc/skel/.profile "skeleton"

template file so all future users created in the ciab-cn1 Desktop system will automatically have this configured for

them so audio will work on first login*.

References

Note: Each project has their own specific open source license



1) Apache Guacamole Apache Guacamole is a clientless remote

desktop gateway.

It's called it clientless because no plugins or client software are required!

Thanks to HTML5, once Guacamole is installed, all you need to access your *CIAB Remote Desktop* is a web browser.

2) boschkundendienst - Github Guacamole with Docker-Compose Create a fully working Apache Guacamole (including Tomcat9, NGINX, PostgreSQL) instance using Docker (Docker-Compose).



3) Pieces/Excerpts from "Easy install xRDP w Pulseaudio support on Ubuntu"



4) LXD - linux containers LXD is a next generation System Container & Virtual Machine (VM) manager



5) LXD Sub-Reddit - moderated by Brian Mullan

(c) CIAB 2016-2021 - Brian Mullan (bmullan.mail@gmail.com)