

# eIDAS-Node Installation, Configuration and Integration Quick Start Guide

Version 1.3

# **Document history**

Version	Date	Modification reason	Modified by
1.0	26/11/2015	Modifications to align with the eIDAS technical specifications.	DIGIT
1.1.0	29/06/2016	Modifications due to installation changes related to architectural and stability improvements  Update of the deployments configuration and related libraries	DIGIT
1.2.0	20/01/2017	Configuration and stability improvements, please see Version 1.2.0 Release Notes.	DIGIT
1.3.0	05/05/2017	Modifications to align with changes in Technical Specifications version 1.1. For details please see the Version 1.3.0 Release Notes.	DIGIT

# **Table of contents**

		NT HISTORY	
TAB	LE OF	CONTENTS	3
LIST	OF A	ABBREVIATIONS	4
LIST	OF D	DEFINITIONS	5
1.	INTR	ODUCTION	6
2.	RELE	ASE CONTENT	7
3.	OVEF	RVIEW OF THE PRECONFIGURED DEMO EIDAS-NODE PACKAGES	8
4.	DEM	O EIDAS-NODE SET UP AND CONFIGURATION	9
5.	SPEC	CIFIC CONFIGURATION	13
	5.1.	Changing the default hostname or http port	13
		5.1.1. eIDAS-Node hostname and port	13
		5.1.2. SP hostname and port	14
		5.1.3. IdP hostname and port	14
	5.2.	Changing the keystore location	15
	5.3.	Changing keystore configuration	15
		5.3.1. Extended configuration	
		5.3.2. Basic configuration	
	5.4.	Preventing a citizen from authenticating in a country other than the requested one	16
	5.5.	eIDAS-Node compliance	17
6.	COM	PILING THE MODULES FROM THE SOURCE	18
7	FΝΔF	BLING LOGGING	20

#### List of abbreviations

The following abbreviations are used within this document.

Abbreviation	Meaning
AT	The ISO 3166 International Standard country code for Austria.
DE	The ISO 3166 International Standard country code for Germany.
eIDAS	electronic Identification and Signature. The Regulation (EU) N°910/2014 governs electronic identification and trust services for electronic transactions in the internal market to enable secure and seamless electronic interactions between businesses, citizens and public authorities.
IdP	Identity Provider. An institution that verifies the citizen's identity and issues an electronic ID.
LoA	Level of Assurance (LoA) is a term used to describe the degree of certainty that an individual is who they say they are at the time they present a digital credential.
MS	Member State.
SAML	Security Assertion Markup Language
SP	Service Provider

#### **List of definitions**

The following definitions are used within this document.

Term	Meaning
eIDAS-Node	An eIDAS-Node is an application component that can assume two different roles depending on the origin of a received request. See eIDAS-Node Connector and eIDAS-Node Proxy Service.
eIDAS-Node Connector	The eIDAS-Node assumes this role when it is located in the <b>Service Provider's</b> Member State. In a scenario with a Service Provider asking for authentication, the eIDAS-Node Connector receives the authentication request from the Service Provider and forwards it to the eIDAS-Node of the citizen's country.
eIDAS-Node Proxy Service	The eIDAS-Node assumes this role when it is located in the <b>citizen's</b> Member State. The eIDAS-Node Proxy Service receives authentication requests from an eIDAS-Node of another MS (their eIDAS-Node Connector). The eIDAS-Node Proxy-Service also has an interface with the national eID infrastructure and triggers the identification and authentication for a citizen at an identity and/or attribute provider.

#### 1. Introduction

This document describes how to quickly install a Service Provider, eIDAS-Node Connector, eIDAS-Node Proxy Service and IdP from the distributions in this release package. The distributions provide preconfigured eIDAS-Node modules for running on each of the supported application servers (Glassfish, Tomcat, JBoss, WebLogic and WebSphere).

Details of the setup and configuration of the sample eIDAS-Nodes, are included in the eIDAS-Node Installation, Configuration and Integration Manual.

This document is divided into the following sections:

- Section 1 *Introduction*;
- Section 2 *Release content* lists the files delivered with this release and describes their contents;
- Section 3 Overview of the preconfigured demo eIDAS-Node packages illustrates the setup of the configurations provided with this distribution;
- Section 4 Demo eIDAS-Node set up and configuration describes step-bystep how to install the demo configuration;
- Section 5 *Specific configuration* provides information on how the setup can be changed to suit your needs;
- Section 6 Compiling the modules from the source describes how to rebuild the Maven project if necessary;
- Section 7 Enabling logging describes how to enable audit logging of the communications between eIDAS-Node Proxy Service and Connector.

#### 2. Release content

For information on the changes in this release, please see the current Release Notes. The deliverable consists of the following zip files:

Deliverable	Description
EIDAS-1.3.0.zip	Distribution version 1.3.0 of the sample eIDAS-Node
EIDAS-Sources-1.3.0.zip	Source files (Maven project) of the sample eIDAS-Node including an example of implementation of a SP (service provider) and IdP (Identity Provider).
EIDAS-Binaries-Glassfish- 1.3.0.zip	Deployable war files of a preconfigured eIDAS-Node for a Glassfish server (including IdP.war, EidasNode.war, SP.war)
EIDAS-Binaries-Jboss-1.3.0.zip	Deployable war files of a preconfigured eIDAS-Node for a JBoss server (including IdP.war, EidasNode.war, SP.war)
EIDAS-Binaries-Tomcat-1.3.0.zip	Deployable war files of a preconfigured eIDAS-Node for a Tomcat server (including IdP.war, EidasNode.war, SP.war)
EIDAS-Binaries-Was-1.3.0.zip	Deployable war files of a preconfigured eIDAS-Node for a WebSphere server (including IdP.war, EidasNode.war, SP.war)
EIDAS-Binaries-Wls-1.3.0.zip	Deployable war files of a preconfigured eIDAS-Node for a WebLogic server (including IdP.war, EidasNode.war, SP.war)

#### 3. Overview of the preconfigured demo eIDAS-Node packages

This distribution provides an example configuration in which each supported server represents one country providing an eID service. For the purpose of this demo, fictitious countries are used (CA, CB, CC, CD, CF).

The following table illustrates the setup of the configurations provided with this distribution.

Application Server	version	Default host	Default port	Country	Description
Tomcat	7*, 8	localhost	8080	CA	Country A
Glassfish	3*, 4	localhost	8081	СВ	Country B
JBoss	6*, 7	localhost	8085	CC	Country C
WebLogic	10.3.6*, 12.1.2	localhost	7001	CD	Country D
WebSphere/	8.5.5*	localhost	9080	CF	Country F
WebSphere Liberty Profile	8.5.5.4				

<sup>\*</sup> Default build server provided with the binaries

#### 4. Demo eIDAS-Node set up and configuration

Each example eIDAS-Node package is preconfigured to use 'localhost' as hostname and a default http listening port; see the table in section 3. The http listening port of your application server must be adapted according to these default values.

If you need to change these default values, refer to section 5.1 — Changing the default hostname or http port for details.

To set up and configure the demo, perform the following steps:

- 1. Install Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy Files which contain no restriction on cryptographic strengths:
- 2. Download the Java Cryptography Extension (JCE) Unlimited Strength Policy Files from Oracle:
  - For Java 7: <a href="http://www.oracle.com/technetwork/java/javase/downloads/jce-7-download-432124.html">http://www.oracle.com/technetwork/java/javase/downloads/jce-7-download-432124.html</a>
  - For Java 8: <a href="http://www.oracle.com/technetwork/java/javase/downloads/jce8-download-2133166.html">http://www.oracle.com/technetwork/java/javase/downloads/jce8-download-2133166.html</a>
- 3. Uncompress and extract the downloaded zip file (it contains README.txt and two jar files).
- 4. For the installation, please follow the instructions in the README.txt file.
- 5. If you are using Tomcat it is necessary to:
  - Create a folder named shared in \$TOMCAT\_HOME.
  - Create a subfolder named lib in \$TOMCAT\_HOME\shared
  - Edit the file \$TOMCAT\_HOME\conf\catalina.properties and change the property shared.loader so that it reads:

```
shared.loader=${catalina.home}\shared\lib\*.jar.
Note that for Linux OS it should be:
```

```
shared.loader=${catalina.home}/shared/lib/*.jar)
```

6. Copy the files below to the endorsed directory on the application server (Tomcat, Glassfish, JBoss). These jars may be found under AdditionalFiles directory in the binary for your application server.

```
endorsed\xml-apis-1.4.01.jar
endorsed\resolver-2.9.1.jar
endorsed\serializer-2.7.2.jar
endorsed\xalan-2.7.2.jar
endorsed\xercesImpl-2.11.0.jar
```

7. It is necessary to increase the default JVM memory settings. Set the following JVM parameter in the startup script of your application server XX:MaxPermSize=512m.

8. Local directory or directories must be defined in order to store the configuration files and the test keystores. These directories need to be defined either as OS/AS environment variables or command-line parameters:

```
EIDAS_CONFIG_REPOSITORY for EidasNode,
SPECIFIC_CONFIG_REPOSITORY for Specific,
SP_CONFIG_REPOSITORY for SP
IDP_CONFIG_REPOSITORY for IdP.
```

It is also possible to use only one common directory for all the modules.JVM command line example:

```
DEIDAS_CONFIG_REPOSITORY=c:/Pgm/projects/configEidas/glassfish_v13/ -
DSPECIFIC_CONFIG_REPOSITORY=c:/Pgm/projects/configEidas/glassfish_v13/specifi
c/ -DSP_CONFIG_REPOSITORY=c:/Pgm/projects/configEidas/glassfish_v13/sp/ -
DIDP_CONFIG_REPOSITORY=c:/Pgm/projects/configEidas/glassfish_v13/idp/
```

By default the following configuration file structure must be present:

```
eidas.xml
encryptionConf.xml
EncryptModule Connector.xml
EncryptModule Service.xml
hazelcast.xml
saml-engine-additional-attributes.xml
SamlEngine.xml
SamlEngine_Connector.xml
SamlEngine Service.xml
SignModule_Connector.xml
SignModule_Service.xml
idp/EncryptModule_IdP.xml
idp/idp.properties
idp/IdPSamlEngine.xml
idp/saml-engine-additional-attributes.xml
idp/saml-engine-eidas-attributes.xml
idp/SamlEngine_IdP.xml
idp/SignModule IdP.xml
idp/user.properties
keystore/demoKeys.jks
keystore/eidasKeyStore.jks
keystore/eidasKeyStore_Connector_CA.jks
keystore/eidasKeyStore_Connector_CB.jks
keystore/eidasKeyStore_Connector_CC.jks
keystore/eidasKeyStore_Connector_CD.jks
keystore/eidasKeyStore_Connector_CF.jks
keystore/eidasKeyStore_IDP_CA.jks
keystore/eidasKeyStore_IDP_CB.jks
keystore/eidasKeyStore_IDP_CC.jks
keystore/eidasKeyStore_IDP_CD.jks
keystore/eidasKeyStore_IDP_CF.jks
keystore/eidasKeyStore_METADATA.jks
keystore/eidasKeyStore_Service_CA.jks
keystore/eidasKeyStore_Service_CB.jks
keystore/eidasKeyStore_Service_CC.jks
keystore/eidasKeyStore_Service_CD.jks
keystore/eidasKeyStore_Service_CF.jks
keystore/eidasKeyStore_SP_CA.jks
keystore/eidasKeyStore_SP_CB.jks
keystore/eidasKeyStore_SP_CC.jks
```

```
keystore/eidasKeyStore_SP_CD.jks
keystore/eidasKeyStore_SP_CF.jks
sp/EncryptModule_SP.xml
sp/saml-engine-additional-attributes.xml
sp/saml-engine-eidas-attributes.xml
sp/SamlEngine_SP.xml
sp/SignModule_SP.xml
sp/sp.properties
sp/SPSamlEngine.xml
specific/eidas_Specific.xml
specific/EncryptModule_SP-Specific.xml
specific/EncryptModule_Specific-IdP.xml
specific/saml-engine-additional-attributes.xml
specific/SamlEngine_SP-Specific.xml
specific/SamlEngine_Specific-IdP.xml
specific/SignModule_SP-Specific.xml
specific/SignModule Specific-IdP.xml
specific/SpecificSamlEngine.xml
```

9. Copy the server configuration files and test keystores into the local directories defined in step 8.

Open the zip file (config.zip in the EIDAS-Binaries-xxx-yyy.zip) and copy the directory keystore and the directory of the application server as required (i.e. glassfish, tomcat, jboss, wls, was) into the configuration directory.

10. On WebSphere Liberty Profile the following features should be enabled:

```
<feature>jsp-2.2</feature>
<feature>servlet-3.0</feature>
<feature>ssl-1.0</feature> (if planning to use https)
```

- 11. On WebSphere, use BouncyCastle provider instead of default IBM JVM default provider:
  - a. Place bouncycastle jar in \$IBM\_JRE\lib\ext directory.
  - b. Copy the IBM unrestricted JCE policy files provided in AdditionalFiles directory and put them under \$IBM\_JRE\lib\security to replace the existing ones.
  - c. Add bouncycastleprovider in the list of providers in \$IBM\_JRE\lib\security\java.security file before the default provider, e.g.

```
security.provider.1=com.ibm.crypto.pkcs1limpl.provider.IBMPKCS1lImpl
security.provider.2=org.bouncycastle.jce.provider.BouncyCastleProvider
security.provider.3=com.ibm.crypto.provider.IBMJCE
```

- 12. Add a static JCE for JBOSS 6/7:
  - a. Locate and open in a text editor the file \$JRE\_HOME\lib\security\java.security.
  - b. Add a line after the lines containing the security providers: security.provider.N= org.bouncycastle.jce.provider.BouncyCastleProvider

(you should set N according to your config, to the next available index in the list of providers).

- c. Put bcprov-jdk15on-1.51.jar into the classpath (e.g. \$JRE\_HOME\lib\ext).
- 13. Deploy the applications according to your application server.
  - EidasNode.war
  - SP.war
  - IdP.war

You now have a Service Provider, eIDAS-Node Connector, eIDAS-Node Proxy Service and IdP configured to run on localhost:

- Tomcat: http://localhost:8080/SP/
- Glassfish: http://localhost:8081/SP
- **Jboss:** http://localhost:8085/SP
- WebLogic: http://localhost:7001/SP
- WebSphere, WebSphere Liberty Profile: http://localhost:9080/SP/

To validate the installation, a first test can be performed simulating that a citizen from a country accesses services in the same country.

- 1. Open the Service Provider URL: http://localhost:defaultport/SP/
- 2. Choose for both the SP and citizen country the fictitious country for which your application server has been configured (CA, CB, CC, CD or CF).
- 3. The generated SAMLRequest is displayed. Submit the form.
- 4. Click **Next** to give your consent to attributes being transferred.
- 5. Enter the user credentials. Type 'xavi' as **Username** and 'creus' as **Password** and submit the page.
- 6. Click **Submit** to validate the values to transfer.

The SAMLResponse is displayed.

7. **Submit** the form.

You should see Login Succeeded.

# 5. Specific configuration

#### 5.1. Changing the default hostname or http port

The parameters below can be adapted to reflect your configuration.

**Note:** The application server must be restarted after changes have been made.

#### **5.1.1.** eIDAS-Node hostname and port

1. Edit the file eidas.xml located in the configuration directory as shown below.

Property	Value
connector.assertion.url	http:// <connector.yourhostname>:<connector.yourport>/EidasN</connector.yourport></connector.yourhostname>
Connector.assertion.uri	ode/ColleagueResponse
connector.destination.url	http:// <connector.yourhostname>:<connector.yourport>/EidasN ode/ServiceProvider</connector.yourport></connector.yourhostname>
connector.node.url	http:// <connector.yourhostname>:<connector.yourport>/EidasN ode/</connector.yourport></connector.yourhostname>
connector.metadata.url	http:// <connector.yourhostname>:<connector.yourport>/EidasN ode/ConnectorMetadata</connector.yourport></connector.yourhostname>
service.node.url	http:// <service.yourhostname>:<service.yourport>/EidasNode/</service.yourport></service.yourhostname>
servicel.url	http:// <service.yourhostname>:<service.yourport>/EidasNode/ColleagueRequest</service.yourport></service.yourhostname>
service.specificidpredirect.url	http:// <service.yourhostname>:<service.yourport>/EidasNode/IdpResponse</service.yourport></service.yourhostname>
service.metadata.url	http:// <service.yourhostname>:<servicer.yourport>/EidasNode/ ServiceMetadata</servicer.yourport></service.yourhostname>
connector.responder.metadata.url	The URL at which the metadata of the eIDAS-Node Connector (presenting itself as an IdP) will be made available, e.g. http:// <connector.yourhostname>:<connector.yourport>/EidasNode/C onnectorResponderMetadata. It will be used as Issuer in the responses that the Connector sends to the SP.</connector.yourport></connector.yourhostname>
service.requester.metadata.url	The URL where the metadata of the Proxy Service (presenting itself as an SP) will be made available, e.g. http:// <service.yourhostname>:<service.yourport>/EidasNode/S erviceRequesterMetadata . It will be used as Issuer in the requests that the Connector sends to the IdP.</service.yourport></service.yourhostname>
ssos.serviceMetadataGeneratorIDP. post.location	The URL for the metadata <md:singlesignonservice> location attribute of the SingleSignOnService related to Binding="urn:oasis:names:tc:SAML:2.0:bindings:H TTP-POST.e.g. http://<service.yourhostname>:<service.yourport>/ EidasNode/ColleagueRequest/</service.yourport></service.yourhostname></md:singlesignonservice>

Property	Value
ssos.serviceMetadataGeneratorIDP. redirect.location	The URL for the metadata <md:singlesignonservice> location attribute of the SingleSignOnService related to Binding="urn:oasis:names:tc:SAML:2.0:bindings:H TTP-Redirect.e.g. http://<service.yourhostname>:<service.yourport>/EidasNode/C olleagueRequest/</service.yourport></service.yourhostname></md:singlesignonservice>
ssos.connectorMetadataGeneratorIDP.post.location	The URL for the metadata <md:singlesignonservice> location attribute of the SingleSignOnService related to Binding="urn:oasis:names:tc:SAML:2.0:bindings:H TTP-POST.e.g. http://<connector.yourhostname>:<connector.yourport>/EidasN ode/ServiceProvider</connector.yourport></connector.yourhostname></md:singlesignonservice>
ssos.connectorMetadataGeneratorIDP.redirect.location	The URL for the metadata <md:singlesignonservice> location attribute of the SingleSignOnService related to Binding="urn:oasis:names:tc:SAML:2.0:bindings:H TTP-Redirect.e.g. http://<connector.yourhostname>:<connector.yourport>/EidasN ode/ServiceProvider</connector.yourport></connector.yourhostname></md:singlesignonservice>

2. Open and edit the file sp.properties as shown below.

Property	Value
country1.metadata.url	http:// <connector.yourhostname>/EidasNode/ConnectorResponderMetadata</connector.yourhostname>

#### **5.1.2. SP** hostname and port

Open and edit the file sp.properties as shown below.

Property	Value
sp.return	http:// <sp.yourhostname>:<sp.yourport>/SP/ReturnPage</sp.yourport></sp.yourhostname>
sp.metadata.url	http:// <sp.yourhostname>:<sp.yourport>/SP/metadata</sp.yourport></sp.yourhostname>

#### **5.1.3.** IdP hostname and port

1. Edit the file  ${\tt eidas\_Specific.xml}$  located in the configuration folder as shown below.

Property	Value
idp.url	http:// <idp.yourhostname>:<idp.yourport>/IdP/AuthenticateCitizen</idp.yourport></idp.yourhostname>
idp.metadata.url	https:// <idp.yourhostname>:<idp.yourport>/IdP/metadata</idp.yourport></idp.yourhostname>

2. Open and edit the file idp.properties as shown below.

Property	Value
idp.metadata.url	http:// <idp.yourhostname>:<idp.yourport>/IdP/metadata</idp.yourport></idp.yourhostname>
idp.ssos.redirect.location	The URL for the metadata <md:singlesignonservice> location attribute of the SingleSignOnService related to Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Redirect.e.g. http://<idp.yourhostname>:<idp.yourport>/IdP/AuthenticateCitizen</idp.yourport></idp.yourhostname></md:singlesignonservice>
idp.ssos.post.location	The URL for the metadata <md:singlesignonservice>location attribute of the SingleSignOnService related to Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST.e.g. http://<idp.yourhostname>:<idp.yourport>/IdP/AuthenticateCitizen</idp.yourport></idp.yourhostname></md:singlesignonservice>

#### 5.2. Changing the keystore location

By default the test keystores are located in the directory 'keystores' under the configuration directory. You can change these values by editing the files below to reflect your configuration. All filenames and path information are relative to the configuration directory for the given module.

Keystore	Files
eIDAS-Node	SignModule_Service.xml SignModule_Connector.xml EncryptModule_Service.xml EncryptModule_Connector.xml
SP	SignModule_SP.xml EncryptModule_SP.xml
IdP	SignModule_IdP.xml EncryptModule_IdP.xml
Specific	SignModule_SP-Specific.xml SignModule_Specific-IdP.xml EncryptModule_SP-Specific.xml EncryptModule_Specific-IdP.xml

#### 5.3. Changing keystore configuration

By default the preconfigured eIDAS components use the following extended configuration.

#### **5.3.1.** Extended configuration

In this configuration all stakeholders (SP/Connector /Proxy Service/IDP) use their own certificate for the signing and encrypting of SAML messages.

This setup is close to a real-life scenario, where the components are distributed across servers and Member States.

#### Example for country 'CA':

	Keystore		Certificate	Country
SP	eidasKeyStore_SP_CA.jks  (SignModule_SP.xml, EncryptModule_SP.xml)	Key Pair	sp-ca-demo- certificate	CA
		Trusted	Metadata (signing certificate)	CA
Connector	(SignModule_SP-Specific.xml,	Key Pair	Connector-ca- demo-certificate	CA
		Trusted	Metadata (signing certificate)	CA
Proxy Service		Key Pair	Service-ca- demo-certificate	CA
		Trusted	Metadata (signing certificate)	CA
IDP	eidasKeyStore_IDP_CA.jks  (SignModule_IdP.xml, EncryptModule_IdP)	Key Pair	idp-ca-demo- certificate	CA
		Trusted	Metadata (signing certificate)	CA
Metadata	eidasKeyStore_METADATA.jks	Key Pair	Metadata (signing certificate)	CA

#### **5.3.2.** Basic configuration

In this configuration all stakeholders share the same certificate.

This setup is a simplified scenario for a lab environment, but corresponds less to a real-life situation.

In order to set up the basic scenario, all SignModule configuration files should be adapted to reference the common test keystore, eidasKeyStore.jks.

# 5.4. Preventing a citizen from authenticating in a country other than the requested one

- 1. By default the preconfigured Demo eIDAS-Node has a protection which does not allow citizens to authenticate in a country other than the one that has been requested.
- 2. If you need to disable this validation, edit the file eidas.xml located in the configuration directory.

Property	Value
check.citizenCertificate.serviceCertificate	false

# 5.5. eIDAS-Node compliance

For validation purposes the demo eIDAS Nodes do not use HTTPS and the configuration parameters are set as shown below. The parameters can be changed to be fully eIDAS compliant if required.

Parameter	Demo value	elDAS value
disallow_self_signed_certificate	False	True: do not allow self-signed and expired certificates
check_certificate_validity_period	False	True: do not allow expired certificates
metadata.activate	True	True:specifies that metadata is generated by the Connector
metadata.restrict.http	False	True: metadata must be only available via HTTPS
tls.enabled.protocols	TLSv1.1,TLSv1.2	TLSv1.1,TLSv1.2: SSL/TLS enabled protocols
metadata.check.signature	True	True: metadata received from a communications partner must be signed
metadata.validity.duration	86400	Metadata validity period in seconds. Default=86400 (i.e. one day)
response.encryption.mandatory	True	True: do not allow response not encrypted
validate.binding	True	True: the bindings are validated
security.header.csp.enabled	True	True: the content-security and security checks are enabled
disable.check.mandatory.eidas.attributes	False	False: check the eIDAS minimum dataset constraint.
		<b>Note:</b> this parameter is used by both Proxy Service and Connector.
disable.check.representative.attributes	False	True: disable the check of representative attributes in the request

#### 6. Compiling the modules from the source

If you need to rebuild the Maven project, open EIDAS-Parent and execute the Maven commands described in the table below according to your application server.

Folder	Command line		
EIDAS-Parent	Tomcat/	mvn clean install -P tomcat	
	Glassfish		
	jBoss6	mvn clean install -P jBoss6	
	jBoss7	mvn clean install -P jBoss7	
	WebLogic	mvn clean install -P weblogic	
	WebSphere	mvn clean install -P websphere	

You can also rebuild each module separately by executing the commands below.

Folder - modules		Command line
EIDAS-Light-Commons	mvn clean install	
EIDAS-Commons	mvn clean install	
Eidas-ConfigModule	mvn clean install	
EIDAS-SpecificCommunicationDefinition	mvn clean install	
EIDAS-SAMLEngine	mvn clean install	
EIDAS-Encryption	mvn clean install	
EIDAS-UPDATER	mvn clean install	
EIDAS-Specific	mvn clean install	
EIDAS-Node	Tomcat/	mvn clean package -P tomcat
	Glassfish	
	jBoss6	mvn clean package -P jBoss6
	jBoss7	mvn clean package -P jBoss7
	WebLogic	mvn clean package -P weblogic
	WebSphere	mvn clean package -P websphere

Folder - modules		Command line
EIDAS-SP	Tomcat/ Glassfish	mvn clean package -P tomcat
	jBoss6	mvn clean package -P jBoss6
	jBoss7	mvn clean package -P jBoss7
	WebLogic	mvn clean package -P weblogic
	WebSphere	mvn clean package -P websphere
EIDAS-IdP-1.0	Tomcat/ Glassfish	mvn clean package -P tomcat
	jBoss6	mvn clean package -P jBoss6
	jBoss7	mvn clean package -P jBoss7
	WebLogic	mvn clean package -P weblogic
	WebSphere	mvn clean package -P websphere

# 7. Enabling logging

The locations of the audit files are by default configured to use a Java system properties variable called  ${\tt LOG\_HOME}$ .

A value can be assigned to this variable by using:  $-DLOG\_HOME = "<myDirectoryName>"$  at server start-up.