



Interapplication Communication API Reference

Adobe® Acrobat® SDK

November 2006 Version 8.0

© 2006 Adobe Systems Incorporated. All rights reserved.

Adobe® Acrobat® SDK 8.0 Interapplication Communication API Reference for Microsoft® Windows® and Mac OS®.

Edition 1.0, November 2006

If this guide is distributed with software that includes an end user agreement, this guide, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by any such license, no part of this guide may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Adobe Systems Incorporated. Please note that the content in this guide is protected under copyright law even if it is not distributed with software that includes an end user license agreement.

The content of this guide is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

Please remember that existing artwork or images that you may want to include in your project may be protected under copyright law. The unauthorized incorporation of such material into your new work could be a violation of the rights of the copyright owner. Please be sure to obtain any permission required from the copyright owner.

Any references to company names and company logos in sample material are for demonstration purposes only and are not intended to refer to any actual organization.

Adobe, the Adobe logo, Acrobat, PostScript, and Reader are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Apple and Mac OS are trademarks of Apple Computer, Inc., registered in the United States and other countries.

JavaScript is a trademark or registered trademark of Sun Microsystems, Inc. in the United States and other countries.

Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries.

All other trademarks are the property of their respective owners.

Adobe Systems Incorporated, 345 Park Avenue, San Jose, California 95110, USA.

Notice to U.S. Government End Users. The Software and Documentation are "Commercial Items," as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation," as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §8227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States. Adobe Systems Incorporated, 345 Park Avenue, San Jose, CA 95110-2704, USA. For U.S. Government End Users, Adobe agrees to comply with all applicable equal opportunity laws including, if appropriate, the provisions of Executive Order 11246, as amended, Section 402 of the Vietnam Era Veterans Readjustment Assistance Act of 1974 (38 USC 4212), and Section 503 of the Rehabilitation Act of 1973, as amended, and the regulations at 41 CFR Parts 60-1 through 60-60, 60-250, and 60-741. The affirmative action clause and regulations contained in the preceding sentence shall be incorporated by reference.

Contents

	Preface	
	What's in this guide?	12
	Who should read this guide?	
	Related documentation	
1	OLE Automation	14
	AcroExch.App	14
	CloseAllDocs	16
	Exit	16
	GetActiveDoc	17
	GetActiveTool	17
	GetAVDoc	18
	GetFrame	18
	GetInterface	19
	GetLanguage	19
	GetNumAVDocs	20
	GetPreference	20
	GetPreferenceEx	
	Hide	
	Lock	
	Minimize	
	Maximize	
	MenultemExecute	
	MenultemIsEnabled	
	MenuItemIsMarked	
	MenultemRemove	
	Restore	
	SetActiveTool	
	SetFrame	
	SetPreference	
	SetPreferenceEx	
	Show	
	ToolButtonIsEnabled	
	ToolButtonRemove	
	Unlock	
	UnlockExAcroExch.AVDoc	
	BringToFront ClearSelection	
	Close	
	FindText	
	GetAVPageView	
	GetFrame	
	GetPDDoc	
	GetTitle	

1 OLE Automation (Continued)

Ac	roExch.AVDoc (Continued)	
	GetViewMode	.35
	IsValid	.35
	Maximize	.36
	Open	.36
	OpenInWindow	.37
	OpenInWindowEx	.38
	PrintPages	.40
	PrintPagesEx	.40
	PrintPagesSilent	.41
	PrintPagesSilentEx	.42
	SetFrame	.43
	SetTextSelection	.44
	SetTitle	.45
	SetViewMode	.45
	ShowTextSelect	.46
Ac	roExch.AVPageView	.47
	DevicePointToPage	.47
	DoGoBack	.48
	DoGoForward	.48
	GetAperture	.49
	GetAVDoc	.49
	GetDoc	.49
	GetPage	.50
	GetPageNum	.50
	GetZoom	.51
	GetZoomType	.51
	Goto	.52
	PointToDevice	.53
	ReadPageDown	.53
	ReadPageUp	.54
	ScrollTo	.54
	ZoomTo	.55
Ac	roExch.HiliteList	.56
	Add	.56
Ac	roExch.PDAnnot	.56
	GetColor	.57
	GetContents	.58
	GetDate	.58
	GetRect	.58
	GetSubtype	.59
	GetTitle	.59
	IsEqual	.60
	lsOpen	.60
	IsValid	
	Perform	
	SetColor	.62
	SetContents	

OLE Automation (Continued)

AcroExch.PDAnnot (Continued)	
SetDate	63
SetOpen	64
SetRect	64
SetTitle	65
AcroExch.PDBookmark	66
Destroy	66
GetByTitle	67
GetTitle	
IsValid	68
Perform	68
SetTitle	69
AcroExch.PDDoc	69
AcquirePage	71
ClearFlags	
Close	72
Create	72
CreateTextSelect	73
CreateThumbs	
CropPages	
DeletePages	
DeleteThumbs	
GetFileName	76
GetFlags	76
GetInfo	
GetInstanceID	77
GetJSObject	78
GetNumPages	78
GetPageMode	79
GetPermanentID	
InsertPages	79
MovePage	
Open	81
OpenAVDoc	
ReplacePages	82
Save	83
SetFlags	
SetInfo	
SetPageMode	
AcroExch.PDPage	
AddAnnot	
AddNewAnnot	
CopyToClipboard	
CreatePageHilite	
CreateWordHilite	
CropPage	
Draw	
DrawFx	92

1 OLE Automation (Continued)

GetAnnot. .93 GetDoc .94 GetNumAnnots .94 GetNumber .95 GetRotate .95 GetSize .96 RemoveAnnot .96 SetRotate .97 AcroExch,POTextSelect .98 Destroy .98 GetBoundingRect .99 GetNumText .99 GetPage .100 GetText .101 AcroExch,Point .102 X .102 Y .102 AcroExch,Point .102 X .102 Y .102 AcroExch,Point .102 Bottom .103 Left .103 Bottom .103 Left .103 Bottom .103 Top. .104 Hour .105 Millisecond .105 Millisecond .105 Millisecond	AcroExch.PDPage (Continued)	
GetDoc .94 GetNumAnnots .94 GetNumber .95 GetRotate .95 GetSize .96 RemoveAnnot .96 SetRotate .97 AcroExch.PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetNumText .99 GetPage .100 GetText .101 AcroExch.Point .102 X .102 Y .102 AcroExch.Rect .102 Bottom .103 Left .103 Right .103 Top .104 AcroExch.Time .104 Date .104 Hour .105 Millisecond .105 Month .105 Month .105 Month .105 More .106 AxAcroPDFLib.AxAcroPDF .106 GetVersions .108 Gos ConvardStack .108		
GetNumhore .94 GetRotate .95 GetSize .96 RemoveAnnot .96 SetRotate .97 AcroExch.PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetNumText .99 GetPage .100 GetText .101 AcroExch.Point .102 Y .102 Y .102 Y .102 Y .102 AcroExch.Rect .102 Bottom .103 Left .103 Right .103 Top. .104 AcroExch.Time .104 Date. .104 Hour .105 Millisecond .105 Minute .105 Month .105 Month .105 More Second .106 AxcroPDFLib.AxAcroPDF .106 AxcroPortub.AxAcroPDF .106 AxcroforeviousPage .109	GetAnnotIndex	93
GetNumber .95 GetRotate .95 GetSize .96 RemoveAnnot .96 AcroExch, PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetNumText .99 GetPage .100 GetText .01 AcroExch, Point .102 X .102 Y .102 AcroExch, Point .102 AcroExch, Point .102 AcroExch, Point .102 AcroExch, Point .102 Bottom .103 Bottom .103 Right .103 Right .103 Top. .104 AcroExch, Time .104 Date .104 Hour .105 Millisecond .105 Millisecond .105 Millisecond .105 Minute .105 Month .105 Second .106 Year .106	GetDoc	94
GetRotate .95 GetSize .96 RemoveAnnot .96 SetRotate .97 AcroExch/PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetNumText .99 GetPage .100 GetPext .101 AcroExch-Point .102 X .102 Y .102 AcroExch, Rect .102 Bottom .103 Left .103 Right .103 Top .104 AcroExch, Time .104 Date .104 Hour .105 Millisecond .105 Minute .105 Minute .105 Minute .105 Month .105 Second .106 Year .106 AxAcroPDFLIb, AxAcroPDF .106 AxAcroPTstage .108 GotoFirstage .108 GotoFirstage .108 <	GetNumAnnots	94
GetSize 96 RemoveAnnot 96 SetRotate 97 AcroExch.PDTextSelect 98 Destroy 98 GetBoundingRect 99 GetBoundingRect 99 GetPage 100 GetPage 100 GetPext 102 X 102 Y 102 Y 102 Y 102 AcroExch.Point 102 X 102 Y 102 AcroExch.Rect 102 Bottom 103 Left 103 Right 103 Top. 104 AcroExch.Time 104 AcroExch.Time 104 AcroExch.Time 105 Milliescond 105 Milliescond 105 Milliescond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 </td <td>GetNumber</td> <td>95</td>	GetNumber	95
RemoveAnnot .96 SetRotate .97 AcroExch,PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetNamText .99 GetPage .100 GetText .101 AcroExch,Point .102 X .102 Y. .102 AcroExch,Rect .102 Bottom .103 Left .103 Right .103 Top .104 AcroExch,Time .104 Date .104 Hour .105 Millisecond .105 Millisecond .105 Minute .105 Month .105 Second .106 Year .106 AxAcroPDFLib,AxAcroPDF .106 Got Versions .108 Got FirstPage .108 Goto FirstPage .109 Goto FirstPage .109 Goto FirstPage .109 Goto FirstPage <t< td=""><td>GetRotate</td><td>95</td></t<>	GetRotate	95
SetRotate .97 AcroExch-PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetPage .100 GetPage .101 AcroExch.Point .102 X .102 Y .102 AcroExch.Rect .102 Bottom .103 Left .103 Right .103 Top .104 AcroExch.Time .104 Date .104 Hour .105 Millisecond .105 Minute .105 Month .105 Second .105 Year .106 AxCroPDFLib.AxAcroPDF .106 GetVersions .108 GoForwardStack .108 GoForwardStack .108 GotoNextPage .109 GotoNextPage .109 GotoNextPage .109 GotoNextPage .109 GotoPreviousPage .109 GotoPrixtAll	GetSize	96
AcroExch.PDTextSelect .98 Destroy .98 GetBoundingRect .99 GetPage .100 GetText .101 AcroExch.Point .102 X .102 Y .102 Y .102 AcroExch.Rect .102 Bottom .103 Left .103 Top .104 AcroExch.Time .104 Date .104 Hour .105 Millisecond .105 Minute .105 Month .105 Second .106 Year .106 AcxCroPDFLib.AxAcroPDF .106 Got GetVersion S .108 Got ForwardStack .108	RemoveAnnot	96
Destroy. .98 GetBoundingRect .99 GetNumText .99 GetPage .100 GetText. .101 AcroExch.Point .102 Y .102 Y .102 AcroExch.Rect .102 Bottom .103 Left .103 Right .103 Top. .104 AcroExch.Time .104 Hour .105 Millisecond .105 Minute .105 Month .105 Second .106 Year .106 AxAcroPDFLib.AxAcroPDF .106 GetVersions .108 GoBackwardStack .108 GoForwardStack .108 GotoPreviousPage .109 GotoNextPage .109 GotoPreviousPage .109 LoadFile .110 Print .110 PrintPages .111 PrintPages .111 PrintWithDialog <t< td=""><td>SetRotate</td><td>97</td></t<>	SetRotate	97
GetBoundingRect .99 GetPNTEXT .99 GetPage .100 GetText .101 AcroExch.Point .102 X .102 Y .102 AcroExch.Rect .102 Bottom .103 Left .103 Right .103 Top .104 AcroExch.Time .104 Date .104 Hour .105 Millisecond .105 Minute .105 Month .105 Second .106 Year .106 AxAcroPDFLib.AxAcroPDF .106 GetVersions .108 GoBackwardStack .108 GotoNextPage .108 GotoNextPage .109 GotoNextPage .109 GotoNextPage .109 GotoNextPage .109 GotoNextPage .109 GotoNextPage .109 GotoNextPages .109 LoadFile .110<	AcroExch.PDTextSelect	98
GetNumText .99 GetPage .100 GetText .101 AcroExch.Point .102 X. .102 Y. .102 AcroExch.Rect .102 Bottom .103 Left .103 Right .103 Top. .104 AcroExch.Time .104 Date .104 Hour .105 Millisecond .105 Minute .105 Month .105 Second .106 Year .106 AxAcroPDFLib.AxAcroPDF .106 GetVersions .108 GoBackwardStack .108 GoForwardStack .108 GotoNextPage .108 GotoNextPage .109 GotoNextPage <t< td=""><td></td><td></td></t<>		
GetPage 100 GetText 101 AcroExch.Point 102 X 102 Y 102 AcroExch.Rect 102 Bottom 103 Left 103 Right 103 Top 104 AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GotoFirstPage 109 GotoNextPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 PrintAll 110 PrintAll 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	GetBoundingRect	99
GetText 101 AcroExch,Point 102 X 102 Y 102 AcroExch,Rect 102 Bottom 103 Left 103 Right 103 Top 104 AcroExch,Time 104 Date 104 Hour 105 Millisecond 105 Millisecond 105 Month 105 Second 106 Year 106 AxcroPDFLib,AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 PrintAll 110 PrintAll 111 PrintAllifit 111 PrintPagesFit 1112 PrintWithDialog 113	GetNumText	99
AcroExch,Point 102 X. 102 Y. 102 AcroExch,Rect 102 Bottom 103 Left 103 Right 103 Top 104 AcroExch,Time 104 Date 104 Hour 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 PrintAll 110 PrintAll 111 PrintPagesFit 111 PrintWithDialog 113	GetPage	100
X 102 Y 102 AcroExch.Rect 102 Bottom 103 Left 103 Right 103 Top 104 AcroExch.Time 104 Date 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoforwardStack 108 GotoFirstPage 109 GotoNextPage 109 GotoNextPage 109 GotoPreviousPage 109 GotoPreviousPage 109 LoadFile 110 PrintAll 110 PrintAllFit 111 PrintPagesFit 111 PrintWithDialog 113	GetText	101
Y 102 AcroExch.Rect 102 Bottom 103 Left 103 Right 103 Top 104 AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Minute 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 Go8ackwardStack 108 GoForwardStack 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAllFit 111 PrintPagesFit 111 PrintWithDialog 113	AcroExch.Point	102
AcroExch.Rect 102 Bottom 103 Left 103 Right 103 Top. 104 AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GeVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 109 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	Χ	102
Bottom 103 Left 103 Right 103 Top 104 AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Minute 105 Second 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 111 PrintWithDialog 113	Υ	102
Left 103 Right 103 Top 104 AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 111 PrintWithDialog 113	AcroExch.Rect	102
Right 103 Top 104 AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 111 PrintWithDialog 113	Bottom	103
Top	Left	103
AcroExch.Time 104 Date 104 Hour 105 Millisecond 105 Month 105 Second 106 Year 106 AXAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 111 PrintWithDialog 113	Right	103
Date 104 Hour 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 111 PrintPages 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	Тор	104
Hour 105 Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoAstPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	AcroExch.Time	104
Millisecond 105 Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 111 PrintWithDialog 113	Date	104
Minute 105 Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 111 PrintWithDialog 113	Hour	105
Month 105 Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	Millisecond	105
Second 106 Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 108 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	Minute	105
Year 106 AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 109 GotoLastPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	Month	105
AxAcroPDFLib.AxAcroPDF 106 GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 109 GotoLastPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	Second	106
GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 109 GotoLastPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113		
GetVersions 108 GoBackwardStack 108 GoForwardStack 108 GotoFirstPage 109 GotoLastPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	AxAcroPDFLib.AxAcroPDF	106
GoForwardStack 108 GotoFirstPage 109 GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113		
GotoFirstPage 108 GotoLastPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	GoBackwardStack	108
GotoLastPage 109 GotoNextPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	GoForwardStack	108
GotoNextPage 109 GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	GotoFirstPage	108
GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	GotoLastPage	109
GotoPreviousPage 109 LoadFile 110 Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	<u> </u>	
Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	GotoPreviousPage	109
Print 110 PrintAll 110 PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113	LoadFile	110
PrintAllFit 111 PrintPages 111 PrintPagesFit 112 PrintWithDialog 113		
PrintPages	PrintAll	110
PrintPages	PrintAllFit	111
PrintPagesFit 112 PrintWithDialog 113		
PrintWithDialog113	_	

1	OLE Automation (Continued)	
	AxAcroPDFLib.AxAcroPDF (Continued)	
	SetCurrentPage	113
	SetLayoutMode	
	SetNamedDest	
	SetPageMode	
	SetShowScrollbars	
	SetShowToolbar	
	SetView	
	SetViewRect	
	SetViewScroll	
	SetZoom	
	SetZoomScroll	
	Src	
2		
_	AppExit	
	··	
	AppHide	
	AppShow	
	CloseAllDocs	
	DocClose	
	DocDeletePages	
	DocFind	
	DocGoTo	
	DocGoToNameDest	
	DocInsertPages	
	DocOpen	
	DocPageDown	
	DocPageLeft	
	DocPageRight	
	DocPageUp	128
	DocPrint	
	DocReplacePages	129
	DocSave	130
	DocSaveAs	130
	DocScrollTo	131
	DocSetViewMode	132
	DocZoomTo	132
	FileOpen	133
	FileOpenEx	133
	FilePrint	134
	FilePrintEx	135
	FilePrintSilent	135
	FilePrintSilentEx	136
	FilePrintTo	137
	FilePrintToEx	
	FullMenus	
	HideToolbar	
	MenuitemExecute	
	ShortMenus	
	ShowToolbar	

Apple Event Objects and Apple Events	141
Objects	
annotation	
application	143
AVPageView	145
bookmarkbookmark	145
conversion	147
document	147
EPS Conversion	149
Link Annotation	149
menu	149
menu item	150
page	151
PDAnnot	151
PDBookMark	152
PDLinkAnnot	152
PDPage	152
PDTextAnnot	152
PDF Window	152
PostScript Conversion	153
Text Annotation	154
Required suite events	155
open	155
print	155
quit	155
run	156
Core suite events	156
close	156
count	157
deletedelete	157
exists	158
get	158
make	159
move	159
open	160
quit	160
save	161
set	161
Acrobat application events	162
bring to front	
clear selection	163
close all docs	163
create thumbs	164
delete pages	
delete thumbs	
execute	
find next note	
find text	167

3 Apple Event Objects and Apple Events (Continued)

	Acrobat application events (Continued)	166
	get infogo backward	
	go forwardgo	
	gotogoto	
	goto next	
	goto previous	
	insert pages	
	is toolbutton enabled	
	maximize	
	perform	
	print pages	
	read page down	
	read page up	
	remove toolbutton	
	replace pages	
	scroll	
	select text	
	set info	
	zoom	
	Miscellaneous events	
	do script	180
4	Acrobat Catalog Plug-In	181
	Catalog Windows messages	
	Catalog DDE methods	
	AppExit	
	AppFront	
	FileBuild	
	FileOpen	
	FilePurge	
_	5	
5	Acrobat Forms Plug-In	
	Forms plug-in OLE automation	
	Exceptions	
	AFormApp	
	Field	
	Methods	
	PopulateListOrComboBox	
	Set Background Color	
	SetBorderColor	
	SetButtonCaption	
	SetButtonIcon	
	SetExportValues	188
	SetForegroundColor	189
	SetJavaScriptAction	190
	SetResetFormAction	191
	SetSubmitFormAction	192

5 Acrobat Forms Plug-In (Continued) Field (Continued)

	Field (Continued)	
	Properties	
	Alignment	
	BorderStyle	
	BorderWidth	
	ButtonLayout	
	CalcOrderIndex	
	CharLimit	
	DefaultValue	
	Editable	
	Highlight	
	IsHidden	
	IsMultiline	
	IsPassword	
	IsReadOnly	
	IsRequired	
	IsTerminal	
	Name	
	NoViewFlag	
	PrintFlag	
	Style	
	TextFont	
	TextSize	
	Type	
	Value	
	Fields	
	Methods	
	Add	
	AddDocJavascript	
	ExecuteThisJavascript	
	ExportAsFDF	
	ExportAsHtml	
	ImportAnFDF	
	Remove	
	Properties	
	Count	
	ltem	
	_NewEnum	208
6	Acrobat Search Plug-in	209
	Search plug-in using DDE	209
	Simple query item	209
	Query item	209
	Query options	210
	Query language type constants	211
	Word option bit-flag constants	211
	Manipulating indexes through DDE	
	Options	
	Index operation selectors	
	·	

6	Acrobat Search Plug-in (Continued)	
	Search plug-in using Apple events	213
	Search plug-in using Apple events SearchAddIndex	213
	SearchCountIndexList	213
	SearchDoQuery	214
	SearchGetIndexByPath	215
	SearchGetIndexByPath SearchGetIndexFlags	216
	SearchGetIndexList	216
	SearchGetIndexPath	216
	SearchGetIndexTitle	217
	SearchGetNthIndex	217
	SearchRemoveIndex	218
	SearchSetIndexFlags	218
	Search lists	219
	Menu names	219
	Menu item names	219
	Toolbar button names	

Preface

The Adobe® Acrobat® Software Development Kit (SDK) provides a set of Acrobat core API calls for creating plug-ins and other programs. You can use a subset of these calls for implementing interapplication communication (IAC) functionality and PDF browser controls. These Acrobat calls support OLE automation, DDE interapplication interfaces, and Apple events, including the use of AppleScript.

What's in this guide?

This document provides a detailed reference of all the calls needed for OLE, DDE, and Apple events.

There is no IAC support for the UNIX® versions of Acrobat. There is no IAC support in the Japanese version of Acrobat.

Who should read this guide?

This guide is for developers that want to communicate with Acrobat from another application or render Adobe PDF files in their own application, or who are writing plug-ins that need to communicate with or use multiple applications.

You should already be familiar with at least one of OLE, DDE, Apple events, or AppleScript. You should also be familiar with the Acrobat core API. Many of the IAC capabilities are actually a subset of those provided in the Acrobat core API, and many of the IAC messages are similar to core API methods.

Related documentation

For information about	See
A guide to the documentation in the Acrobat SDK	Acrobat SDK Documentation Roadmap
A guide to the sections of the Acrobat SDK that pertain to Adobe Reader®	Developing for Adobe Reader
A guide to the sample code included with the Acrobat SDK	Guide to SDK Samples
Prototyping code without the overhead of writing and verifying a complete plug-in or application	Snippet Runner Cookbook
Using DDE, OLE, Apple events, and AppleScript to control Acrobat and Adobe Reader and to render PDF documents	Developing Applications Using Interapplication Communication
Using JavaScript™ to develop and enhance standard workflows in Acrobat and Adobe Reader	Developing Acrobat Applications Using JavaScript
Detailed descriptions of JavaScript APIs for developing and enhancing workflows in Acrobat and Adobe Reader	JavaScript for Acrobat API Reference

For information about	See	
A detailed description of the PDF file format	PDF Reference	
Developing plug-ins for Acrobat and Adobe Reader, as well as for PDF Library applications	Developing Plug-ins and Applications	
Detailed descriptions of the APIs for Acrobat and Adobe Reader plug-ins, as well as for PDF Library applications	Acrobat and PDF Library API Reference	

OLE Automation

This chapter describes the objects, data types, and methods in the OLE automation interface.

The names AcroExch. App and AxAcroPDFLib. AxAcroPDF are the external strings OLE clients use to create objects of certain types. The Acrobat developer type libraries call them CAcro. App and AcroPDFLib, respectively.

Acrobat supports dual interfaces, so the methods all have a return type of HResult.

The following table summarize the available objects and data types.

Object	Description
AcroExch.App	The application itself.
AcroExch.AVDoc	A document as seen in the user interface.
AcroExch.PDDoc	The underlying PDF representation of a document.
AcroExch.HiliteList	An entry in a highlight list.
AcroExch.AVPageView	The area of the window that displays the contents of a page.
AcroExch.PDPage	A single page in the PDF representation of a document.
AcroExch.PDAnnot	An annotation on a page in the PDF file.
AcroExch.PDBookmark	A bookmark in a PDF file.
AcroExch.PDTextSelect	A selection of text on a single page.
AxAcroPDFLib.AxAcroPDF	An object containing PDF browser controls.
AcroExch.Point	A point, specified by its x–coordinate and y–coordinate.
AcroExch.Rect	A rectangle, specified by the top-left and bottom-right points.
AcroExch.Time	A specified time, accurate to the millisecond.

AcroExch.App

The Acrobat application itself. This is a creatable interface. From the application layer, you can control the appearance of Acrobat, whether Acrobat appears, and the size of the application window. This object provides access to the menu bar and the toolbar, as well as the visual representation of a PDF file on the screen (through an AVDoc object).

Methods

The App object has the following methods.

Method	Description
CloseAllDocs	Closes all open documents.
<u>Exit</u>	Exits Acrobat.
GetActiveDoc	Gets the frontmost document.
GetActiveTool	Gets the name of the currently active tool.
<u>GetAVDoc</u>	Gets an AcroExch. AVDoc object via its index within the list of open AVDoc objects.
<u>GetFrame</u>	Gets the window's frame.
<u>GetInterface</u>	Gets an IDispatch interface for a named object, typically a third-party plug-in.
GetLanguage	Gets a code that specifies which language the Acrobat application's user interface is using.
GetNumAVDocs	Gets the number of open AcroExch. AVDoc objects.
<u>GetPreference</u>	Gets a value from the preferences file.
GetPreferenceEx	Gets the specified application preference, using the VARIANT type to pass values.
<u>Hide</u>	Hides the Acrobat application.
Lock	Locks the Acrobat application.
Minimize	Minimizes the Acrobat application.
<u>Maximize</u>	Maximizes the Acrobat application.
<u>MenuItemExecute</u>	Executes the menu item whose language-independent menu item name is specified.
<u>MenuItemIsEnabled</u>	Determines whether the specified menu item is enabled.
MenuItemIsMarked	Determines whether the specified menu item is marked.
<u>MenuItemRemove</u>	Removes the menu item whose language-independent menu item is specified.
Restore	Restores the main window of the Acrobat application.
<u>SetActiveTool</u>	Sets the active tool according to the specified name, and determines whether the tool is to be used only once or should remain active after being used (persistent).
<u>SetFrame</u>	Sets the window's frame to the specified rectangle.

Method	Description
SetPreference	Sets a value in the preferences file.
<u>SetPreferenceEx</u>	Sets the application preference specified by \mathtt{nType} to the value stored at $\mathtt{pVal}.$
Show	Shows the Acrobat application.
ToolButtonIsEnabled	Determines whether the specified toolbar button is enabled.
ToolButtonRemove	Removes the specified button from the toolbar.
Unlock	Unlocks the Acrobat application if it was previously locked.
UnlockEx	Unlocks the Acrobat application if it was previously locked.

CloseAllDocs

Closes all open documents. You can close each individual AVDoc object by calling AVDoc. Close.

You must explicitly close all documents or call App. CloseAllDocs. Otherwise, the process never exits.

Syntax

VARIANT BOOL CloseAllDocs();

Returns

-1 if successful, 0 if not.

Related methods

AVDoc.Close

AVDoc. Open

AVDoc.OpenInWindow

AVDoc.OpenInWindowEx

PDDoc.Close

 ${\tt PDDoc.} \underline{{\tt Open}}$

PDDoc. OpenAVDoc

Exit

Exits Acrobat. Applications should call App. Exit before exiting.

Note: Use App. CloseAllDocs to close all the documents before calling this method.

Syntax

```
VARIANT BOOL Exit();
```

Returns

Returns -1 if the entire shutdown process succeeded. This includes closing any open documents, releasing OLE references, and finally exiting the application. If any step fails, the function returns 0, and the application continues running. This method does not work if the application is visible (if the user is in control of the application). In such cases, if the Show method had previously been called, you can call Hide and then Exit.

Related methods

App.<u>CloseAllDocs</u>

GetActiveDoc

Gets the frontmost document.

Syntax

```
LPDISPATCH GetActiveDoc();
```

Returns

The LPDISPATCH for the frontmost AcroExch. AVDoc object. If there are no documents open, it returns NULL.

Related methods

App. GetAVDoc

GetActiveTool

Gets the name of the currently active tool.

Syntax

```
BSTR GetActiveTool();
```

Returns

Returns NULL if there is no active tool. Returns the name of the currently active tool otherwise. See the *Acrobat and PDF Library API Reference* for a list of tool names.

Related methods

App.SetActiveTool

GetAVDoc

Gets an AcroExch. AVDoc object from its index within the list of open AVDoc objects. Use App. GetNumAVDocs to determine the number of AcroExch. AVDoc objects.

Syntax

LPDISPATCH GetAVDoc(long nIndex);

Parameters

nIndex

The index of the document to get.

Returns

The LPDISPATCH for the specified AcroExch. AVDoc document, or NULL if nIndex is greater than the number of open documents.

Related methods

App.GetActiveTool

GetFrame

Gets the window's frame.

GetFrame is not useful when the PDF file was opened with AVDoc. OpenInWindow. GetFrame returns the application window's frame (not the document window's frame). However, the application's window is hidden when a document is opened using OpenInWindow, and does not change in size as document windows are moved and resized.

This method is also not useful if the Acrobat application is in single document interface (SDI) mode.

Syntax

```
LPDISPATCH GetFrame();
```

Returns

The LPDISPATCH for the window's frame, specified as an AcroExch.Rect.

If the Acrobat application is in SDI mode, a [0,0,0,0] Rect is returned.

Related methods

App. Maximize

App.<u>SetFrame</u>

GetInterface

Gets an IDispatch interface for a named object, typically a third-party plug-in. This is an entry point to functionality that is undefined and which must be provided by the plug-in author. If you are accessing third-party functionality through GetInterface, ask the author for additional information.

Syntax

```
LPDISPATCH GetInterface (BSTR szName);
```

Parameters

szName

Name of the object.

Returns

The LPDISPATCH for the objects's interface or NULL if the object was not found.

GetLanguage

Gets a code that specifies which language the Acrobat application's user interface is using.

Syntax

```
BSTR GetLanguage();
```

Returns

String containing a three-letter language code. Must be one of the following:

- DEU German
- ENU English
- ESP Spanish
- FRA French
- ITA Italian
- NLD Dutch
- SVE Swedish

Related methods

App.GetPreference

App. SetPreference

GetNumAVDocs

Gets the number of open AcroExch. AVDoc objects. The maximum number of documents the Acrobat application can open at a time is specified by the avpMaxOpenDocuments preference, which can be obtained with App. GetPreferenceEx and set by App. SetPreferenceEx.

Syntax

long GetNumAVDocs();

Returns

The number of open AcroExch. AVDoc objects.

Related methods

App. GetActiveDoc

App. GetAVDoc

GetPreference

Note: This method is deprecated; use GetPreference instead. GetPreference is unable to accept important data types such as strings, but GetPreferenceEx can convert many data types into acceptable formats.

Gets a value from the preferences file. Zoom values (used in avpDefaultZoomScale and avpMaxPageCacheZoom) are returned as percentages (for example, 1.00 is returned as 100). Colors (used in avpNoteColor -- PDcolorValue) are automatically converted to RGB values from the representation used in the preferences file.

Syntax

long GetPreference(short nType);

Parameters

nType	The preferences item whose value is set. See the Acrobat and PDF Library API Reference
	for a list of preference items.

Returns

The value of the specified preference item.

Related methods

App. GetLanguage

App.SetPreference

GetPreferenceEx

Gets the specified application preference, using the VARIANT type to pass values.

Syntax

VARIANT GetPreferenceEx(short nType);

Parameters

nType

The name of the preferences item whose value is obtained.

Returns

The value of the specified preference item.

Related methods

```
App. GetLanguage
```

App.<u>SetPreferenceEx</u>

Hide

Hides the Acrobat application. When the viewer is hidden, the user has no control over it, and the Acrobat application exits when the last automation object is closed.

Syntax

```
VARIANT BOOL Hide();
```

Returns

-1 if successful, 0 if not.

Related methods

App. Show

Lock

Locks the Acrobat application. Typically, this method is called when using AVDoc.OpenInWindowEx to draw into another application's window. If you call App.Lock, you should call App.UnlockEx when you are done using OLE automation.

There are some advantages and disadvantages of locking the viewer when using AVDoc.OpenInWindowEx. You must consider these before deciding whether to lock the viewer:

 Locking prevents problems that can sometimes occur if two processes are trying to open a file at the same time.

- Locking prevents a user from using Acrobat's user interface (such as adding annotations) in your application's window.
- Locking can prevent any other application, including the Acrobat application, from opening PDF files. This problem can be minimized by calling App. <u>UnlockEx</u> as soon as the file has been opened.

Syntax

VARIANT_BOOL Lock(BSTR szLockedBy);

Parameters

szLockedBy	A string that is used as the name of the application that has locked the Acrobat application.
------------	---

Returns

-1 if the Acrobat application was locked successfully, 0 otherwise. Locking fails if the Acrobat application is visible.

Related methods

App.UnlockEx

Minimize

Minimizes the Acrobat application.

Syntax

VARIANT BOOL Minimize (long BMinimize);

Parameters

BMinimize	If a positive number, the Acrobat application is minimized. If 0, the Acrobat
	application is returned to its normal state.

Returns

-1 if successful, 0 if not.

Related methods

App.GetFrame

App.<u>SetFrame</u>

Maximize

Maximizes the Acrobat application.

Syntax

VARIANT BOOL Maximize(long bMaximize);

Parameters

bMaximize	If a positive number, the Acrobat application is maximized. If 0, the Acrobat application is returned to its normal state.
	application is returned to its normal state.

Returns

-1 if successful, 0 if not.

Related methods

App. GetFrame

App.<u>SetFrame</u>

MenultemExecute

Executes the menu item whose language-independent menu item name is specified.

Syntax

VARIANT BOOL MenuItemExecute(BSTR szMenuItemName);

Parameters

szMenuItemName	The language-independent name of the menu item to execute. See the Acrobat
	and PDF Library API Reference for a list of menu item names.

Returns

Returns -1 if the menu item executes successfully, or 0 if the menu item is missing or is not enabled.

Related methods

App.MenuItemIsEnabled

App.MenuItemIsMarked

App.MenuItemRemove

MenuItemIsEnabled

Determines whether the specified menu item is enabled.

Syntax

VARIANT BOOL MenuItemIsEnabled(BSTR szMenuItemName);

Parameters

szMenuItemName	The language-independent name of the menu item whose enabled state is obtained. See the <i>Acrobat and PDF Library API Reference</i> for a list of menu item
	names.

Returns

-1 if the menu item is enabled, 0 if it is disabled or does not exist.

Related methods

App.MenuItemExecute

App.MenuItemIsMarked

App.MenuItemRemove

MenuItemIsMarked

Determines whether the specified menu item is marked.

Syntax

VARIANT BOOL MenuItemIsMarked(BSTR szMenuItemName);

Parameters

szMenuItemName	The language-independent name of the menu item whose marked state is obtained. See the <i>Acrobat and PDF Library API Reference</i> for a list of menu item
	names.

Returns

-1 if the menu item is marked, 0 if it is not marked or does not exist.

Related methods

App.MenuItemExecute

App. MenuItemIsEnabled

App. MenuItemRemove

MenultemRemove

Removes the menu item whose language-independent menu item is specified.

Syntax

VARIANT BOOL MenuItemRemove(BSTR szMenuItemName);

Parameters

szMenuItemName	The language-independent name of the menu item to remove. See the Acrobat
	and PDF Library API Reference for a list of menu item names.

Returns

-1 if the menu item was removed, 0 if the menu item does not exist.

Related methods

App. MenuItemExecute

App. MenuItemIsEnabled

App.MenuItemIsMarked

Restore

Restores the main window of the Acrobat application. Calling this with bRestore set to a positive number causes the main window to be restored to its original size and position and to become active.

Syntax

```
VARIANT_BOOL Restore(long bRestore);
```

Parameters

bRestore If a positive number, the Acrobat application is restored, 0 otherwise.

Returns

-1 if successful, 0 if not.

Related methods

App. GetFrame

App.<u>SetFrame</u>

SetActiveTool

Sets the active tool according to the specified name, and determines whether the tool is to be used only once or should remain active after being used (persistent).

Syntax

Parameters

szButtonName	The name of the tool to set as the active tool. See the <i>Acrobat and PDF Library API Reference</i> for a list of tool names.
bPersistent	A request indicating whether the tool should be persistent. A positive number indicates a request to the Acrobat application for the tool to remain active after it has been used. If 0 is specified, the Acrobat application reverts to the previously active tool after this tool is used once.

Returns

-1 if the tool was set, 0 otherwise.

Related methods

App. GetActiveTool

App. ToolButtonIsEnabled

App. ToolButtonRemove

SetFrame

Sets the window's frame to the specified rectangle. This method has no effect if the Acrobat application is in single document interface (SDI) mode.

Syntax

VARIANT BOOL SetFrame (LPDISPATCH iAcroRect);

Parameters

iAcroRect The LPDISPATCH for an AcroExch.Rect specifying the window frame. iAcroRect contains the instance variable m_lpDispatch, which contains the LPDISPATCH.	!
--	---

Returns

-1 if the frame was set, 0 if iAcroRect is not of type AcroExch.Rect.

Related methods

App.GetFrame

App.Maximize

SetPreference

Note: This method is deprecated; use <u>SetPreferenceEx</u> instead. SetPreference is unable to accept important data types such as strings, but <u>SetPreferenceEx</u> can convert many data types into acceptable formats.

Sets a value in the preferences file. Zoom values (used in avpDefaultZoomScale and avpMaxPageCacheZoom) must be passed as percentages and are automatically converted to fixed point numbers (for example, 100 is automatically converted to 1.0). Colors (used in avpHighlightColor or avpNoteColor) are automatically converted from RGB values to the representation used in the preferences file.

Syntax

VARIANT BOOL SetPreference(short nType, long nValue);

Parameters

пТуре	The preferences item whose value is set. See the Acrobat and PDF Library API Reference for a list of preference items.
nValue	The value to set.

Returns

-1 if successful, 0 if not.

Related methods

App.GetLanguage

App. GetPreferenceEx

SetPreferenceEx

Sets the application preference specified by nType to the value stored at pVal. If pVal has a non-conforming VARTYPE, SetPreferenceEx performs type conversion. For example, a string representation of an integer is converted to an actual integer.

Syntax

VARIANT BOOL SetPreferenceEx(short nType, VARIANT* pVal);

Parameters

nType	The preferences item whose value is set. See the <i>Acrobat and PDF Library API Reference</i> for a list of preference items.
pVal	The value to set.

Returns

Returns -1 if nType is a supported type or the type conversion is successful, 0 otherwise.

Related methods

App. GetLanguage

App. GetPreferenceEx

Show

Shows the Acrobat application. When the viewer is shown, the user is in control, and the Acrobat application does not automatically exit when the last automation object is destroyed. However, it will exit if no documents are being displayed.

Syntax

```
VARIANT BOOL Show();
```

Returns

-1 if successful, 0 if not.

Related methods

App. Hide

ToolButtonIsEnabled

Determines whether the specified toolbar button is enabled.

Syntax

VARIANT BOOL ToolButtonIsEnabled(BSTR szButtonName);

Parameters

szButtonName	The name of the button whose enabled state is checked. See the Acrobat and
	PDF Library API Reference for a list of toolbar button names.

Returns

-1 if the button is enabled, 0 if it is not enabled or does not exist.

Related methods

```
App. <u>GetActiveTool</u>

App. <u>SetActiveTool</u>

App. ToolButtonRemove
```

ToolButtonRemove

Removes the specified button from the toolbar.

Syntax

```
VARIANT BOOL ToolButtonRemove(BSTR szButtonName);
```

Parameters

szButtonName	The name of the button to remove. See the Acrobat and PDF Library API
	Reference for a list of toolbar button names.

Returns

-1 if the button was removed, 0 otherwise.

Related methods

```
App. GetActiveTool

App. SetActiveTool

App. ToolButtonIsEnabled
```

Unlock

Note: In version 4.0 or later, use App. UnlockEx instead.

Unlocks the Acrobat application if it was previously locked. This method clears a flag that indicates the viewer is locked. If you called App. Lock, you should call App. Unlock when you are done using OLE automation.

```
Use App. Lock and App. UnlockEx if you call OpenInWindow.
```

Typically, you call $App.\underline{Lock}$ when your application initializes and $App.\underline{Unlock}$ in your application's destructor method.

Syntax

```
VARIANT BOOL Unlock();
```

Returns

-1 if successful, 0 if not.

Related methods

```
App. Lock
```

App. UnlockEx

UnlockEx

Unlocks the Acrobat application if it was previously locked.

Syntax

```
VARIANT BOOL UnlockEx (BSTR szLockedBy);
```

Parameters

szLockedBy A string indicating the name of the application to be unlocked.
--

Returns

-1 if successful, 0 if not.

Related methods

App.Lock

AcroExch.AVDoc

A view of a PDF document in a window. This is a creatable interface. There is one AVDoc object per displayed document. Unlike a PDDoc object, an AVDoc object has a window associated with it.

Methods

The AVDoc object has the following methods.

Method	Description
BringToFront	Brings the window to the front.
ClearSelection	Clears the current selection.
Close	Closes a document.

Method	Description
FindText	Finds the specified text, scrolls so that it is visible, and highlights it.
<u>GetAVPageView</u>	Gets the AcroExch. AVPageView associated with an AcroExch. AVDoc.
<u>GetFrame</u>	Gets the rectangle specifying the window's size and location.
<u>GetPDDoc</u>	Gets the AcroExch. PDDoc associated with an AcroExch. AVDoc.
<u>GetTitle</u>	Gets the window's title.
<u>GetViewMode</u>	Gets the current document view mode (pages only, pages and thumbnails, or pages and bookmarks).
IsValid	Determines whether the AcroExch. AVDoc is still valid.
Maximize	Maximizes the window if bMaxSize is a positive number.
<u>Open</u>	Opens a file.
OpenInWindow	Opens a PDF file and displays it in a user-specified window.
<u>OpenInWindowEx</u>	Opens a PDF file and displays it in a user-specified window.
<u>PrintPages</u>	Prints a specified range of pages displaying a print dialog box.
PrintPagesEx	Prints a specified range of pages, displaying a print dialog box.
PrintPagesSilent	Prints a specified range of pages without displaying any dialog box.
<u>PrintPagesSilentEx</u>	Prints a specified range of pages without displaying any dialog box.
<u>SetFrame</u>	Sets the window's size and location.
SetTextSelection	Sets the document's selection to the specified text selection.
<u>SetTitle</u>	Sets the window's title.
<u>SetViewMode</u>	Sets the mode in which the document will be viewed (pages only, pages and thumbnails, or pages and bookmarks)
ShowTextSelect	Changes the view so that the current text selection is visible.

BringToFront

Brings the window to the front.

Syntax

VARIANT_BOOL BringToFront();

Returns

Returns 0 if no document is open, -1 otherwise.

ClearSelection

Clears the current selection.

Syntax

```
VARIANT BOOL ClearSelection();
```

Returns

Returns -1 if the selection was cleared, 0 if no document is open or the selection could not be cleared.

Related methods

```
AVDoc.SetTextSelection

AVDoc.ShowTextSelect

PDDoc.CreateTextSelect

PDPage.CreatePageHilite

PDPage.CreateWordHilite

PDTextSelect.Destroy

PDTextSelect.GetBoundingRect

PDTextSelect.GetNumText

PDTextSelect.GetPage

PDTextSelect.GetText
```

Close

Closes a document. You can close all open AVDoc objects by calling App. CloseAllDocs.

To reuse an AVDoc object, close it with AVDoc. Close, then use the AVDoc object's LPDISPATCH for AVDoc. OpenInWindow.

Syntax

```
VARIANT_BOOL Close(long bNoSave);
```

Parameters

bNoSave	If a positive number, the document is closed without saving it. If 0 and the document
	has been modified, the user is asked whether or not the file should be saved.

Returns

Always returns -1, even if no document is open.

Related methods

App. CloseAllDocs

AVDoc. Open

AVDoc.OpenInWindow

AVDoc.<u>OpenInWindowEx</u>

PDDoc.Close

PDDoc.<u>Open</u>

PDDoc.OpenAVDoc

FindText

Finds the specified text, scrolls so that it is visible, and highlights it.

Syntax

VARIANT_BOOL FindText(BSTR szText, long bCaseSensitive, long bWholeWordsOnly, long bReset);

Parameters

szText	The text to be found.
bCaseSensitive	If a positive number, the search is case-sensitive. If 0, it is case-insensitive.
bWholeWordsOnly	If a positive number, the search matches only whole words. If 0, it matches partial words.
bReset	If a positive number, the search begins on the first page of the document. If 0 , it begins on the current page.

Returns

-1 if the text was found, 0 otherwise.

GetAVPageView

Gets the AcroExch. AVPageView associated with an AcroExch. AVDoc.

Syntax

LPDISPATCH GetAVPageView();

Returns

The LPDISPATCH for the AcroExch. AVPageView or NULL if no document is open.

Related methods

```
AVDoc. GetPDDoc

AVDoc. SetViewMode

AVPageView. GetAVDoc

AVPageView. GetDoc
```

GetFrame

Gets the rectangle specifying the window's size and location.

Syntax

```
LPDISPATCH GetFrame();
```

Returns

The LPDISPATCH for an AcroExch. Rect containing the frame, or NULL if no document is open.

Related methods

```
AVDoc.<u>SetFrame</u>
```

GetPDDoc

Gets the AcroExch. PDDoc associated with an AcroExch. AVDoc.

Syntax

```
LPDISPATCH GetPDDoc();
```

Returns

The LPDISPATCH for the AcroExch. PDDoc or NULL if no document is open.

Related methods

```
AVPageView. GetAVDoc

AVPageView. GetDoc
```

GetTitle

Gets the window's title.

Syntax

```
BSTR GetTitle();
```

Returns

The window's title or NULL if no document is open.

Related methods

```
AVDoc.<u>Open</u>

AVDoc.<u>SetTitle</u>

PDDoc.<u>OpenAVDoc</u>
```

GetViewMode

Gets the current document view mode (pages only, pages and thumbnails, or pages and bookmarks).

Syntax

```
long GetViewMode();
```

Returns

The current document view mode or 0 if no document is open. The return value is one of the following:

```
PDDontCare: 0 — leave the view mode as it is

PDUseNone: 1 — display without bookmarks or thumbnails

PDUseThumbs: 2 — display using thumbnails

PDUseBookmarks: 3 — display using bookmarks

PDFullScreen: 4 — display in full screen mode
```

Related methods

```
AVDoc.<u>GetAVPageView</u>
AVDoc.<u>SetViewMode</u>
```

IsValid

Determines whether the AcroExch. AVDoc is still valid. This method only checks if the document has been closed or deleted; it does not check the internal structure of the document.

Syntax

```
VARIANT BOOL IsValid();
```

Returns

-1 if the document can still be used, 0 otherwise.

Related methods

```
App. GetAVDoc
```

AVPageView. GetAVDoc

Maximize

Maximizes the window if bMaxSize is a positive number.

Syntax

VARIANT_BOOL Maximize(long bMaxSize);

Parameters

bMaxSize Indicates whether the window should be maximized.	
--	--

Returns

-1 if a document is open, 0 otherwise.

Related methods

AVDoc.<u>GetFrame</u>
AVDoc.<u>SetFrame</u>

Open

Opens a file. A new instance of AcroExch. AVDoc must be created for each displayed PDF file.

Note: An application must explicitly close any AVDoc that it opens by calling AVDoc. <u>Close</u> (the destructor for the AcroExch. AVDoc class does not call AVDoc. <u>Close</u>).

Syntax

VARIANT_BOOL Open(BSTR szFullPath, BSTR szTempTitle);

Parameters

szFullPath	The full path of the file to open.
szTempTitle	An optional title for the window in which the file is opened. If $szTempTitle$ is NULL or the empty string, it is ignored. Otherwise, $szTempTitle$ is used as the window title.

-1 if the file was opened successfully, 0 otherwise.

Related methods

App. CloseAllDocs

AVDoc. Close

AVDoc. GetTitle

AVDoc. OpenInWindow

AVDoc.OpenInWindowEx

AVDoc.<u>SetTitle</u>

PDDoc.Close

PDDoc.Open

PDDoc.OpenAVDoc

OpenInWindow

Note: As of Acrobat 3.0, this method simply returns false. Use the method AVDoc. OpenInWindowEx instead.

Syntax

VARIANT BOOL OpenInWindow(BSTR fileName, short hWnd);

Parameters

fileName	The full path of the file to open.
hWnd	Handle for the window in which the file is displayed.

Returns

-1

Related methods

App.CloseAllDocs

AVDoc. Close

AVDoc. Open

AVDoc.OpenInWindowEx

PDDoc.Close

PDDoc.<u>Open</u>

PDDoc.OpenAVDoc

OpenInWindowEx

Opens a PDF file and displays it in a user-specified window. The default Windows file system is used to open the file.

Note: Acrobat uses only its built-in implementation of the file opening code—not any replacement file system version that a developer might have added with a plug-in.

An application must explicitly close any AVDoc that it opens by calling AVDoc. <u>Close</u> (the destructor for the AcroExch. AVDoc class does not call AVDoc. <u>Close</u>).

Do not set the view mode to <u>Close</u> with AVDoc. <u>SetViewMode</u> when using AVDoc. <u>OpenInWindowEx</u>; this will cause the viewer and application to hang.

If you use a view mode of AV_PAGE_VIEW, the pagemode parameter will be ignored.

See AVApp. Lock for a discussion of whether to lock the viewer before making this call.

Syntax

Parameters

szFullPath	The full path of the file to open.
hWnd	Handle for the window in which the file is displayed.
openFlags	Type of window view. Must be one of the following:
	${\tt AV_EXTERNAL_VIEW}$ — Display the ${\tt AVPageView}$, scrollbars, toolbar, and bookmark or thumbnails pane. Annotations are active.
	${\tt AV_DOC_VIEW}$ — Display the ${\tt AVPageView},$ scrollbars, and bookmark or thumbnails pane. Annotations are active.
	AV_PAGE_VIEW — Display only the AVPageView (the window that displays the PDF file). Do not display scrollbars, the toolbar, and bookmark or thumbnails pane. Annotations are active.
	Note: Use either AV_DOC_VIEW or AV_PAGE_VIEW whenever possible. Use AV_EXTERNAL_VIEW only if you do not want the application to display its own toolbar. Use AV_PAGE_VIEW to open the file with no scrollbars and no status window at the bottom of the page.

useOpenParams	0 indicates that the open action of the file is used; a positive number indicates that the action is overridden with the parameters that follow.
pgNum	Page number at which the file is to be opened if useOpenParams is a positive number. The first page is zero.
pageMode	Specifies page view mode if useOpenParams is a positive number. Possible values:
	PDDontCare: 0 — leave the view mode as it is
	PDUseNone: 1 — display without bookmarks or thumbnails
	PDUseThumbs: 2 — display using thumbnails
	PDUseBookmarks: 3 — display using bookmarks
	PDFullScreen: 4 — display in full screen mode
zoomType	Zoom type of the page view if useOpenParams is a positive number. Possible values are:
	AVZoomFitHeight — Fits the page's height in the window.
	AVZoomFitPage — Fits the page in the window.
	AVZoomFitVisibleWidth — Fits the page's visible content into the window.
	AVZoomFitWidth — Fits the page's width into the window.
	AVZoomNoVary — A fixed zoom, such as 100%.
zoom	Zoom factor, used only for AVZoomNoVary if useOpenParams is a positive number.
top	Used for certain zoom types (such as AVZoomNoVary) if useOpenParams is a positive number. See the <i>PDF Reference</i> for information on views.
left	Used for certain zoom types (such as AVZoomNoVary) if useOpenParams is a positive number. See the <i>PDF Reference</i> for information on views.

-1 if the document was opened successfully, 0 otherwise.

Related methods

App. CloseAllDocs

AVDoc.<u>Close</u>

AVDoc.<u>Open</u>

AVDoc. OpenInWindow

PDDoc.<u>Close</u>

PDDoc.<u>Open</u>

PDDoc. OpenAVDoc

PrintPages

Prints a specified range of pages displaying a print dialog box. PrintPages always uses the default printer setting.

Syntax

Parameters

nFirstPage	The first page to be printed. The first page in a PDDoc object is page 0.
nLastPage	The last page to be printed.
nPSLevel	Valid values are 2 and 3. If 2, PostScript® Level 2 operators are used. If 3, PostScript Language Level 3 operators are also used.
bBinaryOk	If a positive number, binary data can be included in the PostScript program. If 0, all data is encoded as 7-bit ASCII.
bShrinkToFit	If a positive number, the page is shrunk (if necessary) to fit within the imageable area of the printed page. If 0 , it is not.

Returns

0 if there were any exceptions while printing or if no document was open, -1 otherwise.

Related methods

AVDoc. PrintPagesEx

AVDoc. PrintPagesSilent

AVDoc.PrintPagesSilentEx

PrintPagesEx

Prints a specified range of pages, displaying a print dialog box. PrintPagesEx has more parameters than PrintPagesEx always uses the default printer setting.

```
VARIANT_BOOL printPagesEx(long nFirstPage,long nLastPage, long nPSLevel, long bBinaryOk, long bShrinkToFit, long bReverse, long bFarEastFontOpt, long bEmitHalftones, long iPageOption);
```

Parameters

nFirstPage	The first page to be printed. The first page in a PDDoc object is page 0.
nLastPage	The last page to be printed.
nPSLevel	If 2, PostScript Level 2 operators are used. If 3, PostScript Language Level 3 operators are also used.
bBinaryOk	If a positive number, binary data may be included in the PostScript program. If 0, all data is encoded as 7-bit ASCII.
bShrinkToFit	If a positive number, the page is shrunk (if necessary) to fit within the imageable area of the printed page. If 0, it is not.
bReverse	(PostScript printing only) If a positive number, print the pages in reverse order. If false, print the pages in the regular order.
bFarEastFontOpt	(PostScript printing only) Set to a positive number if the destination printer has multibyte fonts; set to 0 otherwise.
bEmitHalftones	(PostScript printing only) If a positive number, emit the halftones specified in the document. If 0, do not.
iPageOption	Pages in the range to print. Must be one of: PDAllPages, PDEvenPagesOnly, or PDOddPagesOnly.

Returns

0 if there were any exceptions while printing or if no document was open, -1 otherwise.

Related methods

AVDoc. PrintPages

AVDoc. PrintPagesSilent

AVDoc.PrintPagesSilentEx

PrintPagesSilent

Prints a specified range of pages without displaying any dialog box. This method is identical to AVDoc. PrintPages except for not displaying the dialog box. PrintPagesSilent always uses the default printer setting.

Syntax

Parameters

nFirstPage	The first page to be printed. The first page in a PDDoc object is page 0.
nLastPage	The last page to be printed.
nPSLevel	If 2, PostScript Level 2 operators are used. If 3, PostScript Language Level 3 operators are also used.
bBinaryOk	If a positive number, binary data may be included in the PostScript program. If 0, all data is encoded as 7-bit ASCII.
bShrinkToFit	If a positive number, the page is shrunk (if necessary) to fit within the imageable area of the printed page. If \circ , it is not.

Returns

0 if there were any exceptions while printing or if no document was open, -1 otherwise.

Related methods

AVDoc. PrintPages

AVDoc.PrintPagesEx

AVDoc. PrintPagesSilentEx

PrintPagesSilentEx

Prints a specified range of pages without displaying any dialog box. This method is identical to AVDoc. PrintPagesEx except for not displaying the dialog box. PrintPagesSilentEx has more parameters than PrintPagesSilent. PrintPagesSilentEx always uses the default printer setting.

Syntax

```
VARIANT_BOOL PrintPagesSilentEx(long nFirstPage,
long nLastPage,
long nPSLevel, long bBinaryOk,
long bShrinkToFit, long bReverse,
long bFarEastFontOpt,
long bEmitHalftones,
long iPageOption);
```

Parameters

nFirstPage	The first page to be printed.
nLastPage	The last page to be printed.
nPSLevel	If 2, PostScript Level 2 operators are used. If 3, PostScript Language Level 3 operators are also used.

If a positive number, binary data may be included in the PostScript program. If 0, all data is encoded as 7-bit ASCII.
If a positive number, the page is shrunk (if necessary) to fit within the imageable area of the printed page. If 0, it is not.
(PostScript printing only) If a positive number, print the pages in reverse order. If false, print the pages in the regular order.
(PostScript printing only) Set to a positive number if the destination printer has multibyte fonts; set to 0 otherwise.
(PostScript printing only) If a positive number, emit the halftones specified in the document. If 0, do not.
Pages in the range to print. Must be one of: PDAllPages, PDEvenPagesOnly, or PDOddPagesOnly.

0 if there were any exceptions while printing, -1 otherwise.

Related methods

AVDoc. PrintPages

AVDoc. PrintPagesEx

AVDoc. PrintPagesSilentEx

SetFrame

Sets the window's size and location.

Syntax

VARIANT BOOL SetFrame(LPDISPATCH iAcroRect);

Parameters

iAcroRect	The LPDISPATCH for an AcroExch. Rect specifying the window frame.
	iAcroRect's instance variable m_lpDispatch contains this LPDISPATCH.

Returns

Always returns -1.

Related methods

AVDoc. GetFrame

SetTextSelection

Sets the document's selection to the specified text selection. Before calling this method, use one of the following to create the text selection:

PDDoc. <u>CreateTextSelect</u> — Creates from a rectangle.

PDPage. <u>CreatePageHilite</u> — Creates from a list of character offsets and counts.

PDPage. <u>CreateWordHilite</u> — Creates from a list of word offsets and counts.

After calling this method, use AVDoc.ShowTextSelect to show the selection.

Syntax

VARIANT BOOL SetTextSelection(LPDISPATCH iAcroPDTextSelect);

Parameters

iAcroPDTextSelect	The LPDISPATCH for the text selection to use. iAcroPDTextSelect contains the instance variable m_lpDispatch, which contains the LPDISPATCH.
-------------------	---

Returns

Returns -1 if successful. Returns 0 if no document is open or the LPDISPATCH is not a PDTextSelect object.

Related methods

AVDoc. ClearSelection

AVDoc. ShowTextSelect

PDDoc. CreateTextSelect

PDPage. CreatePageHilite

PDPage. CreateWordHilite

PDTextSelect. Destroy

PDTextSelect. GetBoundingRect

PDTextSelect. GetNumText

PDTextSelect. GetPage

PDTextSelect. GetText

SetTitle

Sets the window's title.

Syntax

```
VARIANT BOOL SetTitle (BSTR szTitle);
```

Parameters

The title to be set. This method cannot be used for document windows, but only for windows created by plug-ins.

Returns

Returns 0 if no document is open, -1 otherwise.

Related methods

AVDoc. GetTitle

AVDoc. Open

PDDoc. OpenAVDoc

SetViewMode

Sets the mode in which the document will be viewed (pages only, pages and thumbnails, or pages and bookmarks).

Syntax

```
VARIANT_BOOL SetViewMode(long nType);
```

Parameters

nType The view mode to be set. Possible values:

PDDontCare: 0 — leave the view mode as it is

 ${\tt PDUseNone: 1-- display\ without\ bookmarks\ or\ thumbnails}$

 ${\tt PDUseThumbs: 2-display using thumbnails}$

PDUseBookmarks: 3 — display using bookmarks

Note: Do not set the view mode to Close with AVDoc.SetViewMode when using AVDoc.OpenInWindowEx; this will cause the viewer and application to hang.

Returns

0 if an error occurred while setting the view mode or if no document was open, -1 otherwise.

Related methods

AVDoc.<u>GetAVPageView</u>
AVDoc.<u>GetViewMode</u>

ShowTextSelect

Changes the view so that the current text selection is visible.

Syntax

```
VARIANT_BOOL ShowTextSelect();
```

Returns

Returns 0 if no document is open, -1 otherwise.

Related methods

AVDoc. ClearSelection

AVDoc. SetTextSelection

PDDoc. CreateTextSelect

PDPage. CreatePageHilite

PDPage. CreateWordHilite

PDTextSelect. Destroy

PDTextSelect. GetBoundingRect

PDTextSelect. GetNumText

PDTextSelect. GetPage

PDTextSelect. GetText

AcroExch.AVPageView

The area of the Acrobat application's window that displays the contents of a document's page. This is a non-creatable interface. Every AVDoc object has an AVPageView object and vice versa. The object provides access to the PDDoc and PDPage objects for the document being displayed.

Methods

The AVPageView object has the following methods.

Method	Description
<u>DevicePointToPage</u>	Converts the coordinates of a point from device space to user space.
DoGoBack	Goes to the previous view on the view history stack, if any.
DoGoForward	Goes to the next view on the view history stack, if any.
GetAperture	Gets the aperture of the specified page view.
GetAVDoc	Gets the AcroExch. AVDoc associated with the current page.
GetDoc	Gets the AcroExch. PDDoc corresponding to the current page.
GetPage	Gets the AcroExch. PDPage corresponding to the current page.
GetPageNum	Gets the page number of the current page.
GetZoom	Gets the current zoom factor, specified as a percent.
GetZoomType	Gets the current zoom type.
Goto	Goes to the specified page.
PointToDevice	Deprecated. Converts the coordinates of a point from user space to device space.
<u>ReadPageDown</u>	Scrolls forward through the document by one screen area.
ReadPageUp	Scrolls backward through the document by one screen area.
ScrollTo	Scrolls to the specified location on the current page.
ZoomTo	Zooms to the specified magnification.

DevicePointToPage

Converts the coordinates of a point from device space to user space.

Syntax

LPDISPATCH DevicePointToPage(LPDISPATCH iAcroPoint);

Parameters

iAcroPoint	The LPDISPATCH for the AcroExch. Point whose coordinates are converted. iAcroPoint contains the instance variable m_lpDispatch, which contains
	the LPDISPATCH.

Returns

The LPDISPATCH for an AcroExch. Point containing the converted coordinates.

Related methods

AVPageView.PointToDevice

DoGoBack

Goes to the previous view on the view history stack, if any.

Syntax

```
VARIANT_BOOL DoGoBack();
```

Returns

Always returns -1.

Related methods

AVPageView. DoGoForward

DoGoForward

Goes to the next view on the view history stack, if any.

Syntax

```
VARIANT_BOOL DoGoForward();
```

Returns

Always returns -1.

Related methods

AVPageView.DoGoBack

GetAperture

Gets the aperture of the specified page view. The aperture is the rectangular region of the window in which the document is drawn, measured in device space units.

Syntax

```
CAcroRect* GetAperture();
```

Returns

A pointer to the aperture rectangle. Its coordinates are specified in device space.

Related methods

```
AVDoc. <a href="mailto:GetAVPageView">GetAVPageView</a>
AVPageView. <a href="GetAVDoc">GetAVDoc</a>
AVPageView. <a href="GetDoc">GetDoc</a>
AVPageView.GetPage
AVPageView.GetZoomType
```

GetAVDoc

Gets the AcroExch. AVDoc associated with the current page.

Syntax

```
LPDISPATCH GetAVDoc();
```

Returns

The LPDISPATCH for the AcroExch. AVDoc.

Related methods

```
AVDoc.GetAVPageView
AVDoc.GetPDDoc
AVPageView.GetDoc
```

GetDoc

Gets the AcroExch. PDDoc corresponding to the current page.

```
LPDISPATCH GetDoc();
```

The LPDISPATCH for the AcroExch.PDDoc.

Related methods

```
AVDoc. GetAVPageView

AVDoc. GetPDDoc

AVPageView. GetAVDoc
```

GetPage

Gets the AcroExch. PDPage corresponding to the current page.

Syntax

```
LPDISPATCH GetPage();
```

Returns

The LPDISPATCH for the AcroExch. PDPage.

Related methods

```
AVPageView. GetPageNum

PDDoc. AcquirePage

PDDoc. GetNumPages

PDPage. GetDoc

PDPage. GetNumber

PDPage. GetRotate

PDPage. GetSize

PDTextSelect. GetPage
```

GetPageNum

Gets the page number of the current page. The first page in a document is page zero.

```
long GetPageNum();
```

The current page's page number.

Related methods

```
AVPageView. GetPage

PDDoc. AcquirePage

PDDoc. GetNumPages

PDPage. GetDoc

PDPage. GetNumber

PDPage. GetRotate

PDPage. GetSize

PDTextSelect. GetPage
```

GetZoom

Gets the current zoom factor, specified as a percent. For example, 100 is returned if the magnification is 1.0

Syntax

```
long GetZoom();
```

Returns

The current zoom factor.

Related methods

```
App. <a href="Mailto:GetPreference">GetPreference</a>
AVPageView. <a href="Mailto:GetZoomType">GetZoomType</a>
AVPageView. <a href="Mailto:ZoomTo">ZoomTo</a>
```

GetZoomType

Gets the current zoom type.

```
short GetZoomType();
```

```
Zoom type. The value is one of the following:
```

```
AVZoomFitHeight — Fits the page's height in the window.
```

AVZoomFitPage — Fits the page in the window.

AVZoomFitVisibleWidth — Fits the page's visible content into the window.

AVZoomFitWidth — Fits the page's width into the window.

AVZoomNoVary — A fixed zoom, such as 100%.

Related methods

```
App. GetPreference
```

AVPageView. GetZoomType

AVPageView.ZoomTo

Goto

Goes to the specified page.

Syntax

```
VARIANT BOOL GoTo(long nPage);
```

Parameters

nPage

Page number of the destination page. The first page in a PDDoc object is page 0.

Returns

−1 if the Acrobat application successfully went to the page, 0 otherwise.

Related methods

AVPageView.DoGoBack

AVPageView. DoGoForward

AVPageView.ReadPageDown

AVPageView.ReadPageUp

AVPageView.<u>ScrollTo</u>

AVPageView.ZoomTo

PointToDevice

Converts the coordinates of a point from user space to device space.

Note: Deprecated. Do not use this method.

Syntax

LPDISPATCH PointToDevice(LPDISPATCH iAcroPoint);

Parameters

iAcroPoint contains the instance variable ${\tt m_lpDispatch}$, which contains this LPDISPATCH.	iAcroPoint	The LPDISPATCH for the AcroExch. Point whose coordinates are converted. iAcroPoint contains the instance variable m_lpDispatch, which contains this LPDISPATCH.
---	------------	---

Returns

The LPDISPATCH for an AcroExch. Point containing the converted coordinates.

Related methods

AVPageView.DevicePointToPage

ReadPageDown

Scrolls forward through the document by one screen area.

Syntax

```
VARIANT_BOOL ReadPageDown();
```

Returns

Always returns -1.

Related methods

```
AVPageView. <a href="DoGoBack">DoGoBack</a>
```

AVPageView.DoGoForward

AVPageView.Goto

AVPageView.ReadPageUp

AVPageView.ScrollTo

AVPageView.ZoomTo

ReadPageUp

Scrolls backward through the document by one screen area.

Syntax

```
VARIANT_BOOL ReadPageUp();
```

Returns

Always returns -1.

Related methods

```
AVPageView. DoGoBack

AVPageView. DoGoForward

AVPageView. Goto

AVPageView. ReadPageDown

AVPageView. ScrollTo

AVPageView. ZoomTo
```

ScrollTo

Scrolls to the specified location on the current page.

Syntax

```
VARIANT BOOL ScrollTo(short nX, short nY);
```

Parameters

nX	The x-coordinate of the destination.
nY	The y-coordinate of the destination.

Returns

-1 if the Acrobat application successfully scrolled to the specified location, 0 otherwise.

Related methods

```
AVPageView. <u>DoGoBack</u>

AVPageView. <u>DoGoForward</u>

AVPageView. <u>Goto</u>
```

AVPageView.ReadPageDown

AVPageView.ReadPageUp

AVPageView.ZoomTo

ZoomTo

Zooms to the specified magnification.

Syntax

VARIANT_BOOL ZoomTo(short nType, short nScale);

Parameters

nType	Zoom type. Possible values are:
	AVZoomFitHeight — Fits the page's height into the window.
	AVZoomFitPage — Fits the page into the window.
	AVZoomFitVisibleWidth — Fits the page's visible content into the window.
	AVZoomFitWidth — Fits the page's width into the window.
	AVZoomNoVary — A fixed zoom, such as 100%.
nScale	The desired zoom factor, expressed as a percentage. For example, 100 is a magnification of 1.0.

Returns

-1 if the magnification was set successfully, 0 otherwise.

Related methods

AVPageView. GetZoomType
AVPageView. Goto

AVPageView.ScrollTo

AcroExch.HiliteList

A highlighted region of text in a PDF document, which may include one or more contiguous groups of characters or words on a single page. This is a creatable interface. This object has a single method, Add, and is used by the PDPage object to create PDTextSelect objects.

Add

Adds the highlight specified by nOffset and nLength to the current highlight list. Highlight lists are used to highlight one or more contiguous groups of characters or words on a single page.

Highlight lists are used both for character-based and word-based highlighting, although a single highlight list cannot contain a mixture of character and word highlights. After creating a highlight list, use PDPage. CreatePageHilite or PDPage. CreateWordHilite (depending on whether the highlight list is used for characters or words) to create a text selection from the highlight list.

Syntax

VARIANT BOOL Add(short nOffset, short nLength);

Parameters

nOffset	Offset of the first word or character to be highlighted, the first of which has an offset of zero.
nLength	The number of consecutive words or characters to be highlighted.

Returns

Always returns -1.

Related methods

PDPage. CreatePageHilite

PDPage. CreateWordHilite

AcroExch.PDAnnot

An annotation on a page in a PDF file. This is a non-creatable interface. Acrobat applications have two built-in annotation types: PDTextAnnot and PDLinkAnnot. The object provides access to the physical attributes of the annotation. Plug-ins may add movie and Widget (form field) annotations, and developers can define new annotation subtypes by creating new annotation handlers.

Methods

The PDAnnot object has the following methods.

Method	Description
GetColor	Gets an annotation's color.
GetContents	Gets a text annotation's contents.
<u>GetDate</u>	Gets an annotation's date.
GetRect	Gets an annotation's bounding rectangle.
GetSubtype	Gets an annotation's subtype.
<u>GetTitle</u>	Gets a text annotation's title.
<u>IsEqual</u>	Determines whether an annotation is the same as the specified annotation.
<u>IsOpen</u>	Tests whether a text annotation is open.
IsValid	Tests whether an annotation is still valid.
Perform	Performs a link annotation's action.
SetColor	Sets an annotation's color.
SetContents	Sets a text annotation's contents.
<u>SetDate</u>	Sets an annotation's date.
SetOpen	Opens or closes a text annotation.
SetRect	Sets an annotation's bounding rectangle.
<u>SetTitle</u>	Sets a text annotation's title.

GetColor

Gets an annotation's color.

Syntax

long GetColor();

Returns

The annotation's color, a long value of the form 0x00BBGGRR where the first byte from the right (RR) is a relative value for red, the second byte (GG) is a relative value for green, and the third byte (BB) is a relative value for blue. The high-order byte must be 0.

Related methods

PDAnnot.<u>SetColor</u>

GetContents

Gets a text annotation's contents.

Syntax

```
BSTR GetContents();
```

Returns

The annotation's contents.

Related methods

```
PDAnnot. SetContents

PDAnnot. GetDate

PDAnnot. GetRect

PDAnnot. GetSubtype

PDAnnot. GetTitle
```

GetDate

Gets an annotation's date.

Syntax

```
LPDISPATCH GetDate();
```

Returns

The LPDISPATCH for an AcroExch. Time object containing the date.

Related methods

```
PDAnnot. GetContents

PDAnnot. GetRect

PDAnnot. GetSubtype

PDAnnot. GetTitle

PDAnnot. SetDate
```

GetRect

Gets an annotation's bounding rectangle.

Syntax

```
LPDISPATCH GetRect();
```

Returns

The LPDISPATCH for an AcroExch. Rect containing the annotation's bounding rectangle.

Related methods

```
PDAnnot.GetContents
PDAnnot.GetDate
PDAnnot. GetSubtype
PDAnnot.GetTitle
PDAnnot. SetRect
```

GetSubtype

Gets an annotation's subtype.

Syntax

```
BSTR GetSubtype();
```

Returns

The annotation's subtype. The built-in subtypes are Text and Link.

Related methods

```
PDAnnot. GetContents
PDAnnot. GetDate
PDAnnot. GetRect
PDAnnot.GetTitle
```

GetTitle

Gets a text annotation's title.

```
BSTR GetTitle();
```

The annotation's title.

Related methods

```
PDAnnot.GetContents

PDAnnot.GetDate

PDAnnot.GetRect

PDAnnot.GetSubtype

PDAnnot.SetTitle
```

IsEqual

Determines whether an annotation is the same as the specified annotation.

Syntax

```
VARIANT BOOL IsEqual (LPDISPATCH PDAnnot);
```

Parameters

PDAnnot	The LPDISPATCH for the AcroExch. PDAnnot to be tested. PDAnnot contains
	the instance variable ${\tt m_lpDispatch}$, which contains the LPDISPATCH.

Returns

-1 if the annotations are the same, 0 otherwise.

Related methods

```
PDAnnot.GetContents

PDAnnot.GetDate

PDAnnot.GetRect

PDAnnot.GetSubtype

PDAnnot.GetTitle

PDAnnot.IsOpen

PDAnnot.IsValid
```

IsOpen

Tests whether a text annotation is open.

Syntax

```
VARIANT BOOL IsOpen();
```

Returns

-1 if open, 0 otherwise.

Related methods

```
PDAnnot. GetContents

PDAnnot. GetDate

PDAnnot. GetRect

PDAnnot. GetSubtype

PDAnnot. GetTitle

PDAnnot. IsEqual

PDAnnot. IsValid

PDAnnot. SetOpen
```

IsValid

Tests whether an annotation is still valid. This method is intended only to test whether the annotation has been deleted, not whether it is a completely valid annotation object.

Syntax

```
VARIANT BOOL IsValid();
```

Returns

-1 if the annotation is valid, 0 otherwise.

Related methods

```
PDAnnot. GetContents

PDAnnot. GetDate

PDAnnot. GetRect

PDAnnot. GetSubtype

PDAnnot. GetTitle

PDAnnot. IsEqual

PDAnnot. IsOpen
```

Perform

Performs a link annotation's action.

Syntax

VARIANT BOOL Perform(LPDISPATCH iAcroAVDoc);

Parameters

iAcroAVDoc	The LPDISPATCH for the AcroExch. AVDoc in which the annotation is located.
	<pre>iAcroAVDoc contains the instance variable m_lpDispatch, which contains</pre>
	the LPDISPATCH.

Returns

-1 if the action was executed successfully, 0 otherwise.

Related methods

PDAnnot. Is Valid

SetColor

Sets an annotation's color.

Syntax

VARIANT BOOL SetColor(long nRGBColor);

Parameters

nRGBColor	The color to use for the annotation.	

Returns

-1 if the annotation's color was set, 0 if the Acrobat application does not support editing.

nRGBColor is a long value with the form 0x00BBGGRR where the first byte from the right (RR) is a relative value for red, the second byte (GG) is a relative value for green, and the third byte (BB) is a relative value for blue. The high-order byte must be 0.

Related methods

PDAnnot. GetColor

PDAnnot. <u>SetContents</u>

PDAnnot.<u>SetDate</u>

PDAnnot.<u>SetOpen</u>
PDAnnot.<u>SetRect</u>
PDAnnot.SetTitle

SetContents

Sets a text annotation's contents.

Syntax

VARIANT BOOL SetContents (BSTR szContents);

Parameters

szContents

The contents to use for the annotation.

Returns

0 if the Acrobat application does not support editing, -1 otherwise.

Related methods

PDAnnot. GetContents

PDAnnot.<u>SetColor</u>

PDAnnot.<u>SetDate</u>

PDAnnot. SetOpen

PDAnnot. SetRect

PDAnnot. <u>SetTitle</u>

SetDate

Sets an annotation's date.

Syntax

VARIANT_BOOL SetDate(LPDISPATCH iAcroTime);

Parameters

iAcroTime The LPDISPATCH for the date and time to use for the annotation.
iAcroTime's instance variable m lpDispatch contains this LPDISPATCH.

-1 if the date was set, 0 if the Acrobat application does not support editing.

Related methods

```
PDAnnot. GetTitle

PDAnnot. SetColor

PDAnnot. SetContents

PDAnnot. SetOpen

PDAnnot. SetRect

PDAnnot. SetTitle
```

SetOpen

Opens or closes a text annotation.

Syntax

```
VARIANT BOOL SetOpen(long bIsOpen);
```

Parameters

bIsOpen

If a positive number, the annotation is open. If 0, the annotation is closed.

Returns

Always returns -1.

Related methods

```
PDAnnot. IsOpen

PDAnnot. SetColor

PDAnnot. SetContents

PDAnnot. SetDate

PDAnnot. SetRect

PDAnnot. SetTitle
```

SetRect

Sets an annotation's bounding rectangle.

Syntax

VARIANT BOOL SetRect (LPDISPATCH iAcroRect);

Parameters

iA	e LPDISPATCH for the bounding rectangle (AcroExch.Rect) to set. croRect contains the instance variable m_lpDispatch, which contains the DISPATCH.
----	---

Returns

-1 if a rectangle was supplied, 0 otherwise.

Related methods

```
{\tt PDAnnot.} \underline{{\tt GetRect}}
```

PDAnnot.<u>SetColor</u>

PDAnnot.SetContents

PDAnnot. SetDate

PDAnnot.SetOpen

PDAnnot.SetTitle

SetTitle

Sets a text annotation's title.

Syntax

```
VARIANT_BOOL SetTitle(BSTR szTitle);
```

Parameters

Returns

-1 if the title was set, 0 if the Acrobat application does not support editing.

Related methods

PDAnnot. GetByTitle

PDAnnot.<u>SetColor</u>

PDAnnot. <u>SetContents</u>

PDAnnot.SetDate

PDAnnot. SetOpen

PDAnnot.SetRect

AcroExch.PDBookmark

A bookmark for a page in a PDF file. This is a creatable interface. Each bookmark has a title that appears on screen, and an action that specifies what happens when a user clicks on the bookmark.

Bookmarks can either be created interactively by the user through the Acrobat application's user interface or programmatically generated. The typical action for a user-created bookmark is to move to another location in the current document, although any action can be specified. It is not possible to create a bookmark with OLE—only to destroy one.

Methods

The PDBookmark object has the following methods.

Method	Description
Destroy	Destroys a bookmark.
<u>GetByTitle</u>	Gets the bookmark that has the specified title.
<u>GetTitle</u>	Gets a bookmark's title.
<u>IsValid</u>	Determines whether the bookmark is valid.
Perform	Performs a bookmark's action.
<u>SetTitle</u>	Sets a bookmark's title.

Destroy

Destroys a bookmark.

Syntax

VARIANT_BOOL Destroy();

Returns

0 if the Acrobat application does not support editing (making it impossible to delete the bookmark), -1 otherwise.

Related methods

PDBookmark. IsValid

GetByTitle

Gets the bookmark that has the specified title. The AcroExch. PDBookmark object is set to the specified bookmark as a side effect of the method; it is not the method's return value. You cannot enumerate bookmark titles with this method.

Syntax

Parameters

iAcroPDDoc	The LPDISPATCH for the document (AcroExch.PDDoc object) containing the bookmark. iAcroPDDoc contains the instance variable m_lpDispatch, which contains the LPDISPATCH.
bookmarkTitle	The title of the bookmark to get. The capitalization of the title must match that in the bookmark.

Returns

-1 if the specified bookmark exists (the method determines this using the PDBookmark. IsValid method), 0 otherwise.

Related methods

```
PDBookmark. GetTitle
PDBookmark. SetTitle
```

Example

```
CAcroPDBookmark* bookmark = new CAcroPDBookmark;
bookmark->CreateDispatch("AcroExch.PDBookmark");
bookmark->GetByTitle(m_pAcroAVDoc->GetPDDoc(), "Name of Bookmark");
if (bookmark->IsValid())
   bookmark->Perform(m_pAcroAVDoc->m_lpDispatch);
else
   AfxMessageBox("Bookmark not valid");
```

GetTitle

Gets a bookmark's title.

```
BSTR GetTitle();
```

The title.

Related methods

```
PDBookmark. <u>GetByTitle</u>
PDBookmark. <u>SetTitle</u>
```

IsValid

Determines whether the bookmark is valid. This method only checks whether the bookmark has been deleted; it does not thoroughly check the bookmark's data structures.

Syntax

```
VARIANT BOOL IsValid();
```

Returns

-1 if the bookmark is valid, 0 otherwise.

Related methods

```
PDBookmark. <a href="Destroy">Destroy</a>
```

Syntax

Perform

Performs a bookmark's action.

Syntax

```
VARIANT_BOOL Perform(LPDISPATCH iAcroAVDoc);
```

Parameters

iAcroAVDoc	The LPDISPATCH for the AcroExch. AVDoc in which the bookmark is located.
	<pre>iAcroAVDoc contains the instance variable m_lpDispatch, which contains</pre>
	the LPDISPATCH.

Returns

-1 if the action was executed successfully, 0 otherwise.

Related methods

PDBookmark. Is Valid

SetTitle

Sets a bookmark's title.

Syntax

VARIANT BOOL SetTitle (BSTR szNewTitle);

Parameters

szNewTitle	The title to set.		

Returns

0 if the Acrobat application does not support editing, -1 otherwise.

Related methods

PDBookmark. GetByTitle

PDBookmark.GetTitle

AcroExch.PDDoc

The underlying PDF representation of a document. This is a creatable interface. There is a correspondence between a PDDoc object and an ASFile object (an opaque representation of an open file made available through an interface encapsulating Acrobat's access to file services), and the PDDoc object is the hidden object behind every AVDoc object. An ASFile object may have zero or more underlying files, so a PDF file does not always correspond to a single disk file. For example, an ASFile object may provide access to PDF data in a database.

Through PDDoc objects, your application can perform most of the Document menu items from Acrobat (delete pages, replace pages, and so on), create and delete thumbnails, and set and retrieve document information fields.

Methods

The PDDoc object has the following methods.

Method	Description
<u>AcquirePage</u>	Acquires the specified page.
ClearFlags	Clears a document's flags.
Close	Closes a file.

Method	Description	
Create	Creates a new AcroExch. PDDoc.	
CreateTextSelect	Creates a text selection from the specified rectangle on the specified page.	
CreateThumbs	Creates thumbnail images for the specified page range in a document.	
CropPages	Crops the pages in a specified range in a document.	
<u>DeletePages</u>	Deletes pages from a file.	
<u>DeleteThumbs</u>	Deletes thumbnail images from the specified pages in a document.	
<u>GetFileName</u>	Gets the name of the file associated with this AcroExch. PDDoc.	
<u>GetFlags</u>	Gets a document's flags.	
<u>GetInfo</u>	Gets the value of a specified key in the document's Info dictionary.	
GetInstanceID	Gets the instance ID (the second element) from the ID array in the document's trailer.	
<u>GetJSObject</u>	Gets a dual interface to the JavaScript object associated with the PDDoc.	
GetNumPages	Gets the number of pages in a file.	
<u>GetPageMode</u>	Gets a value indicating whether the Acrobat application is currently displaying only pages, pages and thumbnails, or pages and bookmarks.	
<u>GetPermanentID</u>	Gets the permanent ID (the first element) from the ID array in the document's trailer.	
<u>InsertPages</u>	Inserts the specified pages from the source document after the indicated page within the current document.	
MovePage	Moves a page to another location within the same document.	
<u>Open</u>	Opens a file.	
OpenAVDoc	Opens a window and displays the document in it.	
ReplacePages	Replaces the indicated pages in the current document with those specified from the source document.	
Save	Saves a document.	
<u>SetFlags</u>	Sets a document's flags indicating whether the document has been modified, whether the document is a temporary document and should be deleted when closed, and the version of PDF used in the file.	
SetInfo	Sets the value of a key in a document's Info dictionary.	
<u>SetPageMode</u>	Sets the page mode in which a document is to be opened: display only pages, pages and thumbnails, or pages and bookmarks.	

AcquirePage

Acquires the specified page.

Syntax

LPDISPATCH AcquirePage(long nPage);

Parameters

nPage

The number of the page to acquire. The first page is page 0.

Returns

The LPDISPATCH for the AcroExch. PDPage object for the acquired page. Returns NULL if the page could not be acquired.

Related methods

```
AVPageView. GetPage
```

AVPageView. GetPageNum

PDDoc. GetNumPages

PDPage. GetDoc

PDPage.<u>GetNumber</u>

PDPage. GetRotate

PDPage. GetSize

PDTextSelect. GetPage

ClearFlags

Clears a document's flags. The flags indicate whether the document has been modified, whether the document is a temporary document and should be deleted when closed, and the version of PDF used in the file. This method can be used only to clear, not to set, the flag bits.

Syntax

```
VARIANT BOOL ClearFlags(long nFlags);
```

Parameters

nFlags	Flags to be cleared. See PDDoc. GetFlags for a description of the flags. The flags
	PDDocWasRepaired, PDDocNewMajorVersion, PDDocNewMinorVersion, and
	PDDocOldVersion are read-only and cannot be cleared.

Always returns -1.

Related methods

PDDoc.GetFlags
PDDoc.SetFlags

Close

Closes a file.

Note: If PDDoc and AVDoc are constructed with the same file, PDDoc.Close destroys both objects (which closes the document in the viewer).

Syntax

```
VARIANT BOOL Close();
```

Returns

-1 if the document was closed successfully, 0 otherwise.

Related methods

```
App.CloseAllDocs

AVDoc.Close

AVDoc.Open

AVDoc.OpenInWindow

AVDoc.OpenInWindowEx

PDDoc.Open

PDDoc.OpenAVDoc
```

Create

Creates a new AcroExch. PDDoc.

```
VARIANT BOOL Create();
```

-1 if the document is created successfully, 0 if it is not or if the Acrobat application does not support editing.

CreateTextSelect

Creates a text selection from the specified rectangle on the specified page. After creating the text selection, use the AVDoc. <u>SetTextSelection</u> method to use it as the document's selection, and use AVDoc. <u>ShowTextSelect</u> to show the selection.

Syntax

LPDISPATCH CreateTextSelect(long nPage, LPDISPATCH iAcroRect);

Parameters

nPage	The page on which the selection is created. The first page in a PDDoc object is page 0.
iAcroRect	The LPDISPATCH for the AcroExch.Rect enclosing the region to select. iAcroRect contains the instance variable m_lpDispatch, which contains the LPDISPATCH.

Returns

The LPDISPATCH for an AcroExch. PDTextSelect containing the text selection. Returns NULL if the text selection was not created successfully.

Related methods

AVDoc. ClearSelection

AVDoc.SetTextSelection

AVDoc.ShowTextSelect

PDPage.CreatePageHilite

PDPage.CreateWordHilite

PDTextSelect.Destroy

 ${\tt PDTextSelect.} \underline{{\tt GetBoundingRect}}$

PDTextSelect. GetNumText

PDTextSelect. GetPage

PDTextSelect.GetText

CreateThumbs

Creates thumbnail images for the specified page range in a document.

Syntax

VARIANT BOOL CreateThumbs(long nFirstPage, long nLastPage);

Parameters

nFirstPage	First page for which thumbnail images are created. The first page in a PDDoc object is page 0.
nLastPage	Last page for which thumbnail images are created.

Returns

-1 if thumbnail images were created successfully, 0 if they were not or if the Acrobat application does not support editing.

Related methods

PDDoc. DeleteThumbs

CropPages

Crops the pages in a specified range in a document. This method ignores the request if either the width or height of the crop box is less than 72 points (one inch).

Syntax

Parameters

nStartPage	First page that is cropped. The first page in a PDDoc object is page 0.
nEndPage	Last page that is cropped.
nEvenOrOddPagesOnly	Value indicating which pages in the range are cropped. Must be one of the following:
	0 — crop all pages in the range
	1 — crop only odd pages in the range
	2 — crop only even pages in the range
iAcroRect	An LPDISPATCH for a CAcroRect specifying the cropping rectangle, which is specified in user space.

-1 if the pages were cropped successfully, 0 otherwise.

Related methods

```
PDPage. CropPages
```

DeletePages

Deletes pages from a file.

Syntax

```
VARIANT BOOL DeletePages (long nStartPage, long nEndPage);
```

Parameters

nStartPage	The first page to be deleted. The first page in a PDDoc object is page 0.
nEndPage	The last page to be deleted.

Returns

-1 if the pages were successfully deleted. Returns 0 if they were not or if the Acrobat application does not support editing.

Related methods

PDDoc.<u>AcquirePage</u>

PDDoc. DeletePages

PDDoc. GetNumPages

PDDoc.<u>InsertPages</u>

PDDoc. MovePage

PDDoc. ReplacePages

DeleteThumbs

Deletes thumbnail images from the specified pages in a document.

Syntax

```
VARIANT BOOL DeleteThumbs(long nStartPage, long nEndPage);
```

nStartPage	First page whose thumbnail image is deleted. The first page in a PDDoc object is page 0.
nEndPage	Last page whose thumbnail image is deleted.

Returns

-1 if the thumbnails were deleted, 0 if they were not deleted or if the Acrobat application does not support editing.

Related methods

PDDoc.<u>CreateThumbs</u>

GetFileName

Gets the name of the file associated with this AcroExch. PDDoc.

Syntax

```
BSTR GetFileName();
```

Returns

The file name, which can currently contain up to 256 characters.

Related methods

PDDoc. Save

GetFlags

Gets a document's flags. The flags indicate whether the document has been modified, whether the document is a temporary document and should be deleted when closed, and the version of PDF used in the file.

Syntax

long GetFlags();

Returns

The document's flags, containing an OR of the following:

Flag	Description
PDDocNeedsSave	Document has been modified and needs to be saved.

PDDocRequiresFullSave	Document cannot be saved incrementally; it must be written using PDSaveFull.
PDDocIsModified	Document has been modified slightly (such as bookmarks or text annotations have been opened or closed), but not in a way that warrants saving.
PDDocDeleteOnClose	Document is based on a temporary file that must be deleted when the document is closed or saved.
PDDocWasRepaired	Document was repaired when it was opened.
PDDocNewMajorVersion	Document's major version is newer than current.
PDDocNewMinorVersion	Document's minor version is newer than current.
PDDocOldVersion	Document's version is older than current.
PDDocSuppressErrors	Don't display errors.

Related methods

PDDoc.<u>ClearFlags</u>

PDDoc.<u>SetFlags</u>

GetInfo

Gets the value of a specified key in the document's Info dictionary. A maximum of 512 bytes are returned.

Syntax

BSTR GetInfo(BSTR szInfoKey);

Parameters

szInfoKey The key whose value is obtained.
--

Returns

The string if the value was read successfully. Returns an empty string if the key does not exist or its value cannot be read.

Related methods

 ${\tt PDDoc.} \underline{{\tt SetInfo}}$

GetInstanceID

Gets the instance ID (the second element) from the ID array in the document's trailer.

Syntax

```
BSTR GetInstanceID();
```

Returns

A string whose maximum length is 32 characters, containing the document's instance ID.

Related methods

```
PDDoc.GetPermanentID
```

GetJSObject

Gets a dual interface to the JavaScript object associated with the PDDoc. This allows automation clients full access to both built-in and user-defined JavaScript methods available in the document. For more information on working with JavaScript, see *Developing Applications Using Interapplication Communication*.

Syntax

```
LDispatch* GetJSObject();
```

Returns

The interface to the JavaScript object if the call succeeded, NULL otherwise.

GetNumPages

Gets the number of pages in a file.

Syntax

```
long GetNumPages();
```

Returns

The number of pages, or -1 if the number of pages cannot be determined.

Related methods

```
AVPageView. GetPage

AVPageView. GetPageNum

PDDoc. AcquirePage

PDPage. GetNumber

PDTextSelect. GetPage
```

GetPageMode

Gets a value indicating whether the Acrobat application is currently displaying only pages, pages and thumbnails, or pages and bookmarks.

Syntax

```
long GetPageMode();
```

Returns

The current page mode. Will be one of the following values:

```
PDDontCare: 0 — leave the view mode as it is

PDUseNone: 1 — display without bookmarks or thumbnails

PDUseThumbs: 2 — display using thumbnails

PDUseBookmarks: 3 — display using bookmarks

PDFullScreen: 4 — display in full screen mode
```

Related methods

```
PDDoc.<u>SetPageMode</u>
```

GetPermanentID

Gets the permanent ID (the first element) from the ID array in the document's trailer.

Syntax

```
BSTR GetPermanentID();
```

Returns

A string whose maximum length is 32 characters, containing the document's permanent ID.

Related methods

```
PDDoc.<u>GetInstanceID</u>
```

InsertPages

Inserts the specified pages from the source document after the indicated page within the current document.

Syntax

nInsertPageAfter	The page in the current document after which pages from the source document are inserted. The first page in a PDDoc object is page 0.
iPDDocSource	The LPDISPATCH for the AcroExch. PDDoc containing the pages to insert. iPDDocSource contains the instance variable m_lpDispatch, which contains the LPDISPATCH.
nStartPage	The first page in iPDDocSource to be inserted into the current document.
nNumPages	The number of pages to be inserted.
bBookmarks	If a positive number, bookmarks are copied from the source document. If 0, they are not.

Returns

-1 if the pages were successfully inserted. Returns 0 if they were not or if the Acrobat application does not support editing.

Related methods

PDDoc.<u>AcquirePage</u>

PDDoc.DeletePages

PDDoc. GetNumPages

PDDoc.MovePage

PDDoc.ReplacePages

MovePage

Moves a page to another location within the same document.

Syntax

Parameters

nMoveAfterThisPage	The page being moved is placed after this page number. The first page in a PDDoc object is page 0.
nPageToMove	Page number of the page to be moved.

Returns

0 if the Acrobat application does not support editing, -1 otherwise.

Related methods

```
PDDoc. AcquirePage
PDDoc. DeletePages
PDDoc. GetNumPages
PDDoc. InsertPages
PDDoc. ReplacePages
```

Open

Opens a file. A new instance of AcroExch. PDDoc must be created for each open PDF file.

Syntax

```
VARIANT BOOL Open (BSTR szFullPath);
```

Parameters

szFullPath

Full path of the file to be opened.

Returns

-1 if the document was opened successfully, 0 otherwise.

Related methods

```
App.CloseAllDocs

AVDoc.Close

AVDoc.Open

AVDoc.OpenInWindow

AVDoc.OpenInWindowEx

PDDoc.Close

PDDoc.OpenAVDoc
```

OpenAVDoc

Opens a window and displays the document in it.

Syntax

```
LPDISPATCH OpenAVDoc(BSTR szTitle);
```

szTitle	The title to be used for the window. A default title is used if $\mathtt{szTitle}$ is \mathtt{NULL} or
	an empty string.

Returns

The LPDISPATCH for the AcroExch. AVDoc that was opened, or NULL if the open fails.

Related methods

App. CloseAllDocs

AVDoc.Close

AVDoc. GetTitle

AVDoc.<u>Open</u>

AVDoc.OpenInWindow

AVDoc. OpenInWindowEx

AVDoc.SetTitle

PDDoc.Close

PDDoc. Open

ReplacePages

Replaces the indicated pages in the current document with those specified from the source document. No links or bookmarks are copied from iPDDocSource, but text annotations may optionally be copied.

Syntax

nStartPage	The first page within the source file to be replaced. The first page in a PDDoc object is page 0.
iPDDocSource	The LPDISPATCH for the AcroExch. PDDoc containing the new copies of pages that are replaced. iPDDocSource contains the instance variable m_lpDispatch, which contains the LPDISPATCH.
nStartSourcePage	The first page in iPDDocSource to use as a replacement page.
nNumPages	The number of pages to be replaced.
bMergeTextAnnotations	If a positive number, text annotations from iPDDocSource are copied. If 0, they are not.

Returns

-1 if the pages were successfully replaced. Returns 0 if they were not or if the Acrobat application does not support editing.

Related methods

PDDoc.<u>AcquirePage</u>

PDDoc.<u>DeletePages</u>

PDDoc. GetNumPages

PDDoc.<u>InsertPages</u>

PDDoc. MovePage

Save

Saves a document.

Syntax

VARIANT_BOOL Save(short nType, BSTR szFullPath);

nType

Specifies the way in which the file should be saved.

nType is a logical OR of one or more of the following flags:

PDSaveIncremental — Write changes only, not the complete file. This will always result in a larger file, even if objects have been deleted.

PDSaveFull — Write the entire file to the filename specified by szFullPath.

PDSaveCopy — Write a copy of the file into the file specified by szFullPath, but keep using the old file. This flag can only be specified if PDSaveFull is also used.

PDSaveCollectGarbage — Remove unreferenced objects; this often reduces the file size, and its usage is encouraged. This flag can only be specified if PDSaveFull is also used.

PDSaveLinearized — Save the file optimized for the web, providing hint tables. This allows the PDF file to be byte-served. This flag can only be specified if PDSaveFull is also used.

Note: If you save a file optimized for the web using the PDSaveLinearized flag, you must follow this sequence:

- 1. Open the PDF file with PDDoc. Open.
- 2. Call PDDoc. Save using the PDSaveLinearized flag.
- 3. Call PDDoc. Close.

This allows batch optimization of files.

szFullPath

The new path to the file, if any.

Returns

-1 if the document was successfully saved. Returns 0 if it was not or if the Acrobat application does not support editing.

Related methods

PDDoc.GetFileName

SetFlags

Sets a document's flags indicating whether the document has been modified, whether the document is a temporary document and should be deleted when closed, and the version of PDF used in the file. This method can be used only to set, not to clear, the flag bits.

Syntax

VARIANT BOOL SetFlags (long nFlags);

nFlags	Flags to be set. See PDDoc. GetFlags for a description of the flags. The flags
	PDDocWasRepaired, PDDocNewMajorVersion, PDDocNewMinorVersion,
	and PDDocOldVersion are read-only and cannot be set.

Returns

Always returns -1.

Related methods

PDDoc.<u>ClearFlags</u>
PDDoc.GetFlags

SetInfo

Sets the value of a key in a document's Info dictionary.

Syntax

VARIANT BOOL SetInfo(BSTR szInfoKey, BSTR szBuffer);

Parameters

szInfoKey	The key whose value is set.
szBuffer	The value to be assigned to the key.

Returns

-1 if the value was added successfully, 0 if it was not or if the Acrobat application does not support editing.

Related methods

PDDoc. Get Info

SetPageMode

Sets the page mode in which a document is to be opened: display only pages, pages and thumbnails, or pages and bookmarks.

Syntax

VARIANT BOOL SetPageMode(long nPageMode);

nPageMode	The page mode to be set. Possible values:
	PDDontCare: 0 — leave the view mode as it is
	PDUseNone: 1 — display without bookmarks or thumbnails
	PDUseThumbs: 2 — display using thumbnails
	PDUseBookmarks: 3 — display using bookmarks

Returns

Always returns -1.

Related methods

PDDoc.GetPageMode

PDDoc.SetPageMode

AcroExch.PDPage

A single page in the PDF representation of a document. This is a non-creatable interface. Just as PDF files are partially composed of their pages, PDDoc objects are composed of PDPage objects. A page contains a series of objects representing the objects drawn on the page (PDGraphic objects), a list of resources used in drawing the page, annotations (PDAnnot objects), an optional thumbnail image of the page, and the threads used in any articles that occur on the page. The first page in a PDDoc object is page 0.

Methods

The PDPage object has the following methods.

Method	Description
AddAnnot	Adds a specified annotation at a specified location in the page's annotation array
AddNewAnnot	Creates a new text annotation and adds it to the page.
CopyToClipboard	Copies a PDF image to the clipboard without requiring an hwnd or hDC from the client.
<u>CreatePageHilite</u>	Creates a text selection from a list of character offsets and character counts on a single page.
<u>CreateWordHilite</u>	Creates a text selection from a list of word offsets and word counts on a single page.
CropPage	Crops the page.
<u>Draw</u>	Deprecated. Draws page contents into a specified window.

Method	Description
DrawEx	Draws page contents into a specified window.
GetAnnot	Gets the specified annotation from the page's array of annotations.
GetAnnotIndex	Gets the index (within the page's annotation array) of the specified annotation.
GetDoc	Gets the AcroExch. PDDoc associated with the page.
GetNumAnnots	Gets the number of annotations on the page.
GetNumber	Gets the page number of the current page. The first page in a document is page zero.
GetRotate	Gets the rotation value, in degrees, for the current page.
GetSize	Gets a page's width and height in points.
RemoveAnnot	Removes the specified annotation from the page's annotation array.
SetRotate	Sets the rotation, in degrees, for the current page.

AddAnnot

Adds a specified annotation at a specified location in the page's annotation array.

Syntax

Parameters

nIndexAddAfter	Location in the page's annotation array to add the annotation. The first annotation on a page has an index of zero.
iPDAnnot	The LPDISPATCH for the AcroExch. PDAnnot to add. iPDAnnot contains the instance variable m_lpDispatch, which contains the LPDISPATCH.

Returns

0 if the Acrobat application does not support editing, -1 otherwise.

Related methods

PDPage.AddNewAnnot

PDPage. RemoveAnnot

AddNewAnnot

Creates a new text annotation and adds it to the page.

The newly-created text annotation is not complete until PDAnnot . $\underline{\texttt{SetContents}}$ has been called to fill in the /Contents key.

Syntax

```
LPDISPATCH AddNewAnnot(long nIndexAddAfter, BSTR szSubType, LPDISPATCH iAcroRect);
```

Parameters

nIndexAddAfter	Location in the page's annotation array after which to add the annotation. The first annotation on a page has an index of zero.
szSubType	Subtype of the annotation to be created. Must be text.
iAcroRect	The LPDISPATCH for the AcroExch.Rect bounding the annotation's location on the page.iAcroRect contains the instance variable m_lpDispatch, which contains the LPDISPATCH.

Returns

The LPDISPATCH for an AcroExch. PDAnnot object, or NULL if the annotation could not be added.

Related methods

```
PDPage. AddAnnot

PDPage. RemoveAnnot
```

CopyToClipboard

Copies a PDF image to the clipboard without requiring an hwnd or hDC from the client. This method is only available on 32-bit systems.

Syntax

boundRect	The LPDISPATCH for the AcroExch. Rect bounding rectangle in device space coordinates. boundRect contains the instance variable $m_lpDispatch$, which contains the LPDISPATCH.
nXOrigin	The x-coordinate of the portion of the page to be copied.
nYOrigin	The y-coordinate of the portion of the page to be copied.
nZoom	Zoom factor at which the page is copied, specified as a percent. For example, 100 corresponds to a magnification of 1.0.

Returns

-1 if the page is successfully copied, 0 otherwise.

Related methods

PDPage.<u>DrawEx</u>

CreatePageHilite

Creates a text selection from a list of character offsets and character counts on a single page. The text selection can then be set as the current selection using AVDoc. <u>SetTextSelection</u>, and the view can be set to show the selection using AVDoc. <u>ShowTextSelect</u>.

Syntax

LPDISPATCH CreatePageHilite(LPDISPATCH iAcroHiliteList);

Parameters

iAcroHiliteList	The LPDISPATCH for the highlight list for which a text selection is created. iAcroHiliteList contains the instance variable m_lpDispatch, which contains the LPDISPATCH.
	Use HiliteList. Add to create a highlight list.

Returns

The LPDISPATCH for the AcroExch. PDTextSelect containing the text selection, or NULL if the selection could not be created.

Related methods

AVDoc. ClearSelection

AVDoc.SetTextSelection

AVDoc.ShowTextSelect

HiliteList. Add

PDDoc.CreateTextSelect

PDPage.CreateWordHilite

PDTextSelect.Destroy

PDTextSelect.GetBoundingRect

PDTextSelect.GetNumText

PDTextSelect.GetPage

PDTextSelect.GetText

CreateWordHilite

Creates a text selection from a list of word offsets and word counts on a single page. The text selection can then be set as the current selection using AVDoc. <u>SetTextSelection</u>, and the view can be set to show the selection using AVDoc. <u>ShowTextSelect</u>.

Syntax

LPDISPATCH CreateWordHilite(LPDISPATCH iAcroHiliteList);

Parameters

iAcroHiliteList
The LPDISPATCH for the highlight list for which a text selection is created.
iAcroHiliteList contains the instance variable m_lpDispatch, which contains the LPDISPATCH.
Use HiliteList. Add to create a highlight list.

Returns

The LPDISPATCH for the AcroExch. PDTextSelect, or NULL if the selection could not be created.

Related methods

AVDoc.ClearSelection

AVDoc.SetTextSelection

AVDoc.ShowTextSelect

HiliteList.Add

PDDoc.CreateTextSelect

PDPage.CreatePageHilite

PDTextSelect.Destroy

PDTextSelect.GetBoundingRect

PDTextSelect.GetNumText

PDTextSelect.GetPage

PDTextSelect.GetText

CropPage

Crops the page. This method ignores the request if either the width or height of the crop box is less than 72 points (one inch).

Syntax

VARIANT BOOL CropPage (LPDISPATCH iAcroRect);

Parameters

iAcroRect	An LPDISPATCH for a CAcroRect specifying the cropping rectangle, which is specified in user space.
	specified in user space.

Returns

-1 if the page was cropped successfully, 0 otherwise.

Related methods

PDDoc.CropPages

Draw

Note: Deprecated. As of Acrobat 3.0, this method simply returns false. Use the method AVDoc. <u>DrawEx</u> instead.

Syntax

Parameters

window	HWND into which the page is to be drawn.
displayContext	hDC to use for drawing. If NULL, the HDC for window is used.
	${\tt displayContext} \ cannot \ be \ reliably \ used \ as \ the \ {\tt hDC} \ for \ a \ printer \ device. \ In particular, Visual Basic applications cannot use \ {\tt \underline{Draw}} \ to \ print.$
XOrigin	The x-coordinate of the portion of the page to be drawn.
YOrigin	The y–coordinate of the portion of the page to be drawn.
zoom	Zoom factor at which the page is to be drawn, specified as a percent. For example, 100 corresponds to a magnification of 1.0.

Returns

-1 if the page is successfully drawn, 0 otherwise.

Related methods

```
PDPage.<br/>
PDPage.
DrawEx
```

DrawEx

Draws page contents into a specified window.

You can use PDPage. CopyToClipboard to copy page contents to the clipboard without an hWnd or hDC from the client.

Syntax

Parameters

window	Handle for the window (\mathtt{HWND}) into which the page is drawn.
displayContext	This parameter is invalid; do not use it. Assign it a \mathtt{NULL} value. If it is not assigned \mathtt{NULL} , an exception is thrown.
	Note: displayContext cannot be reliably used as the hDC for a printer device. In particular, Visual Basic applications cannot use DrawEx to print.
updateRect	LPDISPATCH for an AcroExch.Rect to be drawn with user space coordinates updateRect contains the instance variable $m_1pDispatch$, which contains the LPDISPATCH.
	Any objects outside of updateRect are not drawn. All objects are drawn if updateRect is NULL.
	Use methods in the CAcroRect class to set the size of the rectangle. For example:
	<pre>CAcroRect* rect = new CAcroRect;</pre>
	<pre>rect->CreateDispatch("AcroExch.Rect", &e); if (rect) {</pre>
	<pre>/* Set values for rect - increases from right to left and bottom to top */ rect->SetLeft(100); rect->SetTop(400); rect->SetRight(400); rect->SetBottom(100); }</pre>
xOrigin	The x-coordinate of the portion of the page to be drawn.

yOrigin	The y-coordinate of the portion of the page to be drawn.
zoom	Zoom factor at which the page is drawn, specified as a percent. For example, 100 corresponds to a magnification of 1.0.

A positive number if the page is successfully drawn, 0 otherwise.

Related methods

PDPage.CopyToClipboard

GetAnnot

Gets the specified annotation from the page's array of annotations.

Syntax

LPDISPATCH GetAnnot(long nIndex);

Parameters

nIndex	Index (in the page's annotation array) of the annotation to be retrieved. The first annotation in the array has an index of zero.
	·

Returns

The LPDISPATCH for the AcroExch. PDAnnot object.

Related methods

```
PDPage.GetAnnotIndex
PDPage.GetNumAnnots
```

GetAnnotIndex

Gets the index (within the page's annotation array) of the specified annotation.

Syntax

long GetAnnotIndex(LPDISPATCH iPDAnnot);

Parameters

iPDAnnot	LPDISPATCH for the AcroExch. PDAnnot whose index is obtained. iPDAnnot
	contains the instance variable ${\tt m_lpDispatch}$, which contains the LPDISPATCH.

The annotation's index.

Related methods

```
PDPage.GetNumAnnots
```

GetDoc

Gets the AcroExch. PDDoc associated with the page.

Syntax

```
LPDISPATCH GetDoc();
```

Returns

The LPDISPATCH for the page's AcroExch. PDDoc.

Related methods

```
AVPageView. GetPage

AVPageView. GetPageNum

PDDoc. AcquirePage

PDDoc. GetNumPages

PDPage. GetNumber

PDPage. GetRotate

PDPage. GetSize

PDTextSelect. GetPage
```

GetNumAnnots

Gets the number of annotations on the page.

Annotations that have associated pop-up windows, such as a strikeout, count as two annotations. Also note that widget annotations (Acrobat form fields) are included.

Syntax

```
long GetNumAnnots();
```

The number of annotations on the page.

Related methods

```
PDPage.<u>GetAnnot</u>
PDPage.<u>GetAnnotIndex</u>
```

GetNumber

Gets the page number of the current page. The first page in a document is page zero.

Syntax

```
long GetNumber();
```

Returns

The page number of the current page. The first page in a PDDoc object is page 0.

Related methods

```
AVPageView. GetPage

AVPageView. GetPageNum

PDDoc. AcquirePage

PDDoc. GetNumPages

PDPage. GetDoc

PDPage. GetRotate

PDPage. GetSize

PDTextSelect. GetPage
```

GetRotate

Gets the rotation value, in degrees, for the current page.

Syntax

```
short GetRotate();
```

Returns

Rotation value.

Related methods

```
AVPageView. GetPage

AVPageView. GetPageNum

PDDoc. AcquirePage

PDPage. GetNumber

PDPage. GetSize

PDPage. SetRotate

PDTextSelect. GetPage
```

GetSize

Gets a page's width and height in points.

Syntax

```
LPDISPATCH GetSize();
```

Returns

The LPDISPATCH for an AcroExch. Point containing the width and height, measured in points. Point x contains the width, point y the height.

Related methods

```
AVPageView. GetPage

AVPageView. GetPageNum

PDDoc. AcquirePage

PDPage. GetNumber

PDPage. GetRotate

PDTextSelect. GetPage
```

RemoveAnnot

Removes the specified annotation from the page's annotation array.

Syntax

```
VARIANT BOOL RemoveAnnot (long nIndex);
```

nIndex	Index within the page's annotation array of the annotation to be deleted. The first
	annotation on a page has an index of zero.

Returns

0 if the Acrobat application does not support editing, a positive number otherwise.

Related methods

```
PDPage. AddNewAnnot

PDPage. GetAnnotIndex
```

SetRotate

Sets the rotation, in degrees, for the current page.

Syntax

```
VARIANT_BOOL SetRotate(short nRotate);
```

Parameters

nRotate	Rotation value of 0, 90, 180, or 270.

Returns

0 if the Acrobat application does not support editing, -1 otherwise.

Related methods

PDPage.<u>GetRotate</u>

AcroExch.PDTextSelect

A selection of text on a single page that may contain more than one disjointed group of words. This is a non-creatable interface. A text selection is specified by one or more ranges of text, with each range containing the word numbers of the selected words. Each range specifies a start and end word, where "start" is the number of the first word of a series of selected words and "end" is the number of the next word after the last word in the selection.

Methods

The PDTextSelect object has the following methods.

Method	Description
Destroy	Destroys a text selection object.
GetBoundingRect	Gets a text selection's bounding rectangle.
<u>GetNumText</u>	Gets the number of text elements in a text selection.
<u>GetPage</u>	Gets the page number on which the text selection is located.
<u>GetText</u>	Gets the text from the specified element of a text selection.

Destroy

Destroys a text selection object.

Syntax

VARIANT_BOOL Destroy();

Returns

Always returns -1.

Related methods

AVDoc. ClearSelection

AVDoc. SetTextSelection

AVDoc. ShowTextSelect

PDDoc.<u>CreateTextSelect</u>

PDPage. CreatePageHilite

PDPage.CreateWordHilite

PDTextSelect.GetBoundingRect

PDTextSelect. GetNumText

```
PDTextSelect.<u>GetPage</u>
PDTextSelect.<u>GetText</u>
```

GetBoundingRect

Gets a text selection's bounding rectangle.

Syntax

```
LPDISPATCH GetBoundingRect();
```

Returns

The LPDISPATCH for an AcroExch. Rect corresponding to the text selection's bounding rectangle.

Related methods

```
AVDoc. ClearSelection

AVDoc. SetTextSelection

AVDoc. ShowTextSelect

PDDoc. CreateTextSelect

PDPage. CreatePageHilite

PDPage. CreateWordHilite

PDTextSelect. Destroy

PDTextSelect. GetNumText

PDTextSelect. GetPage

PDTextSelect. GetText
```

GetNumText

Gets the number of text elements in a text selection. Use this method to determine how many times to call the PDTextSelect.GetText method to obtain all of a text selection's text.

Note: A text element is not necessarily a word. A text element consists of characters of the same font, size and style; therefore, there may be more than one text element in a word.

Syntax

```
long GetNumText();
```

Returns

The number of elements in the text selection.

Related methods

```
AVDoc. ClearSelection

AVDoc. SetTextSelection

AVDoc. ShowTextSelect

PDDoc. CreateTextSelect

PDPage. CreatePageHilite

PDPage. CreateWordHilite

PDTextSelect. Destroy

PDTextSelect. GetBoundingRect

PDTextSelect. GetPage

PDTextSelect. GetText
```

GetPage

Gets the page number on which the text selection is located.

Syntax

```
long GetPage();
```

Returns

The text selection's page number. The first page in a PDDoc object is page 0.

Related methods

```
AVDoc. ClearSelection

AVDoc. SetTextSelection

AVDoc. ShowTextSelect

AVPageView. GetPage

AVPageView. GetPageNum

PDDoc. CreateTextSelect

PDDoc. GetNumPages

PDPage. CreatePageHilite

PDPage. GetNumber
```

```
PDTextSelect. Destroy

PDTextSelect. GetBoundingRect

PDTextSelect. GetNumText

PDTextSelect. GetText
```

GetText

Gets the text from the specified element of a text selection. To obtain all the text within the text selection, use PDTextSelect. GetNumText to determine the number of elements in the text selection, then call this method in a loop to obtain each of the elements.

Syntax

```
BSTR GetText(long nTextIndex);
```

Parameters

nTextIndex

The element of the text selection to get.

Returns

The text, or an empty string if nTextIndex is greater than the number of elements in the text selection.

Related methods

```
AVDoc.ClearSelection

AVDoc.SetTextSelection

AVDoc.ShowTextSelect

PDPage.CreatePageHilite

PDDoc.CreateTextSelect

PDPage.CreateWordHilite

PDTextSelect.Destroy

PDTextSelect.GetBoundingRect

PDTextSelect.GetNumText

PDTextSelect.GetPage
```

AcroExch.Point

Defines the location of an AcroPoint.

Properties

The Point object has the following properties.

Property	Description
X	Gets or sets the x-coordinate of an AcroPoint.
<u>Y</u>	Gets or sets the y-coordinate of an AcroPoint.

X

Gets or sets the x-coordinate of an AcroPoint.

Syntax

[get/set] Short

Return

The x-coordinate of the AcroPoint.

Y

Gets or sets the y-coordinate of an AcroPoint.

Syntax

[get/set] Short

Returns

The y-coordinate of the AcroPoint.

AcroExch.Rect

Defines the location of an AcroRect.

The Rect object has the following properties.

Properties

Property	Description
Bottom	Gets or sets the bottom y-coordinate of an AcroRect.
Left	Gets or sets the left x-coordinate of an AcroRect.
Right	Gets or sets the right x-coordinate of an AcroRect.
Top	Gets or sets the top y-coordinate of an AcroRect.

Bottom

Gets or sets the bottom y-coordinate of an AcroRect.

Syntax

[get/set] Short

Returns

The y-coordinate of the bottom of the AcroRect.

Left

Gets or sets left x-coordinate of an AcroRect.

Syntax

[get/set] Short

Returns

The x-coordinate of the left side of the AcroRect.

Right

Gets or sets the right x-coordinate of an AcroRect.

Syntax

[get/set] Short

Returns

The x-coordinate of the right side of the AcroRect.

Top

Gets or sets the top y-coordinate of an AcroRect.

Syntax

[get/set] Short

Returns

The y-coordinate of the top of the AcroRect.

AcroExch.Time

Defines a specified time, accurate to the millisecond.

Properties

The Time object has the following properties.

Property	Description
<u>Date</u>	Gets or sets the date from an AcroTime.
Hour	Gets or sets the hour from an AcroTime.
Millisecond	Gets or sets the milliseconds from an AcroTime.
Minute	Gets or sets the minutes from an AcroTime.
Month	Gets or sets the month from an AcroTime.
Second	Gets or sets the seconds from an AcroTime.
Year	Gets or sets the year from an AcroTime.

Date

Gets or sets the date from an AcroTime.

Syntax

[get/set] Short

Returns

The date from the AcroTime. The date runs from 1 to 31.

Hour

Gets or sets the hour from an AcroTime.

Syntax

```
[get/set] Short
```

Returns

The hour from the AcroTime. The hour runs from 0 to 23.

Millisecond

Gets or sets the milliseconds from an AcroTime.

Syntax

```
[get/set] Short
```

Returns

The milliseconds from the AcroTime. Milliseconds run from 0 to 999.

Minute

Gets or sets the minutes from an AcroTime.

Syntax

```
[get/set] Short
```

Returns

The minutes from the AcroTime. Minutes run from 0 to 59.

Month

Gets or sets the month from an AcroTime.

Syntax

```
[get/set] Short
```

Returns

The month from the AcroTime. The month runs from 1 to 12, where 1 is January and 12 is December.

Second

Gets or sets the seconds from an AcroTime.

Syntax

[get/set] Short

Returns

The seconds from the AcroTime. Seconds run from 0 to 59.

Year

Gets or sets the year from an AcroTime.

Syntax

[get/set] Short

Returns

The year from the AcroTime. The Year runs from 1 to 32767.

AxAcroPDFLib.AxAcroPDF

An object containing a set of methods that provide access to PDF browser controls. This is a creatable interface. This object makes it possible to load a file, move to various pages within the file, and specify various display and print options.

Methods

The AXACTOPDF object has the following methods.

Method	Description
GetVersions	Deprecated
<u>GoBackwardStack</u>	Goes to the previous view on the view stack, if the previous view exists.
<u>GoForwardStack</u>	Goes to the next view on the view stack, if the next view exists.
<u>GotoFirstPage</u>	Goes to the first page in the document, maintaining the current location within the page and zoom level.
<u>GotoLastPage</u>	Goes to the last page in the document, maintaining the current location within the page and zoom level.
<u>GotoNextPage</u>	Goes to the next page in the document, if it exists. Maintains the current location within the page and zoom level.

Method	Description
<u>GotoPreviousPage</u>	Goes to the previous page in the document, if it exists. Maintains the current location within the page and zoom level.
LoadFile	Opens and displays the specified document within the browser.
Print	Prints the document according to the options selected in a user dialog box.
<u>PrintAll</u>	Prints the entire document without displaying a user dialog box.
PrintAllFit	Prints the entire document without displaying a user dialog box, and the pages are shrunk, if necessary, to fit into the imageable area of a page in the printer.
<u>PrintPages</u>	Prints the specified pages without displaying a user dialog box.
<u>PrintPagesFit</u>	Prints the specified pages without displaying a user dialog box.
PrintWithDialog	Prints the document according to the options selected in a user dialog box.
<u>SetCurrentHighlight</u>	Highlights the text selection within the specified bounding rectangle on the current page.
<u>SetCurrentPage</u>	Goes to the specified page in the document.
<u>SetLayoutMode</u>	Sets the layout mode for a page view according to the specified string.
SetNamedDest	Changes the page view to the named destination in the specified string.
<u>SetPageMode</u>	Sets the page mode according to the specified string.
SetShowScrollbars	Determines whether scrollbars will appear in the document view.
SetShowToolbar	Determines whether a toolbar will appear in the viewer.
<u>SetView</u>	Sets the view of a page according to the specified string.
SetViewRect	Sets the view rectangle according to the specified coordinates.
SetViewScroll	Sets the view of a page according to the specified string.
SetZoom	Sets the magnification according to the specified value.
<u>SetZoomScroll</u>	Sets the magnification according to the specified value, and scrolls the page view both horizontally and vertically according to the specified amounts.

Properties

The AxAcroPDF object has the following property.

Property	Description
Src	Gets or sets the URL for the document.

GetVersions

Note: Deprecated. This method is no longer available.

Syntax

```
VARIANT GetVersions();
```

GoBackwardStack

Goes to the previous view on the view stack, if the previous view exists. The previous view may be in a different document.

Syntax

```
void GoBackwardStack();
```

Related methods

AcroPDF.GoForwardStack

GoForwardStack

Goes to the next view on the view stack, if the next view exists. The next view may be in a different document.

Syntax

```
void GoForwardStack();
```

Related methods

AcroPDF.GoBackwardStack

GotoFirstPage

Goes to the first page in the document, maintaining the current location within the page and the current zoom level.

Syntax

```
void gotoFirstPage();
```

Related methods

```
AcroPDF. GotoLastPage

AcroPDF. GotoNextPage

AcroPDF. GotoPreviousPage

AcroPDF. SetCurrentPage
```

GotoLastPage

Goes to the last page in the document, maintaining the current location within the page and the current zoom level.

Syntax

```
void gotoLastPage();
```

Related methods

```
AcroPDF. GotoFirstPage
AcroPDF. GotoNextPage
AcroPDF. GotoPreviousPage
AcroPDF. SetCurrentPage
```

GotoNextPage

Goes to the next page in the document, if it exists. Maintains the current location within the page and the current zoom level.

Syntax

```
void gotoNextPage();
```

Related methods

```
AcroPDF. GotoFirstPage
AcroPDF. GotoLastPage
AcroPDF. GotoPreviousPage
AcroPDF. SetCurrentPage
```

GotoPreviousPage

Goes to the previous page in the document, if it exists. Maintains the current location within the page and the current zoom level.

Syntax

```
void gotoPreviousPage();
```

Related methods

```
AcroPDF. GotoLastPage
AcroPDF. GotoNextPage
AcroPDF. SetCurrentPage
```

LoadFile

Opens and displays the specified document within the browser.

Syntax

```
VARIANT BOOL LoadFile (BSTR fileName);
```

Parameters

fileName

The path of the file to be opened.

Returns

0 if the file could not be opened, -1 otherwise.

Print

Prints the document according to the options selected in a user dialog box. The options include embedded printing (printing within a bounding rectangle on a given page), as well as interactive printing to a specified printer. This method returns immediately, even if the printing has not completed.

Note: If security settings do not allow printing, this method is ignored.

Syntax

```
void Print();
```

Related methods

```
AcroPDF. PrintAll

AcroPDF. PrintAllFit

AcroPDF. PrintPages

AcroPDF. PrintPagesFit

AcroPDF. PrintWithDialog
```

PrintAll

Prints the entire document without displaying a user dialog box. The current printer, page settings, and job settings are used. This method returns immediately, even if the printing has not completed.

Note: If security settings do not allow printing, this method is ignored.

```
void printAll();
```

Related methods

```
AcroPDF. Print

AcroPDF. PrintAllFit

AcroPDF. PrintPages

AcroPDF. PrintPagesFit

AcroPDF. PrintWithDialog
```

PrintAllFit

Prints the entire document without displaying a user dialog box, and the pages are shrunk, if necessary, to fit into the imageable area of a page in the printer. The current printer, page settings, and job settings are used. This method returns immediately, even if the printing has not completed.

Note: If security settings do not allow printing, this method is ignored.

Syntax

```
void printAllFit(VARIANT BOOL bOn);
```

Parameters

bOn

Determines whether to scale the imageable area when printing the document. A value of 0 indicates that no scaling should be used, and a positive value indicates that the pages are shrunk, if necessary, to fit into the imageable area of a page in the printer.

Related methods

```
AcroPDF. Print

AcroPDF. PrintAll

AcroPDF. PrintPages

AcroPDF. PrintPagesFit

AcroPDF. PrintWithDialog
```

PrintPages

Prints the specified pages without displaying a user dialog box. The current printer, page settings, and job settings are used. This method returns immediately, even if the printing has not completed.

Note: If security settings do not allow printing, this method is ignored.

```
void printPages( Long nFrom, Long nTo);
```

nFrom	The page number of the first page to be printed. The first page in a document is page 0.
nTo	The page number of the last page to be printed.

Related methods

AcroPDF.Print

AcroPDF.PrintAll

AcroPDF.PrintAllFit

AcroPDF.PrintPagesFit

AcroPDF.PrintWithDialog

PrintPagesFit

Prints the specified pages without displaying a user dialog box. The current printer, page settings, and job settings are used. A parameter specifies whether to shrink pages, if necessary. This method returns immediately, even if the printing has not completed.

Note: If security settings do not allow printing, this method is ignored.

Syntax

Parameters

nFrom	The page number of the first page to be printed. The first page in a document is page 0.
пТо	The page number of the last page to be printed.
bShrinkToFit	Specifies whether the pages will be shrunk, if necessary, to fit into the imageable area of a page in the printer.

Related methods

AcroPDF. Print

AcroPDF. PrintAll

AcroPDF. PrintAllFit

AcroPDF. PrintPages

AcroPDF.PrintWithDialog

PrintWithDialog

Prints the document according to the options selected in a user dialog box. The options include embedded printing (printing within a bounding rectangle on a given page), as well as interactive printing to a specified printer. This method returns immediately, even if the printing has not completed.

Note: If security settings do not allow printing, this method is ignored.

Syntax

```
void printWithDialog();
```

Related methods

```
AcroPDF. PrintAll
AcroPDF. PrintAllFit
AcroPDF. PrintPages
AcroPDF. PrintPagesFit
```

SetCurrentHighlight

Highlights the text selection within the specified bounding rectangle on the current page.

Syntax

Parameters

nLeft	The distance in points from the left side of the page.
пТор	The distance in points from the top of the page.
nRight	The width of the bounding rectangle.
nBottom	The height of the bounding rectangle.

SetCurrentPage

Goes to the specified page in the document. Maintains the current location within the page and the current zoom level.

```
void setCurrentPage(LONG nPage);
```

nPage

The page number of the destination page. The first page in a document is page 0.

Related methods

AcroPDF.GotoFirstPage

AcroPDF. GotoLastPage

AcroPDF.GotoNextPage

AcroPDF.GotoPreviousPage

SetLayoutMode

Sets the layout mode for a page view according to the specified string.

Syntax

void setLayoutMode(BSTR szLayoutMode);

Parameters

szLayoutMode	Possible values:
	DontCare — use the current user preference
	SinglePage — use single page mode (as it would have appeared in pre-Acrobat 3.0 viewers)
	OneColumn — use one-column continuous mode
	${\tt TwoColumnLeft}$ — use two-column continuous mode with the first page on the left
	${\tt TwoColumnRightusetwo-columncontinuousmodewiththefirstpage} \\ ontheright$

Related methods

AcroPDF. <u>SetNamedDest</u>

AcroPDF. <u>SetView</u>

AcroPDF. SetViewRect

AcroPDF. <u>SetViewScroll</u>

SetNamedDest

Changes the page view to the named destination in the specified string.

Syntax

void setNamedDest(BSTR szNamedDest);

szNamedDest

The named destination to which the viewer will go.

Related methods

AcroPDF.SetLayoutMode

AcroPDF. <u>SetView</u>

AcroPDF.SetViewRect

AcroPDF. <u>SetViewScroll</u>

SetPageMode

Sets the page mode according to the specified string.

Syntax

void setPageMode(BSTR szPageMode);

Parameters

szPageMode Possible values:

none — displays the document, but does not display bookmarks or

thumbnails (default)

bookmarks — displays the document and bookmarks

thumbs — displays the document and thumbnails

Related methods

AcroPDF. SetShowScrollbars

AcroPDF.<u>SetShowToolbar</u>

SetShowScrollbars

Determines whether scrollbars will appear in the document view.

Syntax

void setShowScrollbars(VARIANT BOOL bOn);

Parameters

bOn A positive value indicates that scrollbars will appear, 0 indicates that they will not.

Related methods

AcroPDF.SetPageMode

AcroPDF.SetShowToolbar

SetShowToolbar

Determines whether a toolbar will appear in the viewer.

Syntax

```
void setShowToolbar(VARIANT_BOOL bOn);
```

Parameters

bOn

A positive value indicates that the toolbar will appear, 0 indicates that it will not.

Related methods

AcroPDF.SetPageMode

AcroPDF.SetShowScrollbars

SetView

Sets the view of a page according to the specified string.

Syntax

void setView(BSTR szViewMode);

Parameters

szViewMode	Possible values:
	${\tt Fit} \ -\!$
	FitH — Fits the entire width of the page within the window.
	\mathtt{FitV} — Fits the entire height of the page within the window.
	${\tt FitB}$ — Fits the bounding box within the window both vertically and horizontally.
	FitBH — Fits the entire width of the bounding box within the window.
	FitB — Fits the entire height of the bounding box within the window.

Related methods

```
AcroPDF. SetNamedDest

AcroPDF. SetViewRect

AcroPDF. SetViewScroll
```

SetViewRect

Sets the view rectangle according to the specified coordinates.

Syntax

Parameters

left	The upper left horizontal coordinate.
top	The vertical coordinate in the upper left corner.
width	The horizontal width of the rectangle.
height	The vertical height of the rectangle.

Related methods

```
AcroPDF. SetNamedDest
AcroPDF. SetView
AcroPDF. SetViewScroll
```

SetViewScroll

Sets the view of a page according to the specified string. Depending on the view mode, the page is either scrolled to the right or scrolled down by the amount specified in offset.

```
void setViewRect(BSTR szViewMode, FLOAT offset);
```

szViewMode	Possible values:
	${ t Fit}$ — Fits the entire page within the window both vertically and horizontally
	FitH — Fits the entire width of the page within the window.
	${ t Fit V}$ — Fits the entire height of the page within the window.
	FitB — Fits the bounding box within the window both vertically and horizontally.
	${ t Fit BH}$ — Fits the entire width of the bounding box within the window.
	FitBV — Fits the entire height of the bounding box within the window.
offset	The horizontal or vertical coordinate positioned either at the left or top edge.

Related methods

AcroPDF. SetNamedDest

AcroPDF. SetView

AcroPDF. SetViewRect

SetZoom

Sets the magnification according to the specified value.

Syntax

void setZoom(FLOAT percent);

Parameters

percent	The desired zoom factor, expressed as a percentage. For example, 1.0 represents
	a magnification of 100%.

Related methods

AcroPDF. <u>SetZoomScroll</u>

SetZoomScroll

Sets the magnification according to the specified value, and scrolls the page view both horizontally and vertically according to the specified amounts.

```
void setZoomScroll(FLOAT percent, FLOAT left, FLOAT top);
```

percent	The desired zoom factor, expressed as a percentage. For example, 1.0 represents a magnification of 100%.
left	The horizontal coordinate positioned at the left edge.
top	The vertical coordinate positioned at the top edge.

Related methods

AcroPDF. SetZoom

Src

Gets or sets the URL for the document.

Syntax

[get/set] src

Returns

The URL for the document, formatted as a string.

2

DDE Messages

This chapter lists all DDE messages supported by Acrobat.

These DDE messages handle the display of the Acrobat application:

- AppExit
- AppHide
- AppShow
- <u>CloseAllDocs</u>
- <u>HideToolbar</u>
- MenuitemExecute
- ShowToolbar

These DDE messages control the display of the document:

- <u>DocClose</u>
- <u>DocDeletePages</u>
- <u>DocInsertPages</u>
- DocOpen
- DocReplacePages
- <u>DocSave</u>
- DocSaveAs
- DocSetViewMode
- FileOpen
- FileOpenEx

These DDE messages handle printing of a document:

- <u>DocPrint</u>
- FilePrint
- FilePrintEx
- FilePrintSilent
- FilePrintSilentEx
- FilePrintTo
- FilePrintToEx

These DDE messages control the view of a document.:

- DocGoTo
- DocGoToNameDest
- <u>DocPageDown</u>
- DocPageLeft

- DocPageRight
- DocPageUp
- <u>DocScrollTo</u>
- DocZoomTo

This DDE message is used for searching:

• DocFind

Adobe Reader supports the following subset of DDE messages:

- AppExit
- <u>CloseAllDocs</u>
- DocClose
- <u>DocGoTo</u>
- <u>DocGoToNameDest</u>
- DocOpen
- FileOpen
- FileOpenEx
- FilePrint
- FilePrintEx
- FilePrintSilent
- FilePrintSilentEx
- FilePrintTo
- FilePrintToEx

AppExit

Exits the Acrobat application.

AppExit is also supported in Adobe Reader.

Syntax

[AppExit()]

Returns

true if the Acrobat application exits successfully, false otherwise.

Related methods

AppHide

AppShow

AppHide

Iconifies or hides the Acrobat application.

Syntax

[AppHide()]

Returns

true if the Acrobat application is hidden successfully, false otherwise.

Related methods

AppExit

AppShow

AppShow

Shows the Acrobat application.

Syntax

[AppShow()]

Returns

true if the Acrobat application is shown successfully, false otherwise.

Related methods

AppExit

AppHide

CloseAllDocs

Closes all open documents.

CloseAllDocs is also supported in Adobe Reader.

Syntax

[CloseAllDocs()]

Returns

true if the documents are closed successfully, false otherwise.

Related methods

DocClose

<u>DocOpen</u>

FileOpen

DocClose

Closes the specified document without saving it, and without prompting the user to save the document if it has been modified.

DocClose is also supported in Adobe Reader.

Syntax

```
[DocClose(char* fullPath)]
```

Parameters

fullPath

The full path of the file to be closed.

Returns

true if the document is closed successfully, false if the document does not exist or is not closed successfully.

Related methods

<u>CloseAllDocs</u>

<u>DocOpen</u>

FileOpen

DocDeletePages

Deletes the specified pages in the document. Requests to delete all pages in a document are ignored because a document must have at least one page.

Syntax

[DocDeletePages(char* fullPath, long fromPage, long toPage)]

fullPath	The full path of the document.
fromPage	The page number of the first page to be deleted.
toPage	The page number of the last page to be deleted.

Returns

true if the pages are deleted successfully. Returns false if the document specified by fullPath does not exist, if the request was to delete all the document's pages, or if the pages are not deleted successfully.

Related methods

DocInsertPages

DocReplacePages

DocFind

Finds a string in a specified file. This does not use a cross-document search, but instead performs a page-by-page search of the specified file.

Syntax

Parameters

fullPath	The full path of the file to be searched.
string	The string to be found.
caseSensitive	true if the search is case-sensitive, false otherwise.
wholeWords	true if the search will only match whole words, false otherwise.
bReset	$\tt true$ if the search begins on the first page of the document, ${\tt false}$ if the search begins on the current page.

Returns

false if the document specified by fullPath does not exist or if the text is not found, true otherwise.

DocGoTo

Goes to the specified page.

DocGoTo is also supported in Adobe Reader.

Syntax

[DocGoTo(char* fullPath, long pageNum)]

Parameters

fullPath	The full path of the file.
pageNum	The page number of the destination page.

Returns

false if the document specified by fullPath does not exist, true otherwise.

DocGoToNameDest

Goes to the specified named destination.

DocGoToNameDest is also supported in Adobe Reader.

Syntax

[DocGoToNameDest(char* fullPath, char* nameDest)]

Parameters

fullPath	The full path of the file.
nameDest	The named destination.

Returns

false if the document specified by fullPath does not exist, true otherwise.

DocInsertPages

Inserts pages from one file into another.

Syntax

[DocInsertPages(char* fullPath, long insertAfterPage, char* sourcePath)]

fullPath	The full path of the target document, which must already be open in the Acrobat application.
insertAfterPage	The page number after which pages are being inserted. Possible values can be a page number or one of the following:
	PDBeforeFirstPage — Pages are inserted at the beginning of the document.
	PDLastPage — Pages are inserted at the end of the document.
sourcePath	The full path of the source document. This file need not be open in the Acrobat application.

Returns

true if the pages are inserted successfully, false if the document does not exist or the pages are not inserted successfully.

Related methods

DocDeletePages

DocReplacePages

DocOpen

Opens a document and adds it to the list of documents known to DDE, allowing it to be manipulated by other DDE messages (see FileOpen).

DocOpen is also supported in Adobe Reader.

Syntax

[DocOpen(char* fullPath)]

Parameters

The fair path of the life to be opened.	fullPath	The full path of the file to be opened.
---	----------	---

Returns

true if the file is opened successfully, false otherwise.

Related methods

CloseAllDocs

DocClose

FileOpen

DocPageDown

Scrolls forward through the document by one screen area.

Syntax

[DocPageDown(char* fullPath)]

Parameters

fullPath

The full path of the document.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

DocPageLeft

DocPageRight

DocPageUp

DocScrollTo

DocPageLeft

Scrolls to the left by a small amount.

Syntax

[DocPageLeft(char* fullPath)]

Parameters

fullPath

The full path of the document.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

<u>DocPageDown</u>

DocPageRight

<u>DocPageUp</u>

DocPageUp

DocPageRight

Scrolls to the right by a small amount.

Syntax

```
[DocPageRight(char* fullPath)]
```

Parameters

fullPath

The full path of the document.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

DocPageDown

DocPageLeft

DocPageUp

DocPageUp

DocPageUp

Scrolls backward through the document by one screen area.

Syntax

```
[DocPageUp(char* fullPath)]
```

Parameters

fullPath

The full path of the document.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

<u>DocPageDown</u>

<u>DocPageLeft</u>

DocPageRight

DocScrollTo

DocPrint

Prints a specified range of pages from a document, without displaying any modal Print dialog box to the user. For PostScript printing, only Level 1 operators are used, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

Syntax

[DocPrint(char* fullPath, long startPage, long endPage)]

Parameters

fullPath	The full path of document.
startPage	The page number of the first page to be printed.
endPage	The page number of the last page to be printed.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

FilePrint

FilePrintSilent

<u>FilePrintTo</u>

DocReplacePages

Replaces pages in the target document using the specified pages from the source document.

Syntax

Parameters

fullPath	The full path of the target document. This file must already be open in the Acrobat application.
startDestPage	The page number of the first page in the target document to be replaced.
sourcePath	The full path of the source document. This file does not have to be already open in the Acrobat application.

startSourcePage	The page number of the first page in the source document to use as a replacement page.
endSourcePage	The page number of the last page in the source document to use as a replacement page.

Returns

true if the pages are replaced successfully. Returns false if the document does not exist or the pages are not replaced successfully.

Related methods

<u>DocDeletePages</u>

DocInsertPages

DocSave

Saves the specified file. The user is not warned if there are any problems saving the file.

Syntax

[DocSave(char* fullPath)]

Parameters

|--|

Returns

true if the document is saved successfully, false if the document does not exist or is not saved successfully.

Related methods

DocSaveAs

DocSaveAs

Saves an open file to a new path. The user is not warned if there are any problems saving the file.

```
[DocSaveAs(char* fullPath, char* newPath)]
```

fullPath	The full path of the existing file.
newPath	The full path of the new file.

Returns

true if the document is saved successfully, false if the document does not exist or is not saved successfully.

Related methods

DocSave

DocScrollTo

Scrolls the view of the current page to the specified location.

Syntax

[DocScrollTo(char* fullPath, int x, int y)]

Parameters

fullPath	The full path of the document.
х	The destination's x-coordinate.
У	The destination's y-coordinate.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

DocPageDown

DocPageLeft

DocPageRight

DocPageUp

DocSetViewMode

Determines whether bookmarks, thumbnail images, or neither are shown in addition to the document.

Syntax

[DocSetViewMode(char* fullPath, char* viewType)]

Parameters

fullPath	The full path of the document.
viewType	The view mode to be used. Must be one of the following:
	PDUseThumbs — Displays pages and thumbnail images.
	PDUseNone — Displays only pages.
	PDUseBookmarks — Displays pages and bookmarks.

Returns

true if the view mode is set successfully, false if the document specified by fullPath does not exist or an unknown view mode is specified.

Related methods

FullMenus

ShortMenus

DocZoomTo

Sets the zoom for a specified document.

Syntax

[DocZoomTo(char* fullPath, char* zoomType, int scale)]

Parameters

fullPath	The full path of the file whose zoom to set.
zoomType	The zoom strategy to use. Must be one of the following:
	AVZoomNoVary — A fixed zoom, such as 100%.
	AVZoomFitPage — Fits the page in the window.
	AVZoomFitWidth — Fits the page's width into the window.
	${\tt AVZoomFitVisibleWidthFits\ the\ page's\ visible\ content\ into\ the\ window.}$
scale	The magnification specified as a percent (for example, 100 corresponds to a magnification of 1.0). scale is used only when zoomType is AVZoomNoVary.

Returns

false if the document specified by fullPath does not exist, or if zoomType has an unknown value. Returns true otherwise.

FileOpen

Opens and displays the specified document. If the file is already open, it becomes the active document and appears in the front. This DDE message does not add the document to the list that can be manipulated using DDE messages; use DocOpen to do that.

FileOpen is also supported in Adobe Reader.

Syntax

```
[FileOpen(char* fullPath)]
```

Parameters

fullPath

The full path of the file to be opened.

Returns

true if the file is opened successfully, false otherwise.

Related methods

CloseAllDocs

DocClose

DocOpen

FileOpenEx

Opens and displays a file. If the file is already open, it becomes the active document and appears in the front. This DDE message does not add the document to the list that can be manipulated using DDE messages; use DocOpen to do that.

This method allows documents that either take a long time to open or are password-protected to open without stopping the flow of DDE messages. Documents opened with FileOpenEx are opened during an idle period. This is useful in situations in which several DDE messages are sent at once, such as a multiple file select from Windows Explorer.

FileOpenEx is also supported in Adobe Reader.

```
[FileOpenEx(char* fullPath)]
```

fullPath

The full path of the file to be opened.

Returns

true is always returned. The specified file may not actually open.

Related methods

FileOpen

<u>CloseAllDocs</u>

<u>DocClose</u>

DocOpen

FilePrint

Prints all pages in a document, displaying a modal print dialog box to the user. For PostScript printing, only Level 1 operators are used, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

FilePrint is also supported in Adobe Reader.

Syntax

```
[FilePrint(char* fullPath)]
```

Parameters

fullPath

The full path of the file to be printed.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

DocPrint

<u>FilePrintSilent</u>

FilePrintTo

FilePrintEx

Prints all pages in a document, displaying a modal print dialog box to the user. For PostScript printing, only Level 1 operators are used, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

Similar to FileOpenEx, this is a special DDE command that returns true right away and performs the action during idle periods. This ensures that no DDE commands are lost when printing a large number of files simultaneously.

FilePrintEx is also supported in Adobe Reader.

Syntax

```
[FilePrintEx(char* fullPath)]
```

Parameters

fullPath

The full path of the file to print.

Returns

true is always returned.

Related methods

DocPrint

FileOpenEx

FilePrint

FilePrintSilent

FilePrintSilentEx

<u>FilePrintTo</u>

<u>FilePrintToEx</u>

FilePrintSilent

Prints all pages in a document, without displaying a print dialog box to the user. For PostScript printing, only Level 1 operators are used, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

FilePrintSilent is also supported in Adobe Reader.

```
[FilePrintSilent(char* fullPath)]
```

fullPath

The full path of the file to be printed.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

DocPrint

FilePrint

<u>FilePrintTo</u>

FilePrintSilentEx

Prints all pages in a document, without displaying a print dialog box to the user. For PostScript printing, only Level 1 operators are used, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

Similar to FileOpenEx, this is a DDE command that returns true right away and does the action during idle periods. This is to ensure that no DDE commands are lost when printing a large number of files simultaneously.

FilePrintSilentEx is also supported in Adobe Reader.

Syntax

[FilePrintSilentEx(char* fullPath)]

Parameters

fullPath

The full path of the file to be printed.

Returns

true is always returned.

Related methods

DocPrint

FileOpenEx

FilePrintEx

<u>FilePrintSilent</u>

<u>FilePrintTo</u>

<u>FilePrintToEx</u>

FilePrintTo

Prints all pages in a document to a specified printer, using a specified driver and port, displaying a modal print dialog box to the user. For PostScript printing, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

FilePrintTo is also supported in Adobe Reader.

Syntax

Parameters

fullPath	The full path of the file to be printed.
printName	The name of the printer. Required for Windows 95 and later.
driverName	Printer driver name.
portName	Port name. Required for Windows NT.

Returns

false if the document specified by fullPath does not exist, true otherwise.

Related methods

DocPrint

FilePrint

FilePrintSilent

FilePrintToEx

Prints all pages in a document to a specified printer, using a specified driver and port, displaying a modal print dialog box to the user. For PostScript printing, only ASCII data is generated, and the document's pages are not shrunk to fit into the imageable area of the printed page.

Similar to FileOpenEx, this is a DDE command that returns true right away and does the action during idle periods. This is to ensure that no DDE commands are lost when printing a large number of files simultaneously.

FilePrintToEx is also supported in Adobe Reader.

fullPath	The full path of the file to be printed.	
printName	The name of the printer. Required for Windows 95 and later.	
driverName	Printer driver name.	
portName	Port name. Required for Windows NT.	

Returns

true is always returned.

Related methods

<u>DocPrint</u>

FileOpenEx

<u>FilePrintEx</u>

FilePrintSilentEx

<u>FilePrintTo</u>

<u>FilePrintToEx</u>

FullMenus

Displays full menus, and sets this option in the Acrobat application's preferences file.

With Acrobat 3.0 or later, all menus are displayed, and this function is ignored.

Syntax

[FullMenus()]

Returns

true if full menus are set successfully, false otherwise.

Related methods

<u>DocSetViewMode</u>

ShortMenus

HideToolbar

Hides the toolbar.

Syntax

[HideToolbar()]

Returns

true if the toolbar is hidden successfully, false otherwise.

Related methods

ShowToolbar

MenuitemExecute

Executes the menu item specified by its language-independent name.

Syntax

[MenuitemExecute(char* menuItemName)]

Parameters

menuItemName	The language-independent name of the menu item to execute. See the Acrobat
	and PDF Library API Reference for a list of menu item names.

ShortMenus

Displays short menus, and sets this option in the Acrobat application's preferences file.

With Acrobat 3.0 or later, all menus are displayed, and this function is ignored.

Syntax

[ShortMenus()]

Returns

true if short menus are set successfully, false otherwise.

Related methods

<u>DocSetViewMode</u>

<u>FullMenus</u>

ShowToolbar

Shows the toolbar.

Syntax

[ShowToolbar()]

Returns

true if the toolbar is shown successfully, false otherwise.

Related methods

HideToolbar

3

Apple Event Objects and Apple Events

This chapter describes the supported Apple event objects, with descriptions of each object's elements and properties, and the supported Apple events.

Objects

Acrobat presents the following objects to the Apple event interface:

- <u>annotation</u>
- application
- bookmark
- conversion
- document
- Link Annotation
- menu
- menu item
- page
- PDF Window
- Text Annotation

annotation

An annotation on a page in a PDF file that corresponds to PDAnnot, an internal Acrobat class. This object was formerly known as PDAnnot.

Acrobat also has two built-in annotation objects. For more information, see <u>"Link Annotation" on page 149</u> and "Text Annotation" on page 154.

Plural form

Annotations

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
bounds	a list of small real	The boundary rectangle for the annotation in PDF space (left, top, right, bottom).
class	type class [r/o]	The class.

Property	Class	Description
color	'RGB'	The color of the border around the annotation.
contents	international text	Text annotations only. The textual contents of the note.
default type	type class [r/o]	The default descriptor type.
destination page number	integer	Link annotations only. The page number to appear in the PDF window when the annotation link is activated.
destination rectangle	a list of small real	Link annotations only. The boundary rectangle (specified in user space) for the view of the destination. Coordinates are specified in the following order: left, top, right, bottom.
fit type	constant	Link annotations only. Determines how the destination rectangle is fitted to the window when the link is activated. Values are: Left Top Zoom, Fit Page, Fit Width, Fit Height, Fit Rect, Fit BBox, Fit BB Width, Fit BB Height These are described in the PDF Reference.
index	intagor [r/o]	
	integer [r/o]	The annotation's index within the <u>page</u> object.
modification date	date	The date and time the annotation was last modified.
name	string	Text annotations only. The annotation's label.
open state	Boolean	Text annotations only. Whether the annotation is open.
subtype	international text [r/o]	The subtype of the annotation.
zoom factor	small real	Link annotations only. If fit type is Left Top Zoom, this specifies the zoom factor; otherwise it is ignored. Setting this property automatically sets fit type to Left Top Zoom.

Related methods

<u>delete</u>

perform

application

The Acrobat or Adobe Reader application itself.

Elements

Element	Accessed by
document	name, numeric index
PDF Window	name, numeric index
menu	name, numeric index
menu item	name

Properties

Property	Class	Description
active doc	reference	The active document.
active tool	international text	The type of the currently active tool. See the Acrobat and PDF Library API Reference for a list of tool names.
anti_alias text	Boolean	Determines whether to anti-alias text and monochrome images.
best type	type class [r/o]	The best descriptor type.
case sensitivity	Boolean	Determines whether searches are casesensitive.
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
default zoom factor	small real	The default zoom factor, in percent, used for displaying new documents. For example, a value of 100 corresponds to a zoom factor of 1.0 (100%).
default zoom type	constant	The default zoom type when opening a new document. Valid values are no vary, fit page, fit width, fit height, and fit visible width.
download entire file	Boolean	Determines whether to download the entire file.
frontmost	Boolean	Determines whether Acrobat is the frontmost application. Value can be set to true only.

Property	Class	Description
fullscreen click advances	Boolean	Determines whether mouse click advances in fullscreen mode.
fullscreen cursor	Boolean	Determines whether to hide the cursor in fullscreen mode.
fullscreen escape	Boolean	Determines whether the Esc key can be used to exit fullscreen mode.
fullscreen loop	Boolean [r/o]	Determines whether the document's pages are displayed in a loop while in fullscreen mode.
fullscreen timer delay	integer	The number of seconds to advance to the next page in fullscreen mode.
fullscreen transition	international text [r/o]	Default fullscreen transition.
highlight color	'RGB '	Color used to highlight selections.
maximum documents	integer [r/o]	Maximum number of open documents.
name	string [r/o]	The application's name.
note color	'RGB '	A list of three values between 0 and 65535 representing the color of the border around text annotations. For example, the following sets the note color to deep blue: set the note color to {0, 0, 32768}.
note font name	international text	Deprecated.
note font size	integer	Deprecated.
open in place	Boolean	Determines whether to open cross-document links in the same window.
page layout	international text	Default page layout. Values are: Single Page, Continuous, Facing, and Continuous - Facing.
page units	international text	Default page display units: Points, Inches or Millimeters.
PS level	integer	Deprecated. Set the PostScript level when using save or print pages commands.
save as linearize	Boolean	Determines whether to save the document as optimized for the web.
show splash at startup	Boolean	Determines whether the splash screen is shown at startup.

Property	Class	Description
skip warnings	Boolean	Determines whether to skip warning dialog boxes during program execution.
shrink to fit	Boolean	Deprecated.
text note label	international text	The text that will appear in the title bar of all newly created text notes.
toolbar visibility	Boolean	Determines whether the toolbar is visible.
UI language	international text [r/o]	A three-character language code identifying which language is used in the Acrobat user interface. Example: ENU represents English.
use fullscreen timer	Boolean	Determines whether to use a timer to advance pages in fullscreen mode
version	string [r/o]	The version number of the application.
whole word searching	Boolean	Determines whether searches are applied to whole words only.

Related methods

close all docs

count

<u>make</u>

open

print

quit

run

AVPageView

Note: Deprecated. Use PDF Window instead.

bookmark

A bookmark on a page in a PDF file. Corresponds to Acrobat's PDBookmark object.

Note: This object was formerly known as PDBookmark.

Plural form

Bookmarks

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
destination page number	integer	The page number to which the PDF Window goes when the bookmark's action is performed.
destination rectangle	list of small real	Boundary rectangle (specified in user space) for the view of the destination when the bookmark's action is performed. Coordinates are specified in the following order: (left, top, right, bottom).
		Note: Set this only after setting fit type.
fit type	constant	Controls how the destination rectangle is fitted to the window when the bookmark's action is performed. Possible values:
		Left Top Zoom — Sets a specified zoom and a specified location on the page.
		Fit Page — Sets the zoom factor so that the entire page fits into the window.
		Fit Width — Sets the zoom factor so that the width of the page fits into the window.
		Fit Height — Sets the zoom factor so that the height of the page fits into the window.
		Fit Rect — Sets the zoom factor so that the specified rectangle fits into the window.
		Fit BBox — Sets the zoom so that the rectangle enclosing all marks on the page (known as the bounding box) fits into the window.
		Fit BB Width — Sets the zoom factor so that the width of the bounding box fits into the window.
		Fit BB Height — Sets the zoom factor so that the height of the bounding box fits into the window.
index	integer [r/o]	The bookmark's index within the document.
name	international text	The bookmark's title.
zoom factor	small real	The zoom factor used when fit type is Left Top Zoom; ignored otherwise. Setting this property automatically sets fit type to Left Top Zoom.

Related methods

insert pages

perform

conversion

A file type converter that exports PDF files into other formats. Conversions correspond to the list of formats specified in the Acrobat Save As menu. A list of formats can be obtained as follows:

get every conversion

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
index	integer [r/o]	The index number of the converter.
name	international text	The conversion's description.

Related methods

save

document

Represents a single open document in Acrobat or Adobe Reader.

Elements

Element	Accessed by	
page	Numeric index. The first page in a document is page 1.	
bookmark	Name or numeric index.	
PDF Window	An index of 1 or with the some keyword in AppleScript. No document has more than one PDF Window.	

Plural form

documents

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
bounds	bounding rectangle [r/o]	The boundary rectangle for the document's window, in screen coordinates (left, top, right, bottom).
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
file alias	alias [r/o]	An alias for the file to which the document will be saved if no other name is specified; this is usually the same path from which the document was read.
modified	Boolean [r/o]	Determines whether the document has been modified and should be saved.
name	international text [r/o]	The document's name as it appears in the window's titlebar.
view mode	constant	The viewing mode of the document. Possible values: just pages, pages and thumbs, or pages and bookmarks.

Related methods

bring to front

clear selection

close

count

create thumbs

<u>delete</u>

<u>delete pages</u>

<u>delete thumbs</u>

find next note

find text

get info

insert pages

maximize

print pages

replace pages

save

set info

EPS Conversion

A file type converter that exports PDF files into EPS format.

Properties

Inherits from PostScript Conversion.

Related methods

save

Link Annotation

A link annotation on a page in a PDF file. Can only be used as the target of a <u>make</u> event. All other access is via the <u>annotation</u> class.

Note: This object was formerly known as PDLinkAnnot.

Properties

Inherits from annotation.

Related methods

delete

perform

menu

A menu in the Acrobat or Adobe Reader menu bar.

Elements

Element	Accessed by
menu item	name, numeric index.

Properties

Property	Class	Description	
best type	type class [r/o]	The best descriptor type.	
class	type class [r/o]	The class.	
default type	type class [r/o]	The default descriptor type.	

Property	Class	Description
name	international text [r/o]	The menu's name (a language-independent name that uniquely identifies the menu). See the Acrobat and PDF Library API Reference for a list of menu names.
title	string [r/o]	The menu's title as it would appear in the user interface.

Related methods

<u>execute</u>

menu item

A menu item contained within a menu in Acrobat or Adobe Reader.

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
enabled	Boolean [r/o]	Determines whether the menu item is enabled.
has submenu	Boolean [r/o]	Determines whether the menu item has a hierarchical sub-menu.
marked	Boolean [r/o]	Determines whether the menu item is checked.
name	international text [r/o]	The menu item's language-independent name. See the <i>Acrobat and PDF Library API Reference</i> for a list of menu item names.
title	string [r/o]	The menu's title as it would appear in the user interface.

Related methods

<u>execute</u>

page

A single page in the PDF representation of a document. Corresponds to Acrobat's internal PDPage object.

Note: This object was formerly known as PDPage.

Elements

Element	Accessed by
annotation	numeric index.

Plural form

Pages

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
bounds	list of small real	The boundary rectangle for the page in user space (left, top, right, bottom).
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
page number	integer [r/o]	The page's number. The first page in a document is page 1.
rotation	integer	The rotation angle of the page in degrees (0, 90, 180, or 270).

Related methods

delete pages

insert pages

replace pages

goto

move

PDAnnot

Note: Deprecated. Use <u>annotation</u> instead.

PDBookMark

Note: Deprecated. Use <u>bookmark</u> instead.

PDLinkAnnot

Note: Deprecated. Use Link Annotation instead.

PDPage

Note: Deprecated. Use <u>page</u> instead.

PDTextAnnot

Note: Deprecated. Use <u>Text Annotation</u> instead.

PDF Window

The area of the Acrobat or Adobe Reader window that displays the contents of a page within the document. Corresponds to the Acrobat internal AvPageView object. A document that is not visible does not have a PDF Window.

Note: This object was formerly known as AVPageView.

Elements

Element	Accessed by
page	numeric index. The first page in a document is page 1.

Properties

Property	Class	Description
best type	type class [r/o]	The best descriptor type.
bounds	bounding rectangle	The boundary rectangle for the window.
class	type class [r/o]	The class.
default type	type class [r/o]	The default descriptor type.
document	document [r/o]	The document that owns this window.
index	integer	The number of the window.
name	international text [r/o]	The document's name as shown in the window's titlebar.
page number	integer	The number of the currently displayed page.

Property	Class	Description
position	point [r/o]	The upper left coordinates of the window.
visible	Boolean [r/o]	Whether the window is visible.
zoomed	Boolean	Whether the window is zoomed.
zoom factor	small real	The current zoom factor specified as a percentage. For example, a value of 100 corresponds to a zoom factor of 1.0 (100%).
zoom type	constant	The zooming and content fitting algorithm currently employed. Possible values: no vary, fit page, fit width, fit height, and fit visible width.

Related methods

go backward

go forward

goto

goto next

goto previous

read page down

read page up

scroll

select text

zoom

PostScript Conversion

A file type converter that exports PDF files into PostScript format.

Properties

Inherits other properties from <u>conversion</u>.

Property	Class	Description
annotations	Boolean [r/o]	Determines whether to include annotations.
binary	Boolean [r/o]	Determines whether the output file should be in binary or ASCII text format.

Property	Class	Description
embedded fonts	Boolean [r/o]	Determines whether to include fonts.
halftones	Boolean [r/o]	Determines whether to use halftone screens.
images	Boolean [r/o]	Determines whether to include RGB and LAB images.
postScript level	integer [r/o]	The PostScript Language level. Only levels 2 and 3 are supported.
preview	Boolean [r/o]	Determines whether to include preview in output.
TrueType	Boolean [r/o]	Determines whether to convert TrueType fonts to Type 1.

Related methods

save

Text Annotation

A PDF text annotation (note) on a page in a PDF file. Can only be used as the target of a <u>make</u> event. All other access is via the <u>annotation</u> class.

Note: This object was formerly known as TextAnnot.

Properties

Inherits from <u>annotation</u>.

Related methods

find next note

perform

replace pages

Required suite events

The following events are sent by the Finder to all applications:

- open
- print
- quit
- run

Note: Most of these events have counterparts in the Core suite that have greater functionality. The Required suite is not listed in the AppleScript dictionary, even though it is implemented.

Adobe Reader also supports the Required suite events, but no others.

open

Opens a file.

Syntax

open [reference]

Parameters

open

The file or files to open.

print

Prints one or more files.

Syntax

print [reference]

Parameters

print

The file or files to print.

quit

Terminates an application. For information on a variant event in the Core suite that accepts options, see guit on page 160.

Syntax

quit

run

Launches the application and invokes its standard startup procedures.

Syntax

run

Core suite events

Acrobat supports the following subset of the Core suite of Apple events:

- close
- count
- <u>delete</u>
- <u>exists</u>
- get
- <u>make</u>
- move
- open
- quit
- save
- set

close

Closes a document.

Syntax

close [reference] saving [constant] linearize [boolean]

Parameters

close	The document to close.
saving	Determines whether to save a document that has been modified before quitting. Possible values:
	yes — Save the document.
	no — Do not save the document.
	ask — Ask the user whether to save the document.
	The default value is ask.
linearize	Determines whether the document should be optimized for the web when saving before closing.

Related events

open

count

Counts the number of instances of a particular class.

Syntax

```
count [type class] of [reference]
```

Parameters

count	The class whose instances are to be counted.
each	The class whose instances are to be counted. This keyword is optional.

Note: There is an alternate form using the keyword each in which the parameters are reversed:

```
count [reference] each [type class]
```

Returns

An integer specifying the number of elements.

AppleScript example

```
count annotation of document "dev_acro.pdf"
count menu item of menu "View"
count document 1 each bookmark
```

delete

Deletes one or more objects.

Syntax

delete [reference]

Parameters

delete	The object to be deleted.
--------	---------------------------

Related events

<u>make</u>

exists

AppleScript example

delete first bookmark of document "test.pdf"

exists

Tests whether a specified object exists.

Syntax

[reference] exists
exists [reference]

Parameters

exists

Object whose existence is checked.

Returns

true if the object exists, false otherwise.

AppleScript example

exists second document second document exists

get

Retrieves the value of an object or property.

Syntax

get [reference] as [class]

Note: The keyword get is optional.

Parameters

get	The object or property whose value is returned.
as	The form in which the data is returned.

Returns

The value of the specified property or object. If the specified object does not exist, no result is returned.

Related events

set

AppleScript example

```
get the name of last bookmark get the index of last bookmark as string
```

make

Creates a new object.

Syntax

make new [type class] at [location reference] with data [anything] with properties [record]

Parameters

make [new]	The class of the new object.
at	The location at which to insert the new object.
with data	The initial data for the new object.
with properties	The initial values for the properties of the new object.

Returns

A reference to the newly created object.

Related events

<u>delete</u>

exists

AppleScript example

```
set myAnnotation to make TextAnnotation at beginning set name of myAnnotation to "Werner Heisenberg" set contents of myAnnotation to "Might have been here"
```

move

Moves a page object.

Syntax

move [reference] to [location reference]

Parameters

move	The page object to move. The first page in a document is page 1.
to	The new location for the page.

Returns

A reference to the page that is moved.

AppleScript example

move page 3 to before page 1

open

Opens a document or documents.

Syntax

open [list of alias] invisible [boolean] options [string]

Parameters

open	The document or documents to open.
invisible	Whether the opened document should be hidden. Default is false.
options	Optional parameter string of open actions.

Related events

close

quit

Causes the Acrobat application to quit.

Syntax

quit saving [constant]

Parameters

saving	Determines whether to save documents that have been modified before quitting. Possible values:
	yes — Save the document.
	no — Do not save the document.
	${\tt ask}$ — If the documents have been modified, ask the user whether to save them.
	The default value is ask.

AppleScript example

quit saving yes

save

Saves a document.

Syntax

save [reference] to [file specification] using [reference] linearize[boolean]

Parameters

save	The document to be saved.
to	The file into which the document is to be saved. This parameter is optional in Acrobat 6.0 and higher. Specifying the to parameter is equivalent to doing a Save As. You can save a document in one of the supported formats with the using parameter.
linearize	Determines whether the document should be optimized for the web.
using	The conversion method used to save the document in the desired format. Supported conversions by name are EPS Conversion and PostScript Conversion . All others can be specified by index using the conversion object.

AppleScript example

save document 1 to file "MyHardDrive:tempBig.ps" using PostScript Conversion with embedded fonts, images, preview, and annotation without binary given postScript level: 1

set

Sets an object's data or properties.

Syntax

set [reference] to [anything]

Parameters

set	The object or property whose value is set.
to	The new value.

Related events

get

AppleScript example

set the name of first bookmark to "Chapter 1"

Acrobat application events

This section describes a number of Acrobat API calls for the Apple event interface that are specific to Acrobat applications. The supported events in this suite are:

- bring to front
- <u>clear selection</u>
- close all docs
- create thumbs
- delete pages
- delete thumbs
- <u>execute</u>
- find next note
- find text
- get info
- go backward
- go forward
- goto
- goto next
- goto previous
- insert pages
- is toolbutton enabled
- <u>maximize</u>
- perform
- print pages
- read page down
- read page up
- remove toolbutton
- replace pages
- scroll
- select text
- set info
- zoom

Apple encourages the use of an application's signature as the name of its class for application-specific Apple events. The string CARO is the name of the class for Acrobat-specific Apple events:

#define kAEAcrobatViewerClass 'CARO'

AppleScript does not need this information.

bring to front

Brings the specified document's window to the front.

Syntax

bring to front [reference]

Parameters

bring to front

The document to be displayed as the active document in the front window.

AppleScript example

bring to front document "AppleEvt.pdf"

Apple event ID

kAEBringToFront ('bfrt')

clear selection

Clears the document's current selection, if any.

Syntax

clear selection [reference]

Parameters

clear selection

The document containing the selection to be cleared

Related events

select text

AppleScript example

clear selection document "PLUGINS.PDF"

Apple event ID

kAEClearSelection ('clsl')

close all docs

Closes all documents.

Syntax

close all docs saving [constant]

Parameters

saving	Determines whether to save modified documents before closing. Possible values:
	yes — Save the document.
	no — Do not save the document.
	ask — If the document has been modified, ask the user whether to save it.
	The default value is ask.

Related events

open (Required suite)

open (Core suite)

AppleScript example

close all docs

Apple event ID

kAECloseAllDocs ('cldc')

create thumbs

Creates thumbnail images for all pages in the document.

Syntax

create thumbs [reference]

Parameters

create thumbs	The document in which thumbnails are created.	
---------------	---	--

Related events

delete thumbs

AppleScript example

create thumbs document "roadmap.pdf"

Apple event ID

kAECreateThumbs ('crtb')

delete pages

Deletes the specified pages in the document.

Syntax

```
delete pages [reference] first [integer] last [integer]
```

Parameters

delete pages	The document containing the pages to be deleted.
first	The first page to be deleted. The first page in a document is page 1.
last	The last page to be deleted.

Related events

insert pages

replace pages

AppleScript example

```
delete pages document "AppleEvt.pdf" first 1 last 3
```

Apple event ID

```
kAEDeletePages ('dlpg')
```

Apple event parameters

```
keyAEFirstPage ('frpg')
keyAELastPage ('lapg'')
```

delete thumbs

Deletes all thumbnails from the document.

Syntax

```
delete thumbs [reference]
```

Parameters

delete thumbs	The document from which thumbnails are deleted.

Related events

create thumbs

AppleScript example

delete thumbs document "AppleEvt.pdf"

Apple event ID

kAEDeleteThumbs ('dltb')

execute

Executes the specified menu item.

Syntax

execute [reference]

Parameters

execute	The menu item to execute. See the Acrobat and PDF Library API Reference
	for a list of menu item names.

AppleScript example

activate
execute menu item "Open"

Apple event ID

kAEExecute ('exec')

find next note

Finds and selects the next text note in a document.

Syntax

find next note [reference] wrap around [boolean]

Parameters

find next note	The document in which to find the next text note.
wrap around	Determines whether to continue the search at the beginning of a document if a note has not been found after the end of the document is reached. If true, the search wraps around; otherwise it does not. The default value is false.

Returns

The text annotation found.

Related events

find text

AppleScript example

find next note document "dev_acro.pdf"

Apple event ID

kAEFindNextNote ('fnnt')

Apple event parameters

keyAEWrapAround ('wrar')

find text

Finds text in a document.

Syntax

find text [reference] string [international text] case sensitive [boolean]
whole words [boolean] wrap around [boolean]

Parameters

find text	The document to be searched.
string	The string to be found.
case sensitive	Determines whether searching is case-sensitive. The default value is false.
whole words	Determines whether to search only for whole words. The default value is false.
wrap around	Determines whether to continue the search at the beginning of a document if the specified text has not been found after the end of the document is reached. If true, the search wraps around; otherwise it does not. The default value is false.

Related events

find next note

AppleScript example

find text document "PLUGINS.PDF" string "Develop" whole words true

Apple event ID

kAEFindText ('ftxt')

Apple event parameters

```
keyAESearchString ('sstr')
keyAECaseSensitive ('case')
keyAEWholeWordsOnly ('whwd')
keyAEWrapAround ('wrar')
```

get info

Gets the value of the specified key in the document's Info dictionary.

Syntax

```
get info [reference] key [international text]
```

Parameters

get info	The document from which to obtain the Info dictionary entry.
key	The case-sensitive Info dictionary key whose value is to be obtained. The predefined keys are: Creator, Producer, CreationDate, Author, Title, Subject, and Keywords. None of these is required in the PDF file.

Returns

A string containing the specified key's value, or an empty string if the key is not found.

AppleScript example

```
get info document "PLUGINS.PDF" key "CreationDate"
```

Apple event ID

```
kAEGetInfo ('gnfo')
```

Apple event parameters

keyAEInfoKey ('inky')

go backward

Goes to the previous view in the stored view history. Does nothing if the current view is the first view in the history.

Syntax

```
go backward [reference]
```

Parameters

Related events

```
go forward
goto
goto next
goto previous
```

AppleScript example

```
go backward first PDF Window
```

Apple event ID

```
kAEGoBack ('gbck')
```

go forward

Goes to the next view in the stored view history. Does nothing if the current view is the last view in the history.

Syntax

```
go forward [reference]
```

Parameters

go forward

A PDF Window object

Related events

```
go backward
goto
goto next
```

goto previous

AppleScript example

```
go forward first PDF Window
```

Apple event ID

kAEGoForward ('qfwd')

goto

Displays the page that has the specified page number.

Syntax

```
goto [reference] page [integer]
```

Parameters

goto	The PDF Window object in which to change the page.
page	The page number of the page to be displayed. The first page in a document is page 1.

Related events

```
go backward
```

go forward

goto next

goto previous

AppleScript example

```
goto first PDF Window page 2
```

Apple event ID

```
kAEGotoPage ('gtpg')
```

Apple event parameters

```
keyAEPageNumber ('pg #')
```

goto next

Displays the next page after the one currently displayed in the <u>PDF Window</u>. Does nothing if the current page is the last page in the document.

Syntax

```
goto next [reference]
```

Parameters

Related events

```
go backward

go forward

goto

goto previous
```

AppleScript example

```
goto next first PDF Window
```

Apple event ID

```
kAEGotoNextPage ('nxpg')
```

goto previous

Displays the previous page before the one currently displayed in the <u>PDF Window</u>. Does nothing if the current page is the first page in the document.

Syntax

```
goto previous [reference]
```

Parameters

goto previous

The PDF Window object in which to change the page.

Related events

```
go backward
go forward
goto
goto next
```

AppleScript example

```
goto previous first PDF Window
```

Apple event ID

kAEGotoPrevPage ('pvpg')

insert pages

Inserts one or more pages from one document into another.

Syntax

insert pages [reference] after [integer] from [reference] starting with [integer] number of pages [integer] insert bookmarks [boolean]

Parameters

insert pages	The target document in which to insert the page or pages.
after	The number of the page after which the pages will be inserted. The first page in a document is page 1.
from	The source document containing the page or pages to be inserted.
starting with	The first page to be inserted.
number of pages	The number of pages to be inserted.
insert bookmarks	Determines whether to copy bookmarks that point to the inserted pages. Default is true.

Related events

delete pages

AppleScript example

insert pages document "AppleEvt.pdf" after 2 from document "dev_acro.pdf"
starting with 1 number of pages 4

Apple event ID

kAEInsertPages ('inpg')

Apple event parameters

keyAEInsertAfter ('inaf')
keyAESourceDoc ('srdc')
kAESourceStartPage ('stpg')
keyAENumPages ('nmpg')
keyAEInsertBookmarks ('inbm')

is toolbutton enabled

Determines whether the specified toolbar button is enabled.

Syntax

is toolbutton enabled named [international text]

Parameters

named	Button name. See the <i>Acrobat and PDF Library API Reference</i> for a list of toolbar button names.

Returns

true if the toolbar button is enabled, false otherwise.

Related events

remove toolbutton

AppleScript example

is toolbutton enabled named "AcroSrch:Query"

Apple event ID

kAEIsToolButtonEnabled ('tben')

Apple event parameters

keyAEButtonname ('tbnm')

maximize

Sets the document's window size to either its maximum or original size.

Syntax

```
maximize [reference] max size [integer]
```

Parameters

maximize	The document whose window is to be resized.
max size	If true, the document's window is set to full size. If false, the window is returned to its original size.

AppleScript example

maximize document "AppleEvt.pdf" max size false

Apple event ID

kAEMaximize ('maxi')

Apple event parameters

keyAEMaxSize ('mxsz')

perform

Executes a bookmark's or link annotation's action.

Syntax

perform [reference]

Parameters

object	The bookmark or page object whose action is to be performed.
=	

AppleScript example

perform last bookmark

Apple event ID

kAEPerform ('prfm')

print pages

Prints one or more pages from a document without displaying a modal Print dialog box.

Syntax

print pages [reference] first [integer] last [integer] PS Level [integer]
binary output [boolean] shrink to fit [boolean]

Parameters

print pages	The document containing the page or pages to be printed. This keyword and the actual filename must be specified.
first	The first page to be printed. The default value is 1.
last	The last page to print. The default value is the number of the last page in the document.
PS Level	The PostScript language level (1 or 2) to use when printing to a PostScript printer. The default value is 1.
binary output	Determines whether binary output is permitted (used for PostScript printing only). The default value is false.
shrink to fit	Determines whether pages should be shrunk to fit paper in printer. The default value is false.

AppleScript example

print pages document "AppleEvt.pdf" first 1 last 3 PS Level 2 binary output true shrink to fit true

Apple event ID

```
kAEPrintPages ('prpg')
```

Apple event parameters

```
keyAEFirstPage ('frpg')
keyAELastPage ('lapg')
keyAEPSLevel ('pslv')
keyAEBinaryOK ('binO')
keyAEShrinkToFit ('s2ft')
```

read page down

Scrolls forward through the document by one screen.

Syntax

```
read page down [reference]
```

Parameters

read page down

The PDF Window object to be scrolled.

Related events

```
read page up scroll
```

AppleScript example

```
read page down first PDF Window
```

Apple event ID

```
kAEReadPageDown ('pgdn')
```

read page up

Scrolls backward through the document by one screen.

Syntax

```
read page up [reference]
```

Parameters

read page up

The PDF Window object to be scrolled.

Related events

read page down

scroll

AppleScript example

read page up first PDFPageWindow

Apple event ID

kAEReadPageUp ('pgup')

remove toolbutton

Removes the specified button from the toolbar.

Syntax

remove toolbutton named [international text]

Parameters

named

The name of the toolbar button to be removed. See the *Acrobat and PDF Library API Reference* for a list of toolbar button names.

Related events

is toolbutton enabled

AppleScript example

remove toolbutton named "ZoomIn"

Apple event ID

kAERemoveToolButton ('rmtb')

Apple event parameters

keyAEButtonname ('tbnm')

replace pages

Replaces one or more pages in a document with pages from another document.

Syntax

replace pages [reference] over [integer] from [reference] starting with [integer] number of pages [integer] merge notes [boolean]

Parameters

replace pages	The target document whose pages are to be replaced.
over	The first page to be replaced. The first page in a document is page 1.
from	The source document from which the replacement page or pages are obtained.
starting with	The first page in the source document to be copied.
number of pages	The number of pages to be replaced.
merge notes	Determines whether to copy notes from the source document. The default value is true.

Related events

delete pages

insert pages

AppleScript example

replace pages document "AppleEvt.pdf" over 2 from document "dev_acro.pdf" starting with 1 number of pages 4 merge notes false

Apple event ID

kAEReplacePages ('rppg')

Apple event parameters

```
keyAEDestStartPage ('dtpg')
keyAESourceDoc ('srdc')
keyAESourceStartPage ('stpg')
keyAENumPages ('nmpg')
keyAEMergeNotes ('mgnt')
```

scroll

Scrolls the view of a page by the specified amount.

Syntax

```
scroll [reference] X Amount [integer] Y Amount [integer]
```

Parameters

scroll	The PDF Window object in which to scroll the view.	
X Amount	The amount to scroll in the horizontal direction, in pixels. Positive values move the view to the right.	
Y Amount	The amount to scroll in the vertical direction, in pixels. Positive values move the view down.	

Related events

```
read page down
read page up
```

AppleScript example

```
scroll first PDFWindow X Amount 20 Y Amount 100
```

Apple event ID

```
kAEScroll ('scrl')
```

Apple event parameters

```
keyAEXDelta ('xdlt')
keyAEYDelta ('ydlt')
```

select text

Selects text as specified by either character or word offsets.

Syntax

```
select text [reference] from words [list of integer] from chars [list of integer]
```

Parameters

select text	The PDF Window object in which to select text.
from words	The words to be selected. This consists of one or more pairs of word offsets from the beginning of the document and word lengths (the number of contiguous words).
from chars	Characters to be selected. This consists of one or more pairs of character offsets from the beginning of the document and character lengths (the number of contiguous characters).

Related events

clear selection

AppleScript example

```
repeat with i from 1 to 10
    repeat with j from 1 to (10 - i)
    select text from words {i, j}
    end repeat
end repeat
```

Apple event ID

kAESetTextSelection ('stxs')

Apple event parameters

```
keyAEWordList ('fmwd')
keyAECharList ('fmch')
```

set info

Sets the value of a specified key in the document's Info dictionary

Syntax

```
set info [reference] key [international text] value [international text]
```

Parameters

set info	The PDF Window in which to set the value of an Info dictionary entry.
key	The Info dictionary key whose value is to be set.
value	The value to be stored.

AppleScript example

```
set info document "PlugIns.pdf" key "Author"
value "Wolfgang Pauli"
```

Apple event ID

```
kAESetInfo ('snfo')
```

Apple event parameters

```
keyAEInfoKey ('inky')
keyAEInfoValue ('invl')
```

zoom

Changes the zoom level of the specified PDF Window.

Syntax

```
zoom [reference] to [small real]
```

Parameters

zoom	The PDF Window object to be zoomed.
to	The zoom factor specified as a percentage. For example, a value of 100 (100%) displays the document with a magnification of 1.0.

AppleScript example

zoom first PDFWindow to 150

Apple event ID

kAEZoomTo ('zmto')

Apple event parameters

keyAEZoomFactor ('zmft')

Miscellaneous events

Acrobat provides an Apple event that does not fall into one of the regular suites: do script

do script

Executes the specified JavaScript script.

Syntax

do script [international text] file [alias]

Parameters

do script	The JavaScript script to be executed.
file	File holding the JavaScript script to be executed.

Returns

Result of JavaScript execution as text.

AppleScript example

do script MyJavaScriptFile.js

4

Acrobat Catalog Plug-In

This chapter describes IAC support for the Acrobat Catalog plug-in, which allows you to create a full-text index of a set of PDF documents. A full-text index is a searchable database of all the text in the documents. After building an index, you can use the Acrobat Search command to search the entire library quickly. Searches of full-text indexes created using Catalog are faster and more convenient than using the Find command.

For more information on Catalog, see the Acrobat Help and the Acrobat and PDF Library API Reference.

Catalog Windows messages

Catalog broadcasts a set of Windows messages when certain operations occur. These messages are broadcast whether the operations are initiated from the user interface, HFT methods, or DDE methods.

AcrobatCatalogBuildSuccess — On every successful build.

AcrobatCatalogBuildFail — On every failed build.

AcrobatCatalogBuildStopped — When a build has stopped.

Catalog DDE methods

Clients can connect to the Catalog plug-in through DDE using the service name Acrobat and the topic name Control. This section lists the available DDE methods.

AppExit

Exits Acrobat Catalog.

Syntax

[AppExit()]

Returns

If true, Catalog exited successfully, otherwise false.

AppFront

Brings Catalog to the front.

Syntax

[AppExit()]

FileBuild

Builds an index based on the specified index definition file.

Syntax

```
[FileBuild(char* fullPath)]
```

Parameters

fullPath

The full path of the file to be opened, including the .pdx extension.

Returns

If true, the file opened successfully, otherwise false.

FileOpen

Opens an index definition file and displays the Edit Index Definition dialog box.

Syntax

```
[FileOpen(char* fullPath)]
```

Parameters

fullPath

The full path of the file to be opened, including the .pdx extension.

Returns

true if the file opened successfully, otherwise false.

FilePurge

Purges an index definition file.

Syntax

```
[FilePurge(char* fullPath)]
```

Parameters

fullPath

The full path of the file to be purged, including the .pdx extension.

Returns

true if the file was successfully purged, otherwise false.

Acrobat Forms Plug-In

The Acrobat Forms plug-in allows a PDF document to act as a form; that is, the Acrobat equivalent of a paper form with fields. This chapter describes the OLE automation methods exported by the Acrobat AcroForm plug-in.

The Forms plug-in for Acrobat (versions 4.0 and above) allows users to author form fields. For Adobe Reader, the Forms plug-in does not allow form authoring, but allows users to fill in data and print Acrobat forms. The Adobe Reader Forms plug-in also does not allow users to save data to the local hard disk. Both Acrobat and Adobe Reader allow Web designers to send data from the form back to a Web server.

Note: Forms as used here do not refer to XObject forms as defined in the PDF Reference.

For more information on Forms, see the Acrobat Help and the Acrobat and PDF Library API Reference.

Forms plug-in OLE automation

The Acrobat Forms plug-in works as an automation server in the Windows environment. Because the automation capabilities have been added to a plug-in, rather than an executable that can be directly launched, the following steps are necessary to access them from an automation controller:

 Instantiate the Acrobat application by using the Visual Basic CreateObject method. For example: CreateObject ("AcroExch.App")

This causes the Acrobat Forms plug-in to run, at which time it registers its class object with OLE.

2. Instantiate the main exposed object:

```
CreateObject("AFormAut.App")
```

Registration in the Windows registry (which is different from the class object registration described above) happens every time Acrobat loads the plug-in. Therefore, you must run Acrobat at least once with the AForm32.api file in the plug-ins folder before its type library can be found for object browsing within the Microsoft Visual Studio environment. This is also necessary in order to allow early binding. Declare the program variables as objects of the corresponding classes in AFORMAUTLib, and not simply as Object.

Note: Neither Acrobat nor the Acrobat Forms plug-in are thread-safe, and therefore Acrobat Forms OLE automation uses the single-threading model.

Exceptions

All methods and properties may return an exception. These may include standard OLE exceptions, such as:

- E_OUTOFMEMORY (0x8007000E)
- E INVALIDARG (0x80070057)

These exceptions are not specifically listed in the descriptions of the methods and properties that appear in this chapter. Others are Acrobat Forms-specific, and are listed in the following table.

The actual numeric value of the returned exception is assembled as an HRESULT, uses the FACILITY_ITF, and starts with decimal 512 (hex 0x0200), as recommended by Microsoft. For example, the numeric value of the exception AutErcNoForm is 0x80040201. The important part is the right-most (0x201), which is the first error in the enumeration below.

Exception name	Numeric value	Description
AutErcNoDoc	1	No document is currently open in the Acrobat application.
AutErcNotTerminal	2	This property or method applies to terminal fields or their annotations.
AutErcNotToThisFieldType	3	This property or method is not applicable to this type of field.

AFormApp

AFormApp is the only object the controller can externally instantiate (that is, using CreateObject). All other objects must be created by navigating down the hierarchy with the methods and properties described in this section.

Field

A field in the document that is currently active in Acrobat.

Methods

The Field object has the following methods.

- PopulateListOrComboBox
- SetBackgroundColor
- SetBorderColor
- SetButtonCaption
- SetButtonIcon
- SetExportValues
- SetForegroundColor
- SetJavaScriptAction
- SetResetFormAction
- SetSubmitFormAction

PopulateListOrComboBox

Specifies the item names and optionally exports values for a field of type listbox or combobox.

Syntax

Parameters

arrItems	An array of strings, with each element representing an item name.
	There is a limit of 64K for string data in a combo or list box control on Windows platforms. For Mac OS systems, the limit is 200 entries for the combo or list box control. Using more than these limits degrades performance and makes the control unusable.
arrExportVal	Optional. An array of strings, the same size as the first parameter, with each element representing an export value.
. <u>.</u>	Some of the elements in exportString may be empty strings.

Exceptions

Raises <u>AutErcNotToThisFieldType</u> if the field is not of type listbox or combobox.

Related methods

<u>Add</u>

${\bf Set Background Color}$

Specifies the background color for a field. The background color is used to fill the field's rectangle.

Syntax

void SetBackgroundColor (LPCTSTR bstrColorSpace, float GorRorC, float GorM,
float BorY, float K);

Parameters

bstrColorSpace	Values are defined by using a transparent, gray, RGB or CMYK color space. Valid strings include:	
	• T	
	• G	
	• RGB	
	• CMYK	
GorRorC	Used if bstrColorSpace is set to T, G, or RGB. A float range between zero and one inclusive.	
GorM	Used if bstrColorSpace is set to G. A float range between zero and one inclusive.	

BorY	Used if bstrColorSpace is set to RGB. A float range between zero and one inclusive.
K	Used if bstrColorSpace is set to CMYK. A float range between zero and one inclusive.

Related methods

SetBorderColor

<u>SetForegroundColor</u>

Example

Field.SetBackgroundColor "RGB", 0.7, 0.3, 0.6, 0

SetBorderColor

Specifies the border color for a field. The border color is used to stroke the field's rectangle with a line as large as the border width. The new border color is propagated to any child annotations underneath, so the field may be non-terminal.

Syntax

void SetBorderColor (LPCTSTR bstrColorSpace, float GorRorC, float GorM, float
BorY, float K);

Parameters

bstrColorSpace	Values are defined by using a transparent, gray, RGB or CMYK color space. Valid strings include:
	• T
	• G
	• RGB
	• CMYK
GorRorC	Used if bstrColorSpace is set to T, G, or RGB. A float range between zero and one inclusive.
GorM	Used if bstrColorSpace is set to G. A float range between zero and one inclusive.
BorY	Used if bstrColorSpace is set to RGB. A float range between zero and one inclusive.
K	Used if bstrColorSpace is set to CMYK. A float range between zero and one inclusive.

Related methods

SetBackgroundColor

<u>SetForegroundColor</u>

Example

Field.SetBorderColor "RGB", 0.7, 0.3, 0.6, 0

SetButtonCaption

The caption to be used for the appearance of a field of type button.

Syntax

void SetButtonCaption (LPCTSTR bstrFace, LPCTSTR bstrCaption);

Parameters

bstrFace	A string that specifies the face for which the caption will be used. Valid strings include:
	N — Normal appearance
	D — Down appearance
	R — Appearance for rollover
bstrCaption	The caption for the button.
	If a button's layout is of type icon only, the caption is not used in generating its appearance. In addition, only the Normal face is displayed, unless the Highlight is of type push.

Exceptions

Raises <u>AutErcNotToThisFieldType</u> if the field is not of type button. The new appearance is propagated to any child annotations underneath; the field may be non-terminal.

Related methods

SetButtonIcon

Example

Field.SetButtonCaption "D", "Submit Form"

SetButtonIcon

Specifies the icon to be used for the appearance of a field of type button.

Syntax

void SetButtonIcon (LPCTSTR bstrFace, LPCTSTR bstrFullPath, short pageNum);

Para	meters
------	--------

bstrFace	A string that specifies the face for which the icon will be used. Valid strings include:
	N — Normal appearance
	D — Down appearance
	R — Appearance for rollover
bstrFullPath	The full path of the PDF file to be used as the source of the appearance.
pageNum	Used to select the page inside that PDF file (zero-based).
	If a button's layout is of type icon only, the caption is not used in generating its appearance. In addition, only the Normal face is displayed, unless the Highlight is of type push.

Exceptions

Raises <u>AutErcNotToThisFieldType</u> if the field is not of type button. The new appearance is propagated to any child annotations underneath, so it is OK if the field is non-terminal.

Related methods

SetButtonCaption

Example

Field.SetButtonIcon "N", "c:\Clipart.pdf", 0

SetExportValues

Sets the export values for each of the annotations of a field of type radio button and checkbox.

For radio button fields, this is necessary to make the field work properly as a group. One button is checked at any given time, giving its value to the field as a whole.

For checkbox fields, unless an export value is specified, the default is used when the field checked is Yes. When it is unchecked, its value is Off (this is also true for a radio button field when none of its buttons are checked).

Syntax

void SetExportValues (const VARIANT& arrExportVal);

Parameters

arrExportVal	An array of strings, which is expected to have as many elements as there are
	annotations in the field. The elements of the array are distributed among the individual annotations comprising the field, using their tab order.

Exceptions

Raises AutErcNotToThisFieldType if the field is not of type radio button or checkbox.

Related methods

Add

Example

```
Dim arrExp(1) As String
arrExp(0) = "CreditCardA"
arrExp(1) = "CreditCardB"
Field.SetExportValues arrExp
```

SetForegroundColor

Specifies the foreground color for a field. It represents the text color for text, button, combobox, or listbox fields and the check color for checkbox or radio button fields.

The parameters are similar to SetBorderColor and SetBackgroundColor, except that the transparent color space is not allowed.

Syntax

void SetForegroundColor (LPCTSTR bstrColorSpace, float GorRorC, float GorM,
float BorY, float K);

Parameters

bstrColorSpace	Values are defined by using a transparent, gray, RGB or CMYK color space. Valid strings include:	
	• T	
	• G	
	• RGB	
	• CMYK	
GorRorC	Used if bstrColorSpace is set to T, G, or RGB. A float range between zero and one inclusive.	
GorM	Used if bstrColorSpace is set to G. A float range between zero and one inclusive.	
BorY	Used if bstrColorSpace is set to RGB. A float range between zero and one inclusive.	
K	Used if bstrColorSpace is set to CMYK. A float range between zero and on inclusive.	

Related methods

SetBackgroundColor

SetBorderColor

Example

Field.SetForegroundColor "CMYK", 0.25, 0.25, 0.25, 0.1

SetJavaScriptAction

Sets the action of the field to be of type JavaScript. When using SetJavaScriptAction within Visual Basic, you can use Chr(13) to add a <CR>, and Chr(9) for tabs, so that the function is well formatted.

Syntax

void SetJavaScriptAction (LPCTSTR bstrTrigger, LPCTSTR bstrTheScript);

Parameters

bstrTrigger	A string that specifies the trigger for the action. Valid strings include:
	• up
	• down
	• enter
	• exit
	• calculate
	• validate
	• format
	• keystroke
bstrTheScript	The script itself.
	If the trigger is calculate, an entry is added at the end of the calculation order array (see the CalcorderIndex property).

Calculation script

A simple calculate script is supplied with Acrobat.

AFSimple_Calculate(cFunction, cFields)

- cFunction is one of AVG, SUM, PRD, MIN, MAX
- *cFields* is the list of the fields to use in the calculation.

Formatting scripts

The following scripts and formats can be used for the format and keystroke triggers:

AFDate_KeystrokeEx(cFormat)	cFormat is one of: "m/d", "m/d/yy", "mm/dd/yy", "mm/yy", "d-mmm", "d-mmm-yy", "dd-mmm-yy", "yy-mm-dd", "mmm-yy", "mmmm-yy", "mmm d, yyyy", "mmmm d, yyyy", "m/d/yy h:MM tt", "m/d/yy HH:MM"	
AFDate_Format(cFormat)		
AFTime_Keystroke(ptf) AFTime_Format(ptf)	<pre>ptf is the time format: 0 = 24HR_MM [14:30] 1 = 12HR_MM [2:30 PM] 2 = 24HR_MM_SS [14:30:15] 3 = 12HR MM SS [2:30:15 PM]</pre>	

AFPercent_Keystroke(nDec, sepStyle)	n Dec is the number of places after the decimal point.
AFPercent_Format(nDec, sepStyle)	sepStyle is an integer denoting whether to use a separator. If $sepStyle$ is 0, use commas. If $sepStyle$ is 1, do not separate.
AFSpecial_Keystroke(psf)	psf is the type of formatting to use:
AFSpecial_Format(psf)	0 = zip code
	1 = zip + 4 2 = phone
	3 = SSN
AFNumber_Format(nDec, sepStyle,	nDec is the number of places after the decimal point.
<pre>negStyle, currStyle, strCurrency, bCurrencyPrepend) AFNumber_Keystroke(nDec, sepStyle, negStyle, currStyle, strCurrency,</pre>	sepStyle is an integer denoting whether to use a separator. If $sepStyle$ is 0, use commas. If $sepStyle$ is 1, do not separate.
bCurrencyPrepend)	<pre>sepStyle is the formatting used for negative numbers:</pre>
	0 = MinusBlack 1 = Red 2 = ParensBlack 3 = ParensRed
	currStyle is the currency style - not used.
	strCurrency is the currency symbol.
	bCurrencyPrepend is true to prepend the currency symbol; false to display on the end of the number.

SetResetFormAction

Sets the action of the field to be of type ResetForm.

Syntax

void SetResetFormAction (LPCTSTR bstrTrigger, long theFlags, const VARIANT& arrFields);

Parameters

bstrTrigger	A string that specifies which trigger is used for the action. Valid strings include:
	up — Mouse up
	down — Mouse down
	enter — Mouse enter
	exit — Mouse exit
theFlags	When 0 (Include), arrFields specifies which fields to include in the reset operation. When non-zero (Exclude), arrFields specifies which fields to exclude from the reset operation.

arrFields	Optional. An array of strings for the fully-qualified names of the fields. Depending on the value of $theFlags$, these fields are included in or excluded from the reset operation.
	When the fields are included, the set can include the names of non-terminal fields, which is a fast and easy way to cause all their children to be included in the action.
	When not supplied, all fields are reset.

SetSubmitFormAction

Sets the action of the field to be of type SubmitForm.

Syntax

void SetSubmitFormAction (LPCTSTR bstrTrigger, LPCTSTR bstrTheURL, long theFlags, const VARIANT& arrFields);

Parameters

bstrTrigger	A string that specifies which trigger is used for the action. Valid strings include: up — Mouse up
	down — Mouse down
	enter — Mouse enter
	exit — Mouse exit
bstrTheURL	A string containing the URL.
theFlags	A collection of flags that define various characteristics of the action.
	See the PDF Reference to learn how the binary value of this long is interpreted.
arrFields	Optional. If specified, represents an array of strings for the fully-qualified names of the fields to submit when the action is executed. If the array is interpreted as fields to submit (as opposed to fields excluded from the submission, depending on the least-significant bit in the flags), then it may include the names of non-terminal fields, which is a way to cause all their children to be included in the submission.
	If not specified, the created action does not include a /Fields key.

Properties

The Field object has the following properties.

- Alignment
- BorderStyle
- BorderWidth
- ButtonLayout
- <u>CalcOrderIndex</u>
- CharLimit

- DefaultValue
- Editable
- Highlight
- IsHidden
- <u>IsMultiline</u>
- <u>IsPassword</u>
- IsReadOnly
- IsRequired
- <u>IsTerminal</u>
- Name
- NoViewFlag
- PrintFlag
- Style
- TextFont
- <u>TextSize</u>
- Type
- Value

Alignment

The text alignment of a text field. Valid alignments are:

```
left
center
right
```

Syntax

```
[get/set] String
```

Returns

If the field is terminal and has multiple child annotations, a get returns the alignment for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, so the field may be non-terminal.

Exceptions

If the field is not of type text, an exception AutErcNotToThisFieldType is returned.

On a get, if the field is non-terminal, an exception AutercNotTerminal is returned.

Example

```
Field.Alignment = left
```

BorderStyle

The border style for a field. Valid border styles include solid, dashed, beveled, inset, and underline.

Syntax

[get/set] String

Returns

If it is terminal and has multiple child annotations, a get returns the value of the border style for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, so the field may be non-terminal.

Exceptions

On a get, raises AutErcNotTerminal if the field is non-terminal, an exception is returned.

Example

Field.BorderStyle = "beveled"

BorderWidth

The thickness of the border when stroking the perimeter of a field's rectangle. If the border color is transparent, this property has no effect except in the case of a beveled border. The value 0 represents no border, and the value 3 represents a thick border.

Syntax

[qet/set] short

Returns

If it is terminal and has multiple child annotations, a get returns the value of the border width for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, so the field may be non-terminal.

Exceptions

On a get, if the field is non-terminal, an exception <u>AutErcNotTerminal</u> is returned.

Example

Field.BorderWidth = 1

ButtonLayout

The layout appearance of a button. Valid values include:

- 0 Text only; the button has a caption but no icon.
- 1 Icon only; the button has an icon but no caption.
- 2 Icon over text; the icon should appear on top of the caption.
- 3 Text over icon; the text should appear on top of the icon.
- 4 Icon then text; the icon should appear to the left of the caption.
- 5 Text then icon; the icon should appear to the right of the caption.
- 6 Text over icon; the text should be overlaid on top of the icon.

If it is terminal and has multiple child annotations, a get returns the layout for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, therefore the field can be non-terminal.

Syntax

```
[get/set] short
```

Exceptions

If the field is not of type button, an exception AutErcNotToThisFieldType is returned.

On a get, if the field is non-terminal, an exception <u>AutErcNotTerminal</u> is returned.

Example

```
Field.ButtonLayout = 2
```

CalcOrderIndex

The zero-based calculation order of fields in the document. If you want the calculation for a field f2 to be performed after that for field f1, you need only set the CalcOrderIndex for f2 to f1's CalcOrderIndex + 1. The elements in the calculation order array are shifted to make room for the insertion, but the first calculation is still at index 0.

For more information, see the JavaScript for Acrobat API Reference.

Syntax

```
[get/set] short
```

Example

```
Set F1 = Fields("SubTotal")
Set F2 = Fields("Total")
F2.CalcOrderIndex = F1.CalcOrderIndex + 1
```

CharLimit

The limit on the number of characters that a user can type into a text field.

On a set, the property is propagated to any child annotations underneath, if any.

Syntax

[get/set] short

Exceptions

If the field is not of type text, an exception AutErcNotToThisFieldType is returned.

DefaultValue

The default value of the field. It returns the empty string if the field has no default value. If the field is non-terminal, an exception AutErcNotTerminal is returned.

Syntax

[get/set] String

See also

Value

Editable

Determines whether the user can type in a selection or must choose one of the provided selections. Comboboxes can be editable; that is, the user can type in a selection.

On a set, the property is propagated to any child annotations underneath, if any.

Syntax

[get/set] Boolean

Exceptions

Returns an exception of AutErcNotToThisFieldType if the field is not of type combobox.

Example

Field.Editable = False

Defines how a button reacts when a user clicks it. The four highlight modes supported are:

- none
- invert
- push
- outline

If it is terminal and has multiple child annotations, a get returns the highlight for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, so the field may be non-terminal.

Syntax

```
[get/set] String
```

Exceptions

If the field is not of type button, an exception <u>AutErcNotToThisFieldType</u> is returned.

On a get, if the field is non-terminal, an exception <u>AutErcNotTerminal</u> is returned.

Example

```
Field.Highlight = "invert"
```

IsHidden

Determines whether the field is hidden or visible to the user. If the value is true the field is invisible, and false indicates that the field is visible.

During get operations, if the field is non-terminal, an exception <u>AutErcNotTerminal</u> is returned. If it is terminal, and has multiple child annotations, a get returns the value of the hidden flag for the first child, whichever annotation that happens to be.

During set operations, the property is propagated to any child annotations underneath, therefore a field can be non-terminal.

Syntax

```
[get/set] Boolean
```

Example

```
'Hide "name.last"
Set Field = Fields("name.last")
Field.IsHidden = True
```

IsMultiline

Determines whether the text field is multi-line or single-line. On a set, the property is propagated to any child annotations underneath, if any.

Syntax

[get/set] Boolean

Exceptions

If the field is not of type text, an exception <u>AutErcNotToThisFieldType</u> is returned.

Example

Field.IsMultiline = True

IsPassword

Determines whether the field will display asterisks for the data entered. Upon submission, the actual data entered is sent. Fields that have the password attribute set will not have the data in the field saved when the document is saved to disk.

On a set, the property is propagated to any child annotations underneath, if any.

Syntax

[get/set] Boolean

Exceptions

If the field is not of type text, an exception AutErcNotToThisFieldType is returned.

Example

Field.IsPassword = True

IsReadOnly

The read-only characteristic of a field. When a field is read-only, the user can see the field but cannot change it. If a button is read-only, the user cannot click it to execute an action.

Because this is a field flag and not an annotation flag, both a get and a set of this property are allowed regardless of whether the field is terminal or non-terminal.

- A get on a non-terminal field retrieves that field's flag.
- A set changes the flag on all its terminal children.

Syntax

[get/set] Boolean

The required characteristic of a field. When a field is required, its value must be non-NULL when the user clicks a submit button that causes the value of the field to be sent to the web. If the field value is NULL, the user receives a warning message and the submit does not occur.

Since this is a field flag and not an annotation flag, both a get and a set of this property are allowed, regardless of whether the field is terminal or non-terminal.

A get on a non-terminal field retrieves that field's flag. A set changes the flag on all its terminal children.

Syntax

[get/set] Boolean

IsTerminal

true if the field is terminal, otherwise false.

Syntax

[read-only] Boolean

Example

Dim Field As AFORMAUTLib.Field Dim bTerminal As Boolean

'bTerminal should be True bTerminal = Field.IsTerminal

Name

The fully qualified name of the field. It is the default member of the Field interface.

Syntax

[read-only] String

NoViewFlag

Determines whether a given field prints but does not display on the screen.

Set the NoViewFlag property to true to allow the field to appear when the user prints the document but not when it displays on the screen; set it to false to allow both printing and displaying.

On a get, if the field is non-terminal, an exception <u>AutErcNotTerminal</u> is returned. If it is terminal, and has multiple child annotations, a get returns the value of the no-view flag for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, so the field may be non-terminal.

Syntax

[get/set] Boolean

PrintFlag

Determines whether a field prints. Set the PrintFlag property to true to allow the field to appear when the user prints the document, set it to false to prevent printing.

On a get, if the field is non-terminal, an exception <u>AutErcNotTerminal</u> is returned. If it is terminal, and has multiple child annotations, a get returns the value of the print flag for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, so the field may be non-terminal.

Syntax

```
[get/set] Boolean
```

Style

The style of a checkbox or a radio button (the glyph used to indicate that the check box or radio button has been selected).

Valid styles include:

```
check
cross
diamond
circle
star
square
```

If it is terminal and has multiple child annotations, a get returns the style for the first child, whichever annotation that happens to be.

On a set, the property is propagated to any child annotations underneath, therefore a field can be non-terminal.

Syntax

```
[get/set] String
```

Exceptions

During set, if the field is not of type checkbox or radio button, an exception https://doi.org/10.1007/journal.com/ is returned.

On a get, if the field is non-terminal, an exception AutErcNotTerminal is returned.

Example

```
Field.Style = "star"
```

The text font used when laying out the field. Valid fonts include:

```
Courier
Courier-Bold
Courier-Oblique
Courier-BoldOblique
Helvetica
Helvetica-Bold
Helvetica-Oblique
Helvetica-BoldOblique
Symbol
Times-Roman
Times-Bold
Times-Italic
Times-BoldItalic
ZapfDingbats
```

On a set, the property is propagated to any child annotations underneath, if any.

Syntax

```
[get/set] String
```

Example

```
Field.TextFont = "Times-BoldItalic"
```

TextSize

The text points size used in the field. In combobox and radio button fields, the text size determines the size of the check. Valid text sizes include zero and the range from 4 to 144 inclusive.

A text size of zero means that the largest point size that can still fit in the field's rectangle should be used. In multi-line text fields and buttons this is always 12 points.

On a set, the property is propagated to any child annotations underneath, if any.

Syntax

```
[get/set] short
```

Example

```
Field.TextSize = 18
```

Type

The type of the field as a string. Valid types that are returned:

```
text
button
combobox
listbox
checkbox
radiobutton
signature
```

Syntax

```
[read-only] String
```

Example

```
Set Field = Fields("name.last")
'Should print "name.last"
print Field
' Should print the type of field. Example,
' "text"
print Field.Type
```

Value

A string that represents the value of the field. Returns the empty string if the field has no value. If the field is non-terminal, an exception AuteroNotTerminal is returned.

For fields of type checkbox, the value Off represents the unchecked state. The checked state is represented using the export value. This is also true for radio buttons (where each individual button in a group should have a different export value; see SetExportValues on page 188). For fields of type listbox or combobox, if an export value is defined, then that represents the value, otherwise the item name is used.

These remarks apply also to DefaultValue.

Syntax

```
[get/set] String
```

Example

```
Dim arrExp(1) As String
arrExp(0) = "CreditCardV"
arrExp(1) = "CreditCardM"
Field.SetExportValues arrExp
Field.Value = arrExp(0)
```

Fields

A collection of all the fields in the document that are currently active in Acrobat at the time Fields is instantiated.

The Fields collection includes both terminal and non-terminal fields. A terminal field is one that either does not have children, or if it does, they are simply multiple appearances (that is, child annotations) of the field in question.

Note: If you instantiate a Fields object, and subsequently fields are manually added or removed using the Forms tool in Acrobat, the Fields object will no longer be in sync with the document. You must re-instantiate the Fields object.

Methods

The Fields object has the following methods.

- Add
- AddDocJavascript
- ExecuteThisJavascript
- ExportAsFDF
- ExportAsHtml
- ImportAnFDF
- Remove

Add

Dynamically adds a new field to the Acrobat form and to the Fields collection.

Returns the newly-created Field object. You can pass the name of an existing field as a parameter, as long as that field is of the same type as the one being created.

This is useful in the following circumstances:

- For radio buttons to use the <u>SetExportValues</u> method to make the radio buttons mutually exclusive.
- For fields that should have multiple appearances (that is, child annotations) in the document.

Syntax

LPDISPATCH Add (LPCTSTR bstrFieldName, LPCTSTR bstrFieldType, short pageNum, float left, float top, float right, float bottom);

Parameters

bstrFieldName	The fully-qualified name of the field.
bstrFieldType	Field type for the newly created field. Valid types are:
	• text
	• button
	• combobox
	• listbox
	• checkbox
	• radio button
	• signature
	You must use the quotation marks. See the sample code below.
	When creating list or combo boxes, there is a limit of 64K for string data on Windows platforms. Mac OS systems have a limit of 200 entries for the list or combo boxes. Using more than the limit degrades performance. You populate the fields of the list and combo boxes using the populateListOrComboBox method.

pageNum	The page number (zero-based).
<pre>left, top, right, bottom</pre>	These parameters are floats representing the left, top, right, and bottom coordinates of the field rectangle, measured in rotated page space; that is, [0,0] is always at the left bottom corner regardless of page rotation.

Returns

The newly-created Field object.

Related methods

<u>PopulateListOrComboBox</u>

Remove

Example

```
Set Field = Fields.Add("payment",_ "radiobutton", 0, 100, 600, 130, 570)
```

AddDocJavascript

Adds a document-level JavaScript function to the PDF file. When using AddDocJavascript, within Visual Basic, you can use Chr(13) to add a <CR>, and Chr(9) for tabs, so that the function is well formatted.

Syntax

void AddDocJavascript (LPCTSTR bstrScriptName, LPCTSTR bstrTheScript);

Parameters

bstrScriptName	The name of the function to be added to the document.
bstrTheScript	The definition to be added to the document.

Related methods

ExecuteThisJavascript

Example

```
'Adding a document-level JavaScript
'function, to compute factorials:
Fields.AddDocJavaScript "Fact", _
"function Fact(n)" & Chr(13) & _
"{" & Chr(13) & _
Chr(9) & "if (n <= 0)" & Chr(13) & _
Chr(9) & Chr(9) & "return 1;" & Chr(13) & _
Chr(9) & "else" & Chr(13) & _
Chr(9) & Chr(9) & "return n * Fact(n - 1);" & Chr(13) & _
"}"
```

ExecuteThisJavascript

Executes the specified JavaScript script.

Syntax

CString ExecuteThisJavascript (LPCTSTR bstrTheScript);

Parameters

bstrTheScript	A string containing a JavaScript script, which is executed by Acrobat in the context of the currently active document.
	See the JavaScript for Acrobat API Reference for information on event level values.

Returns

Returns a result by assigning it to event value.

Related methods

AddDocJavascript

Example

```
Fields.ExecuteThisJavaScript "var f = this.getField(""myButton""); f.delay = false;"
```

To get the returns in Visual Basic:

```
Dim cSubmitName As String
cSubmitName = Fields.ExecuteThisJavaScript
   "event.value = this.getField(""myField"").submitName;"
```

ExportAsFDF

Exports the data as FDF from an Acrobat form.

Syntax

```
void ExportAsFDF (LPCTSTR bstrFullPath, LPCTSTR bstrSubmitButton,
BOOL bEmptyFields, const VARIANT& arrFields);
```

Parameters

bstrFullPath	A full path of the file to which the produced FDF file will be saved.
bstrSubmitButton	The name of an existing form field of type button (in case you want to include it in the FDF file, as if it had been used to trigger a SubmitForm action). You can specify an empty string.

bEmptyFields	A Boolean value to indicate whether fields with no value should be included in the produced FDF file.
arrFields	Optional. An array of strings representing the fully-qualified names of the fields to include in the FDF file. This array may include the names of non-terminal fields, which is a fast and easy way to cause all their children to be included in the FDF file.

Related methods

ImportAnFDF

ExportAsHtml

Example

```
Dim arrFields(1) As String
arrFields(0) = "name"
arrFields(1) = "address"
'This will create an FDF that includes
'name.last, name.first, address.street,
'etc., but only if they have a value
'(since we are passing False for the
' "bEmptyFields" parameter.
Fields.ExportAsFDF "C:\Temp\out.fdf", "", False, arrFields
```

ExportAsHtml

Exports the data as HTML from an Acrobat form. This method is similar to <u>ExportAsFDF</u>. The only difference is that the form data is exported in URL-encoded format.

Syntax

void ExportAsHtml (LPCTSTR bstrFullPath, LPCTSTR bstrSubmitButton, BOOL bEmptyFields, const VARIANT& arrFields);

Parameters

bstrFullPath	A full path of the file to which the produced FDF file will be saved.
bstrSubmitButton	The name of an existing form field of type button (in case you want to include it in the FDF file, as if it had been used to trigger a SubmitForm action). You may pass an empty string.
bEmptyFields	A Boolean to indicate whether fields with no value should be included in the produced FDF file.
arrFields	Optional. An array of strings representing the fully-qualified names of the fields to include in the FDF file. This array may include the names of non-terminal fields, which is a fast and easy way to cause all their children to be included in the FDF file.

Related methods

ExportAsFDF

ImportAnFDF

Imports the FDF file into an Acrobat form.

Syntax

void ImportAnFDF (LPCTSTR bstrFullPath);

Parameters

bstrFullPath The full path of the file containing the FDF file to be imported.

Related methods

ExportAsFDF

Remove

Removes a field from the Acrobat Form and from the Fields collection.

Syntax

void Remove (LPCTSTR bstrFieldName);

Parameters

bstrFieldName	The fully-qualified name of the field to be removed from the Acrobat form. If the field has multiple child annotations, all of them are removed. If multiple fields
	have the same name, all are removed.

Related methods

Add

Example

```
'Remove fields you no longer used. Fields.Remove("MyOldField")
```

Properties

The Fields object has the following properties.

- Count
- <u>Item</u>
- NewEnum

Count

The number of items in the collection.

Syntax

[read-only] long

Example

```
Dim Field As AFORMAUTLib.Field
Dim nFields As Long

nFields = Fields.Count

For Each Field In Fields
If Field.IsTerminal Then
print Field.Value
End If
Next Field
```

Item

Takes the fully qualified name of the field (for example, "name.last") as a parameter, and returns the Field object for it. It is the default member of the Fields interface. That is, item is the property invoked if the object name is specified by itself without a property or a method in the controller script.

Syntax

```
[read-only] IDispatch*
```

Example

```
Dim Field As AFORMAUTLib.Field
Dim nFields As Long

Set Field = Fields.Item("name.last")
'Since Item is the default_ property:
Set Field = Fields("name.last")
```

NewEnum

The IEnumVariant enumerator for the collection.

You do not need to call this property directly. Visual Basic calls it in the background whenever the code contains a For Each Field In Fields loop. For example:

```
For Each Field in Fields
If Field.IsTerminal
print Field.Value
End If
Next Field
```

Syntax

[read-only] IUnknown*

Acrobat Search Plug-in

This chapter describes IAC support for the Acrobat Search plug-in, which allows users to perform text searches in PDF documents. It adds menus, menu items, toolbar buttons, and a Search panel to the Acrobat application. The Search plug-in exports a host function table (HFT) containing several methods that can be used by other plug-ins.

Search supports interapplication communication in the form of DDE messages in Windows and Apple events in Mac OS. These messages and events allow remote clients to submit search queries and manipulate a list of indexes (the list of indexes is referred to as the shelf).

For more information on the Search plug-in, see the Acrobat Help and the *Acrobat and PDF Library API Reference*.

Search plug-in using DDE

A client can connect to the Search plug-in with DDE using the service name "Acrobat Search" and the topic name "Acrobat Search".

```
DdeInitialize(&id, &DDE_ProcessMessage, APPCMD_CLIENTONLY, 0);
hszServerName = DdeCreateStringHandle(id, "Acrobat Search", 0);
hszTopicName = DdeCreateStringHandle(id, "Acrobat Search", 0);
hConv = DdeConnect(id, hszServerName, hszTopicName, NULL);
```

After a connection has been made, a single poke transaction will submit a search query. Two types of queries are supported: simple query and query.

Simple query item

A simple query has the item name "SimpleQuery". When using a simple query, pass only a string that contains the query, using the ASQL query parser's format (see QLangType_CQL in the table "Query language type constants" on page 211). It is not possible to choose another parser or to set word options using the simple query item.

Query item

A query has the item name "Query". When using query, a QueryData structure is used. This structure contains the query, as well as specifying the query parser to use and additional options.

```
hszItemName = DdeCreateStringHandle(id, "Query", 0);
DdeClientTransaction(qd, nLen, hConv, hszItemName, CF_TEXT, XTYP_POKE,
1000, &dwResult);
DdeDisconnect(hConv)
```

The global data handle (qd) passed to the server must be in the following format:

```
typedef struct _QueryData {
   eQLangType qlt;
   boolean bOverrideWordOptions;
   uns32 nWordOptions;
   uns16 nMaxDocs;
   uns16 nQueryOffset;
   uns16 nNumSorts; //deprecated in Acrobat 6.0
   uns16 nSortOffset[QP_MAX_SORT_FIELDS]; //deprecated in Acrobat 6.0
   boolean bSortWays[QP_MAX_SORT_FIELDS]; //deprecated in Acrobat 6.0
   unsigned char cData[1];
} QueryData;
```

Query options

qlt	The query language type. Must be one of the values shown in <u>"Query language type constants"</u> on page 211.
bOverrideWordOptions	Indicates that the client wishes to use different word options than those currently set by the user.
nWordOptions	The word options. Must be an OR of the values shown in <u>"Word option bit-flag constants"</u> on page 211.
nMaxDocs	If non-zero, the client wishes to use a different limit for the maximum number of documents than the limit currently set by the user.
nSortOffsets	A list of offsets into the cData chunk. Each offset points to a NULL-terminated string containing the field name.
	This value has no effect in Acrobat 6.0 or later, because sort options are not valid.
nQueryOffset	An offset into the \mathtt{cData} chunk that points to a $\mathtt{NULL}\text{-terminated}$ string containing the query to execute.
nNumSorts	The number of fields in the sort spec. If this number is 0, the plug-in uses the current sort spec set by the user.
	This value has no effect in Acrobat 6.0 or later, because sort options are not valid.
bSortWays	A list of sort order flags, one for each sort field. true indicates an ascending sort, and false indicates a descending sort.
	This value has no effect in Acrobat 6.0 or later, because sort options are not valid.

Query language type constants

QLangType_Simple	Allows only simple phrase searches; does not allow Boolean searching.
	This query type does not work in the DDE interface of the Search plug-in shipped with version 2.0 of Acrobat.
QLangType_CQL	Allows Boolean searches using AND, OR, and NOT, as described in the Acrobat Search plug-in's online help file.
QLangType_Passthrough	The Verity BooleanPlus query language. Contact Verity for further information on this language.

Word option bit-flag constants

QPON_Case	The search is case-sensitive.
QPON_Stemming	Find not only the specified word, but other words that have the same stem. For example, run and ran have the same stem.
QPON_SoundsLike	Find not only the specified word, but other words that sound like it.
QPON_Thesaurus	Find not only the specified word, but other words that have the same meaning.
QPON_Proximity	Consider the proximity of results when using the AND operator to look for more than one word in a document. Without this option, AND terms can be anywhere in a document. Searching for "red" and "blue," for example, finds a document where "red" is the first word on the first page and where "blue" is the last word on the last page. With this option, however, AND terms must be within two or three pages of each other to be found. Also, the closer AND terms appear together, the higher the relevance ranking of the document that contains them.
QPON_Refine	Do not search the entire list of indexes, but only the documents that matched the previous search. This is used to refine the results of the previous search.

To create and populate this structure correctly, the client must know the sum of the lengths of each sort field (sls), the length of the query (lq), and the size of the QueryData structure. The client then allocates memory as follows:

```
nSize = sizeof(QueryData) + sls + lq;
qd = (QueryData *)malloc(nSize);
```

For example, if the query was "Adobe" and the sort spec was "Title" ascending and "Score" descending then the structure would be packed as follows:

```
memset(qd, 0, nSize);
qd->nQueryOffset = 0;
strcpy(&cData[0], "Adobe");
qd->nNumSort = 2;
qd->nSortOffset[0] = strlen("Adobe") + 1;
qd->bSortWays[0] = TRUE;
strcpy(&cData[qd->nSortOffset[0]], "Title");
qd->bSortWays[1] = FALSE;
qd->nSortOffset[1] = qd->nSortOffset[0] + strlen("Title") + 1;
strcpy(&cData[qd->nSortOffset[1]], "Score");
```

Manipulating indexes through DDE

After a connection has been made, a single poke transaction can add, delete, add, or remove indexes. The item name to use is "Index".

```
hszItemName = DdeCreateStringHandle(id, "Index", 0);
DdeClientTransaction(qd, nLen, hConv, hszItemName, CF_TEXT, XTYP_POKE,
1000, &dwResult);
DdeDisconnect(hConv);
```

The global data handle (gd) passed to the server must be in the following format:

```
typedef struct _IndexData {
   IndexActionType eAction;
   int16 nIndexOffset;
   int16 nTempNameOffset;
   unsigned char cData[1];
} IndexData;
```

Options

eAction	The operation to be performed on the index. Must be one of values listed in <u>"Index operation selectors" on page 212</u> .
nIndexOffset	An offset into the \mathtt{cData} chunk that points to a \mathtt{NULL} -terminated string containing the PDX file representing the index.
nTempNameOffset	An offset into cData. It points to a temporary name that is displayed by the Search plug-in when the index is unavailable. This field must specify an offset either to an empty string (\setminus 0) or to a non-empty C string.

Index operation selectors

IndexAction_Add	Adds an index to the shelf.
IndexAction_Remove	Removes an index from the shelf.
IndexAction_Enable	Enables an index on the shelf.
IndexAction_Disable	Disables an index on the shelf.

To create and populate this structure correctly, the client must know the sum of the lengths of the Index (li) and Temp names (lt) (including NULL-terminating characters), and the size of the IndexData structure.

The client then allocates memory as follows:

```
nSize = sizeof(IndexData) + li + lt;
id = (IndexData *)malloc(nSize);
```

For example, to add the index C:\FOO.PDX to the Search plug-in's shelf:

```
memset(id, 0, nSize);
id->eAction = IndexAction_Add;
id->nIndexOffset = 0;
strcpy(&id->cData[0], "C:\\FOO.PDX");
id->nTempNameOffset = strlen("C:\\FOO.PDX") + 1;
strcpy(&id->cData[id->nTempNameOffset],
"My Favorite Index");
```

Search plug-in using Apple events

The Search plug-in supports the Apple events described in this section.

SearchAddIndex

Adds a specified index to the shelf.

Apple event ID

kSearchAddIndex ('addx')

Parameters

kIndexListTag ('SilP'), typeLongInteger	An opaque void* representing the shelf, obtained from SearchGetIndexList.
kPathTag ('Path'), typeChar	Mac OS full path representing an index, of the form: MyDisk:TopFolder:BottomFolder:Strange.pdx
kFlagTag ('Flag'), typeLongInteger	Index flags. See SearchGetIndexFlags on page 216 for a description. The kIndexAvailable flag should always be set.

Returns

```
kIndexTag ('SixP'), typeLongInteger
```

An opaque void* representing an index. Returns NULL if failure.

Returns

```
#define kIndexExists ((SearchIndexPtr)-1)
```

if the index already exists in the index list. If the index already exists, you can retrieve it using SearchGetIndexByPath on page 215.

SearchCountIndexList

Gets the number of indexes currently on the shelf.

Apple event ID

kSearchCountIndexList ('cidx')

Parameters

kIndexListTag ('SilP'),	An opaque void* representing the shelf, obtained from
typeLongInteger	SearchGetIndexList.

Returns

kIndexListTag ('SilP'), typeLongInteger

Number of indexes on the shelf (kIndexListTag here is not semantically correct, but works).

SearchDoQuery

Executes a specified query, using the set of indexes currently on the shelf. The search results are displayed in the Acrobat Search plug-in's Results window.

Apple event ID

kSearchDoQuery ('kwry')

Parameters

kQueryStringTag ('Quryv), typeChar	The query string, a NULL-terminated block of text. Its format is the same as what a user would type into the search Query window, and depends on the search language specified by kParserTag.
kParserTag ('Prsr'),	The query parser to use; may be one of (see SrchType.h):
typeShortInteger	${\tt kParserSimple\ 0}$ — Allows only simple phrase searches; does not allow Boolean searching.
	kParserCQL 1 — Allows Boolean searches using AND, OR, and NOT, as described in the Acrobat Search plug-in's online help file.
	kParserBPlus 2 — The Verity BooleanPlus query language. Contact Verity for further information on this language.
kSortSpecTag ('Sort'), typeAEList	A list of C strings representing fields to sort by. The first element is the first level sort, the second is the second level sort, and so forth.
	Each string may be any field that appears in the index, plus Score (which sorts results by relevance ranking). Some common fields are Title, ModificationDate, CreationDate, and Keywords.
kWordOptionsTag ('WOpt'), typeLongInteger	A bit field of word options. Must be a logical OR of the values listed below in "Word options for Apple events" on page 215.
	The manner in which the options are used depends on the value associated with kOptionsOverrideTag.
kOptionsOverrideTag ('WOer'), typeShortInteger	Flag that indicates whether the word options are $OR' ed$ with the search options set in the user interface, or used instead of them. If 0, the word options are $OR' ed$ with the user interface search options, and the resulting value is used. If non-zero, the word options are used instead of the user interface search options.
kMaxDocsTag ('MaxD'), typeShortInteger	The maximum number of documents to display in the Results window. If more documents than this have hits, only the first maxDocs are displayed. maxDocs cannot be greater than 999.

Word options for Apple events

kWordOptionCase	The search is case-sensitive.
kWordOptionStemming	Find not only the specified word, but other words that have the same stem (for example, run and ran have the same stem).
kWordOptionSoundsLike	Find not only the specified word, but other words that sound like it.
kWordOptionThesaurus	Find not only the specified word, but other words that have the same meaning.
kWordOptionProximity	Consider the proximity of results when using the AND operator to look for more than one word in a document. Without kWordOptionProximity, AND terms can be anywhere in a document. Searching for "red" and "blue," for example, finds a document where "red" is the first word on the first page and where "blue" is the last word on the last page. With kWordOptionProximity, however, AND terms must be within two or three pages of each other to be found. Also, with kWordOptionProximity, the closer AND terms appear together, the higher the relevance ranking of the document that contains them.
kWordOptionRefine	Do not search the entire list of indexes, but only the documents that matched the previous search. This is used to refine the results of the previous search.

SearchGetIndexByPath

Gets the index that has the specified path. The index must already be on the shelf. The index can be passed to other Search Apple events to remove it from the shelf, obtain its title, and so forth.

Apple event ID

kSearchGetIndexByPath ('fpdx')

Parameters

kIndexListTag ('SilP'), typeLongInteger	An opaque void* representing the shelf, obtained from <pre>SearchGetIndexList</pre> .
kPathTag ('Path'), typeChar	Mac OS full path representing an index, of the form: MyDisk:TopFolder:BottomFolder:Strange.pdx

Returns

kIndexTag ('SixP'), typeLongInteger

An opaque void* representing an index. Returns NULL if the specified index is gone.

SearchGetIndexFlags

Get the flags for an index.

Apple event ID

kSearchGetIndexFlags ('gfdx')

Parameters

```
kIndexTag ('SixP'),
typeLongInteger
```

An opaque void* representing an index.

Returns

```
kFlagTag ('Flag'), typeLongInteger
```

A logical OR of the following:

```
kIndexAvailableFlag (1L << 0) — Set if the index is available for searching.
```

kIndexSelectedFlag (1L << 1) — Set if the index appears with a check mark in the Search plug-in's user interface.

kIndexPtrInvalidFlag (1L << 31) — Set if the index is not valid or is no longer valid.

SearchGetIndexList

Gets a list of the indexes currently on the shelf.

Apple event ID

```
kSearchGetIndexList ('gidx')
```

Returns

```
kIndexListTag ('SilP'), typeLongInteger
```

An opaque void* representing the list of indexes currently on the shelf. This value can subsequently be used by other search Apple events to obtain information about a specific index, the number of indexes on the shelf, and so forth.

SearchGetIndexPath

Gets the full path to an index.

Apple event ID

kSearchGetIndexPath ('gpdx')

Parameters

kIndexTag ('SixP'), typeLongInteger	An opaque $void*$ representing the index whose path is to be obtained. The index may be obtained using
	<pre>SearchGetIndexByPath, SearchGetNthIndex, or</pre>
	SearchAddIndex.

Returns

```
kPathTag ('Path'), typeChar
```

A NULL-terminated character string representing the full path of the index. Returns an empty string if the requested index is not valid.

SearchGetIndexTitle

Gets the title of an index.

Apple event ID

kSearchGetIndexTitle ('gtdx')

Parameters

kIndexTag ('SixP'), typeLongInteger	An opaque $void*$ representing the index whose title is to be obtained. The index may be obtained using
	<pre>SearchGetIndexByPath, SearchGetNthIndex, or</pre>
	<u>SearchAddIndex</u> .

Returns

```
kTitleTag ('Title'), typeChar
```

A NULL-terminated character string representing the title of the index. If there is no title, it returns the index's path. Returns an empty string if the requested index is not valid.

SearchGetNthIndex

Gets the nth index on the shelf. The index can be passed to other Search Apple events to remove it from the shelf, obtain its title, and so forth.

Apple event ID

kSearchGetNthIndex ('fndx')

Parameters

kIndexListTag ('SilP'), typeLongInteger	An opaque void* representing the shelf, obtained from <pre>SearchGetIndexList</pre> .
kNthIndexTag ('Enth'), typeLongInteger	The index to get. The first index on the shelf is index zero.

Returns

```
kIndexTag ('SixP'), typeLongInteger
```

An opaque $\mathtt{void}*$ representing an index. Returns \mathtt{NULL} if the n^{th} index is gone.

SearchRemoveIndex

Removes the specified index from the shelf.

Apple event ID

kSearchRemoveIndex ('rmdx')

Parameters

kIndexListTag ('SilP'), typeLongInteger	An opaque void* representing the shelf, obtained from <pre>SearchGetIndexList</pre> .
kIndexTag ('SixP'), typeLongInteger	An opaque void* representing the index to be removed. The index may be obtained using SearchGetNthIndex , or SearchAddIndex .

${\bf Search SetIndex Flags}$

Sets the flags for an index.

Apple event ID

kSearchSetIndexFlags ('sfdx')

Parameters

<pre>kIndexTag ('SixP'), typeLongInteger</pre>	An opaque void* representing an index.
kFlagTag ('Flag'), typeLongInteger	Index flags. See the description in SearchGetIndexFlags . In practice, kIndexAvailableFlag should always be set.

Returns

kFlagTag ('Flag'), typeLongInteger

Index flags. See the description in <u>"SearchGetIndexFlags" on page 216</u>. This value is returned because it is possible for a request to set a flag to fail.

Search lists

The Search plug-in adds a new menu, menu items, and toolbar buttons to the Acrobat application.

Menu names

The Search plug-in adds the following menu to Acrobat.

Menu name	Description
AcroSrch:ToolsSubMenu	Acrobat Search submenu of Edit menu

Menu item names

The Search plug-in adds the following menu items to Acrobat.

Menu item name	Description
AcroSrch:Query	Displays the Search dialog box.
AcroSrch: Indexes	Displays the Index dialog box.
AcroSrch:Results	Displays the Results dialog box.
AcroSrch:Assist	Displays the Word Assistant dialog box.
AcroSrch:Separator	A separator item in the Search tools menu.
AcroSrch: PrevDoc	Goes to the previous document in the hit list.
AcroSrch: PrevHit	Goes to the previous hit in the hit list.
AcroSrch:NextHit	Goes to the next hit in the hit list.
AcroSrch: NextDoc	Goes to the next document in the hit list.

Toolbar button names

The Search plug-in adds the following buttons to the Acrobat toolbar.

Button name	Description
AcroSrch:Separator	Separator (not visible).
AcroSrch:Query	Displays the Acrobat Search plug-in's query dialog box.
AcroSrch:Results	Displays the Acrobat Search plug-in's search results dialog box.
AcroSrch: Prev	Goes to the previous hit in the Acrobat Search plug-in's results list.
AcroSrch:Next	Goes to the next hit in the Acrobat Search plug-in's results list.

7


Coordinate Systems

This chapter describes the coordinate systems used by IAC: user space and device space.

User space

The user space is the coordinate system used within PDF files. In the IAC interface, it is used for most PD layer objects (that is, objects such as PDBookmark whose names begin with "PD"). The following graphic shows the user space coordinate system. The orientation, origin, and scale of the user space coordinate system can be changed by operators in the page description in a PDF file.

User space coordinate system




The default user space is the user space coordinate system in effect immediately before each page begins drawing. The origin of this coordinate system is the lower left corner of a page's media box. The x-coordinate increases to the right, and the y-coordinate increases upward. One unit in the default user space is 1/72 of an inch.

Device space

The device space specifies coordinates in screen pixels, as shown in the following graphic. It is used in the AV layer of the IAC interface (that is, objects such as AVDoc whose names begin with "AV").

Device space coordinate system



The origin of the device space coordinate system is at the upper left corner of the visible page on the screen (that is, the upper left corner of the white part of the page). The x-coordinate increases to the right, and the y-coordinate increases downward.

The upper left corner of the visible page is determined by the intersection of a page's PDF crop box and media box. As a result, the device space coordinate system changes if the cropping on a page changes.

Index

clear selection event 163

ClearSelection method 32 AcquirePage method 71 close all docs event 163 Acrobat application events 162 close event 156 AcroExch.App 14 Close method 32,72 AcroExch.AVDoc 30 CloseAllDocs message 122 AcroExch.AVPageView 47 CloseAllDocs method 16 AcroExch.HiliteList 56 conversion object 147 AcroExch.PDAnnot 56 coordinate systems 221 AcroExch.PDBookmark 66 CopyToClipboard method 88 AcroExch.PDDoc 69 Core suite events 156 AcroExch.PDPage 86 count event 157 AcroExch.PDTextSelect 98 Count property 207 AcroExch.Point 102 Create method 72 AcroExch.Rect 102 create thumbs event 164 AcroExch.Time 104 CreatePageHilite method 89 Add method 56, 203 CreateTextSelect method 73 AddAnnot method 87 CreateThumbs method 74 AddDocJavascript method 204 CreateWordHilite method 90 AddNewAnnot method 88 CropPage method 91 Adobe Reader CropPages method 74 Apple events 155 DDE support 121 AFormApp object 184 D Alignment property 193 Date property 104 annotation object 141 DDE App object 14 Adobe Reader support 121 AppExit message 121 messages 120 AppExit method 181 DefaultValue property 196 AppFront method 181 delete event 157 AppHide message 122 delete pages event 165 Apple events and objects 141 delete thumbs event 165 application object 143 DeletePages method 75 AppShow message 122 DeleteThumbs method 75 AVDoc object 30 Destroy method 66, 98 AVPageView object 47, 145 device space 222 AxAcroPDF object 106 DevicePointToPage method 47 AxAcroPDFLib.AxAcroPDF 106 do script event 180 DocClose message 123 DocDeletePages message 123 DocFind message 124 bookmark object 145 DocGoTo message 125 BorderStyle property 194 DocGoToNameDest message 125 BorderWidth property 194 DocInsertPages message 125 Bottom property 103 DocOpen message 126 bring to front event 163 DocPageDown message 127 BringToFront method 31 DocPageLeft message 127 ButtonLayout property 195 DocPageRight message 128 DocPageUp message 128 C DocPrint message 129 CalcOrderIndex property 195 DocReplacePages message 129 Catalog plug-in 181 DocSave message 130 CharLimit property 196 DocSaveAs message 130

ClearFlags method 71

DocScrollTo message 131

DocSetViewMode message 132 document object 147 DocZoomTo message 132 DoGoBack method 48 DoGoForward method 48 Draw method 91 DrawEx method 92 dual interfaces 14

Ε

Editable property 196
EPS Conversion object 149
events
 Acrobat application 162
 Core suite 156
 miscellaneous 180
 Required suite 155
exceptions, Forms plug-in 183
execute event 166
ExecuteThisJavascript method 205
exists event 158
Exit method 16
ExportAsFDF method 205
ExportAsHtml method 206

F

Field object 184 Fields collection 202 FileBuild method 182 FileOpen message 133 FileOpen method 182 FileOpenEx message 133 FilePrint message 134 FilePrintEx message 135 FilePrintSilent message 135 FilePrintSilentEx message 136 FilePrintTo message 137 FilePrintToEx message 137 FilePurge method 182 find next note event 166 find text event 167 FindText method 33 Forms plug-in 183 FullMenus message 138

G

get event 158
get info event 168
GetActiveDoc method 17
GetActiveTool method 17
GetAnnot method 93
GetAnnotIndex method 93
GetAperture method 49
GetAVDoc method 18, 49
GetAVPageView method 33
GetBoundingRect method 99
GetByTitle method 67
GetColor method 57

GetContents method 58 GetDate method 58 GetDoc method 49, 94 GetFileName method 76 GetFlags method 76 GetFrame method 18, 34 GetInfo method 77 GetInstanceID method 77 GetInterface method 19 GetJSObject method 78 GetLanguage method 19 GetNumAnnots method 94 GetNumAVDocs method 20 GetNumber method 95 GetNumPages method 78 GetNumText method 99 GetPage method 50, 100 GetPageMode method 79 GetPageNum method 50 GetPDDoc method 34 GetPermanentID method 79 GetPreference method 20 GetPreferenceEx method 21 GetRect method 58 GetRotate method 95 GetSize method 96 GetSubtype method 59 GetText method 101 GetTitle method 35, 59, 67 GetVersions method 108 GetViewMode method 35 GetZoom method 51 GetZoomType method 51 go backward event 168 go forward event 169 GoBackwardStack method 108 GoForwardStack method 108 goto event 170 Goto method 52 goto next event 170 goto previous event 171 GotoFirstPage method 108 GotoLastPage method 109 GotoNextPage method 109 GotoPreviousPage method 109

н

HFT 209 Hide method 21 HideToolbar message 138 Highlight property 197 HiliteList object 56 host function table 209 Hour property 105

ı

ImportAnFDF method 207 index, Catalog plug-in 181 insert pages event 172

InsertPages method 79
is toolbutton enabled event 172
IsEqual method 60
IsHidden property 197
IsMultiline property 198
IsOpen method 60
IsPassword property 198
IsReadOnly property 198
IsRequired property 199
IsTerminal property 199
IsValid method 35, 61, 68
Item property 208

L

Left property 103 Link Annotation object 149 LoadFile method 110 Lock method 21

M

make event 159 maximize event 173 Maximize method 23, 36 menu item object 150 menu object 149 MenuitemExecute message 139 MenuItemExecute method 23 MenuItemIsEnabled method 24 MenuItemIsMarked method 24 MenuItemRemove method 25 Millisecond property 105 Minimize method 22 Minute property 105 Month property 105 move event 159 MovePage method 80

N

Name property 199 _NewEnum property 208 NoViewFlag property 199

0

OLE automation 14 open event 155, 160 Open method 36, 81 OpenAVDoc method 81 OpenInWindow method 37 OpenInWindowEx method 38

P

page object 151 PDAnnot object 56, 151 PDBookMark object 152 PDBookmark object 66 PDDoc object 69 PDF Window object 152

PDLinkAnnot object 152 PDPage object 86, 152 PDTextAnnot object 152 PDTextSelect object 98 perform event 174 Perform method 62, 68 plug-ins Catalog 181 Forms 183 Search 209 Point object 102 PointToDevice method 53 PopulateListOrComboBox method 185 PostScript Conversion object 153 print event 155 Print method 110 print pages event 174 PrintAll method 110 PrintAllFit method 111 PrintFlag property 200 PrintPages method 40, 111 PrintPagesEx method 40 PrintPagesFit method 112 PrintPagesSilent method 41 PrintPagesSilentEx method 42 PrintWithDialog method 113

Q

queries 209 quit event 155, 160

R

read page down event 175
read page up event 175
ReadPageDown method 53
ReadPageUp method 54
Rect object 102
Remove method 207
remove toolbutton event 176
RemoveAnnot method 96
replace pages event 176
ReplacePages method 82
Required suite events 155
Restore method 25
Right property 103
run event 156

5

save event 161
Save method 83
scroll event 177
ScrollTo method 54
search lists 219
Search plug-in 209
SearchAddIndex event 213
SearchCountIndexList event 213
SearchDoQuery event 214
SearchGetIndexByPath event 215

SearchGetIndexFlags event 216 SearchGetIndexList event 216 SearchGetIndexPath event 216 SearchGetIndexTitle event 217 SearchGetNthIndex event 217 SearchRemoveIndex event 218 SearchSetIndexFlags event 218 Second property 106 select text event 178 set event 161 set info event 179 SetActiveTool method 26 SetBackgroundColor method 185 SetBorderColor method 186 SetButtonCaption method 187 SetButtonIcon method 187 SetColor method 62 SetContents method 63 SetCurrentHighlight method 113 SetCurrentPage method 113 SetDate method 63 SetExportValues method 188 SetFlags method 84 SetForegroundColor method 189 SetFrame method 26, 43 SetInfo method 85 SetJavaScriptAction method 190 SetLayoutMode method 114 SetNamedDest method 114 SetOpen method 64 SetPageMode method 85, 115 SetPreference method 27 SetPreferenceEx method 27

SetRect method 64

SetRotate method 97

SetResetFormAction method 191

SetShowScrollbars method 115

SetShowToolbar method 116 SetSubmitFormAction method 192 SetTextSelection method 44

SetTitle method 45, 65, 69

SetViewMode method 45 SetViewRect method 117

SetView method 116

SetViewScroll method 117 SetZoom method 118 SetZoomScroll method 118 ShortMenus message 139 Show method 28 ShowTextSelect method 46 ShowToolbar message 140 Src property 119 Style property 200

Т

Text Annotation object 154 text searches 209 TextFont property 201 TextSize property 201 Time object 104 ToolButtonIsEnabled method 28 ToolButtonRemove method 29 Top property 104 Type property 201

U

Unlock method 29 UnlockEx method 30 user space 221

V

Value property 202

X

X property 102

Y

Y property 102 Year property 106

Z

zoom event 179 ZoomTo method 55