ATOM User Manual

Version 3.2.2, January 2006

Alberto García Universidad del País Vasco, Bilbao, SPAIN wdpgaara@lg.ehu.es vfill

${\bf Contents}$

1	PREFACE	2						
2	A PRIMER ON AB-INITIO PSEUDOPOTENTIALS							
3	COMPILING THE PROGRAM							
4	USING THE ATOM PROGRAM	3						
	4.1 All-electron calculations	3						
	4.2 Pseudopotential generation	5						
	4.2.1 Core Corrections	7						
	4.3 Pseudopotential test	8						
5	APPENDIX: THE INPUT FILE							
6	APPENDIX: INPUT FILE DIRECTIVES	15						

1 PREFACE

ATOM is the name of a program originally written (circa 1982) by Sverre Froyen at the University of California at Berkeley, modified starting in 1990 by Norman Troullier and Jose Luis Martins at the University of Minnesota, and currently maintained by Alberto Garcia (wdp-gaara@lg.ehu.es), who added some features and made substantial structural changes to the April 1990 (5.0) Minnesota version while at Berkeley and elsewhere.

Jose Luis Martins is maintaining his own version of the code:

{\tt http://bohr.inesc.pt/~jlm/pseudo.html

The program's basic capabilities are:

- All-electron DFT atomic calculations for arbitrary electronic configurations.
- Generation of ab-initio pseudopotentials (several flavors).
- Atomic calculations in which the effect of the core is represented by a previously generated pseudopotential. These are useful to make sure that the pseudopotential correctly reproduces the all-electron results for the valence complex.

2 A PRIMER ON AB-INITIO PSEUDOPOTENTIALS

Time constraints prevent the inclusion of this section in this first release of the ATOM manual. But, in this case more than ever, there is a lot to be gained from reading the original literature... Here are some basic references:

• Original idea of the ab-initio pseudopotential:

```
Kerker, J. Phys. C 13, L189-94 (1980)
Hamann, Schluter, Chiang, Phys. Rev. Lett. 43, 1494 (1979)
```

• More on HSC scheme:

```
Bachelet, Schluter, Phys. Rev. B 25, 2103 (1982)
Bachelet, Hamann, Schluter, Phys. Rev. B 26, 4199 (1982)
```

• Troullier-Martins elaboration of Kerker method:

```
Troullier, Martins, Phys. Rev. B 43, 1993 (1991)
Troullier, Martins, Phys. Rev. B 43, 8861 (1991)
```

• Core corrections:

```
Louie, Froyen, Cohen, Phys. Rev. B 26, 1738 (1982)
```

• The full picture of plane-wave pseudopotential ab-initio calculations:

W. E. Pickett, "Pseudopotential Methods in Condensed Matter Applications", Computer Physics Reports 9, 115 (1989)

M. C. Payne, M. P. Teter, D. C. Allan, T. A. Arias and J. D. Joannopoulos, "Iterative minimization techniques for ab initio total-energy calculations: molecular dynamics and conjugate gradients", Rev. Mod. Phys. 64, 1045, (1992)

Also, the book by Richard Martin "Electronic Structure: Basic Theory and Practical Methods" (Cambridge University Press) has a chapter on pseudopotentials.

• Use in SIESTA:

J.M. Soler, E. Artacho, J.D. Gale, A. Garcia, J. Junquera, P. Ordejon, D. Sanchez-Portal, "The SIESTA method for ab initio O(N) materials simulation", Jour. Phys.: Condens. Matter, 14, 2745-2779 (2002).

3 COMPILING THE PROGRAM

Edit makefile in the main source directory, and modify, if needed, the defaults for Fortran compiler and auxiliary file containing date and time routines (not standard in Fortran77).

Type make. After a short while you will have the executable (called atm) in that same directory. The program should work for any atom without recompilation.

Directory Tutorial in the source distribution contains a set of scripts to automate the process of running ATOM and to analyze the results. The file-manipulation details involved in each of the basic functions of all-electron calculations, generation of pseudopotentials, and testing of the pseudopotentias, are taken care of by ae.sh, pg.sh, and pt.sh, respectively. These scripts need to know where the ATOM executable atm is. If you have moved the Tutorial directory around, or you do not have the source, the default location might not be right for you. The easiest way to fix it is to define an environmental variable ATOM_PROGRAM. Assuming atm is in /somedir/somewhere, you would do:

```
ATOM_PROGRAM=/somedir/somewhere/atm ; export ATOM_PROGRAM # sh-derived shells setenv ATOM_PROGRAM /somedir/somewhere/atm # csh-derived shells
```

Due to the shortcommings of the basic (GNUplot) plotting package used in the Tutorial section, it is also necessary to copy some scripts from a central repository. Again, if the default does not work for you, define the ATOM_UTILS_DIR variable:

```
ATOM_UTILS_DIR=/somewhere ; export ATOM_UTILS_DIR # sh-derived shells setenv ATOM_UTILS_DIR /somewhere # csh-derived shells
```

4 USING THE ATOM PROGRAM

4.1 All-electron calculations

Assume we want to find the orbital eigenvalues, total energy, and/or charge density of Si in its ground state. (You should now go to the Tutorial/All_electron directory and try the following.) Our input file is named si.ae.inp and contains the lines (see Sect. 5 for more details):

```
ae Si ground state all-electron
Si ca
    0.0
3    2
3    0    2.00    0.00
3    1    2.00    0.00
```

#2345678901234567890123456789012345678901234567890

We can run the calculation by using the ae.sh script. Following the layout of the Tutorial directory, we will assume that the script is in the directory directly above the current one. We run the script and go into the directory created for the calculation (named as the input file without the extension .inp):

```
$ sh ../ae.sh si.ae.inp
==> Output data in directory si.ae
$ cd si.ae
$ ls
AECHARGE CHARGE RHO
                            charge.gplot
                                            vcharge.gps
AEWFNRO
          INP
                            charge.gps
                                            vspin.gplot
                  ae.gplot
AEWFNR1
          OUT
                  ae.gps
                            vcharge.gplot vspin.gps
$
```

We see some data files (those in all caps) and a few GNUPLOT plotting scripts¹.

The files are:

- INP: A copy of the input file for the calculation.
- OUT: Contains detailed information about the run.
- AECHARGE: Contains in four columns values of r, the "up" and "down" parts of the total charge density, and the total core charge density (the charges multiplied by $4\pi r^2$). CHARGE is exactly identical and is generated for backwards compatibility.
- RHO: Like CHARGE, but without the $4\pi r^2$ factor.
- AEWFNRO...AEWFNR3: All-electron valence wavefunctions as function of radius, for s, p, d, and f valence orbitals (0, 1, 2, 3, respectively some channels might not be available). They include a factor of <math>r, the s orbitals also going to zero at the origin.

It is interesting to peruse the OUT file. In particular, it lists the orbital eigenvalues (in Rydbergs, as every other energy in the program):

nl	s	occ	eigenvalue	kinetic energy	pot energy
1s	0.0	2.0000	-130.36911241	183.01377616	-378.73491463
2s	0.0	2.0000	-10.14892694	25.89954259	-71.62102169
2p	0.0	6.0000	-7.02876268	24.42537874	-68.74331203
3s	0.0	2.0000	-0.79662742	3.23745215	-17.68692611
Зр	0.0	2.0000	-0.30705179	2.06135782	-13.62572515

(For a relativistic or spin-polarized calculation, there would be "up" and "down" flags in the s column above.)

The **plotting** scripts come in two flavors: .gplot for terminal use (default X11, use gnuplot -persist), and .gps for postscript output.

For all-electron calculations, the relevant scripts (without .gplot or .gps extensions) are:

¹GNUPLOT is not a publication-quality package, and suffers from serious shortcomings, but it is free, and installed almost everywhere. Hence we have chosen it as the lowest-common denominator for basic plotting

- charge: Charge density (separated core and valence contributions, multiplied by $4\pi r^2$).
- vcharge: Valence charge density (same normalization).
- ae: Orbital valence wavefunctions (radial part multiplied by r)

4.2 Pseudopotential generation

(You should now go to the Tutorial/Si directory and try the following.) We are going to generate a pseudopotential for Si, using the Troullier-Martins scheme. The calculation is relativistic and we use the LDA (Ceperley-Alder flavor). The input file is named Si.tm2.inp and contains the lines (see Sect. 5 for more details):

```
#
#
   Pseudopotential generation for Silicon
#
   pg: simple generation
           Silicon
   pg
        tm2
                  3.0
                                   # PS flavor, logder R
                                   # Symbol, XC flavor, { |r|s}
 n=Si c=car
       0.0
                  0.0
                            0.0
                                       0.0
                                                  0.0
                                                             0.0
    3
         4
                                   # norbs_core, norbs_valence
    3
         0
                 2.00
                           0.00
                                   # 3s2
    3
         1
                 2.00
                            0.00
                                   # 3p2
    3
         2
                 0.00
                            0.00
                                   # 3d0
    4
         3
                 0.00
                            0.00
                                   # 4f0
      1.90
                 1.90
                            1.90
                                      1.90
                                                 0.00
                                                            0.00
#
# Last line (above):
#
     rc(s)
                rc(p)
                          rc(d)
                                     rc(f)
                                              rcore_flag
#
#2345678901234567890123456789012345678901234567890
```

Note the two extra lines with respect to an all-electron calculation. The pseudopotential core radii for all channels are 1.90 bohrs. Even though they are nominally empty in the ground state, we include the 3d and 4f states in order to generate the corresponding pseudopotentials.

We can run the calculation by using the pg.sh script. Following the layout of the Tutorial directory, we will assume that the script is in the directory directly above the current one. We run the script and go into the directory created for the calculation (named as the input file without the extension .inp):

```
$ sh ../pg.sh Si.tm2.inp
==> Output data in directory Si.tm2
==> Pseudopotential in Si.tm2.vps and Si.tm2.psf
$ cd Si.tm2
$ ls [A-Z]*
               # show only the data filesAE
CHARGE
        AEWFNR3
                  PSLOGD3 PSPOTR3
                                    PSWFNR3
AELOGDO
          CHARGE
                    PSPOTQO PSWFNQO
                                      RHO
AELOGD1
          INP
                    PSPOTQ1 PSWFNQ1
                                      SCRPSPOTRO
AELOGD2
          OUT
                    PSPOTQ2 PSWFNQ2
                                      SCRPSPOTR1
```

AELOGD3	PSCHARGE	PSPOTQ3	PSWFNQ3	SCRPSPOTR2
AEWFNRO	PSLOGD0	PSPOTR0	PSWFNRO	SCRPSPOTR3
AEWFNR1	PSLOGD1	PSPOTR1	PSWFNR1	VPSFMT
AEWFNR2	PSLOGD2	PSPOTR2	PSWFNR2	VPSOUT

There are quite a few data files now. The new ones are:

- PSCHARGE: Contains in four columns values of r, the "up" and "down" parts of the pseudo valence charge density, and the pseudo core charge density (see Sect. 4.2.1) (the charges multiplied by $4\pi r^2$).
- PSWFNRO...PSWFNR3: Valence pseudowavefunctions as function of radius, for s, p, d, and f valence orbitals (0, 1, 2, 3, respectively some channels might not be available). They include a factor of <math>r, the s orbitals also going to zero at the origin.
- PSPOTRO...PSPOTR3: Ionic pseudopotentials (i.e. unscreened) as a function of r, for s, p, d, and f channels (0, 1, 2, 3, respectively some channels might not be available). The last column is $-2Z_{ps}/r$, that is, the Coulomb potential of the pseudo atom. All the ionic pseudopotentials tend to this Coulomb tail for r beyond the range of the core electrons.
- SCRPSPOTRO...SCRPSPOTR3: Screened pseudopotentials as a function of r, for s, p, d, and f channels (0, 1, 2, 3, respectively some channels might not be available). They tend to $-2Z_{ion}/r$ for large r, where Z_{ion} is the global charge of the reference configuration used in pseudopotential generation.
- PSPOTQO...PSPOTQ3: Fourier transform V(q) (times q^2/Z_{ps}) of the ionic pseudopotentials as a function of q (in bohr⁻¹), for s, p, d, and f channels (0, 1, 2, 3, respectively some channels might not be available).
- PSWFNQ3: Fourier transform $\Psi(q)$ of the valence pseudowavefunctions as a function of q (in bohr⁻¹), for s, p, d, and f channels (0, 1, 2, 3, respectively some channels might not be available).
- VPSOUT, VPSFMT: Files (formatted and unformatted) containing pseudopotential information. They are used for *ab-initio* codes such as SIESTA and PW. Copies of these files are deposited in the top directory after the run.

The OUT file has two sections, one for the all-electron (AE) run, and another for the pseudopotential (PS) generation itself. It is instructive to compare the AE and PS eigenvalues. Simply do

\$ grep '&v' OUT							
ATM	3	12-JUL-02	Silicon				
3s	0.5	2.0000	-0.79937161	0.00000000	-17.74263363		
Зр	-0.5	0.6667	-0.30807129	0.00000000	-13.66178958		
Зр	0.5	1.3333	-0.30567134	0.00000000	-13.60785822		
3d	-0.5	0.0000	0.00000000	0.00000000	-0.27407047		
3d	0.5	0.0000	0.00000000	0.00000000	-0.27407047		
4f	-0.5	0.0000	0.00000000	0.00000000	-0.26482365		
4f	0.5	0.0000	0.00000000	0.00000000	-0.26482365		
			&v				
3s	0.5	2.0000	-0.79936061	0.50555315	-3.74113059		

Зр	-0.5	0.6667	-0.30804995	0.77243805	-3.26356669
Зр	0.5	1.3333	-0.30565760	0.76702460	-3.25197500
3d	-0.5	0.0000	0.0000000	0.00140505	-0.07847269
3d	0.5	0.0000	0.0000000	0.00140505	-0.07847269
4f	-0.5	0.0000	0.0000000	0.00243411	-0.07586534
4f	0.5	0.0000	0.0000000	0.00243411	-0.07586534
			0		

(The AE and PS eigenvalues are not exactly identical because the pseudopotentials are changed slightly to make them approach their limit tails faster).

The relevant plotting scripts (without .gplot or .gps extensions) are:

- charge: It compares the AE and PS charge densities.
- pseudo: A multi-page plot showing, on one page/window per channel:
 - The AE and PS wavefunctions
 - The AE and PS logarithmic derivatives.
 - The real-space pseudopotential
 - The Fourier-transformed pseudopotential (times q^2/Z_{ps})
- pots: All the real-space pseudopotentials.
- scrpots: Comparison of the screened and unscreened pseudopotentials.

4.2.1 Core Corrections

The program can generate pseudopotentials with the non-linear exchange-correlation correction proposed in S. G. Louie, S. Froyen, and M. L. Cohen, Phys. Rev. B 26, 1738 (1982).

In the traditional approach (which is the default for LDA calculations), the pseudocore charge density equals the charge density outside a given radius r_{pc} , and has the smooth form

$$\rho_{pc}(r) = Ar\sin(br)$$

inside that radius. A smooth matching is provided with suitable A and b parameters calculated by the program.

A new scheme has been implemented to fix some problems in the generation of GGA pseudopotentials. The smooth function is now

$$\rho_{pc}(r) = r^2 \exp(a + br^2 + cr^4)$$

and derivatives up to the second are continuous at r_{pc} .

To use core corrections in the pseudopotential generation the jobcode in the first line should be pe instead of pg.

The radius r_{pc} should be given in the sixth slot in the last input line (see above). If it is negative or zero (or blank), the radius is then computed using the fifth number in that line (rcore_flag, see the example input file above) and the following criterion: at r_{pc} the core charge density equals rcore_flag*(valence charge density). It is highly recommended to set an explicit value for the pseudocore radius r_{pc} , rather than letting the program provide a default.

If rcore_flag is input as negative, the full core charge is used. If rcore_flag is input as zero, it is set equal to one, which will be thus the default if pe is given but no numbers are given for these two variables.

The output file contains the radius used and the A (a) and b (and c) parameters used for the matching. The VPSOUT and VPSFMT files will contain the pseudocore charge in addition to the pseudopotential.

It is possible to override the default (new scheme for GGA calculations, old scheme for LDA calculations) by using the directives

```
%define NEW_CC %define OLD_CC
```

The program will issue the appropriate warnings. (See Sect. 5)

Relevant files:

- PSCHARGE: Contains the pseudocore charge in column four. (multiplied by $4\pi r^2$).
- COREQ: Fourier transform of the pseudocore charge density $\rho_{pc}(q)$ in units of electrons, with q in bohr⁻¹.

Useful plotting scripts (without .gplot or .gps extensions) are:

- charge: Shows also the pseudocore charge.
- coreq: Shows the Fourier transform of the pseudocore charge.

4.3 Pseudopotential test

While it is helpful to "have a look" at the plots of the pseudopotential generation to get a feeling for its quality, there is no substitute for a proper **transferability testing**. A pseudopotential with good transferability will reproduce the all-electron energy levels and wavefunctions in arbitrary environments, (i.e., in the presence of charge transfer, which always takes place when forming solids and molecules). We know that norm conservation guarantees a certain degree of transferability (usually seen clearly in the plot of the logarithmic derivative), but we can get a better assessment by performing all-electron and "pseudo" calculations on the same series of atomic configurations, and comparing the eigenvalues and excitation energies.

In the same Tutorial/Si directory we can find file Si.test.inp, containing the concatenation of ten jobs. The first five are all-electron (ae) calculations, and the last five, pseudopotential test (pt) runs for the same configurations:

```
#
# All-electron calculations for a series of Si configurations
#
   ae Si Test -- GS 3s2 3p2
   Si   ca
      0.0
   3   2
   3   0   2.00
```

```
3
         1
                2.00
   ae Si Test -- 3s2 3p1 3d1
        ca
       0.0
    3
         3
    3
         0
                2.00
    3
         1
                1.00
    3
         2
                1.00
   ae Si Test -- 3s1 3p3
   Si
        ca
       0.0
    3
         2
    3
                1.00
         0
    3
         1
                3.00
   ae Si Test -- 3s1 3p2 3d1
   Si
        ca
       0.0
    3
         3
    3
         0
                1.00
    3
         1
                2.00
    3
         2
                1.00
   ae Si Test -- 3s0 3p3 3d1
   Si
        ca
       0.0
    3
         3
    3
                0.00
         0
                3.00
    3
         1
    3
         2
                1.00
# Pseudopotential test calculations
  pt Si Test -- GS 3s2 3p2
   Si
        ca
       0.0
    3
         2
    3
         0
                2.00
    3
         1
                2.00
   pt Si Test -- 3s2 3p1 3d1
   Si
        ca
       0.0
    3
         3
    3
         0
                2.00
    3
         1
                1.00
    3
         2
                1.00
   pt Si Test -- 3s1 3p3
   Si
        ca
       0.0
    3
         2
    3
                1.00
         0
    3
                3.00
         1
```

```
pt Si Test -- 3s1 3p2 3d1
     ca
    0.0
 3
       3
 3
       0
               1.00
 3
       1
               2.00
       2
 3
               1.00
pt Si Test -- 3s0 3p3 3d1
    0.0
 3
       3
 3
       0
               0.00
 3
       1
               3.00
 3
       2
               1.00
```

The configurations differ in the promotion of electrons from one level to another (it is also possible to transfer fractions of an electron).

We can run the file by using the pt.sh script. Following the layout of the Tutorial directory, we will assume that the script is in the directory directly above the current one. We need to give it two arguments: the calculation input file, and the file containing the pseudopotential we want to test. Let's make the latter Si.tm2.vps:

```
$ sh ../pt.sh Si.test.inp Si.tm2.vps
$ sh ../pt.sh Si.test.inp Si.tm2.vps
==> Output data in directory Si.test-Si.tm2
$ cd Si.test-Si.tm2/
$ ls [A-Z]*
AECHARGE
          AEWFNR1
                   CHARGE
                            OUT
                                      PTWFNRO
                                               PTWFNR2
                                                         VPSIN
AEWFNRO
          AEWFNR2
                   INP
                            PTCHARGE
                                     PTWFNR1
                                               RHO
```

The working directory is named after *both* the test and pseudopotential files. It contains several new files:

- VPSIN: A copy of the pseudopotential file to be tested.
- PTCHARGE: Contains in four columns values of r, the "up" and "down" parts of the pseudo valence charge density, and the pseudo core charge density (see Sect. 4.2.1) (the charges multiplied by $4\pi r^2$).
- PTWFNR0...PTWFNR3: Valence pseudowavefunctions as function of radius, for s, p, d, and f valence orbitals (0, 1, 2, 3, respectively some channels might not be available). They include a factor of <math>r, the s orbitals also going to zero at the origin.

The OUT file has two sections, one for the all-electron (AE) runs, and another for the pseudopotential tests (PT). At the end of each series of runs there is a table showing the excitation energies. A handy way to compare the AE and PT energies is:

```
$ grep '&d' OUT
[...elided...]
&d total energy differences in series
```

```
1
                       2
                                 3
                                                    5
&d
          0.0000
&d
    1
&d
     2
          0.4308
                    0.0000
     3
                    0.0653
                             0.0000
&d
          0.4961
&d
    4
          0.9613
                    0.5305
                             0.4652
                                       0.0000
                                       0.5384
&d
    5
          1.4997
                    1.0689
                             1.0036
                                                0.0000
*---- End of series ----* spdfg &d&v
           12-JUL-02
                        Si Test -- GS 3s2 3p2
EMTA
EMTA
           12-JUL-02
                        Si Test -- 3s2 3p1 3d1
EMTA
           12-JUL-02
                        Si Test -- 3s1 3p3
EMTA
           12-JUL-02
                        Si Test -- 3s1 3p2 3d1
EMTA
           12-JUL-02
                        Si Test -- 3s0 3p3 3d1
&d total energy differences in series
             1
                       2
                                 3
                                          4
                                                    5
&d
          0.0000
&d
    1
&d
     2
          0.4299
                    0.0000
                    0.0694
&d
     3
          0.4993
                             0.0000
&d
    4
          0.9635
                    0.5336
                             0.4642
                                       0.0000
    5
          1.5044
                    1.0745
                             1.0051
                                       0.5409
                                                 0.0000
&d
*---- End of series ----* spdfg &d&v
```

The tables (top AE, bottom PT) give the cross-excitations among all configurations. Typically, one should be all right if the AE-PT differences are not much larger than 1 mRy.

You can also compare the AE and PT eigenvalues. Simply do

```
$ grep '&v' OUT | grep s
EMTA
           12-JUL-02
                        Si Test -- GS 3s2 3p2
      0.0
             2.0000
                                             3.23745215
                                                            -17.68692611
3s
                          -0.79662742
EMTA
           12-JUL-02
                        Si Test -- 3s2 3p1 3d1
      0.0
             2.0000
                                             3.53885995
                                                            -18.40569836
3s
                          -1.08185979
EMTA
           12-JUL-02
                        Si Test -- 3s1 3p3
3s
      0.0
             1.0000
                          -0.85138783
                                             3.35438895
                                                             -17.96219240
EMTA
           12-JUL-02
                        Si Test -- 3s1 3p2 3d1
             1.0000
                                             3.62997498
3s
      0.0
                          -1.11431855
                                                             -18.60814708
EMTA
           12-JUL-02
                        Si Test -- 3s0 3p3 3d1
      0.0
             0.0000
                          -1.14358268
                                             3.71462770
                                                             -18.79448684
3s
*---- End of series ----* spdfg &d&v
           12-JUL-02
                        Si Test -- GS 3s2 3p2
EMTA
      0.0
             2.0000
                                             0.50556261
                                                              -3.74114712
1s
                          -0.79938037
EMTA
           12-JUL-02
                        Si Test -- 3s2 3p1 3d1
             2.0000
                                             0.55070398
                                                              -3.81988817
1s
      0.0
                          -1.08384468
EMTA
           12-JUL-02
                        Si Test -- 3s1 3p3
1s
      0.0
             1.0000
                          -0.85392666
                                             0.52020429
                                                              -3.76852577
EMTA
           12-JUL-02
                        Si Test -- 3s1 3p2 3d1
1s
      0.0
             1.0000
                          -1.11546463
                                             0.56048425
                                                              -3.83646615
EMTA
           12-JUL-02
                        Si Test -- 3s0 3p3 3d1
             0.0000
                          -1.14353959
 1s
      0.0
                                             0.56945741
                                                              -3.85106049
*---- End of series ----* spdfg &d&v
```

(and similarly for p, d, and f, if desired). Again, the typical difference should be of around

1 mRyd for a "good" pseudopotential. (The *real* proof of good transferability, remember, can only come from a molecular or solid-state calculation). Note that the PT levels are labeled starting from principal quantum number 1.

The relevant plotting scripts (without .gplot or .gps extensions) are:

- charge: It compares the AE and PT charge densities.
- pt: Compares the valence all-electron and pseudo-wavefunctions.

5 APPENDIX: THE INPUT FILE

For historical reasons, the input file is in a rigid column format. Fortunately, most of the column fields line up, so the possibility of errors is reduced. We will begin by describing in detail a very simple input file for an **all-electron calculation** for the ground state of Si. More examples can be found in the **Tutorial** directory.

The file itself is:

```
#
   Comments allowed here
   ae Si ground state all-electron
   Si
        car
       0.0
    3
         2
    3
         0
                2.00
                          0.00
    3
         1
                2.00
                          0.00
 Comments allowed here
#234567890123456789012345678901234567890
                                                        Ruler
```

- The first line specifies:
 - The calculation code (ae here stands for "all-electron").
 - A title for the job (here Si ground state all-electron).

(format 3x,a2,a50)

- Second line:
 - Chemical symbol of the nucleus (here Si, obviously)
 - Exchange-correlation type. Here, ca stands for Ceperley-Alder. Other options are wi (Wigner), hl (Hedin-Lundqvist), gl (Gunnarson-Lundqvist), and bh (von Barth-Hedin). The "best" LDA choice should be ca. It is also possible to use a gradient-corrected functional: pb indicates use of the PBE scheme by Perdew, Burke, and Ernzerhof (PRL 77, 3865 (1996)),rp indicates the RPBE scheme by Hammer, Hansen, and Norskov, (PRB 59, 7413 (1999)), rv indicates the revPBE scheme by Zhang and Yang, (PRL 80,890(1998)), and bl selects the BLYP (Becke-Lee-Yang-Parr) scheme (see source file xc.f for more details). By default, the exchange-correlation energy and potential are computed using the Soler-Balbás package, except for the wi, hl, gl, and bh flavors.

- The character r next to ca is a flag to perform the calculation relativistically, that is, solving the Dirac equation instead of the Schrodinger equation. The full range of options is:
 - * s : Spin-polarized calculation, non-relativistic.
 - * r: Relativistic calculation, obviously polarized.
 - * (blank): Non-polarized (spin ignored), non-relativistic calculation.

(format 3x, a2, 3x, a2, a1, 2x)

• Third line. Its use is somewhat esoteric and for most calculations it should contain just a 0.0 in the position shown.

The rest of the file is devoted to the specification of the electronic configuration:

• Fourth line:

Number of core and valence orbitals. For example, for Si, we have 1s, 2s, and 2p in the core (a total of 3 orbitals), and 3s and 3p in the valence complex (2 orbitals).

(format 2i5)

- Fifth, sixth... lines: (there is one line for each valence orbital)
 - n (principal quantum number)
 - 1 (angular momentum quantum number)
 - Occupation of the orbital in electrons.

```
(format 2i5,2f10.3)
```

(There are two f input descriptors to allow the input of "up" and "down" occupations in spin-polarized calculations (see example below))

Comments or blank lines may appear in the file at the beginning and at the end. It is possible to perform two or more calculations in succession by simply concatenating blocks as the one described above. For example, the following file is used to study the ground state of N and an excited state with one electron promoted from the 2s to the 2p orbital taking into account the spin polarization:

```
ae N ground state all-electron
   N
        cas
       0.0
    1
          2
    2
          0
                 2.00
                            0.00
          1
                 3.00
                            0.00
#
#
   Second calculation starts here
   ae N 1s2 2s1 2p4 all-electron
   N
        cas
       0.0
    1
          2
```

2	0	1.00	0.00
2	1	3.00	1.00

#234567890123456789012345678901234567890

The different treatment of core and valence orbitals in the input for an all-electron calculation is purely cosmetic. The program "knows" how to fill the internal orbitals in the right order, so it is only necessary to give their number. That is handy for heavy atoms... Overzealous users might want to check the output to make sure that the core orbitals are indeed correctly treated.

Ruler

For a **pseudopotential test calculation**, the format is exactly the same, except that the job code is pt instead of ae.

For a **pseudopotential generation run**, in addition to the electronic configuration chosen for the generation of the pseudopotentials (which is input in the same manner as above), one has to specify the "flavor" (generation scheme) and the set of core radii r_c for the construction of the pseudowavefunction. Here is an example for Si using the Hamann-Schluter-Chiang scheme:

#

pg	pg Si Pseudopotencial					
	hsc	2.00				
Si	ca					
	0					
3	3					
3	0	2.00				
3	1	0.50				
3	2	0.50				
	1.12	1.35	1.17	0.0	0.0	0.0
#						

#

#23456789012345678901234567890123456789012345678901234567890 Ruler

Apart from the pg (pseudopotential generation) job code in the first line, there are two extra lines:

• Second line:

Flavor and radius at which to compute logarithmic derivatives for test purposes.

hsc Hamann-Schluter-Chiang

The flavor can be one of: ker Kerker

tm2 Improved Troullier-Martins

The ker and tm2 schemes can get away with larger r_c , due to their wavefunction matching conditions.

(format 8x, a3, f9.3)

- The last line (before the blank line) specifies:
 - The values of the r_c in atomic units (bohrs) for the s, p, d, and f orbitals (it is a good practice to input the valence orbitals in the order of increasing angular momentum, so that there is no possible confusion).

(format 4f10.5)

- Two extra fields (2f10.5) which are relevant only if non-local core corrections are used (see Sect 4.2.1).

In the hsc example above, only s, p, and d r_c 's are given. Here is an example for Silicon in which we are only interested in the s and p channels for our pseudopotential, and use the Kerker scheme:

#

pg	Si Kerker	generation	n			
	ker	2.00				
Si	ca					
	0					
3	2					
3	0	2.00				
3	1	2.00				
	1.80	1.80	0.00	0.0	0.0	0.0

#2345678901234567890123456789012345678901234567890 Ruler

This completes the discussion of the more common features of the input file. See the Appendix 6 for more advanced options.

6 APPENDIX: INPUT FILE DIRECTIVES

The fixed format can be a source of desperation for the beginner, and its rigidity means that it is not easy to add new items to the input. For this purpose, the program takes another route: several variables can be entered in a specially flexible format by means of *directives* at the top of the file. For example

```
%define NEW_CC
.... rest of the input file
```

would signal that we want to use a new core-correction scheme.

There are two kinds of directives, with syntax:

```
%VARIABLE=value %define NAME
```

In the first case we assign the value value to the variable VARIABLE. The program can look at the value via a special subroutine call.

The second form is a bit more abstract, but can be understood as assigning a special "existence" value of 1 to the variable NAME. Again, the program can check for the existence of the variable via a special subroutine call.

Currently, the program understands the following NAMEs:

• COMPAT_UCB: Revert to the standard circa 1990 UCB values. Note that these correspond to the first released version of Jose Luis Martins code, not to the old Froyen version. (The defaults are: use a denser grid up to larger radii. Use a larger value for the pseudopotential cutoff point. Use the Soler-Balbas XC package.)

- NEW_CC: New core-correction scheme
- OLD_CC: Old core-correction scheme (see Sect. 4.2.1)
- USE_OLD_EXCORR: Use the old exchange-correlation package.
- NO_PS_CUTOFFS: Avoid cutting off the tails of the pseudopotentials. Currently, a simple exponential tapering function is used, which introduces a discontinuity in the first derivative of the ionic pseudopotential.