# **Hybrid BASS/Kyrandia template for AGS**

by brewton


## **Features**

Single click on inventory items to pick up or pop out of slots. Retains useful right-click and left-click handling from BASS template. Player can carry items between rooms – without having to slot it in inventory. Custom cursors for displaying room exits on mouseover. Dummy item generation.

#### Walkable areas

Since dropped inventory items are actually characters, they can get stuck behind walk-behinds. Walkable Area ID # 2 is used by the drop\_item() script to prevent items being placed there.

To take advantage of this feature, on your walkable area masks use pallete index #2 for large areas that intersect the walk behind mask. See below for example.



## **Scripts**

- TwoClickHandler.asc
  - A heavily modified version of the TwoClickHandler from the BASS stub. The hideable controls have been removed and many functions are delegated to KyrHandler.
- KyrHandler.asc

Handles most of the interface which is not handled by

Dummyltems.asc

Handles all parts of generating and destroying dummy characters from inventory items.

#### **Functions**

## <u>KyrHandler.asc</u>

- get\_exit\_type()
  - Returns a directional exit arrow based on the value of ExitType in the active hotspot.
- drop\_held\_item()

Drops the item held in the cursor and summons a dummy character.

pick\_up\_item(character)

Adds the inventory item to the cursor slot and destroys the dummy character.

dummy\_item\_interaction()

Returns a boolean value to the unhandled event script. If the character is not a dummy it will default to unhandled character interaction.

get\_item\_index(item)

Finds which inventory slot an item is in.

return\_blank()

Populates a blank inventory slot based on which inventory slot has been used.

take\_item\_from\_slot(item)

Puts an inventory item from a slot into the cursor

drop\_item\_in\_slot(item)

Puts an inventory item from the cursor into a slot

switch\_item\_in\_slot(item)
 Switches items between the cursor and a slot.

#### **DummyItems.asc**

init\_dummies()
 Initializes array of dummy characters.

get\_next\_dummy()

Searches through the dummyltem array for an available dummy character.

If there are no dummy characters left, the player will say "Dummy maximum reached!"

If this happens, increase the amount of dummy characters.

create\_dummy(item)

Creates a dummy character at the mouse position based on an inventory item

destroy\_dummy(character)

Resets the dummy character and restores it to the pool of available characters.

#### **Custom variables**

• int invSlots default = 10

This is the amount of inventory slots you're using.

This is used to determine the maximum amount of slots you have by indexing the inventory window.

If you want more slots, make sure you increase this number and create more blank items in the range 1-invSlots.

Note that you actually have invSlots + 1 since the inventory index starts at 0. The end index is used for the inventory item hold in

Note that you actually have invSlots + 1 since the inventory index starts at 0. The end index is used for the inventory item held in the cursor.

• int offset default = 8

This is an offset about half the cursor size - so items don't jump all around the screen when swapping them.

int dummy\_count (int) default = 30

This is the maximum amount of dummy items that can be dropped throughout the game at a time. If you are experiencing a "Dummy Maximum Reached!" state, you can increase this number, but be sure to

- o change it in the header file
- modify the array total
- and create additional dummy characters.

# **Custom Properties**

There are a few custom properties that need to be set up to get the most out of this template.

Name	Description	Туре	Default Value	Applies to
RoomName	Displays in the status bar. Useful if you want custom text to show up but still want a friendly name in Description.	Text	Empty Room	Rooms
ExitType	What kind of directional arrow to show over a hotspot. Used for showing room exits or entrances.  0 = Normal 1 = Up 2 = Right 3 = Down 4 = Left 5 = NoExit	Number	0	Hotspots
InvFrame	Inventory item's sprite number in vInvItems  Allows a single view to hold all inventory item sprites.	Number	0	Inventory Items