

# Merative Social Program Management 8.1

## Note

Before using this information and the product it supports, read the information in  $\underline{\text{Notices on page}}$   $\underline{21}$ 

## **Edition**

This edition applies to Merative<sup>™</sup> Social Program Management 8.0.0, 8.0.1, 8.0.2, 8.0.3, and 8.1.

© Merative US L.P. 2012, 2023

Merative and the Merative Logo are trademarks of Merative US L.P. in the United States and other countries.

## **Contents**

Note	iii
Edition	v
1 Configuring Watson Assistant settings	9
2 Generating the JWT keystore and certificates	11
2.1 Adding the public key to Watson <sup>™</sup> Assistant	13
3 Configuring application servers for JSON Web Tokens	15
3.1 Configuring WebSphere® Application Server for JWT	15
3.2 Configuring WebLogic Server for JWT	16
3.3 Configuring WebSphere® Liberty for JWT	16
4 Getting started with your virtual assistant	19
Notices	21
Privacy policy	22
Trademarks	

Merative Social Program Management 8.1 viii

## 1 Configuring Watson Assistant settings

Complete the following steps to configure IBM® Watson™ Assistant settings in Merative™ Social Program Management.

#### About this task

For more information about Watson<sup>™</sup> Assistant web chat configuration, see <u>Configuration</u>.

For more information about the issuer for Watson<sup>™</sup> Assistant, see <u>Securing the web chat</u>.

#### **Procedure**

- 1. Log in to Social Program Management as a system administrator.
- 2. Select System Configurations > Shortcuts > Application Data.
- 3. Select the Watson Assistant Configuration category and click Search.
- **4.** To update any of the following properties, select ... > **Edit Value** to update the value and click **Save**.

Property	Value		
curam.watson.assistant.accepted.application	**Meapplication codes for the user workspaces where you want the web chat to be displayed. You can specify multiple workspaces with a commaseparated list. For example, you can specify DefaultApp, CustomApp to show the web chat to users of the DefaultApp and CustomApp applications. Application codes are not case-sensitive.		
curam.watson.assistant.enabled	Set to true to enable the Watson Assistant web chat widget to be displayed in the specified workspaces.		
curam.watson.assistant.integration.id	The integration ID of your web chat integration, which is a UUID, such as 250058a9-11f5-4deb-a91e-7ac24878c6a3.		
curam.watson.assistant.issuer	The issuer of the JSON Web Tokens (JWT).		
curam.watson.assistant.region	The data center where your web integration was created. For example, us-south.		
curam.watson.assistant.service.instance.id	The service instance ID of the assistant that hosts your web chat integration, which is a UUID such as fba14cb7-95da-45e3-bf4a-e61d80e46598. You can find it in the Assistant URL.		

5. Click **Publish** to publish your changes.

## 2 Generating the JWT keystore and certificates

A JSON Web Token (JWT) is used to secure requests between Merative<sup>™</sup> Social Program Management and IBM<sup>®</sup> Watson<sup>™</sup> Assistant. The JWT is digitally signed by the Social Program Management application by using a public/private key pair, which is stored in a keystore.

The private key in the keystore must be accessible by the Social Program Management runtime code so the JWT can be generated and signed when an outbound request to Watson<sup>TM</sup> Assistant is made.

You must add the public key in two locations:

- Watson<sup>™</sup> Assistant needs the public key so that requests from Social Program Management to Watson<sup>™</sup> Assistant are trusted.
- The Social Program Management application server's truststore, so if Watson<sup>™</sup> Assistant needs to make an API call back into Social Program Management to retrieve data in order to answer questions, the JWT that is passed along with the request is accepted. For more information about configuring the application server to allow authentication with JWT, see the *Configuring application servers for JSON Web Tokens* related link.

#### Self-signed certificates for development and test

For development and test environments, you can generate a keystore with a self-signed cert with Social Program Management Ant build scripts if needed.

For production environments, a keystore with a certificate that is signed by a Trusted Certificate Authority is recommended.

To generate and use a self-signed cert, use the configurest or configure Ant build scripts. These scripts generate a keystore and self-signed cert by using the properties that are specified in the <code>/EJBServer/project/properties/JWTKeystore.properties</code> file. Both the generated keystore and properties file are added to a <code>JWTCryptoConfig.jar</code> file, which is placed in the <code>JAVA\_HOME/jre/lib/ext</code> directory. The public certificate is also exported to this directory, so it can be retrieved later and added to Watson Assistant. The <code>configure</code> build script also imports the public certificate into the application servers truststore.

The values that are used for the keystore and certificate are in the file /EJBServer/project/properties/JWTKeystore.properties as shown in this example.

```
KEYSTORE PROPERTIES
jwt.keystore.filename=jwtkeystore.p12
jwt.keystore.location= (Leave empty when you use the generated self-signed certificate)
jwt.keystore.password=password
jwt.keystore.type=PKCS12
jwt.key.alias=jwtkeyalias (The alias name for the private key used for signing the JWT)
jwt.cert.alias=jwtcertalias (The alias name of the public cert in the truststore)
jwt.public.cert.filename=jwtcert.cer (The name of the file that will be created which
contains the cert's public key)
CERTIFICATE PROPERTIES
(These are used to create a self-signed cert, if using the default generated keystore,
at build time.
These properties are not required if using an existing keystore with existing
certificate).
iwt.cert.common.name=JWT
jwt.cert.organisation.unit=
jwt.cert.organisation=
jwt.cert.locality=
jwt.cert.state=
iwt.cert.country=
jwt.cert.key.validity=1825
jwt.key.alg=RSA
jwt.key.size=2048
```

#### Use existing keystore and certificate

You can use an existing keystore and certificate instead of the default keystore and self-signed certificate by updating the appropriate properties in the /EJBServer/project/properties/JWTKeystore.properties file.

1. If needed, customize the properties in the /EJBServer/project/properties/ JWTKeystore.properties file.

```
jwt.keystore.filename= (The name of the keystore file)
jwt.keystore.location= (The absolute path to the keystore file)
jwt.keystore.password= (The password of the keystore)
jwt.keystore.type= (The type of the keystore)
jwt.key.alias= (The alias of the private key to use for signing the JWT)
```

2. From EJBServer directory, run the configtest build target to generate the JWTCrypto.jar file and the public key jwtcert.cer in the \$JAVA\_HOME/jre/lib/ext/directory.

#### **Troubleshooting**

• Rerunning configtest build target and reimporting the JWT public certificate into the truststore

If you rerun the configtest build target after you followed the steps for importing the JWT certificate into the truststore, you must reimport the certificate again because the original certificate is no longer valid. Reimporting the certificate again applies only to applications deployed on WebSphere® or on WebSphere® Liberty.

For more information, see the *Configuring application servers for JSON Web Tokens* related link.

• Starting the Watson<sup>™</sup> Assistant chatbot

If you can't start Watson™ Assistant chatbot, search for all files that start with 'jwtcert'. Where there are multiple entries, delete the old files. Then, rerun the build configtest target.

#### **Related concepts**

Configuring application servers for JSON Web Tokens on page 15

You must configure the application server in your development or test environment to accept JSON Web Tokens for the integration with IBM® Watson™ Assistant.

## 2.1 Adding the public key to Watson™ Assistant

Complete the following steps to add your public key to IBM® Watson™ Assistant.

#### About this task

For more information about security for Watson<sup>™</sup> Assistant, see Securing the web chat.

#### **Procedure**

- 1. Open the \$JAVA\_HOME/jre/lib/ext/jwtcert.cer file with a text editor to copy the public key details.
- 2. Log in to IBM® Cloud® and open your Watson Assistant service.
- 3. Click the Launch Watson Assistant button and select Integrations for your assistant.
- 4. Under Integrations, select Web chat.
- 5. Select the Security tab, paste the public key in the Your public key section, and save.

Merative Social Program Management 8.1 14

## 3 Configuring application servers for JSON Web Tokens

You must configure the application server in your development or test environment to accept JSON Web Tokens for the integration with  $IBM^{\textcircled{R}}$  Watson<sup>TM</sup> Assistant.

## 3.1 Configuring WebSphere® Application Server for JWT

Complete the following steps to configure IBM® WebSphere® Application Server to accept JSON Web Tokens (JWT).

Complete the following steps in the WebSphere® Application Server documentation, see Configuring authentication with JSON Web Tokens (JWT).

When you configure the new interceptor, add the following relying party custom properties for Merative<sup>TM</sup> Social Program Management.

- The following properties are required for JWT authentication.
  - provider <id>.useJwtFromRequest: (must be set to required)
  - provider\_<id>.identifier
  - provider\_<id>.issuerIdentifier This value must match the iss attribute value in the JWT token.
- Configure the following property to obtain the JWT signer certificate.
  - provider\_<id>. signVerifyAlias This value must match the alias name that is used to import the signer certificate into the truststore.
- Configure the following property to enable the OIDC TAI to intercept requests.
  - provider <id>.filter Authorization%=Bearer

If the request includes a header that is called Authorization and that contains Bearer in the value, use the TAI interceptor.

# Import the JWT signer's public certificate into the default truststore Using the default self-signed certificate

The configure, configure, installapp, and configurewebserverplugin ant build scripts all generate a self-signed certificate that is used to sign the JWT. The configure build script also imports the corresponding public certificate into the application server's default truststore. However, where the other build scripts are run after the configure build script then a new self-signed certificate is generated. The newer public certificate must be imported into the truststore.

The following list outlines how to use the default self-signed certificate:

- 1. In the administrative console, click Security > SSL certificate and key management > Key stores and certificates > NodeDefaultTrustStore > Signer certificates.
- 2. Click **jwtcertalias**, where an entry of this name exists, and click **Delete**.
- 3. Click Add.
- **4.** Enter jwtcertalias for the **Alias** field. The name must also match the alias name that you specified for the signVerifyAlias TAI custom property.

**5.** Enter the absolute path to the public certificate for the **File name** field. When the self-signed certificate was created, a file that contains the public certificate was created in the directory <JAVA\_HOME>/jre/lib/ext . For example: <JAVA\_HOME>/jre/lib/ext/jwtcert.cer.

#### Using an existing keystore and signer certificate

If you are using an existing keystore and signer certificate instead of the generated self-signed certificate, use the preceding steps to import the public certificate into the application server's truststore. Ensure that you first run the configtest ant build script. The script exports the public key certificate to <JAVA\_HOME>/jre/lib/ext/jwtcert.cer.

## 3.2 Configuring WebLogic Server for JWT

Complete the following steps to configure Oracle WebLogic Server to accept JSON Web Tokens (JWT).

#### **Procedure**

- 1. From the WebLogic Server Admin pane, select Security Realms.
- 2. Select myrealm in the Realms list.
- 3. Select the **Providers** tab.
- 4. Select the **Authentication** tab
- 5. Click New.
- **6.** Enter these values for the following fields:
  - Name: The name of your new provider.
  - Type: CuramJWTIdentityAsserter
- 7. Click OK.
- 8. Click Save.
- **9.** Restart the server.

## 3.3 Configuring WebSphere® Liberty for JWT

Import the JWT signer's public certificate into the default truststore and then update the server.xml configuration file.

# Importing the JWT signer's public certificate into the default truststore Using the default self-signed certificate

The configures, configure, installapp, and configurewebserverplugin ant build scripts all generate a self-signed certificate that is used to sign the JWT. The configure build script also imports the corresponding public certificate into the application server's default truststore. However, where the other build scripts are run after the configure build script then a new self-signed certificate is generated. The newer public certificate must be imported into the truststore.

First, delete any existing public certificate entries with the alias name jwtcertalias, or the value that is used in the jwt.cert.alias property in the /EJBServer/project/properties/JWTKeystore.properties file where it was updated.

To do this, run the keytool command that is provided with the Java<sup>TM</sup> SE Development Kit, or equivalent. For example:

```
keytool -delete -alias <alias_name> -keystore <keystore_file> -storetype <store_type> -
storepass <store_password>
```

Then, import the new public certificate file into the application server's keystore. For example:

```
keytool -import -trustcacerts -alias <alias_name> -storetype <store_type> -storepass
<store_password> -keystore <keystore_file> -file <certificate_file>
```

#### where:

- <alias\_name> is the string identifier for the truststore entry. This is defined in the jwt.cert.alias property in the /EJBServer/project/properties/
  JWTKeystore.properties file. The default name isjwtcertalias.
- <keystore\_file> is the absolute path to a keystore or truststore file that is used by the application server. The simplest option is to use the default keystore, which is already defined in the <keystore> element in the \${server.config.dir}/adc\_conf/server\_security.xml configuration file. The default keystore is located in the directory \${server.config.dir}/resources/security.
- <store type> is the type of keystore, for example JKS or PKCS12.
- <store password> is the password of the keystore or truststore.
- <certificate\_file> is the absolute path to the file that contains the public certificate. When the self-signed cert was created, a file that contains the public certificate is created in the <JAVA\_HOME>/jre/lib/ext directory. For example: <JAVA\_HOME>/jre/lib/ext/jwtcert.cer.

#### Using an existing keystore and signer certificate

If you are using an existing keystore and signer certificate instead of the generated self-signed certificate, use the preceding steps to import the public certificate into the application server's truststore. Ensure that you first run the configtest and build script. The script exports the public key certificate to <JAVA\_HOME>/jre/lib/ext/jwtcert.cer.

#### Updating the server.xml configuration file

The following list outlines the changes that you must make to the server.xml configuration file:

1. Add these features to the <featureManager> element:

```
<feature>openidConnectClient-1.0</feature>
<feature>transportSecurity-1.0</feature>
```

2. Add a new <authFilter> element:

This defines a filter for any incoming requests that contain the Authorization request header, by using the Bearer scheme. This is used so that OpenIDConnect functionality is applied only to incoming requests that include this header.

**3.** Add a new openidConnectClient> element:

```
<openidConnectClient
id="<unique_id>"
inboundPropagation="required"
issuerIdentifier="<issuer_identifier>"
audiences="ALL_AUDIENCES"
signatureAlgorithm="Rs256"
trustStoreRef="<keystore_ref>"
trustAliasName="<alias_name>"
authFilterRef="jwtAuthFilter"
/>
```

#### where:

- <unique id> can be any string ID for the element.
- <keystore\_ref> is the reference ID of the keystore that contains the public certificate. For default configurations, this is defaultKeyStore as defined in the /adc\_conf/ server\_security.xml configuration file.
- <alias\_name> is the alias of the entry in the keystore or truststore for the public certificate and it must match the alias name that is given when the public certificate was imported. This is jwtcertalias for default configurations that use the generated self-signed certificate.
- **4.** <issuer\_identifier> must exactly match the value of the iss field of the JWT. This value is configured by using the curam.watson.assistant.issuer system property in Merative™ Social Program Management. When the token is generated, the value is added to the JWT.
- **5.** Restart the server.

## 4 Getting started with your virtual assistant

To help you get started, see the open-source GitHub repository that provides sample code and guidance for a caseworker assistant called Case Assistant. Case Assistant enables caseworkers to get information more quickly, reducing the amount of navigation to complete their tasks. Caseworkers can ask about verifications on a case or client, and about caseworker policies and procedures.

Use Case Assistant and Watson<sup>™</sup> Assistant to build your own live virtual assistant into Social Program Management. Refer to the sample dialog skills and cloud functions, and see how to query Social Program Management data with REST APIs. For more information, see the *Social Program Management Virtual Assistant Cookbook* related link.

#### **Related information**

Social Program Management Virtual Assistant Cookbook

	_				
Morativo	Sacial	Drogram	Management	0 1	20
weranve	Social	rioulaiii	IVIALIAUEITIETI	Ο. Ι	20

### **Notices**

Permissions for the use of these publications are granted subject to the following terms and conditions.

#### **Applicability**

These terms and conditions are in addition to any terms of use for the Merative website.

#### Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of Merative

#### Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of Merative.

#### **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

Merative reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by Merative, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

MERATIVE MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

Merative or its licensors may have patents or pending patent applications covering subject matter described in this document. The furnishing of this documentation does not grant you any license to these patents.

Information concerning non-Merative products was obtained from the suppliers of those products, their published announcements or other publicly available sources. Merative has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-Merative products. Questions on the capabilities of non-Merative products should be addressed to the suppliers of those products.

Any references in this information to non-Merative websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this Merative product and use of those websites is at your own risk.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

The licensed program described in this document and all licensed material available for it are provided by Merative under terms of the Merative Client Agreement.

#### **COPYRIGHT LICENSE:**

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to Merative, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. Merative, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. Merative shall not be liable for any damages arising out of your use of the sample programs.

## Privacy policy

The Merative privacy policy is available at <a href="https://www.merative.com/privacy">https://www.merative.com/privacy</a>.

#### **Trademarks**

Merative  $^{TM}$  and the Merative  $^{TM}$  logo are trademarks of Merative US L.P. in the United States and other countries.

IBM®, the IBM® logo, and ibm.com® are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide.

Adobe<sup>™</sup>, the Adobe<sup>™</sup> logo, PostScript<sup>™</sup>, and the PostScript<sup>™</sup> logo are either registered trademarks or trademarks of Adobe<sup>™</sup> Systems Incorporated in the United States, and/or other countries.

Oracle and Java are registered trademarks of Oracle and/or its affiliates.

The registered trademark Linux® is used pursuant to a sublicense from the Linux Foundation, the exclusive licensee of Linus Torvalds, owner of the mark on a worldwide basis.

Microsoft<sup>™</sup>, Windows<sup>™</sup>, and the Windows<sup>™</sup> logo are trademarks of Microsoft<sup>™</sup> Corporation in the United States, other countries, or both.

UNIX<sup>™</sup> is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.