## SAND REPORT

SAND2008-draft Unlimited Release Printed Unpublished Draft

# Pamgen, a Library for Parallel Generation of Simple Finite Element Meshes

D. M. Hensinger, R. A. Drake, J. G. Foucar, T. A. Gardiner

Prepared by Sandia National Laboratories Albuquerque, New Mexico 87185 and Livermore, California 94550

Sandia is a multiprogram laboratory operated by Sandia Corporation, a Lockheed Martin Company, for the United States Department of Energy's National Nuclear Security Administration under Contract DE-AC04-94-AL85000.

Approved for public release; further dissemination unlimited.



Issued by Sandia National Laboratories, operated for the United States Department of Energy by Sandia Corporation.

**NOTICE:** This report was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government, nor any agency thereof, nor any of their employees, nor any of their contractors, subcontractors, or their employees, make any warranty, express or implied, or assume any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represent that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government, any agency thereof, or any of their contractors or subcontractors. The views and opinions expressed herein do not necessarily state or reflect those of the United States Government, any agency thereof, or any of their contractors.

Printed in the United States of America. This report has been reproduced directly from the best available copy.

Available to DOE and DOE contractors from

U.S. Department of Energy Office of Scientific and Technical Information P.O. Box 62 Oak Ridge, TN 37831

Telephone: (865) 576-8401 Facsimile: (865) 576-5728

E-Mail: reports@adonis.osti.gov Online ordering: http://www.doe.gov/bridge

Available to the public from

U.S. Department of Commerce National Technical Information Service 5285 Port Royal Rd Springfield, VA 22161

Telephone: (800) 553-6847 Facsimile: (703) 605-6900

E-Mail: orders@ntis.fedworld.gov

Online ordering: http://www.ntis.gov/help/ordermethods.asp?loc=7-4-0#online



#### SAND2008-draft Unlimited Release Printed Unpublished Draft

# Pamgen, a Library for Parallel Generation of Simple Finite Element Meshes

D. M. Hensinger, R. A. Drake, J. G. Foucar, T. A. Gardiner Sandia National Laboratories P.O. Box 5800 Albuquerque, NM 87185-0378

#### Abstract

Generating finite-element meshes is a serious bottleneck for large parallel simulations. When mesh generation is limited to serial machines and element counts approach a billion, this bottleneck becomes a roadblock. PAMGEN is a parallel mesh generation library that allows on-the-fly scalable generation of hexahedral and quadrilateral finite element meshes for several simple geometries. It has been used to generate more that 1.1 billion elements on 17,576 processors.

PAMGEN generates an unstructured finite element mesh on each processor at the start of a simulation. The mesh is specified by commands passed to the library as a "C"-programming language string. The resulting mesh geometry, topology, and communication information can then be queried through an API. PAMGEN allows specification of boundary condition application regions using sidesets (element faces) and nodesets (collections of nodes). It supports several simple geometry types. It has multiple alternatives for mesh grading. It has several alternatives for the initial domain decompositon. PAMGEN makes it easy to change details of the finite element mesh and is very usesful for performance studies and scoping calculations.

## Acknowledgment

The PAMGEN capabilities would not have been developed without the support and inspiration of the ALEGRA community of users and developers. Within the users community, Chris Garasi and his challenging analysis requirements were the spur for development of the most complex and rewarding capabilities. Tom Brunner severely stressed the code with his early testing on large platforms. Within the developers community, the build and benchmark utilities written by Richard Drake enabled continual improvement in functionality and robustness. Tom Gardiner provided the code that is the heart of the default load balance capability.

This page intentionally left blank.

## Contents

1	Intr	roduction	<b>12</b>
2	Cap	pabilities	13
	2.1	Dimensions	13
	2.2	Mesh Geometries	13
	2.3	Boundary Conditions	14
	2.4	Decomposition	14
	2.5	Geometry Transformation	14
	2.6	Element Density	15
3	Арр	oroach	16
4	Usa	ge	17
5	Spe	cifying a Mesh	18
	5.1	Dimensionality	18
	5.2	Block IDs	19
	5.3	Geometry and Topology	20
		5.3.1 Rectilinear	20
		5.3.2 Spherical	22
		5.3.3 Cylindrical	24
		5.3.4 Radial and Radial Trisection	26
		5.3.5 Brick	33
	5.4	Boundary Conditions (Nodesets and Sidesets)	35

	5.5	User I	Defined Geometry Transformation	38
	5.6	User I	Defined Element Density	41
	5.7	Decon	nposition Strategy	43
6	Lib	rary Ir	nterface	47
	6.1	Creati	ing a Mesh	47
		6.1.1	Create_Pamgen_Mesh	47
		6.1.2	getPamgenEchoStreamSize	48
		6.1.3	getPamgenEchoStream	48
		6.1.4	getPamgenErrorStreamSize	48
		6.1.5	getPamgenErrorStream	48
		6.1.6	getPamgenWarningStreamSize	49
		6.1.7	getPamgenWarningStream	49
		6.1.8	getPamgenInfoStreamSize	49
		6.1.9	getPamgenInfoStream	49
	6.2	Query	ring a Mesh	51
		6.2.1	im_ex_get_init	51
		6.2.2	im_ex_inquire	52
		6.2.3	$im\_ex\_get\_coord \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	53
		6.2.4	im_ex_get_coord_names	53
		6.2.5	im_ex_get_map	54
		6.2.6	im_ex_get_elem_num_map	54
		6.2.7	im_ex_get_node_num_map	55
		628	im ex get elem blk ids	55

6.2.9	im_ex_get_elem_block	. 55
6.2.10	im_ex_get_elem_conn	. 56
6.2.11	$im_ex_get_node_set_ids$	. 57
6.2.12	$im\_ex\_get\_node\_set\_param  .  .  .  .  .  .  .  .  .  $	. 58
6.2.13	$im\_ex\_get\_node\_set  .  .  .  .  .  .  .  .  .  $	. 58
6.2.14	$im\_ex\_get\_side\_set\_ids \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	. 59
6.2.15	$im\_ex\_get\_side\_set\_param \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	. 59
6.2.16	$im_ex_get\_side\_set$	. 60
6.2.17	$im\_ex\_get\_qa \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	. 60
6.2.18	im_ex_get_info	. 61
6.2.19	im_ne_get_init_global	. 62
6.2.20	im_ne_get_init_info	. 63
6.2.21	im_ne_get_eb_info_global	. 63
6.2.22	im_ne_get_ns_param_global	. 64
6.2.23	im_ne_get_ss_param_global	. 64
6.2.24	im_ne_get_loadbal_param	. 65
6.2.25	im_ne_get_elem_map	. 60
6.2.26	im_ne_get_node_map	. 67
6.2.27	im_ne_get_cmap_params	. 67
6.2.28	$im\_ne\_get\_node\_cmap \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	. 68
6.2.29	$im\_ne\_get\_elem\_cmap \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	. 69
Deletin	ng a Mesh	. 70
6.3.1	Delete Pamgen Mesh	. 70

6.3

$\mathbf{A}$	Rur	ntime (	Compiler Functionality	<b>71</b>
	A.1	The R	TC language	71
		A.1.1	Operators	71
		A.1.2	Control flow	72
		A.1.3	Line Structure	73
		A.1.4	Variables	73
		A.1.5	Math	74
		A.1.6	Strings	75
		A.1.7	Printf	75
		A.1.8	Comments	76
		A.1.9	Unsupported Features	76
В	reac	$_{ m l\_mesh}$	$_{ m Lto\_memory}$	77
Re	efere	nces		85
In	$\operatorname{dex}$			87

# List of Figures

1	The mesh geometry zoo in 3D	13
2	Examples of geometry transformation	14
3	Definition of a three-dimensional RECTILINEAR mesh	21
4	Definition of a two-dimensional spherical mesh	23
5	Definition of a three-dimensional spherical mesh	23
6	Three dimensional CYLINDRICAL mesh	25
7	Three dimensional RADIAL mesh	28
8	A 360 degree RADIAL mesh	29
9	A RADIAL TRISECTION mesh with three trisection blocks	30
10	A RADIAL TRISECTION mesh with three trisection blocks	31
11	A 360 degree RADIAL TRISECTION mesh	32
12	Three dimensional BRICK mesh	34
13	Block topology and labels	36
14	A RADIAL TRISECTION mesh with sidesets	37
15	3D Geometry Transformation Example	39
16	2D Geometry Transformation Example	40
17	$2\mathrm{D}$ mesh created with a USER DEFINED ELEMENT DENSITY	42
18	BISECTION decomposition run on 7 processors	44
19	PROCESSOR LAYOUT decomposition run on 8 processors	45
20	PROCESSOR LAYOUT decomposition on 8 processors	45

# List of Tables

1	Keywords for RECTILINEAR END	20
2	Keywords for SPHERICAL END	22
3	Keywords for CYLINDRICAL END	24
4	Keywords for DECOMPOSITION STRATEGY END	46

#### 1 Introduction

To overcome the challenge of producing multi-million finite element meshes for simulations using more than 1000 processors a library has been developed (PAMGEN) that for several simple geometries produces each processor's mesh as an early step of the analysis execution. The specification for these meshes is provided by a block of terse instructions that may be placed in an input file. These instructions are passed to the library as a "C"-programming language character array. PAMGEN is also referred to as an "in line" mesh generator because the meshing instructions may be included in one of the analysis input decks.

The simple input format allows analysts to change the resolution of a simulation by altering a few parameters. It also allows them to execute their simulations on different numbers of processors without requiring any pre-processing.

The mesh generation proceeds through steps of decomposition, local element creation, and communication information generation. The final product of the library is a data structure that can be queried using an API (Application Programming Interface) that is based on the NEMESIS and EXODUS APIs. Currently the library is limited to generating meshes of domains with cylindrical, tubular, and block shapes. Substantial control is allowed over the element density within these shapes. Boundary condition application regions can be specified on the surfaces and interior of the mesh .

Development of this capability revealed that the parallel mesh generation process can be reduced to answering a series of questions: What elements are on this processor? What nodes are on this processor? What is the connectivity of this element? What elements border this element? What processor does this element reside on?... Resolving these questions inductively, without resolution to communication, is essential for preserving scalability. Once a framework for posing and answering these questions for a particular geometry is established, expanding the capability to support additional geometries is straightforward.

## 2 Capabilities

The capabilities of PAMGEN are best understood by studying Section 5, which documents in detail the instructions available for specifying a mesh. This section provides a brief overview of the library's capabilities. PAMGEN will be distributed as part of the Trilinos package of matrix and finite element tools.

#### 2.1 Dimensions

PAMGEN can create both two and three dimensional meshes. It creates quadrilateral finite element meshes if two dimensions are specified, and it creates hexahedral finite element meshes if three dimensions are specified. For two dimensional quadrilateral meshes the Z component of nodal coordinates is not supplied.

#### 2.2 Mesh Geometries

The PAMGEN library handles the mesh geometries shown below:

- Bricks
- Partial hollow cylinders
- Complete hollow cylinders
- Partial solid cylinders
- Complete solid cylinders











Figure 1: The mesh geometry zoo in 3D.

## 2.3 Boundary Conditions

Boundary conditions application regions in the form of node sets and side sets can be applied to the face, edge, or corner of any element block in the finite element mesh. They may also be applied to any face, edge, or corner of the entire mesh.

### 2.4 Decomposition

There are several mesh decomposition strategies available in PAMGEN:

- A default decomposition based on a constrained optimized solution that slices through the entire mesh in its three (or two in 2D) topological dimensions.
- A user defined slicing strategy that specifies the number of slices through the mesh in each topological direction.
- A sequential strategy that distributes elements beetween processors based on their element ids with the first n elements going to processor 0 ...
- A random strategy that assigns element to processors randomly.

## 2.5 Geometry Transformation

Any mesh can be modified by re-evaluating the nodal coordinate values using a user-supplied function. This function has the original nodal coordinates as input values. Its output values define the new nodal coordinates.




Figure 2: Examples of geometry transformation.

## 2.6 Element Density

Several of the geometry types allow specification of first and last element sizes within a block in a particular cartesian direction. In addition the user may control node distribution over any geometry by providing a user defined distribution function. This function is evaluated so that nodes are shifted towards areas where the function has its highest values.

## 3 Approach

PAMGEN operates on the premise that mesh generation is deterministic. This means that every execution of code compiled with compiler A and run on processor B under operating system C reading mesh instructions file D will produce an identical mesh. The mesh will have the same topology and the nodes will have the same coordinate locations. On a multi-processor machine of identical nodes an arbitrary number of processors executing identical instructions produce an identical mesh. Use of PAMGEN on heterogeneous machines may produce unexpected results.

With one significant exception, PAMGEN operates in the same way as these identical processors producing identical mesh. The exception is that each processor only allocates for a subset of the nodes and elements, and each processor performs topology and geometry calculations only for the entities and dependencies present on that processor. PAMGEN exploits the fact that each processor is capable of producing the entire mesh in order to allow each processor to produce its own mesh. The deterministic nature of the meshing process is essential to allow correspondence in topologies and geometries produced on adjacent processors.

The implementation of the mesh generation in PAMGEN is as much as possible implicit. Quantities are not allocated until they are ready for output, and they are not calculated until they can be stored, or until they are required by a dependent calculation. This approach can result in duplication of intermediate calculations, but it avoids the severe limitations on total problem size that occur if attempts are made to allocate any quantity with a size related to the total mesh size.

## 4 Usage

For the few simple geometries and element types it supports, the PAMGEN library is a substitute for pre-processed finite element mesh files. Successful usage of the library requires some modification of the analysis code.

The PAMGEN library must be linked into the analysis executable to allow access to the mesh creation, query and deletion functions.

The modules in the analysis code that read finite element mesh data from a file must be adapted to:

- Read in a "C"-programming language string that specifices the geometry, topology, and boundary conditions of a mesh.
- Pass that string to the PAMGEN Create\_Pamgen\_Mesh(...) function along with the rank of the mesh requested and the total number of processors across which the mesh is spread.
- Handle message and possibly error strings available after calling Create\_Pamgen\_Mesh(...).
- Call the PAMGEN query functions to populate the analysis code's mesh and communication data structures.
- Call the PAMGEN Delete\_Pamgen\_Mesh() function release memory allocated within the library.

The source code for a stand-alone executable called "pamgen\_lt\_c" is distributed with the PAMGEN library. This example code is an excellent starting point for adapting an analysis code to use the PAMGEN library.

## 5 Specifying a Mesh

The "C"-programming language string passed to PAMGEN is the complete definition of the mesh's geometry, topology, node sets, side sets, and parallel decomposition. It must begin with a MESH keyword, and it must end with an END keyword. The MESH -- END keyword pair must surround a RECTILINEAR -- END, SPHERICAL -- END, BRICK -- END, RADIAL -- END, RADIAL TRISECTION -- END, or CYLINDRICAL -- END keyword pair and may have additional SET ASSIGN -- END, DECOMPOSITION STRATEGY -- END, USER DEFINED ELEMENT DENSITY -- END, or USER DEFINED GEOMETRY TRANSFORMATION -- END keyword pairs.

```
MESH
{RECTILINEAR | SPHERICAL | BRICK | RADIAL | RADIAL TRISECTION | CYLINDRICAL}

[subkeyword-list]

END

[SET ASSIGN]

[END]

[DECOMPOSITION STRATEGY]

[END]

[USER DEFINED GEOMETRY TRANSFORMATION]

[END]

[USER DEFINED ELEMENT DENSITY]

[END]

END

END
```

## 5.1 Dimensionality

The dimensionality of the mesh is not specified in the "C" programming language string. It is passed to the PAMGEN library at execution time through the PAMGEN API. In general a 2D mesh can be specified by removing 3D specific keywords and values (those referencing a third coordinate [for example Z or k]) from a 3D mesh description.

#### 5.2 Block IDs

The finite elements created using PAMGEN are grouped into blocks. Each block has a positive non-zero id. These ids are automatically assigned by PAMGEN and are not under the control of the user. If there is a single block then its id is 1. When there are more than one block, the ids are assigned beginning with the block in the lowest topological position in i, j, k space. Subsequent blocks are incrementally numbered first in the i topological direction, next in the j topological direction, and finally in the k topological direction. In the case of BRICK and RECTILINEAR meshes i, j, and k correspond to the coordinate directions x, y, and z. In the case of CYLINDRICAL, RADIAL, and RADIAL TRISECTION meshes i, j, and k correspond to r,  $\theta$ , and z.

## 5.3 Geometry and Topology

#### 5.3.1 Rectilinear

RECTILINEAR
[subkeyword-list]
END

The RECTILINEAR -- END block pair surrounds the description of the geometry of a rectilinear mesh. The extent of the domain is given by a pair of vectors (gmin and gmax). The number of blocks in each coordinate direction and the number of elements in each block are given by additional keywords. The total number of elements specified in this type of mesh is the product of the total number of blocks BX  $\times$  BY  $\times$  BZ and the total number of elements per block NX  $\times$  NY  $\times$  NZ. For a 2D mesh NZ and BZ must be omitted. The keywords associated with the RECTILINEAR keyword are given in Table 1.

Table 1: Keywords for RECTILINEAR -- END.

Sub-Keyword	Input	Description
NX	int	Number of cells in x-direction.
NY	int	Number of cells in y-direction.
NZ	int	Number of cells in z-direction.
ВХ	int	Number of blocks in the x-direction.
ВҮ	int	Number of blocks in the y-direction.
BZ	int	Number of blocks in the z-direction.
GMIN	vector	Minimum domain coordinates (x,y,z).
GMAX	vector	Maximum domain coordinates (x,y,z).

An example of a mesh specification with the RECTILINEAR option is illustrated in Figure 3.

```
mesh
   rectilinear
      nx = 10
      ny = 10
                                                                                        MAGNIFIED BY 1.000
ELEMENT BLOCKS ACTIVE:
140 OF 140
     nz = 10
      bx = 4
     by = 7
      bz = 5
      gmin = 1.0 1.0 1.0
      gmax = 4.0 7.0 5.0
   end
                                                                                        TIME 19.64E-6
   set assign
     nodeset, ihi, 2
     nodeset, jhi, 1
   \quad \text{end} \quad
end
```

Figure 3: Definition of a three-dimensional RECTILINEAR mesh.

#### 5.3.2 Spherical

SPHERICAL
[subkeyword-list]
END

The SPHERICAL -- END block pair allows the description of a curvilinear spherical mesh centered at the origin and described by an inner and outer radius, and the extent of revolution in  $\theta$  and  $\phi$  directions. Angle  $\theta$  is measured counter-clockwise about the z-axis from the x-axis, and angle  $\phi$  is measured counter-clockwise from the y-axis about the x-axis. The number of elements and blocks in each curvilinear coordinate direction are specified by the keywords in Table 2. The parameters PHI, NPHI, and BPHI are only appropriate for 3D problems. When used in 2D simulations, CYLINDRICAL and SPHERICAL keywords produce identical meshes.

Table 2: Keywords for SPHERICAL -- END.

Sub-Keyword	Input	Description
NR	int	Number of cells in r-direction.
NTHETA	int	Number of cells in $\theta$ -direction.
NPHI	int	Number of cells in $\phi$ -direction.
BR	int	Number of blocks in the r-direction.
BTHETA	int	Number of blocks in $\theta$ -direction.
BPHI	int	Number of blocks in $\phi$ -direction.
RI	real	Inner radius
RO	real	Outer radius
THETA	real	Angular extent in $\theta$ (degrees,0180. in 3D, 0360.
		in 2D)
PHI	real	Angular extent in $\phi$ (0360)

An example of a mesh definition syntax with the SPHERICAL option is illustrated in Figure 4 for a 2D simulation. An example of 3D spherical mesh generation follows in Figure 5.

```
0.40
mesh
                                            0.35
   spherical
                                            0.30
     ri = 0.0
                                            0.25
     ro = 0.5
     theta = 45
                                            0.20
     ntheta = 10
     nr = 20
                                            0.10
     br = 2
                                            0.05
     btheta = 2
                                            0.00
   end
                                           -0.05
end
                                              0.00 0.05 0.10 0.15 0.20 0.25 0.30 0.35 0.40 0.45 0.50
```

Figure 4: Definition of a two-dimensional spherical mesh.

```
mesh
                                      0.0
  spherical
     ri = 0.5
                                      -0.3
     ro = 1.0
                                      -0.6
     theta = 180.0
    ntheta = 10
                                      -0.9
     nr = 10
     br = 2
                                      -1.2
     btheta = 2
                                      -1.5
     bphi = 2
     nphi = 10
                                      -1.8
    phi = 90
  end
                                                         0.0
                                               -0.6
                                                    -0.3
end
```

Figure 5: Definition of a three-dimensional spherical mesh.

#### 5.3.3 Cylindrical

CYLINDRICAL [subkeyword-list] END

The CYLINDRICAL -- END block pair allows the description of a curvilinear cylindrical mesh centered at the origin in x and y, and aligned along the z-axis. It is described by an inner and outer radius, the extent of revolution in angle  $\theta$  about the z-axis, and its start and end in the z-direction. Angle  $\theta$  is measured counter-clockwise about the z-axis from the x-axis. The number of elements and blocks in each indicial direction are specified by the keywords in Table 3. The parameters ZMIN, ZMAX, NZ, and BZ are only appropriate for 3D problems. When used in 2D solutions, CYLINDRICAL and SPHERICAL produce identical meshes.

Table 3: Keywords for CYLINDRICAL -- END.

Sub-Keyword	Input	Description
NR	int	Number of cells in r-direction.
NTHETA	int	Number of cells in $\theta$ -direction.
NZ	int	Number of cells in z-direction.
BR	int	Number of blocks in the r-direction.
BTHETA	int	Number of blocks in $\theta$ -direction.
BZ	int	Number of blocks in z-direction.
RI	real	Inner radius
RO	real	Outer radius
THETA	real	Angular extent in $\theta$ degrees, 0360.
ZMIN	real	Start of mesh in z-direction
ZMAX	real	End of mesh in z-direction

An example of a PAMGEN mesh definition with the CYLINDRICAL option is illustrated in Figure 6.

```
{\tt mesh}
   cylindrical
                                                                                  MAGNIFIED BY 1.000
ELEMENT BLOCKS ACTIVE:
      ri = 0.5
      ro = 1.0
      theta = 90.0
      ntheta = 10
      nr = 10
      br = 2
      zmin = 1.0
      zmax = 2.0
                                                                                   TIME 0.0000
      nz = 10
      bz = 2
   \quad \text{end} \quad
end
```

Figure 6: Three dimensional CYLINDRICAL mesh.

#### 5.3.4 Radial and Radial Trisection

```
{RADIAL | RADIAL TRISECTION }
   [ENFORCE PERIODICITY]
   [TRISECTION BLOCKS, int]
   [TRANSITION RADIUS, int]
   [ZMIN real]
   NUMZ int
       ZBLOCK int real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
   {NUMR | NUMX} int INITIAL RADIUS real
       RBLOCK int real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
   {NUMA | NUMY} int
       ABLOCK int real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
END
```

The RADIAL and RADIAL TRISECTION block pairs allow the description of a curvilinear cylindrical mesh centered at the origin in x and y, and aligned along the z-axis. The RADIAL TRISECTION -- END block pair fills in the center of the cylindrical mesh with transition elements. These options are similar to the CYLINDRICAL but they have a different set of controls on element distribution. The successful creation of these meshes requires sequential specification of the information for the number of elements blocks and their sizes in each coordinate direction.

The ENFORCE PERIODICITY keyword applies only to RADIAL and RADIAL TRISECTION mesh descriptions that meet certain requirements:

- The meshes must have azimuthal angles of 90, 180, or 360 degrees.
- The meshes must have a single block of elements in the azimuthal direction.
- The meshes must have an even number of elements in each 90 degree segment of the mesh.
- For RADIAL TRISECTION meshes, one transition zone is required for each 90 degrees of azimuth.

This keyword causes the mesh generation to perform all node coordinate calculations in the first 45 degrees of the azimuthal domain. Coordinate

locations of nodes ouside of 45 degrees are formed by permuting the sign and oder of the components of periodically corresponding nodes' locations. This guarantees that there will be no differences between the absolute floating point values of periodically corresponding nodes' coordinates.

The NUMZ | NUMR | NUMA keywords are followed by an integer specifying the number of element blocks in that coordinate direction. The NUMR line includes an additional real parameter that specifies the inner radius of the cylindrical mesh. Specification of an inner radius of 0.0 will result in degenerate elements with co-located nodes along the Z axis. The innner radius specification is ignored for RADIAL TRISECTION meshes.


Immediately following the NUMZ int | NUMR int INITIAL RADIUS real | NUMA int lines, there must be a ZBLOCK | RBLOCK | ABLOCK line for each of the blocks in that direction. These lines specify the spatial extent of the particular block and the distribution of elements in the block in that direction. The INTERVAL int keyword specifies a fixed number of elements in the block. A FIRST SIZE real LAST SIZE real pair specifies the absolute size of the first and last elements in the block. When the FIRST SIZE real LAST SIZE real specification is used, the element sizing will be linear between the first and last elements. The sizes of the first and last elements may be adjusted slightly to provide linear sizing. The approximate number of elements that will be generated using FIRST SIZE and LAST SIZE sizing controls is given by truncating to an integer, the length of the mesh segment divided by the average of the FIRST SIZE and LAST SIZE values. There is a slight chance that this calculation will result in a different number of elements on different computer platforms. Omission of the LAST real keyword is equivalent to setting the element size to that given by the FIRST SIZE real keyword.

The RADIAL TRISECTION -- END block pair requires the additional input of TRISECTION BLOCKS, int and it accepts the optional TRANSITION RADIUS, real keyword value pair. The TRISECTION BLOCKS keyword specifies the number of transition zones that will be used in the central region of the mesh. This number must be supplied. One transition zone is recommended for each 90 degrees of azimuth. The TRANSITION RADIUS is the distance from the origin to the corners of the transition zones of mesh. Without this parameter the transition radius is chosen to be one half of the radial thickness of the first block. When RADIAL TRISECTION is selected, any INITIAL RADIUS supplied is ignored.

The ZMIN real keyword value pair is available to specify an offset for the entire mesh in the Z direction.

If the cumulative values of the sizes of the azimuthal blocks, given by the second argument of ABLOCK int real is equal to 360.0 degrees, then the mesh will form an single closed ring of elements.

An example of PAMGEN mesh definition with the RADIAL option is illustrated in Figure 7.



```
mesh
  radial
  numz 2
    zblock 1 10.0 first size 1 last size 2
    zblock 2 10.0 first size 2 last size 1
  numr 2 initial radius 1.
    rblock 1 10. first size 1. last size 2.
    rblock 2 10. first size 2. last size 1.
  numa 1
    ablock 1 120. interval 10
  end
end
```

Figure 7: Three dimensional RADIAL mesh.

A second example of PAMGEN mesh definition with the RADIAL option is

illustrated in Figure 8. In this case the sum of the azimuthal blocks is 360.0 and the mesh is a complete cylinder.

```
mesh
radial
numz 1
zblock 1 10.0 interval 6
numr 3
rblock 1 2. interval 12
rblock 2 5. interval 6
rblock 3 5. interval 12
numa 1
ablock 1 360. interval 36
end
end
```





Figure 8: Three dimensional RADIAL mesh with azimuthal angle of 360 degrees.

An example of a PAMGEN mesh definition with the RADIAL TRISECTION option is illustrated in Figure 9. This figure is annotated to show the correspondence between input parameters and the resulting mesh. This mesh uses a TRISECTION BLOCKS setting of 3. In this case the azimuthal angle is 90. degrees and the FIRST SIZE, LAST SIZE, and TRANSITION RADIUS directives are used.

An second example of a PAMGEN mesh definition with the RADIAL TRISECTION option is illustrated in Figure 10.

A third example of a PAMGEN mesh definition with the RADIAL TRISECTION option is illustrated in Figure 11. In this case the azimuthal angle is 360. degrees and the mesh is a complete circular disk.



```
mesh
  radial trisection
    trisection blocks, 3
    transition radius, 6.5
  numz 1
    zblock 1 1. interval 1
  numr 3
    rblock 1 8.0 interval 4
    rblock 2 3.0 first size 0.05 last size 0.5
    rblock 3 4.0 first size 0.5 last size 0.05
  numa 1
    ablock 1 90. interval 12
  end
end
```

Figure 9: A RADIAL TRISECTION mesh with azimuthal angle of 90 degrees and three trisection blocks. FIRST SIZE and LAST SIZE commands are used to specify element density.

```
mesh
  radial trisection
    trisection blocks, 2
  zmin -0.00075
  numz 1
    zblock 1 1. interval 4
  numr 3
    rblock 1 2.0 interval 4
    rblock 2 3.0 interval 4
    rblock 3 4.0 interval 4
  numa 1
    ablock 1 90. interval 12
  end
end
```

Figure 10: Three dimensional RADIAL TRISECTION mesh with azimuthal angle of 90 degrees and two trisection blocks.

```
radial trisection

trisection blocks, 4

zmin -0.00075

numz 1

zblock 1 4. interval 4

numr 3

rblock 1 2.0 interval 4

rblock 2 3.0 interval 4

rblock 3 5.0 interval 4

numa 1

ablock 1 360. interval 32

end
end
```

Figure 11: Three dimensional RADIAL TRISECTION mesh with azimuthal angle of 360 degrees and four trisection blocks.

#### 5.3.5 Brick

```
BRICK
  NUMZ int (1)
    ZBLOCK 1 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
    ZBLOCK 2 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
    . . .
    ZBLOCK 1 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
  NUMX int (m)
    XBLOCK 1 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
    XBLOCK 2 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
    . . .
    XBLOCK m real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
  NUMY int (n)
    YBLOCK 1 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
    YBLOCK 2 real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
    YBLOCK n real {INTERVAL int | FIRST SIZE real [LAST SIZE real]}
END
```

The BRICK mesh topology type is a more flexible version of the RECTILINEAR type in that it allows different numbers of elements in each element block in each coordinate direction. The creation of a BRICK mesh is analogous to the RADIAL mesh option and successful creation of these meshes requires sequential specification of the information for the number of elements blocks and their sizes in each coordinate direction.

The NUMX | NUMY | NUMZ keywords are followed by an integer specifying the number of element blocks in that coordinate direction. The

Immediately following the NUMX int | NUMY int | NUMZ int lines, there must be a XBLOCK | YBLOCK | ZBLOCK line for each of the blocks in that direction. The first integer on this line corresponds to the ordinal (beginning with 1) of the line. These lines specify the spatial extent of the particular block and the distribution of elements in the block in that direction. The INTERVAL int keyword specifies a fixed number of elements in the block. A FIRST SIZE real LAST SIZE real pair specifies the absolute size of the

first and last elements in the block. When the FIRST SIZE real LAST SIZE real specification is used, the element sizing will be linear between the first and last elements. The sizes of the first and last elements may be adjusted slightly to provide linear sizing. Omission of the LAST real keyword is equivalent to setting the element size to that given by the FIRST SIZE real keyword.

An example of a PAMGEN mesh definition with the BRICK option is illustrated in Figure 12.




Figure 12: Three dimensional BRICK mesh.

#### 5.4 Boundary Conditions (Nodesets and Sidesets)

The SET ASSIGN -- END keyword pair allows the specification of nodesets and sidesets on the exterior of meshes. These nodesets and sidesets can be used for specifying boundary conditions on the domain. The nodeset or sideset is applied to the topological face, edge, or vertex associated with the prescribed topological direction. The mesh domain topology and associated labels are shown in Figure 13. This specification applies to the entire domain and cannot be used to specify individual blocks.

The most commonly used sub-domains are the exterior faces of the domain. They can be prescribed using IHI, JHI, KHI, ILO, JLO, or KLO. For RECTILINEAR meshes I,J, and K correspond to the coordinate directions x, y, and z. For SPHERICAL meshes I,J, and K correspond to the coordinate directions r,  $\theta$ , and  $\phi$ . For CYLINDRICAL meshes I,J, and K correspond to the coordinate directions r,  $\theta$ , and z. The KHI, KLO options do not exist in two dimension simulations.

Specifying a nodeset on the ILO face of a RADIAL TRISECTION mesh refers to the edge aligned with the Z axis (see Figure 14). Sidesets may not be specified on the ILO face of RADIAL TRISECTION meshes.

BLOCK NODESETS and BLOCK SIDESETS are only available to the BRICK, RADIAL, and RADIAL TRISECTION geometry mesh types.

The [BLOCK SIDESET | BLOCK NODESET, IHI | JHI | KHI | ILO | JLO | KLO , int, int] command allows specification of nodesets and sidesets on the topological faces of blocks that may be within the finite element mesh. The first integer specifies the id that the sideset or nodeset will have, the second integer specifies the block on which the sideset or nodeset is applied.

An example of BLOCK SIDESET applied to a mesh definition with the

```
Side: 0-4-7-3 - ILO
                         k 7----6
                                              Edge:
                                                    0-1 - E00
Side: 1-2-6-5
              - IHI
                          | /| j
                                     /1
                                              Edge:
                                                     1-2 - E01
              - JLO
                          1/ 1 /
                                     / |
                                              Edge:
Side: 0-1-5-4
                                                     3-2 - E02
                          4----5 |
Side: 3-7-6-2
              - JHI
                                              Edge:
                                                    0-3 - E03
                          | 3-----|
Side: 0-3-2-1
              - KLO
                                              Edge:
                                                    0-4 - E04
Side: 4-5-6-7
              - KHI
                          | /
                                   | /
                                              Edge:
                                                     1-5 - E05
                          1/
                                    1/
                                                     2-6 - E06
                                              Edge:
                          0----1 --i
Vertex: 0 - V00
                                              Edge:
                                                     3-7 - E07
Vertex: 1 - V01
                                                    4-5 - E08
                                              Edge:
Vertex: 2 - V02
                                              Edge:
                                                     5-6 - E09
Vertex: 3 - V03
                                              Edge:
                                                    7-6 - E10
                                                    4-7 - E11
Vertex: 4 - VO4
                                              Edge:
Vertex: 5 - V05
Vertex: 6 - V06
Vertex: 7 - V07
```

Figure 13: Block topology and labels.

RADIAL TRISECTION option is illustrated in Figure 14. In this example a side is applied to the IHI face of block 2. The sideset applied to block 2 will have sideset id 45. The faces called out in these sidesets will have outward normals facing in the IHI direction.

```
mesh
  radial trisection
    trisection blocks, 2
    zmin -0.00075
    numz 1
      zblock 1 1. interval 4
    numr 3
      rblock 1 2.0 interval 4
      rblock 2 3.0 interval 4
      rblock 3 4.0 interval 4
    numa 1
      ablock 1 90. interval 12
  end
  set assign
    nodeset, ilo, 100
    block sideset, ihi, 45, 2
  end
end
```

Figure 14: Three dimensional RADIAL TRISECTION mesh with azimuthal angle of 90 degrees and two trisection blocks having sidesets specified on the radially outward directed faces of blocks 1 and 2. A nodeset is specified on the ILO face of this mesh and marks the edge corresponding to the z axis (blue circles).

## 5.5 User Defined Geometry Transformation

```
USER DEFINED GEOMETRY TRANSFORMATION

"
user supplied 'C' language instructions;

"
END
```

The USER DEFINED GEOMETRY TRANSFORMATION — END keyword pair provides a powerful way to modify the coordinats of any node of a mesh. The keyword-end pair must surround a double quote surrounded block of 'C' code. This code will be called with coordinates of every node in the mesh. It may modify the the coordinats by setting the output variables outxcoord, outycoord, and outzcoord. The unmodified values of the node's coordinates are available in the input variables inxcoord, inycoord, and inzcoord. The coordinates will remain unchanged if the output variables are not modified. A presentation of the capabilities and limitations of runtime compiled 'C' functions is included in Appendix A.

Examples of meshes produced using this capability feature of PAMGEN are shown below in Figure 15 and Figure 16. In the first example the nodes with positive Z coordinate values are rotated about the Z axis an angle propportional to their distance from the Z=0 plane. In the second example nodes a distance of 0.5 from the origin are rotated about the origin in proportion to their distance from the origin.




Figure 15: 3D mesh illustrating the ability to modify nodal coordinates using USER DEFINED GEOMETRY TRANSFORMATION.




Figure 16: 2D mesh illustrating the ability to modify nodal coordinates using USER DEFINED GEOMETRY TRANSFORMATION.

## 5.6 User Defined Element Density

The USER DEFINED ELEMENT DENSITY -- END keyword pair provides a flexible way to bias RECTILINEAR, SPHERICAL, and CYLINDRICAL meshes. The keyword-end pair must surround a double quote surrounded block of 'C' code that evaluates on the input variable coord and sets the return value field. The return value field must be set to a positive value across the range of the mesh in the selected topological direction. A presentation of the capabilities and limitations of runtime compiled 'C' functions is included in Appendix A.

The mesh biasing adjusts the nodal coordinates such that the density of the elements in a region of the mesh in the selected coordinate direction is proportional to the value of field relative to the integral of field across the mesh domain. This is implemented by numerically solving the equation given below. In this equation  $x_i$  is the coordinate of node i, n is the total number of nodes in the coordinate direction, and f(u) is the user supplied function.

$$\frac{\int_0^{x_i} f(u)du}{\int_0^{x_n} f(u)du} = \frac{i}{n}$$

$$(5.1)$$

When these functions are applied to a two dimensional RECTILINEAR mesh spanning from (0.0,0.0) to (1.0,1.0) and having two blocks and 10 elements in both the 'I', and 'J' directions, the resulting mesh is graded as shown in Figure 17. The grading is a continuous exponential function in the 'I' direction and is a discontinuous function in the 'J' direction. In the 'J' direction the domain stretching from 0.0 to 0.5 has twice the element density as the range from 0.5 to 1.0.

Diagnostic information for the user provided functions is included in the runid.out file. This information includes the total integrated value of the function, the minimum and maximum value of the function, and a plot of the function's values across the range of evaluation.

Figure 17: 2D mesh created with a USER DEFINED ELEMENT DENSITY.

## 5.7 Decomposition Strategy

```
DECOMPOSITION STRATEGY
{BISECTION}
{PROCESSOR LAYOUT}
{NUMPROCS, I, int (1)}
{NUMPROCS, J, int (1)}
{NUMPROCS, K, int (1)}
{END}
{SEQUENTIAL}
{RANDOM}
END
```

An optional DECOMPOSITION STRATEGY -- END block pair surrounds the description of the decomposition method used for parallel simulations. The default strategy is BISECTION. The keywords associated with the DECOMPOSITION STRATEGY keyword are given in Table 4.

The BISECTION decomposition strategy is the default for parallel calculations. This is because it is robust in providing decompositions and the resulting regions have satisfactory surface area to volume ratios. This strategy attempts to automatically determine the number of slices to make through the entire mesh domain to provide an equal number of elements to each processor. This strategy will be most successful when the number of processors, and the number of elements in each direction are a power of 2 or a product of several prime numbers.

The PROCESSOR LAYOUT decomposition strategy offers the user improved control of the distribution of elements to each processor in a parallel simulation. The strategy divides the mesh into the number of segments specified by the keyword-value pair for each coordinate direction. The number of processors must equal the product of the values given for each of the NUMPROCS directions. The default value for a coordinate direction is one.

When using a RADIAL TRISECTION mesh the number of processors in the I (radial) direction is fixed at 1, and the total number of processors must be equal to the product of the values given for the J and K NUMPROCS directions. For this mesh type the decomposition assigns elements from the inner transition blocks to the processor that owns the adjacent elements in the outer cylinderical blocks. An example of the PROCESSOR LAYOUT decomposition

option applied to a RADIAL TRISECTION mesh is shown in Figure 20.

Examples of BISECTION and PROCESSOR LAYOUT decomposition options applied to a mesh definition with the RADIAL option are shown below in Figures 18 and 19. The total number of elements in this problem was 204, 17 in the radial or I direction and 12 in the azimuthal or J direction.

For the BISECTION decomposition the recursive cuts made on the 17x12x1 array of elements results in three processors with 3x12x1 elements, four processors with 2x12x1 elements and a single processor 6x8x1 elements.

For the PROCESSOR LAYOUT decomposition the 17 elements in the I or radial direction are divided by 4 to set the size of segments produced in that direction at 4. The first segment's size is increased by one to handle the remainder of dividing 14 by 4. This decomposition would equally distribute elements to each processor if the I direction had a number of elements evenly divisible by 4.

```
mesh
  radial
    numz 1
      zblock 1 10.0 interval 1
    numr 4 initial radius 1.
      rblock 1 2. interval 3
      rblock 2 4. interval 3
      rblock 3 6. interval 5
      rblock 4 8. interval 6
    numa 1
      ablock 1 60. interval 12
  end
  decomposition strategy
    bisection
  end
end
```

Figure 18: Three dimensional RADIAL mesh with azimuthal angle of 60 degrees run on 7 processors using BISECTION decomposition.

```
mesh
  radial
    numz 1
      zblock 1 10.0 interval 1
    numr 4 initial radius 1.
      rblock 1 2. interval 3
      rblock 2 4. interval 3
      rblock 3 6. interval 5
      rblock 4 8. interval 6
    numa 1
      ablock 1 60. interval 12
  end
  decomposition strategy
    numprocs i, 4
    numprocs j, 2
  end
end
```

Figure 19: Three dimensional RADIAL mesh with azimuthal angle of 60 degrees run on 8 processors using PROCESSOR LAYOUT decomposition.




Figure 20: Three dimensional RADIAL TRISECTION mesh run on 8 processors using PROCESSOR LAYOUT decomposition.

Table 4: Keywords for DECOMPOSITION STRATEGY -- END.

Sub-Keyword	Input	Description
BISECTION		Recursively bisect domain making slices calculated to assign nearly equal numbers of elements to each processor.  This option is the default.
PROCESSOR LAYOUT NUMPROCS {I J K}, int (1) END	int (1)	Invokes a decomposition strategy that slices up the mesh in accordance with the request of the user. The integer value value is number of segments into which the mesh should be divided in the given direction. The product of the number of segments requested in each direction must equal the number of processors.
SEQUENTIAL		Invokes a decomposition strategy that distributes the elements between processors in sequential order. If there are k elements and n processors an average of k/n elements will go to each processor. This decomposition strategy is not for large simulations and is intended mainly for testing and verification purposes.
RANDOM		Invokes a decomposition strategy that randomly distributes the elements between processors. It results in tremendous communications overhead. This decomposition strategy is not for production simulations and is intended mainly for testing and verification purposes.

# 6 Library Interface

## 6.1 Creating a Mesh

Mesh creation proceeds through a single function call. Additional functions are available to access messages generated during the mesh creation.

## 6.1.1 Create\_Pamgen\_Mesh

This function creates a representation of the mesh for the processor of the specified rank out of the total num\_procs. It returns an enumerated value. A return value of ERROR\_FREE\_CREATION signifies success. A return value of ERROR\_CREATING\_IMD significes an error in the specification of the mesh geometry, topology, or boundary conditions. A return value of ERROR\_CREATING\_MS significes an error in allocating and populating the arrays that store the mesh geometry and topology. A return value of ERROR\_PARSING\_DEFINITION significes an error occurred while parsing the string passed in file\_char\_array. The details of the syntax error are recoverable by subsequent calls.

**char \*file\_char\_array** This input variable points to a null terminated string that holds a terse description of the desired mesh. This form of this description is given in a later section.

int dimension This input variable indicates the dimension of the desired mesh. Acceptable values are 2 (quadrilaterals created in x,y plane) and 3 (hexahedral elements created in 3 space).

int rank This input variable may range from 0 to one less than num\_procs. It specifies for which processor the mesh is being generated.

int num\_procs This input variable must be greater than 0. It specifes the total number of processors across which the mesh is decomposed.

## 6.1.2 getPamgenEchoStreamSize

int getPamgenEchoStreamSize(void);

This function returns the size of the string (not counting termination character) that contains an echo of the **char** \* **file\_char\_array** string previously passed to Create\_Pamgen\_Mesh. If a parsing error occurred, this string will be annotated with a summary of the error. Use of this function and subsequent access and display of this string is highly recommended if the value pointed to by **int** \* **parse\_error\_count** is non-zero on return.

### 6.1.3 getPamgenEchoStream

```
char * getPamgenEchoStream(char * echo_stream_pointer);
```

This function takes a character pointer and returns that same pointer after it has been filled.

char \*echo\_stream\_pointer This input variable must point to allocated memory big enough to hold the results of "getEchoStreamSize(void)" plus a termination character.

## 6.1.4 getPamgenErrorStreamSize

```
int getPamgenErrorStreamSize(void);
```

This function returns the size of an error string associated with a return value of **ERROR\_CREATING\_MS** from Create\_Pamgen\_Mesh.

#### 6.1.5 getPamgenErrorStream

```
char * getPamgenErrorStream(char * error_stream_pointer);
```

This function takes a character pointer and returns that same pointer after it has been filled.

char \*error\_stream\_pointer This input variable must point to allocated memory big enough to hold the results of getErrorStreamSize plus a termination character.

## 6.1.6 getPamgenWarningStreamSize

```
int getPamgenWarningStreamSize(void);
```

This function returns the size of a string containing warnings generated within the Create\_Pamgen\_Mesh function.

#### 6.1.7 getPamgenWarningStream

```
char * getPamgenWarningStream(char * warning_stream_pointer);
```

This function takes a character pointer and returns that same pointer after it has been filled.

**char \*warning\_stream\_pointer** This input variable must point to allocated memory big enough to hold the the results of getWarningStreamSize plus a termination character.

#### 6.1.8 getPamgenInfoStreamSize

```
int getPamgenInfoStreamSize(void);
```

This function returns the size of a string containing information messages generated within the Create\_Pamgen\_Mesh function. These messages include information such as the total number of elements in the mesh, the total number of nodes in the mesh, and the mesh distribution based on decomposition.

#### 6.1.9 getPamgenInfoStream

```
char * getPamgenInfoStream(char * info_stream_pointer);
```

This function takes a character pointer and returns that same pointer after it has been filled.

**char \*info\_stream\_pointer** This input variable must point to allocated memory big enough to hold the the results of getInfoStreamSize plus a termination character.

## 6.2 Querying a Mesh

All of the mesh query and access functions are based on the EXODUS II [2] and NEMESIS [1] APIs. These APIs were written to standardize a platform independent interface for writing and reading binary mesh specification files. NEMESIS is a parallel extension of the serial EXODUS II API. The PAMGEN function names are formed by prefixing the EXODUS II or NEMESIS function name with **im**.. The remainder of the function signature and functionality remains unchanged. It may help to note that the original EXODUS II functions begin with **ex**., and the original NEMESIS functions begin with **ne**..

Querying a mesh database to build up a complete representation in accessible memory is a straightforward process. Typically a query function is used to ascertain the number of items in an array, then memory is allocated and passed in through an access function which fills the memory with the requested information. The query and access functions will be presented in the same order they appear in the example function "read\_mesh\_to\_memory()" shown in Appendix B.

## 6.2.1 im\_ex\_get\_init

This function is based on the EXODUS II API and is concerned only with serial information. The number of nodes, elements, element blocks is limited to those entities local to the rank processor for which the mesh was created. It returns a non-zero value if an error occurs.

int exoid An unused input variable.

**char** \*title A title string containing "PAMGEN Inline Mesh".

**char \*num\_dim** On return points to the number of coordinates per node (2 or 3).

**char \*num\_nodes** On return points to the number of nodes.

char \*num\_elem On return points to the number of elements.

char \*num\_elem\_blk On return points to the number of element blocks.

char \*num\_node\_sets On return points to the number of node sets.

char \*num\_side\_sets On return points to the number of side sets.

## 6.2.2 im\_ex\_inquire

This function is based on the EXODUS II API and is concerned only with serial information. This is a general purpose query function that takes an enumerated query value and changes the value pointed to by int\_value, float\_value, or char\_array\_value depending on the data requested by the query\_value. It returns a non-zero value in case of error. Im\_ex\_inquire supports the following query values:

IM\_EX\_INQ\_NS\_NODE\_LEN The length of the concatenated nodeset list is returned in int\_value.

IM\_EX\_INQ\_NS\_DF\_LEN The length of the concatenated nodeset distribution list is returned in int\_value.

IM\_EX\_INQ\_SS\_ELEM\_LEN The length of the concatenated sidesets element list is returned in int\_value.

IM\_EX\_INQ\_SS\_NODE\_LEN The aggregate length of the sideset nodes is returned in int\_value.

IM\_EX\_INQ\_SS\_DF\_LEN The length of the concatenated side sets distribution factor is returned in int\_alue.

IM\_EX\_INQ\_API\_VERS The API version is returned in float\_value.

**IM\_EX\_INQ\_EB\_PROP** The number of element block properties is returned in int\_value.

**IM\_EX\_INQ\_NS\_PROP** The number of node sets properties is returned in int\_value.

IM\_EX\_INQ\_SS\_PROP The number of side set properties is returned in int\_value.

IM\_EX\_INQ\_QA The number of QA records is returned in int\_value. IM\_EX\_INQ\_INFO The number of INFO records is returned in int\_value.

#### 6.2.3 im\_ex\_get\_coord

This function is based on the EXODUS II API and is concerned only with serial information. This function takes pointers to memory allocated to a length equal to the number of nodes local to the processor and fills in the nodal coordinate values. A non-zero return value indicates an error.

int exoid Unused input variable.

double \* x\_coors Returned X coordinates of the nodes.

**double \* y\_coors** Returned Y coordinates of the nodes.

**double \* z\_coors** Returned Z coordinates of the nodes (if num\_dim = 3).

#### 6.2.4 im\_ex\_get\_coord\_names

This function is based on the EXODUS II API and is concerned only with serial information. It returns the names of the coordinates. A non-zero return indicates an error.

int exoid Unused input variable.

**char** \*\* **coord\_names** Returned vector pointing to num\_dim coord names. **coord\_names** can be declared and allocated as shown below.

```
char* coord_names[3];
for(int i = 0; i < num_dim; i++)
    coord_names[i] = (char*)calloc((MAX_STR_LENGTH+1), sizeof(char));

6.2.5 im_ex_get_map
int im_ex_get_map( int exoid,</pre>
```

This function is based on the EXODUS II API and is concerned only with serial information. It loads the global element numbers into the provided storage. A non-zero return value indicates an error.

int \* element\_map);

int exoid Unused input variable.

int \* element\_map On return this array holds the global element ids of the elements local to this processor. For a serial problem this runs sequentially from 1 to num\_elem. Memory sized to num\_elem must be allocated prior to making this call.

### 6.2.6 im\_ex\_get\_elem\_num\_map

For PAMGEN this function is identical to "im\_ex\_get\_map".

int exoid Unused input variable.

int \* element\_num\_map On return this array holds the global element ids of the elements local to this processor. For a serial problem these values run sequentially from 1 to num\_elem. Memory sized to num\_elem must be allocated prior to making this call.

#### 6.2.7 im\_ex\_get\_node\_num\_map

This function is based on the EXODUS II API and is concerned only with serial information. It loads the global node numbers into the provided storage. A non-zero return indicates an error.

int exoid Unused input variable.

int \* node\_num\_map On return this array holds the global node ids of the nodes local to this processor. For a serial problem this runs from 1 to num\_nodes. Memory sized to num\_nodes must be allocated prior to making this call.

#### 6.2.8 im\_ex\_get\_elem\_blk\_ids

This function is based on the EXODUS II API and is concerned only with serial information. It loads the element block ids into the provided storage. A non-zero return value indicates an error.

int exoid Unused input variable.

int \* elem\_blk\_ids On return this array holds the ids of the element blocks on this processor. For PAMGEN meshes the element block ids across the entire problem will run sequentially from 1 to num\_elem\_blk. On any particular processor of a parallel mesh any set of the global element blocks may be present. Storage sized to num\_elem\_blk must be allocated prior to making this call.

#### 6.2.9 im\_ex\_get\_elem\_block

```
char * elem_type,
int * num_elem_this_blk,
int * num_nodes_per_elem,
int * num_attr);
```

This function is based on the EXODUS II API and is concerned only with serial information. It provides information about the requested element block. Review of the conventions documented in the EXODUS II manual is the most effective way to understand the mesh storage and retrieval. Under the EXODUS II convention, a finite element mesh is composed of one or more blocks of elements. Each block contains elements of the same type. Within a block, all elements have the same number of nodes and the same connectivity convention. The number of nodes is stored explicitly, and the connectivity convention is called out by a string. This string corresponds to a table of conventional element connectivities in the EXODUS II manual. A non-zero return value indicates an error.

int exoid Unused input variable.

int elem\_blk\_id Input variable specifying the id of the block for which information is requested. This id must be one of the values in the elem\_blk\_ids array.

char \* elem\_type On return this variable holds one of the standard EXODUS II element types as a string. The element\_type pointer must be allocated as length MAX\_STR\_LENGTH+1. For PAMGEN the stored value will be QUAD in 2D or HEX in 3D.

int \* num\_elem\_this\_blk On return this variable holds the number of elements in this block.

int \* num\_nodes\_per\_elem On return this variable holds the number of nodes per element for the elements in this block.

int \* num\_attr On return this variable holds the number of attributes for this block for PAMGEN this is always 0.

#### 6.2.10 im\_ex\_get\_elem\_conn

int im\_ex\_get\_elem\_conn( int exoid,

```
int elem_blk_id,
int * connect);
```

This function is based on the EXODUS II API and is concerned only with serial information. It fills the storage pointed to by connect with the connectivity of the elements in the block referred to by elem\_blk\_id. A non-zero return value indicates an error.

int exoid Unused input variable.

int elem\_blk\_id Input variable specifying the id of the block for which information is requested. This id must be one of the values in the elem\_blk\_ids array.

int \* connect On return the storage pointed to by connect holds the connectivity for the requested block. Connect must point to storage sized to num\_elem\_this\_block\*num\_nodes\_per\_elem. Connect holds (in the order specified by the EXODUS II convention) the nodes of each element in the specified block. The first element's connectivity begins at an offset of 0 and the nth element's connectivity begins at an offset of n\*num\_nodes\_per\_element. The EXODUS II standard specifies that the indices of the connectivity are numbered from 1 so that in order to retrieve the coordinates of an element's nodes the indices given in connect must be decrimented by 1.

#### 6.2.11 im\_ex\_get\_node\_set\_ids

This function is based on the EXODUS II API and is concerned only with serial information. It loads the node set ids into the provided storage. Node set ids are specified in the string passed to the Create\_Pamgen\_Mesh function. By convention they must be non-zero and positive. A non-zero return value indicates an error.

int exoid Unused input variable.

int \* node\_set\_ids On return this array holds the ids of the node sets on this processor. Storage sized to num\_node\_sets must be allocated prior to making this call.

## 6.2.12 im\_ex\_get\_node\_set\_param

This function is based on the EXODUS II API and is concerned only with serial information. It function provides sizing information for node set data. A non-zero return value indicates an error.

int exoid Unused input variable.

int node\_set\_id Input variable specifying the id of the node set for which information is requested. This id must be one of the values in the node\_set\_ids array.

int \* num\_nodes\_in\_node\_set On return this variable is set to the number of nodes in the specified node set.

int \* num\_df\_in\_node\_set On return this variable is set to the number of df in the specified node set. Distribution factors are scalar values linked to the members of node sets or side sets. PAMGEN does not produce any distribution factors on node sets or side sets. For PAMGEN this will be 0.

#### 6.2.13 im\_ex\_get\_node\_set

This function is based on the EXODUS II API and is concerned only with serial information. On return the provided storage is populated with the local nodes of the node set.

int exoid Unused input variable.

int node\_set\_id Input variable specifying the id of the node set for which information is requested. This id must be one of the values in the node\_set\_ids array.

int \* node\_set\_node\_list On return this array holds the local ids of the nodes in the node set. The ids are numbered from 1. Storage must be sized for num nodes in nodeset.

#### $6.2.14 \quad im\_ex\_get\_side\_set\_ids$

This function is based on the EXODUS II API and is concerned only with serial information. It loads the side set ids into the provided storage. Side set ids are specified in the string passed to the Create\_Pamgen\_Mesh function. By convention they must be non-zero and positive. A non-zero return value indicates an error.

int exoid Unused input variable.

int \* side\_set\_ids On return this array holds the ids of the side sets on this processor. Storage sized to num\_side\_sets must be allocated prior to making this call.

#### 6.2.15 im\_ex\_get\_side\_set\_param

This function is based on the EXODUS II API and is concerned only with serial information. It provides sizing information for side set data. A non-zero return value indicates an error.

int exoid Unused input variable.

int side\_set\_id Input variable specifying the id of the side set for which information is requested. This id must be one of the values in the side\_set\_ids array.

int \* num\_sides\_in\_side\_set On return this variable is set to the number of sides in the specified side set.

int \* num\_df\_in\_side\_set On return this variable is set to the number of df in the specified side set. Distribution factors are scalar values linked to the members of node sets or side sets. PAMGEN does not produce any distribution factors on node sets or side sets. For PAMGEN this will be 0.

#### 6.2.16 im\_ex\_get\_side\_set

This function is based on the EXODUS II API and is concerned only with serial information. It populates storage that specifies the sides of elements that are in a particular side set. The EXODUS II convention specifies a side by listing an element id and the side of that element that is in the sideset. This information is provided in two corresponding arrays of equal length. The sides specify a set of nodes on the element by reference to element topology tables in the EXODUS II manual. A non-zero return value indicates an error.

int exoid Unused input variable.

int side\_set\_id Input variable specifying the id of the side set for which information is requested. This id must be one of the values in the side\_set\_ids array.

int \* side\_set\_element\_list On return this array holds the local ids of the elements having sides in the side set. Storage must be sized for num\_sides\_in\_sideset.

int \* side\_set\_side\_list On return this array holds the sides that are in the side set. Storage must be sized for num\_sides\_in\_sideset.

#### 6.2.17 im\_ex\_get\_qa

```
int im_ex_get_qa( int exoid,
```

```
char * qa_record[][4]);
```

This function is based on the EXODUS II API and is concerned only with serial information. It populates previously allocated qa\_record storage with Quality Assurance (QA) information. By convention the four components of each record are:

- 1. The analysis code name
- 2. The analysis code QA descriptor
- 3. The analysis time
- 4. The analysis date

PAMGEN will return "PAMGEN", "Parallel Mesh Generator" and then two copies of the date and time. A non-zero return value indicates an error.

int exoid Unused input variable.

**char** \* **qa\_record**[][4] Previously allocated storage that is filled with QA records. The memory may be allocated as shown below.

```
char * qa_record[10][4];
for(int i = 0; i < 10; i++)
  for(int j=0; j<4; j++) qa_record[i][j] = (char*)malloc(MAX_STR_LENGTH+1);</pre>
```

### 6.2.18 im\_ex\_get\_info

This function is based on the EXODUS II API and is concerned only with serial information. It populates previously allocated info\_record storage. A non-zero return value indicates an error.

int exoid Unused input variable.

**char** \*\* **info\_record** Previously allocated storage into which info records are copied. At present for PAMGEN num\_info\_records is zero. Memory should would be allocated as shown below.

```
char ** info_record;
info_record = (char**)malloc(num_info_records*sizeof(char*));
for(int i = 0; i < num_info_records; i++)
  info_record[i] = (char*)malloc(MAX_STR_LENGTH+1);
```

#### 6.2.19 im\_ne\_get\_init\_global

This function is adapted from the NEMESIS API. It is typically the first function called when gathering information about the parallel nature of the mesh. It retrieves the mesh sizing information for the complete mesh. A non-zero return value indicates an error.

int neid Unused input variable.

int \* num\_nodes\_global On return this variable is set to the total number of nodes in the mesh.

int \* num\_elems\_global On return this variable is set to the total number of elements in the mesh.

int \* num\_elem\_blks\_global On return this variable is set to the total number of element blocks in the mesh.

int \* num\_node\_sets\_global On return this variable is set to the total number of node sets in the mesh.

int \* num\_side\_sets\_global On return this variable is set to the total number of side sets in the mesh.

### 6.2.20 im\_ne\_get\_init\_info

This function is adapted from the NEMESIS API. It retrieves information about the decomposition of the mesh. A non-zero return value indicates an error.

int neid Unused input variable.

int \*num\_proc On return this variable is filled with the total number of processors over which the mesh is spread.

int \*num\_proc\_in\_file On return this variable is filled with the number of processors for which mesh is available via query. This value will always be 1 when using PAMGEN.

char \*file\_type Unused variable should be sized as shown below.

```
char file_type [2];
```

#### 6.2.21 im\_ne\_get\_eb\_info\_global

This function is adapted from the NEMESIS API. It retrieves the element block ids from the entire mesh as well as the sizes of each of these element blocks. A non-zero return value indicates an error.

int neid Unused input variable.

int \*el\_blk\_ids\_global On return this array holds the element block ids for the entire mesh. It must be sized to hold num\_elem\_blks\_global integers.

int \*el\_blk\_cnts\_global On return this array holds the number of elements in each element block of the entire mesh. It must be sized to hold num\_elem\_blks\_global integers.

#### 6.2.22 im\_ne\_get\_ns\_param\_global

This function is adapted from the NEMESIS API. It retrieves node set information for the entire mesh. A non-zero return value indicates an error.

int neid Unused input variable.

int \*ns\_ids\_global On return this array holds the node set ids for the entire mesh. It must be sized to hold num\_node\_sets\_global integers.

int \*ns\_n\_cnt\_global On return this array holds the number of nodes in each node set for the entire mesh. It must be sized to hold num\_node\_sets\_global integers.

int \*ns\_df\_cnt\_global On return this array holds the number of node set distribution factors for the entire mesh. It must be sized to hold num\_node\_sets\_global integers. For PAMGEN the number of distribution factors for each node set will be 0.

#### 6.2.23 im\_ne\_get\_ss\_param\_global

This function is adapted from the NEMESIS API. It retrieves side set information for the entire mesh. A non-zero return value indicates an error.

int neid Unused input variable.

int \*ss\_ids\_global On return this array holds the side set ids for the entire mesh. It must be sized to hold num\_side\_sets\_global integers.

int \*ss\_s\_cnt\_global On return this array holds the number of sides in each side set for the entire mesh. It must be sized to hold num\_side\_sets\_global integers.

int \*ss\_df\_cnt\_global On return this array holds the number of side set distribution factors for the entire mesh. It must be sized to hold num\_side\_sets\_global integers. For PAMGEN the number of distribution factors for each side set will be 0.

## 6.2.24 im\_ne\_get\_loadbal\_param

This function is adapted from the NEMESIS API. On return its arguments are filled with sizing information for processor communication data. This information is the first step in gathering all the information required to construct communication protocols between adjacent regions of decomposed mesh. A non-zero return value indicates an error.

int neid Unused input variable.

int \* num\_internal\_nodes On return this variable is filled with the number of nodes that are local to the mesh on this processor.

int \* num\_border\_nodes On return this variable is filled with the number of nodes that are common to the mesh on this processor and to adjacent processors.

int \* num\_external\_nodes On return this variable is filled with the number

of nodes that are not local to this processor but are common to elements that share nodes with this processor.

int \* num\_internal\_elems On return this variable is filled with the number of elements that are local to this processor.

int \* num\_border\_elems On return this variable is filled with the number of elements that are not local to this processor but do share nodes with elements local to this processor.

int \* num\_node\_cmaps On return this variable is filled with the number of node communication maps.

int \* num\_elem\_cmaps On return this variable is filled with the number of element communication maps.

int proc Unused input variable.

## 6.2.25 im\_ne\_get\_elem\_map

This function is adapted from the NEMESIS API. On return the the arguments of this function are populated with the internal and boundary element maps.

int neid Unused input variable.

int \* elem\_mapi On return this variable is filled with the internal element ids. Storage sized to num\_internal\_elems must be supplied.

int \* elem\_mapb On return this variable is filled with the border element ids. Storage sized to num\_border\_elems must be supplied.

int proc Unused input variable.

## 6.2.26 im\_ne\_get\_node\_map

This function is adapted from the NEMESIS API. On return the the arguments of this function are populated with the internal and boundary node maps.

int neid Unused input variable.

int \* node\_mapi On return this variable is filled with the internal node ids. Storage sized to num\_internal\_nodes must be supplied.

int \* node\_mapb On return this variable is filled with the border node ids. Storage sized to num\_border\_nodes must be supplied.

int \* node\_mape On return this variable is filled with the external node ids. Storage sized to num\_external\_nodes must be supplied.

int proc Unused input variable.

## 6.2.27 im\_ne\_get\_cmap\_params

This function is adapted from the NEMESIS API. On return the storage passed in its arguments is filled with the communication map ids and counts. A non-zero return value indicates an error.

int neid Unused input variable.

int \* node\_cmap\_ids On return this storage is filled with the ids for each node communication map. Storage sized to num\_node\_cmap must be provided. For PAMGEN these values will run from 0 to num\_node\_cmaps-1.

int \* node\_cmap\_cnts On return this storage is filled with the number of nodes in each node communication map. Storage sized to num\_node\_cmap must be provided.

int \* elem\_cmap\_ids On return this storage is filled with the ids for each element communication map. Storage sized to num\_elem\_cmap must be provided. For PAMGEN these values will run from 0 to num\_elem\_cmaps-1.

int \* elem\_cmap\_elem\_cnts On return this storage is filled with the number of elements in each element communication map. Storage sized to num\_elem\_cmap must be provided.

int proc Unused input variable.

#### 6.2.28 im\_ne\_get\_node\_cmap

This function is adapted from the NEMESIS API. On return the storage passed in its arguments is filled with the node communication maps. A non-zero return value indicates an error.

int neid Unused input variable.

int map\_ids The id of the node communication map that is being queried. This must be one of the entries in node\_cmap\_ids.

int \* node\_ids On return this storage is filled with the ids of nodes in the map. Storage must be sized to node\_cmap\_cnts[map\_id].

int \* proc\_ids The processor id onto which the associated node in node\_ids maps. Storage must be sized to node\_cmap\_cnts[map\_id].

int proc Unused input variable.

#### 6.2.29 im\_ne\_get\_elem\_cmap

This function is adapted from the NEMESIS API. On return the storage passed in its arguments is filled with the element communication maps. A non-zero return value indicates an error.

int neid Unused input variable.

int map\_ids The id of the element communication map that is being queried. This must be one of the entries in elem\_cmap\_ids.

int \* elem\_ids On return this storage is filled with the ids of elements in the map. Storage must be sized to elem\_cmap\_cnts[map\_id].

int \* side\_ids On return this storage is filled with the ids sides of elements in the map. Storage must be sized to elem\_cmap\_cnts[map\_id].

int \* proc\_ids The processor id onto which the associated element in elem\_ids maps. Storage must be sized to elem\_cmap\_cnts[map\_id].

int proc Unused input variable.

# 6.3 Deleting a Mesh

## $6.3.1 \quad Delete\_Pamgen\_Mesh$

int Delete\_Pamgen\_Mesh(void);

This function clears and deletes the memory used to store mesh data created with the "Create\_Pamgen\_Mesh(...)" function. After this function is called "Create\_Pamgen\_Mesh(...)" may be called again to create a different mesh.

# A Runtime Compiler Functionality

The runtime compiler allows inclusion of double quoted ("") 'C' language style functions within unformatted input files. The functions are evaluated during program setup or execution to calculate independent solution variables.

This provides the user with an endlessly flexible method for describing boundary conditions, initial conditions, source terms, material properties, or any other independent variable.

The specific variable names expected within runtime compiled functions depends on the host code and the context of the function use. In general it should be remembered that the runtime functions return quantities by modifying variables that are passed in by reference.

## A.1 The RTC language

The RTC language can be thought of as a small subset of the C language with a couple minor modifications.

## A.1.1 Operators

The RTC language has the following operators that work exactly as they do in C and have the same precedence as they do in C:

- + Addition
- - Subtration
- - Negation
- \* Multiplication
- / Division
- $\bullet == Equality$
- > Greater than

- < Less than
- >= Greater than or equal to
- <= Less than or equal to
- $\bullet$  = Assignment
- || Logical or
- && Logical and
- ! = Inequality
- % Modulo
- ! Logical not

The following operators do not occur in the C language, but were added to the RTC language for convenience:

• ^ Exponentiation

#### A.1.2 Control flow

The RTC language has the following control flow statements:

- for( expr ; expr ; expr ) { ... }
- while( expr ) { ... }
- if (expr)  $\{...\}$
- else if (expr)  $\{...\}$
- else {...}

These control flow statements work exactly as they do in C except that the code blocks following a control flow statement **MUST** be enclosed within braces even if the block only consists of one line.

#### A.1.3 Line Structure

The line structure in the RTC language is the same as that of C. Expressions end with a semicolon unless they are inside a control flow statement.

#### A.1.4 Variables

Declaring scalar variables in RTC is done exactly as it is done in C except that only the following types are supported:

- int
- float
- double
- char

For scalars, variables can be declared and assigned all at once. Both of the following approaches will work:

```
int myVar = 9;

OR

int myVar;
myVar = 9;
```

Arrays work a little differently in RTC than they do in C. There are no *new* or *malloc* operators, instead the user may declare dynamically sized arrays in the same manner as statically sized arrays. Also, in C all the values of an array may be initialized at once by putting the values within braces. This is not supported in the RTC language. Users will have to loop through the array and assign the values one by one. For example:

```
LEGAL:
```

```
int ia[x*y]; //Note: in C this would not be legal for non-const x,y
```

```
int ia2[3];

NOT LEGAL:
  int ia[3] = {1, 2, 3};
```

Indexing arrays can be done using the index operator: array[expr] = ...;

Bounds checking is done at run time. If the bounds of an array are exceeded, it will dump an error to stdout.

#### A.1.5 Math

The following math.h functions are available in RTC:

- asin(arg): returns the arc sine of arg
- acos(arg): returns the arc cosine of arg
- atan(arg): returns the arc tangent of arg
- atan2(y, x): returns the arc tangent of y/x
- $\sin(\arg)$ : returns the sine of arg
- cos(arg): returns the cosine of arg
- tan(arg): returns the tangent of arg
- sqrt(arg): returns the square root of arg
- exp(arg): returns the natural logarithm base e raised to the arg power
- sinh(arg): returns the hyperbolic sine of arg
- $\cosh(\arg)$ : returns the hyperbolic cosine of arg
- tanh(arg): returns the hyperbolic tangent of arg
- log(arg): returns the natural logarithm for arg
- log10(arg): returns the base 10 logarithm for arg

- rand(arg): returns a system-generated random integer between 0 and RAND\_MAX using seed arg
- fabs(arg): returns the absolute value of arg
- pow(b, e): returns b to the e power (Note: the Exponentiation operator is available)
- j0(arg): Bessel function of order zero
- j1(arg): Bessel function of order one
- i0(arg): Modified Bessel function of order zero
- i1(arg): Modified Bessel function of order one
- erf(arg) : Error function
- $\operatorname{erfc}(\operatorname{arg})$ : Complementary error function  $(1.0 \operatorname{erf}(x))$
- gamma(arg) : returns  $\Gamma(arq)$

## A.1.6 Strings

The user may pass quoted strings as arguments to functions. Note: it may be necessary to escape-out the double quotes so that they do not confuse the input-file parser. See printf section below for an example.

#### A.1.7 Printf

The RTC printf method is called just like its C counterpart. The first argument is a quoted character string. This string will contain the % symbol which will tell RTC to output the corresponding argument. The only difference between RTC's printf and C's printf is that in RTC's version, a type character after the % is unnecessary. For example, inside an RTC method the following is appropriate:

```
printf(\"One:% Two:% Three:% \", 5-4, 2.0e0, 'c');\n\
```

Which would generate this output: One:1 Two:2 Three:c

### A.1.8 Comments

The traditional C-comment mechanism may be used inside RTC functions. Use /\* to begin a comment and \*/ to end the comment.

## A.1.9 Unsupported Features

Implementing the entire C-language was well beyond the intent of RTC. Features that were too difficult or did not add enough value have been left out. The following is a list of common C features that are unsupported in RTC:

- There are no ++ or -- operators. Use i = i + 1 instead of + + i
- Structs
- Pointers
- Instant array initialization: int array[5] = 1,2,3,4,5;
- Case statements
- Casting
- Labels and gotos
- Function definition/declaration
- $\bullet$  stdio
- Keywords: break, continue, const, enum, register, return, sizeof, typedef, union, volatile, static.

## B read\_mesh\_to\_memory

This appendix lists an example of the "C" source code that an application linked to PAMGEN would use to read a finite element mesh description from PAMGEN.

```
void read_mesh_to_memory()
int im_exoid = 0;
 int idum = 0;
 float fdum;
 mss.bptr[0] = mss.buffer[0];
 mss.bptr[1] = mss.buffer[1];
 mss.bptr[2] = mss.buffer[2];
 for(int i = 0; i < 100; i++)
   for(int j=0; j<4; j++) mss.qaRecord[i][j] = (char*)malloc(MAX_STR_LENGTH+1) ;
 char * cdum = NULL;
 int error = 0;
 int id = 0;
 error += im_ex_get_init ( id,
                        mss.title,
                        &mss.num_dim,
                        &(mss.num_nodes),
                        &mss.num_elem,
                        &mss.num_elem_blk,
                        &mss.num_node_sets,
                        &mss.num_side_sets);
 error += im_ex_inquire(id, IM_EX_INQ_NS_NODE_LEN, (int*)&mss.num_node_set_nodes,
                     &fdum, cdum);
 error += im_ex_inquire(id, IM_EX_INQ_NS_DF_LEN,
                                            (int*)&mss.num_node_set_dfs,
                     &fdum, cdum);
 error += im_ex_inquire(id, IM_EX_INQ_SS_ELEM_LEN, (int*)&mss.num_side_set_elements,
                     &fdum, cdum);
 error += im_ex_inquire(id, IM_EX_INQ_SS_NODE_LEN, (int*)&mss.num_side_set_nodes,
```

```
&fdum, cdum);
error += im_ex_inquire(id, IM_EX_INQ_SS_DF_LEN, (int*)&mss.num_side_set_dfs,
                       &fdum, cdum);
// // get version number
error += im_ex_inquire(id, IM_EX_INQ_API_VERS, &idum, &fdum, cdum);
mss.version_number = (double) fdum;
mss.version = (int) mss.version_number;
// // get genesis-II parameters
error += im_ex_inquire(id, IM_EX_INQ_EB_PROP,
                       (int*)&mss.num_block_properties,
                       &fdum, cdum);
error += im_ex_inquire(id, IM_EX_INQ_NS_PROP,
                       (int*)&mss.num_node_set_properties,
                       &fdum, cdum);
error += im_ex_inquire(id, IM_EX_INQ_SS_PROP,
                       (int*)&mss.num_side_set_properties,
                       &fdum, cdum);
mss.coord = (double *)malloc(mss.num_nodes*mss.num_dim*sizeof(double));
error += im_ex_get_coord(id,
                         mss.coord,
                         mss.coord+mss.num_nodes,
                         mss.coord+2*mss.num_nodes);
error += im_ex_get_coord_names (id, mss.bptr);
if (mss.num_elem){
  mss.element_order_map = (int *)malloc(mss.num_elem * sizeof(int));
  error += im_ex_get_map(id, mss.element_order_map);
  if (mss.num_elem){
    mss.global_element_numbers = (int *)malloc(mss.num_elem*sizeof(int));
    error += im_ex_get_elem_num_map(id, mss.global_element_numbers);
```

```
}
if (mss.num_nodes){
  mss.global_node_numbers = (int *)malloc(mss.num_nodes * sizeof(int));
  error += im_ex_get_node_num_map(id, mss.global_node_numbers);
}
//block info
                       = (int *)malloc(mss.num_elem_blk*sizeof(int));
mss.block_id
mss.nodes_per_element = (int *)malloc(mss.num_elem_blk*sizeof(int));
mss.element_attributes = (int *)malloc(mss.num_elem_blk*sizeof(int));
mss.elements
                       = (int *)malloc(mss.num_elem_blk*sizeof(int));
mss.element_types
                       = (char **)malloc(mss.num_elem_blk*sizeof(char *));
mss.elmt_node_linkage = (int **)malloc(mss.num_elem_blk*sizeof(int*));
error += im_ex_get_elem_blk_ids(id, mss.block_id);
for(int i = 0; i < mss.num_elem_blk; i ++){</pre>
  mss.element_types[i] = (char *)malloc((MAX_STR_LENGTH + 1)*sizeof(char));
  error += im_ex_get_elem_block(id,
                                mss.block_id[i],
                                mss.element_types[i],
                                (int*)&(mss.elements[i]),
                                (int*)&(mss.nodes_per_element[i]),
                                (int*)&(mss.element_attributes[i]));
}
//connectivity
for(int b = 0; b < mss.num_elem_blk; b++){</pre>
  mss.elmt_node_linkage[b] = (int*)malloc(mss.nodes_per_element[b]*
                                           mss.elements[b]*sizeof(int));
  error += im_ex_get_elem_conn(id,mss.block_id[b],mss.elmt_node_linkage[b]);
}
if(mss.num_node_sets){
  mss.node_set_id
                            = (int *) malloc(mss.num_node_sets*sizeof(int));
  mss.num_nodes_in_node_set = (int *) malloc(mss.num_node_sets*sizeof(int));
  mss.node_set_nodes
                            = (int **)malloc(mss.num_node_sets*sizeof(int*));
  mss.num_df_in_node_set
                            = (int *) malloc(mss.num_node_sets*sizeof(int*));
```

```
error += im_ex_get_node_set_ids(id, mss.node_set_id);
  for(int i = 0; i < mss.num_node_sets; i ++){</pre>
    error += im_ex_get_node_set_param(id, mss.node_set_id[i],
                                       (int*)&mss.num_nodes_in_node_set[i],
                                       (int*)&mss.num_df_in_node_set[i]);
          mss.node_set_nodes[i] = NULL;
    if(mss.num_nodes_in_node_set[i]) {
      mss.node_set_nodes[i] =
       (int *)malloc(mss.num_nodes_in_node_set[i]*sizeof(int));
      error += im_ex_get_node_set(id,
                                   mss.node_set_id[i],
                                  mss.node_set_nodes[i]);
    }
 }
}
//side sets
if(mss.num_side_sets){
  mss.side_set_id = (int*)malloc(mss.num_side_sets*sizeof(int));
  mss.num_elements_in_side_set = (int*)malloc(mss.num_side_sets*sizeof(int));
  mss.num_df_in_side_set = (int*)malloc(mss.num_side_sets*sizeof(int));
  mss.side_set_elements = (int**)malloc(mss.num_side_sets*sizeof(int *));
  mss.side_set_faces = (int **)malloc(mss.num_side_sets*sizeof(int*));
  error += im_ex_get_side_set_ids(id, mss.side_set_id);
  for(int i = 0; i < mss.num_side_sets; i ++){</pre>
    error += im_ex_get_side_set_param(id, mss.side_set_id[i],
                                       (int*)&mss.num_elements_in_side_set[i],
                                       (int*)&mss.num_df_in_side_set[i]);
    int ne = mss.num_elements_in_side_set[i];
    mss.side_set_elements[i] = (int*)malloc(ne*sizeof(int));
    mss.side_set_faces[i] = (int*)malloc(ne*sizeof(int));
    if(ne){}
      error += im_ex_get_side_set(id, mss.side_set_id[i],
                                   mss.side_set_elements[i],
                                  mss.side_set_faces[i]);
```

```
}
  }
}
error += im_ex_inquire(id, IM_EX_INQ_QA, (int*)&mss.num_qa_records, &fdum, cdum);
if(mss.num_qa_records)error += im_ex_get_qa(id,mss.qaRecord);
error += im_ex_inquire(id, IM_EX_INQ_INFO, (int*)&mss.num_info_records, &fdum, cdum)
if(mss.num_info_records) {
  mss.info_records = (char **)malloc(mss.num_info_records*sizeof(char *));
  for(int i = 0; i < mss.num_info_records; i ++){</pre>
    mss.info_records[i] = (char *)malloc(MAX_STR_LENGTH+1);
  }
  error += im_ex_get_info(id, mss.info_records);
}
//nemesis data
// global info
if ( im_ne_get_init_global(id, &mss.num_nodes_global, &mss.num_elems_global,
                           &mss.num_elm_blks_global, &mss.num_node_sets_global,
                           &mss.num_side_sets_global) < 0 )
  ++error;
if ( im_ne_get_init_info(id,
                         &mss.num_total_proc,
                         &mss.num_proc_in_file, mss.type) < 0 )
  ++error;
mss.elem_blk_ids_global = (int*)malloc(mss.num_elm_blks_global*sizeof(int));
mss.elem_blk_cnts_global = (int*)malloc(mss.num_elm_blks_global*sizeof(int));
if ( im_ne_get_eb_info_global(id,
                              mss.elem_blk_ids_global,
                              mss.elem_blk_cnts_global) < 0 )</pre>
  ++error;
mss.ns_ids_global = (int *)malloc(mss.num_node_sets_global*sizeof(int));
mss.ns_cnts_global = (int *)malloc(mss.num_node_sets_global*sizeof(int));
```

```
mss.ns_df_cnts_global = (int *)malloc(mss.num_node_sets_global*sizeof(int));
mss.ss_ids_global = (int *)malloc(mss.num_side_sets_global*sizeof(int));
mss.ss_cnts_global = (int *)malloc(mss.num_side_sets_global*sizeof(int));
mss.ss_df_cnts_global = (int *)malloc(mss.num_side_sets_global*sizeof(int));
if ( mss.num_node_sets_global > 0 ) {
  if ( im_ne_get_ns_param_global(id,mss.ns_ids_global,mss.ns_cnts_global,
                                  mss.ns_df_cnts_global) < 0 )++error;</pre>
}
if ( mss.num_side_sets_global > 0 ) {
  if ( im_ne_get_ss_param_global(id,mss.ss_ids_global,mss.ss_cnts_global,
                                  mss.ss_df_cnts_global) < 0 ) ++error;</pre>
}
//parallel info
if ( im_ne_get_loadbal_param( id,
                               &mss.num_internal_nodes,
                               &mss.num_border_nodes,
                               &mss.num_external_nodes,
                               &mss.num_internal_elems,
                               &mss.num_border_elems,
                               &mss.num_node_comm_maps,
                               &mss.num_elem_comm_maps,
                               0/*unused*/ ) < 0 )++error;</pre>
mss.internal_elements = (int *)malloc(mss.num_internal_elems*sizeof(int));
mss.border_elements = (int *)malloc(mss.num_border_elems*sizeof(int));
mss.internal_nodes
                      = (int *)malloc(mss.num_internal_nodes*sizeof(int));
                      = (int *)malloc(mss.num_border_nodes*sizeof(int));
mss.border_nodes
mss.external_nodes
                      = (int *)malloc(mss.num_external_nodes*sizeof(int));
if (im_ne_get_elem_map(id,
                         mss.internal_elements,
                         mss.border_elements,
                         0/* not used proc_id*/ ) < 0 )++error;</pre>
if ( im_ne_get_node_map( id,
                         mss.internal_nodes,
                         mss.border_nodes,
                         mss.external_nodes,
                         0/* not used proc_id*/ ) < 0 )++error;</pre>
```

```
mss.node_cmap_node_cnts = (int*) malloc(mss.num_node_comm_maps*sizeof(int));
                        = (int*) malloc(mss.num_node_comm_maps*sizeof(int));
mss.node_cmap_ids
mss.comm_node_ids
                        = (int**)malloc(mss.num_node_comm_maps*sizeof(int*));
mss.comm_node_proc_ids = (int**)malloc(mss.num_node_comm_maps*sizeof(int*));
mss.elem_cmap_elem_cnts = (int*) malloc(mss.num_elem_comm_maps*sizeof(int));
                        = (int*) malloc(mss.num_elem_comm_maps*sizeof(int));
mss.elem_cmap_ids
mss.comm_elem_ids
                        = (int**)malloc(mss.num_elem_comm_maps*sizeof(int*));
                        = (int**)malloc(mss.num_elem_comm_maps*sizeof(int*));
mss.comm_side_ids
mss.comm_elem_proc_ids = (int**)malloc(mss.num_elem_comm_maps*sizeof(int*));
if ( im_ne_get_cmap_params( id,
                            mss.node_cmap_ids,
                             (int*)mss.node_cmap_node_cnts,
                            mss.elem_cmap_ids,
                             (int*)mss.elem_cmap_elem_cnts,
                             0/*not used proc_id*/ ) < 0 )++error;</pre>
for(int j = 0; j < mss.num_node_comm_maps; j++) {</pre>
                             = (int *)malloc(mss.node_cmap_node_cnts[j]*sizeof(int
  mss.comm_node_ids[j]
  mss.comm_node_proc_ids[j] = (int *)malloc(mss.node_cmap_node_cnts[j]*sizeof(int
  if (im_ne_get_node_cmap(id,
                            mss.node_cmap_ids[j],
                            mss.comm_node_ids[j],
                            mss.comm_node_proc_ids[j],
                            0/*not used proc_id*/ ) < 0 )++error;</pre>
}
for(int j = 0; j < mss.num_elem_comm_maps; j++) {</pre>
  mss.comm_elem_ids[j]
                              = (int *)malloc(mss.elem_cmap_elem_cnts[j]*sizeof(int
  mss.comm_side_ids[j]
                              = (int *)malloc(mss.elem_cmap_elem_cnts[j]*sizeof(int
  mss.comm_elem_proc_ids[j] = (int *)malloc(mss.elem_cmap_elem_cnts[j]*sizeof(int
  if ( im_ne_get_elem_cmap( id,
                            mss.elem_cmap_ids[j],
                            mss.comm_elem_ids[j],
                            mss.comm_side_ids[j],
```

if(mss.num\_node\_comm\_maps > 0){

## References

- [1] G. L. Hennigan, M. St. John, and J. N. Shadid. NEMESIS I: A set of functions for describing unstructured finite-element data on parallel computers. Technical report, Sandia National Laboratories, Albuquerque, NM, May 1998.
- [2] L. A. Schoof and V. R. Yarberry. EXODUS II: A Finite Element Data Model. Technical report SAND92-2137, Sandia National Laboratories, Albuquerque, NM, November 1995.

# Index

Block IDs, 19 Boundary Conditions, 35 Brick, 33

Cylindrical, 24

Decomposition Strategy, 43 Dimensionality, 18

Geometry and Topology, 20

Nodesets, 35

Radial, 26 Radial Trisection, 26 Rectilinear, 20

Set Assign, 35 Sidesets, 35 Spherical, 22

Trisection, 26

User Defined Element Density, 41 User Defined Geometry Transformation, 38

## DISTRIBUTION:

- Oak Ridge National Laboratory
  P.O. Box 2009,
  Oak Ridge, TN 37831
  J. Michael Starbuck, MS 8048
  Seokho Kim, MS 8045
- Vanden, K. J.
  AFRL/MNAC
  101 West Eglin Blvd.
  Eglin AFB, FL 32542-6810
- 1 Chin, Chuck U.S. Army ARDEC SMCAR-AEE-WW -Bldg. 3022 Picatinny Arsenal, NJ 07806-5000
- 1 Doney, Bobby U.S. Army Research Laboratory AMSRL-WT-TA Aberdeen Proving Ground, MD, 21005-5066
- 1 Fermen-Coker, M. U.S. Army Research Laboratory AMSRL-WT-TC Aberdeen Proving Ground, MD 21005-5066
- 1 Filbey, Gordon L., Jr. U.S. Army Research Laboratory AMSRL-WT-TC Aberdeen Proving Ground, MD 21005-5066
- 1 Kimsey, Kent D. U.S. Army Research Laboratory AMSRL-WT-TC Aberdeen Proving Ground, MD 21005-5066
- 1 Kingman, Pat U.S. Army Research Laboratory AMSRL-WT-TD Aberdeen Proving Ground, MD 21005-5066

- 1 Schraml, Stephen J. U.S. Army Research Laboratory AMSRL-WT-TC Aberdeen Proving Ground, MD 21005-5066
- Becker, J. D.
   Attn: CEERD-IH-N
   U.S. Army Engineering & Research
   Development Center
   3909 Halls Ferry Road
   Vicksburg, MS 39180-6199
- 1 Howard, Scott US Army AMCOM AMSAM-RD-PS-WF Bldg 5400 Redstone Arsenal, AL 35808
- Poy, Stephen
  Code 673
  Carderock Division
  Naval Surface Warfare Center
  9500 MacArthur Blvd.
  West Bethesda, MD 20817-5700
- Sorenson, Carl D.
  Brigham Young University
  Dept. of Mechanical Engineering
  435 CTB
  Provo, UT 84602
- 1 Ding, Jow L. Institute for Shock Physics Washington State University P.O. Box 642814 Pullman, WA 99164-2814
- Haque, Aamer
   U. S. Deptartment of Energy
   MS DP-153
   1000 Independence Ave. S. W.
   Washington, DC 20585
- 1 Stecher, Frederick Alliant TechSystems MS: MN07-MW44 4700 Nathan Lane, North Plymouth, MN 55442-2512

- Scott, Daniel SAIC
   1710 SAIC Dr.
   M/S T1-5-2
   McLean, VA 22102
- Bassler, Robert
   Applied Research Assoc.
   Capital Area Division
   Eisenhower Ave., Suite 308
   Alexandria, VA 22314-4569
- $\begin{array}{ccc} \textbf{1} & \text{MS} & 0139 \\ & & \text{P. Yarrington, } 9902 \end{array}$
- 1 MS 0321 W. J. Camp, 9200
- 1 MS 0370 P. N. Demmie, 9232
- 1 MS 0370A. V. Farnsworth, Jr., 9232
- 1 MS 0370 M. E. Kipp, 9232
- 1 MS 0370 T. G. Trucano, 9211
- $\begin{array}{ccc} \mathbf{1} & \mathrm{MS} & 0378 \\ & & \mathrm{W.\ J.\ Bohnhoff,\ 9231} \end{array}$
- **1** MS 0378 S. Carroll, 9231
- 1 MS 0378 M. A. Christon, 9231
- 1 MS 0378 R. R. Drake, 9231
- 1 MS 0378 D. M. Hensinger, 9231
- 1 MS 0378 D. A. Labreche, 9231

- 1 MS 0378 C. B. Luchini, 9231
- 1 MS 0378 R. J. MacKinnon, 9231
- 1 MS 0378 S. J. Mosso, 9231
- 1 MS 0378 S. V. Petney, 9231
- 1 MS 0378 A. C. Robinson, 9231
- $\begin{array}{ccc} \textbf{1} & \text{MS} & 0378 \\ & \text{J. Robbins, } 9231 \end{array}$
- $\begin{array}{ccc} \mathbf{1} & \mathrm{MS} & 0378 \\ & & \mathrm{R.~M.~Summers,~9231} \end{array}$
- 1 MS 0378 T. E. Voth, 9231
- 1 MS 0378 M. K. Wong, 9231
- 1 MS 0378 R. L. Bell, 9232
- 1 MS 0378 G. C. Bessette, 9232
- 1 MS 0378 R. A. Cole, 9232
- 1 MS 0378 S. A. Silling, 9232
- 1 MS 0378 P. A. Taylor, 9232
- 1 MS 0521 S. T. Montgomery, 2561
- $\begin{array}{ccc} \mathbf{1} & \mathrm{MS} & 0557 \\ & & \mathrm{T.~W.~Simmermacher,~9124} \end{array}$

1 MS 0826 J. D. Zepper, 9143 1 MS 0835 E. A. Boucheron, 9141 **1** MS 0835 M. W. Glass, 9141 **1** MS 0836 D. A. Crawford, 9116 **1** MS 0836 E. S. Hertel, Jr., 9116 1 MS 0836 R. G. Schmitt, 9116 **1** MS 1110 P. B. Bochev, 9214 **1** MS 1110 J. B. Aidun, 9230 1 MS 1152 S. J. Chantrenne, 1642 **1** MS 1152 R. S. Coats, 1642 **1** MS 1152 M. L. Kiefer, 1642 **1** MS 1152 J. D. Kotulski, 1642 **1** MS 1152 L. P. Mix, Jr., 1642 1 MS 1152 M. F. Pasik, 1642 **1** MS 1152 T. D. Pointon, 1642

**1** MS 1152

D. B. Seidel, 1642

**1** MS 1152 C. D. Turner, 1642 **1** MS 1166 C. R. Drumm, 15345 **1** MS 1166 W. C. Fan, 15345 **1** MS 1152 S. J. Chantrenne, 1642 **1** MS 1168 C. Deeney, 1646 **1** MS 1181 J. P. Davis, 1646 **1** MS 1186 R. B. Campbell, 1674 **1** MS 1186 P. J. Christenson, 1674 **1** MS 1186 K. R. Cochrane, 1674 **1** MS 1186 M. P. Desjarlais, 1674 **1** MS 1186 C. J. Garasi, 1674 **1** MS 1186 T. A. Haill, 1674 **1** MS 1186 R. J. Lawrence, 1674 **1** MS 1186 R. W. Lemke, 1674 **1** MS 1186 T. A. Mehlhorn, 1674 **1** MS 1186 T. K. Mattsson, 1674

**1** MS 1186

B. V. Oliver, 1674

**1** MS 1186

K. Peterson, 1674

**1** MS 1186

S. A. Slutz, 1674

**1** MS 1186

R. A. Vesey, 1674

**1** MS 1186

E. C. Wemlinger, 1674

**1** MS 1186

E. P. Yu, 1674

**1** MS 1190

J. P. Quintenz, 1600

**1** MS 1191

M. K. Matzen, 1670

**1** MS 1191

M. A. Sweeney, 1670

**1** MS 1194

S. E. Rosenthal, 1644

**1** MS 1194

E. M. Waisman, 1644

**1** MS 1452

S. L. Szarka, 2552

**1** MS 9051

S. E. Wunsch, 8351

**1** MS 9159

J. J. Hu, 9214

**1** MS 9159

R. S. Tuminaro, 9214

**2** MS 0899

Technical Library, 9616

**1** MS 9018

Central Technical Files, 8945-1