

COMP SUPERSCALAR

User Manual

Application execution guide

Version: 1.3

August 31, 2015



This manual only provides information about how to execute COMPSs aplications. Specifically, it details the options, results and logs of an execution and it provides an overview of the COMPSs tools usage. It is highly recommended to follow this manual with a working COMPSs installation. For this purpose we provide a *COMPSs Virtual Machine* available at http://compss.bsc.es/.

For information about the installation process please refer to the $COMPSs\ Installation\ Guide$ available at http://compss.bsc.es/ .

For further information about the application development please refer to the *COMPSs User Manual: Application development guide* available at http://compss.bsc.es/.

For full COMPSs application examples (codes, execution commands, results, logs, etc.) please refer to the COMPSs Sample Applications available at http://compss.bsc.es/

.

Contents

T	CO	MP Superscalar (COMPSs)
2	Exe	ecuting COMPSs applications
	2.1	Prerequisites
	2.2	Runcompss command
	2.3	Running a COMPSs application
		2.3.1 Running Java applications
		2.3.2 Running Python applications
		2.3.3 Running C/C++ applications
	2.4	Additional configurations
	2.4	2.4.1 Resources file
	0.5	2.4.2 Project file
	2.5	Configuration examples
		2.5.1 Services configuration example
		2.5.2 Cluster configuration (static resources) example
		2.5.3 Shared Disks configuration example
		2.5.4 Cloud configuration (dynamic resources) example
		2.5.4.1 Cloud connectors: Amazon EC2
		2.5.4.2 Cloud connectors: rOCCI
0	D	
3		sults and logs
	3.1	Results
	3.2	Logs
4	CO	MPSs Tools
	4.1	Application graph
	4.2	COMPSs Monitor
		4.2.1 Service configuration
		4.2.2 Usage
		4.2.3 Graphical Interface features
	4.3	Application tracing
	1.0	4.3.1 Trace Command
		4.3.2 Application Instrumentation
		4.3.3 Trace Visualization
		4.3.3.1 Trace Loading
		4.3.3.2 Configuration File
		4.3.3.3 View Adjustment
		4.3.4 Trace Interpretation
		4.3.5 Trace Analysis
		4.3.5.1 Graphical Analysis
		4.3.5.2 Numerical Analysis
		4.3.6 Other Trace examples
	4.4	COMPSs IDE

5	Con	nmon Issues	37
	5.1	How to debug	37
	5.2	Tasks are not executed	37
	5.3	Jobs sistematically fail	37
	5.4	Compilation error: @Method not found	38

List of Figures

1	Execution of a Java COMPSs application	4
2	Execution of a Python COMPSs application	4
3	Execution of a C++ COMPSs application	5
4	Ouput generated by the execution of the Simple java application with	
	COMPSs	15
5		15
6	COMPSs execution of the <i>Hello</i> java application	16
7	Structure of the logs folder for the Simple java application in off mode	16
8	Structure of the logs folder for the Simple java application in info mode	17
9	runtime.log generated by the execution of the $Simple$ java application	17
10	resources.log generated by the execution of the $Simple$ java application	18
11	Structure of the logs folder for the Simple java application in debug mode	18
12	The dependency graph of the SparseLU application	19
13	COMPSs Monitor start command	20
14	COMPSs monitoring interface	21
15	Execution of the Simple java application with the monitoring flag enabled .	22
16	Logs generated by the Simple java application with the monitoring flag	
	enabled	22
17	Paraver menu	26
18		26
19	Paraver view adjustment: Fit window	27
20	Paraver view adjustment: View Event Flags	27
21	Paraver view adjustment: Show info panel	28
22	y	28
23	Paraver view adjustment: Zoom configuration	28
24	Trace interpretation	29
25	Caption	30
26	1	30
27	Caption	31
28	•	31
29	Paraver Menu - New Histogram	31
30	1 0	32
31	© 1	33
32	1 0	34
33	Examples of complex traces	35

List of Tables

1	Configuration of resources.xml file, $tag < CloudProvider >$.	11
2	Configuration of project.xml file, $tag < Cloud > \dots \dots \dots$	12
3	Configuration of project.xml file, $tag < Provider > \dots \dots \dots$	
4	Properties of the Amazon EC2 connector	13
5	rOCCI extensions in the project.xml file	14
6	Configuration of the $\langle provider \rangle$. xml templates file	14

1 COMP Superscalar (COMPSs)

COMP Superscalar (COMPSs) is a programming model which aims to ease the development of applications for distributed infrastructures, such as Clusters, Grids and Clouds. COMP Superscalar also features a runtime system that exploits the inherent parallelism of applications at execution time.

For the sake of programming productivity, the COMPSs model has four key characteristics:

- Sequential programming: COMPSs programmers do not need to deal with the typical duties of parallelization and distribution, such as thread creation and synchronization, data distribution, messaging or fault tolerance. Instead, the model is based on sequential programming, which makes it appealing to users that either lack parallel programming expertise or are looking for better programmability.
- Infrastructure unaware: COMPSs offers a model that abstracts the application from the underlying distributed infrastructure. Hence, COMPSs programs do not include any detail that could tie them to a particular platform, like deployment or resource management. This makes applications portable between infrastructures with diverse characteristics.
- Standard programming languages: COMPSs is based on the popular programming language Java, but also offers language bindings for Python and C/C++ applications. This facilitates the learning of the model, since programmers can reuse most of their previous knowledge.
- No APIs: In the case of COMPSs applications in Java, the model does not require to use any special API call, pragma or construct in the application; everything is pure standard Java syntax and libraries. With regard the Python and C/C++ bindings, a small set of API calls should be used on the COMPSs applications.

2 Executing COMPSs applications

2.1 Prerequisites

Prerequisites vary depending on the application's code language: for Java applications the users need to have a **jar archive** containing all the application classes, for Python applications there are no requirements and for C/C++ applications the code must have been previously compiled by using the *buildapp* command.

For further information about how to develop applications for COMPSs please refer to the *COMPSs User Manual: Application development guide* available at the http://compss.bsc.es/webpage.

2.2 Runcompss command

All COMPSs applications are executed using the **runcompss** command which is invoked as follows:

```
compss@bsc:~$ runcompss [options] application_name [application_arguments]
```

The application name stands for the fully qualified name of the application in Java, for the path to the .py file containing the main program in Python and for the path to the master binary in C/C++.

The application arguments are the arguments that the users' main application recieves. If needed, they can be empty.

The runcompss command allows the users to customize each COMPSs execution by specifying different options. For clarity purposes, parameters are grouped in *Runtime configuration*, *Tools enablers* and *Advanced options*. Users can add any of them to the runcompss call by following the next usage description.

```
compss@bsc:~$ runcompss -h
 Runtime configuration options:
    -project=<path>
                                            Path to the project XML file
                                            Default: /opt/COMPSs/Runtime/configuration/
                                            xml/projects/project.xml
                                            Path to the resources XML file
     -resources=<path>
                                            Default: /opt/COMPSs/Runtime/configuration/
                                            xml/resources/resources.xml
    - -lang=<name>
                                            Language of the application (java/c/python)
                                            Default: java
     -log_level=<level>, - -debug, -d
                                            Set the debug level: off | info | debug
                                            Default: off
 Tools enablers:
    - -graph=<bool>, - -graph, -g
                                            Generation of the complete graph (true/false)
                                            When no value is provided it is set to true
                                            Default: false
                                            Generation of traces (true/false)
     -tracing=<bool>, - -tracing, -t
                                            When no value is provided it is set to true
                                            Default: false
```

```
- -monitoring=<int>, - -monitoring, -m Period between monitoring samples
                                           (milliseconds)
                                           When no value is provided it is set to 2000
                                           Default: 0
Advanced options:
  - -comm=<path>
                                           Class that implements the adaptor for
                                           communications
                                           Default: integratedtoolkit.nio.master.
                                           NIOAdaptor
                                           Non-standard directories to search for
  - -library_path=<path>
                                           libraries (e.g. Java JVM library, Python
                                           library, C binding library)
                                           Default: .
    -classpath=<path>
                                           Path for the application classes / modules
                                           Only for C/Python Bindings.
   -task_count=<int>
                                           Maximum number of different functions/methods
                                           invoked from the application that have been
                                           selected as tasks
                                           Default: 50
   -uuid=<int>
                                           Preset an application UUID
                                           Default: Automatic random generation
```

2.3 Running a COMPSs application

Before running COMPSs applications it is important to notice that the application files **must** be in the **CLASSPATH**. Thus, when launching a COMPSs application, users can manually pre-set the **CLASSPATH** environment variable or can add the - - *classpath* option to the runcompss command.

The next three sections provide specific information for launching COMPSs applications in different code languages (Java, Python and C/C++). For clarity purposes we will use the Simple application (developed in Java, Python and C++) available at our Virtual Machine or at https://compss.bsc.es/projects/bar webpage. This application takes an integer as input parameter and increases it by one unit using a task. For further details about the codes please refer to the Sample Applications document available at http://compss.bsc.es.

2.3.1 Running Java applications

A Java COMPSs application can be launched through the following command:

```
compss@bsc:~$ cd workspace_java/simple/jar/
compss@bsc:~/workspace_java/simple/jar$ runcompss simple.Simple <initial_number>
```

In this first execution we are taking advantage of the default value of the --classpath option to automatically add the jar file to the classpath (by moving to the directory which contains the jar file before launching the COMPSs application). However, we can explicitly do this by exporting the **CLASSPATH** variable or by providing the --classpath value. Next, we provide another two ways to perform the same execution:

Figure 1: Execution of a Java COMPSs application.

```
compss@bsc:~$ runcompss --classpath=/home/compss/workspace_java/simple/jar/simple.jar simple.Simple <initial_number>
```

2.3.2 Running Python applications

To lauch a Python application with COMPSs users only need to provide the - -lang=python option to the runcompss command. Next, we provide an example of a simple python application.

```
compss@bsc:~$ cd workspace_python/simple/
compss@bsc:~/workspace_python/simple$ runcompss --lang=python simple.py <initial_number>
```

Figure 2: Execution of a Python COMPSs application.

2.3.3 Running C/C++ applications

To lauch a C/C++ application with COMPSs users need to compile the C/C++ application by using the *buildapp* command. For further information please refer to the *COMPSs User Manual: Application development guide* document available at our webpage http://compss.bsc.es. Once done, to run the C/C++ application with COMPSs,

the users only need to provide the -lang=c option to the runcompss command. Next, we provide an example of a simple C++ application:

```
compss@bsc:~$ cd workspace_c/simple/
compss@bsc:~/workspace_c/simple$ runcompss --lang=c simple <initial_number>
```

Figure 3: Execution of a C++ COMPSs application.

2.4 Additional configurations

COMPSs has **two** configuration files: resources.xml and project.xml. These files are meant to provide information about the execution environment and are completely independent from the application.

For each execution users can load the default configuration files or specify their custom configurations by using, respectively, the $--resources = < absolute_path_to_resources.xml >$ and the $--project = < absolute_path_to_project.xml >$ inside the runcompss command. The default files are located under the /opt/COMPSs/Runtime/configuration/xml/ path. Users can edit these two files manually or can take advantage of the $Eclipse\ IDE$ tool developed for COMPSs. For further information about the $Eclipse\ IDE$ please refer to Section 4.4.

Next sections provide more in-depth information about the *resources.xml* and the *project.xml* files, listing and explaining the available tags.

2.4.1 Resources file

The resources file provides information about **all** the available resources. This file should normally be managed by the system administrators. Its full definition schema can be found at /opt/COMPSs/Runtime/configuration/xml/resources/resource_schema.xsd.

The typical structure of this file is one entry per available resource defining its name, its capabilities and its requirements. Administrators can define several resource capabilities (see example in next listing) but we would like to underline the importance of **Processor CoreCount**. This capability represents the number of available cores in the resource and it is used to schedule the correct number of tasks into a resource. Thus, it becomes essential to define it accordingly to the number of cores in the physical resource.

```
compss@bsc:~$ cat /opt/COMPSs/Runtime/configuration/xml/resources/resources.xml
<?xml version="1.0" encoding="UTF-8"?>
<ResourceList>
        <Resource Name="localhost">
                <Capabilities>
                        <Host>
                                 <TaskCount>0</TaskCount>
                                 <Queue>short</Queue>
                                 <Queue/>
                         </Host>
                         <Processor>
                                 <Architecture>IA32</Architecture>
                                 <Speed>3.0</Speed>
                                 < CoreCount > 4 < /CoreCount >
                         </Processor>
                         <0S>
                                 <OSType>Linux</OSType>
                                 <MaxProcessesPerUser>32</MaxProcessesPerUser>
                         </OS>
                         <StorageElement>
                                 <Size>8</Size>
                         </StorageElement>
                         <Memory>
                                 <PhysicalSize>4</PhysicalSize>
                                 <VirtualSize>8</VirtualSize>
                         <ApplicationSoftware>
                                 <Software>Java</Software>
                         </ApplicationSoftware>
                         <Service/>
                         < Vn />
                         <Cluster/>
                         <FileSystem/>
                         <NetworkAdaptor/>
                         <JobPolicy/>
                         <AccessControlPolicy/>
                </Capabilities>
                <Requirements/>
                <Adaptors>
                         <Adaptor name="integratedtoolkit.nio.master.NIOAdaptor">
                                 <MinPort>43001</MinPort>
                                 <MaxPort>43002</MaxPort>
                        </Adaptor>
                </Adaptors>
        </Resource>
</ResourceList>
```

2.4.2 Project file

The project file provides specific execution information. Particularly, it selects and configures in which resources is the application going to be executed. Consequently, the resources that appear in this file are a **subset** of the resources described in the *resources.xml* file. This file should normally be managed by the application users and

will usually change from execution to execution. Its full definition schema can be found at /opt/COMPSs/Runtime/configuration/xml/projects/project_schema.xsd.

The typical structure of this file is one entry per worker, indicating the the resource name that it uses and some configuration properties (see example in next listing). We emphasize the importance of correctly defining the following entries:

installDir Indicates the path of the COMPSs installation inside the resource (not necessarily the same than in the local machine).

User Indicates the username used to connect via ssh to the resource. This user must have passwordless access to the resource (for more information check the *COMPSs Installation Manual* available at our website http://compss.bsc.es). If left empty COMPSs will automatically try to access the resource with the same username than the one that lauches the COMPSs main application.

LimitOfTasks The maximum number of tasks that can be simultaneously scheduled to a resource. Considering that a task can use more than one core but not least, this value must be lower or equal to the number of available cores in the resource.

```
compss@bsc:~$ cat /opt/COMPSs/Runtime/configuration/xml/projects/project.xml

<
```

2.5 Configuration examples

In the next subsections we provide specific information about the services, shared disks, cluster and cloud configurations. Moreover there are *project.xml* and *resources.xml* examples for each case that can be used as templates.

2.5.1 Services configuration example

To allow COMPSs applications use WebServices the *resources.xml* can include a special type of resource called *Service*. For each WebService it is necessary to specify its wsdl, its name, its namespace and its port as shown in the following example.

When configuring the *project.xml* file it is necessary to include the service as a worker by adding an special entry indicating only the name and the limit of tasks as shown in the following example:

2.5.2 Cluster configuration (static resources) example

In order to use external resources to execute the applications, the following steps have to be followed:

- 1. Install the COMPSs Worker package (or the full COMPSs Framework package) on all the new resources following the Installation manual available at http://compss.bsc.es.
- 2. Set SSH passwordless access to the rest of the remote resources.
- 3. Create the *WorkingDir* directory in the resource (remember this path because it is needed for the *project.xml* configuration).
- 4. Deploy the application manually on each resource.

Once these steps are done, users need to configure the *resources.xml* and the *project.xml* files accordingly. On the following lines, we provide examples about configuration files for Grid and Cluster environments, which can serve as a reference

```
<OSType>Linux</OSType>
            </0S>
            <StorageElement>
               <Size>250.0</Size>
           </StorageElement>
            <Memorv>
               <PhysicalSize>4.0</PhysicalSize>
            </Memory>
            <ApplicationSoftware>
                <Software>BLAST</Software>
            </ApplicationSoftware>
        </Capabilities>
       <Requirements/>
       <Adaptors>
            <Adaptor name="integratedtoolkit.nio.master.NIOAdaptor">
                <MinPort>43001</MinPort>
                <MaxPort>43002</MaxPort>
           </Adaptor>
       </Adaptors>
   </Resource>
   <Resource Name="hostname2.domain.es">
   </Resource>
</ResourceList>
```

2.5.3 Shared Disks configuration example

Configuring shared disks might reduce the amount of data transfers improving the application performance. To configure a shared disk the users must edit the *resources.xml* indicating how the shared disk is hosted in the master node and how the shared disk is mounted in each worker.

To indicate a shared disk hosted in the master node the resources.xml file must include a Disk tag describing the disk and the mount point. The following example states that in the master node there is a shared disk labelled sharedDisk0 mounted on the /sharedDisk directory.

On the other side, to declare that a worker has a shared disk mounted the resources.xml file must include a Disk tag inside the specific worker indicating its name (defined in the master Disk tag) and its mount point inside the worker. The following example states that the sharedDisk0 is mounted on resource hostname1.domain.es under the path /home/user/mySharedDisk/.

Although, the example only contains the definition of a single shared disk, the *Disks* tag can have multiple disk child nodes.

2.5.4 Cloud configuration (dynamic resources) example

In order to use cloud resources to execute the applications, the following steps have to be followed:

- 1. Prepare cloud images with the COMPSs Worker package or the full COMPSs Framework package installed.
- 2. The application will be deployed automatically during execution but the users need to set up the configuration files to specify the application files that must be deployed.

The COMPSs runtime communicates with the Cloud by means of Cloud connectors. Each connector implements the interaction of the runtime with a given Cloud provider, more precisely by supporting four basic operations: ask for the price of a certain VM in the provider, get the time needed to create a VM, create a new VM and terminate a VM. This design allows connectors to abstract the runtime from the particular API of each provider and facilitates the addition of new connectors for other providers.

In order to add cloud resources the *resources.xml* file can contain one or more < CloudProvider > tags that encompass the information about a particular Cloud provider, associated to a given connector. The tag **must** have an attribute **name** to uniquely identify the provider. Table 1 summarizes the information to be specified by the user inside this tag.

Server	Endpoint of the provider's server
Connector	Class that implements the connector

ImageList	Multiple entries of VM templates
• Image	• VM image
- Architecture	- Architeture of the VM image
- OSType	 Operative System installed in the VM image
- ApplicationSoftware	 Multiple entries of software installed in the VM image
* Software	* Software installed in the VM image
- SharedDisks	 Multiple entries of shared disks mounted in the VM im- age
* Disk	* Disk description
- Adaptors	 Multiple entries of adaptors available at the VM image
* Adaptor	* Adaptor name and specific properties
InstanceTypes	Multiple entries of resource templates
• Resource	• Instance type offered by the provider
- Capabilities	 Hardware details of instance type
* Processor	* Architecture and number of available cores
* StorageElement	* Size in GB of the storage
* Memory	* PhysicalSize, in GB of the available RAM
Table 1: Configuration of	magaymag yml filo tag

Table 1: Configuration of resources.xml file, tag < CloudProvider >

The project.xml complements the information about Cloud providers specified in the resources.xml file. This file can contain a < Cloud > tag where to specify a list of providers, each with a < Provider > tag, whose \mathbf{name} attribute must match one of the providers in the resources.xml file. Thus, the project.xml file \mathbf{must} contain a subset of the providers specified in the resources.xml file. Table 3 summarizes the information that users need to specify inside the < Cloud > tag and Table 2 summarizes the information that users need to specify inside the < Provider > tag of the project.xml file.

InitialVMs	Number of VM to be created at the beginning of the application
minVMCount	Minimum number of VMs available in the computation
maxVMCount	Maximum number of VMs available in the computation
Provider	Multiple entries of Cloud providers

Table 2: Configuration of project.xml file, tag < Cloud >

LimitOfVMs	Maximum number of VMs allowed by the provider
Property	Multiple entries of provider-specific properties
• Name	• Name of the property
• Value	• Value of the property
ImageList	Multiple entries of VM images available at the provider
• Image	• VM image
– InstallDir	 Path of the COMPSs worker scripts in the image
– WorkingDir	 COMPSs working directory in the de- ployed instances
– User	- Account username
– Package	 Multiple entries of local packages that have to be deployed in new instances
* Source	* Local path of the package
* Target	* Path where to deploy the package in the new instance
* InstalledSoftware	* List of software included in the package
InstanceTypes	List of resource types that are available in the provider
• Resource	• Resource description

Table 3: Configuration of project.xml file, tag < Provider >

The next sections provide a description of each of the currently available connector. $12\,$

2.5.4.1 Cloud connectors: Amazon EC2

The COMPSs runtime features a connector to interact with the Amazon Elastic Compute Cloud (EC2).

Amazon EC2 offers a well-defined pricing system for VM rental. A total of 8 pricing zones are established, corresponding to 8 different locations of Amazon datacenters around the globe. Besides, inside each zone, several per-hour prices exist for VM instances with different capabilities. The EC2 connector stores the prices of standard on-demand VM instance types (t1.micro, m1.small, m1.medium, m1.large and m1.xlarge) for each zone. Spot instances are not currently supported by the connector.

When the COMPSs runtime chooses to create a VM in the Amazon public Cloud, the EC2 connector receives the information about the requested characteristics of the new VM, namely the number of cores, memory, disk and architecture (32/64 bits). According to that information, the connector tries to find the VM instance type in Amazon that better matches those characteristics and then requests the creation of a new VM instance of that type.

Once an EC2 VM is created, a whole hour slot is paid in advance; for that reason, the connector keeps the VM alive at least during such period, saving it for later use if necessary. When the task load decreases and a VM is no longer used, the connector puts it aside if the hour slot has not expired yet, instead of terminating it. After that, if the task load increases again and the EC2 connector requests a VM, first the set of saved VMs is examined in order to find a VM that is compatible with the requested characteristics. If one is found, the VM is reused and becomes eligible again for the execution of tasks; hence, the cost and time to create a new VM are not paid. A VM is only destroyed when the end of its hour slot is approaching and it is still in saved state.

Table 4 summarizes the provider-specific properties that must be defined in the project.xml file for the Amazon EC2 connector.

Placement	Location of the amazon datacentre to use	
Access Key Id	Identifier of the access key of the Amazon EC2 account	
Secret Key Id	Identifier of the secret key of the Amazon EC2 account	
Key host location	Path to the SSH key in the local host, used to connect to the VMs	
KeyPair name	Name of the key pair to use	
SecurityGroup name	Name of the security group to use	

Table 4: Properties of the Amazon EC2 connector.

2.5.4.2 Cloud connectors: rOCCI

In order to execute a COMPSs application in the cloud, the rOCCI connector has to be configured properly. The connector uses the rOCCI binary client¹ (version newer or equal than 4.2.5) which has to be installed in the node where the COMPSs main application is executed.

This connector needs additional files providing details about the resource templates available on each provider. This file is located under $< COMPSs_INSTALL_DIR > /configuration/xml/templates$ path. Additionally, the user must define the virtual images flavour and instance types offered by each provider; thus, when the runtime asks for the creation of a VM, the connector selects the appropriate image and resource template according to the requirements (in terms of CPU, memory, disk, etc) by invoking the rOCCI client through Mixins (heritable classes that override and extend the base templates).

Table 5 contains the rOCCI specific properties that must be defined under the *Provider* tag in the *project.xml* file and Table 5 contains the specific properties that must be defined under the *Instance* tag.

Provider	
ca-path	Path to CA certificates directory
user-cred	Path of the VOMS proxy
auth	Authentication method, x509 only supported
owner	Optional. Used by the VENUS-C Job Manager (PMES)
jobname	Optional. Used by the VENUS-C 300 Manager (1 MES)

Table 5: rOCCI extensions in the project.xml file.

Instance	Multiple entries of resource templates.
Type	Name of the resource template. It has to be the same name than in the previous files
CPU	Number of cores
Memory	Size in GB of the available RAM
Disk	Size in GB of the storage
Price	Cost per hour of the instance

Table 6: Configuration of the < provider > .xml templates file.

https://appdb.egi.eu/store/software/rocci.cli

3 Results and logs

3.1 Results

When executing a user application we consider different type of results:

- Application Output: Output generated by the application.
- Application Files: Files used or generated by the application.
- Tasks Output: Output generated by the tasks invoked from the application.

Regarding the application output, COMPSs will preserve the application output but will add some pre and post output to indicate the COMPSs Runtime state. Figure 4 shows the standard output generated by the execution of the simple java application. The green box highlights the application stdout while the rest of the output is produced by COMPSs.

Figure 4: Ouput generated by the execution of the Simple java application with COMPSs

Regarding the application files, COMPSs does not modify any of them and thus, the results obtained by executing the application with COMPSs are the same than the ones generated by the sequential execution of the application.

Regarding the task output, COMPSs does introduce some modifications due to the fact that tasks can be executed in remote machines. Considering that we call a job the execution of a task in a given resource, after the execution, COMPSs stores the stdout and the stderr of each job inside the $/home/\$USER/.COMPSs/\$APPNAME/\$EXEC_NUMBER/jobs/$ directory.

Figures 5 and 6 show an example of the results obtained from the execution of the Hello java java application. While Figure 5 provides the sequential execution of the application, Figure 6 provides its equivalent COMPSs execution. Notice that, the sequential execution produces the Hello World! (from a task) message in the stdout while the COMPSs execution stores the message inside the $job1_NEW.out$ file.

```
compss@bsc:~/workspace_java/hello/jar$ java -cp hello.jar hello.Hello
Hello World! (from main application)
Hello World! (from a task)
```

Figure 5: Sequential execution of the *Hello* java application

```
Compss@bsc:-/workspace_java/hello/jar$ runcompss .d hello.Hello
Using default location for project file: /opt/COMPSs/Runtime/scripts/user/.././configuration/xml/projects/project.xml
Using default location for resources file: /opt/COMPSs/Runtime/scripts/user/../../configuration/xml/projects/project.xml
Using default location for resources file: /opt/COMPSs/Runtime/scripts/user/../../configuration/xml/projects/project.xml

WARNING: IT Properties file is null. Setting default values

[ API] - Deploying COMPSs Runtime v1.3 (build 20150820-1617.rnull)
[ API] - Starting COMPSs Runtime v1.3 (build 20150820-1617.rnull)
[ API] - Initializing components
[ API] - Ready to process tasks
Hello Morld! (from main application)
[ API] - Creating task from method sayHello in hello.HelloImpl
[ API] - There is 0 parameter
[ API] - No more tasks for app 1
[ API] - Stopting Result Files 1
[ API] - Stopping AP...
[ API] - Stopping AP...
[ API] - Stopping Omm...
[ API] - Stopping Comm...
[ API] - Stopping Comm...
[ API] - Execution Finished

compss@bsc:-$ more ~/.COMPSs/hello.Hello_01/jobs/job1 NEW.out
2015-08-20 16:47:31,615 [DEBUG|integratedtoolkit.Worker|Executor] Creating sandbox for job 1

WORKER - Parameters of execution:

* Method class: hello.HelloImpl

* Method name: sayHello
* Parameter values:

* Parameter values:
```

Figure 6: COMPSs execution of the *Hello* java application

3.2 Logs

COMPSs includes three log levels for running applications but users can modify them or add more levels by editing the logger files under the /opt/COMPSs/Runtime/configuration/log/ folder. Any of these log levels can be selected by adding the $--log_level = < debug|info|off > flag to the runcompss command. The default value is off.$

The logs generated by the execution number NUM_EXEC of the application APP by the user USER are stored under $/home/\$USER/.COMPSs/\$APP/\$NUM_EXEC/$ folder (from this point on: **base log folder**). The execution number is automatically tracked to prevent the loss of data from previous executions, but users do not need to take care of this value.

When running COMPSs with **log level off** only the errors are reported. This means that the *base log folder* will contain two empty files (**runtime.log** and **resources.log**) and one empty folder (*jobs*). If somehow the application has failed, the *runtime.log* and/or the *resources.log* will not be empty and a new file per failed job will appear inside the *jobs* folder to store the *stdout* and the *stderr*. Figure 7 shows the logs generated by the execution of the Simple java application (without errors) in **off** mode.

```
.COMPSs/

[4.0K] simple.Simple_01

[4.0K] jobs

[0] resources.log

[0] runtime.log

[4.0K] tmpFiles
```

Figure 7: Structure of the logs folder for the Simple java application in off mode

When running COMPSs with log level info the base log folder will contain two files (runtime.log and resources.log) and one folder (jobs). The runtime.log file

contains the execution information retrieved from the master resource; including the file transfers and the job submission details. The **resources.log** file contains information about the available resources such as the number of processors of each resource (slots), the information about running or pending tasks in the resource queue and the created and destroyed resources. The jobs folder will be empty unless there has been a failed job. In this case, for each failed job, it will store one file for the *stdout* and another for the *stderr*. As an example, Figure 8 shows the logs generated by the same execution than the previous case but with **info** mode.

```
.COMPSs/

[4.0K] simple.Simple_02

[4.0K] jobs

[612] resources.log

[10K] runtime.log

[4.0K] tmpFiles
```

Figure 8: Structure of the logs folder for the Simple java application in **info** mode

The runtime.log and resources.log are quite large files and, thus, should be only checked by advanced users. For an easier interpretation of these files the COMPSs Framework includes a monitor tool. For further information about the COMPSs Monitor please check Section 4.2.

Figures 9 and 10 provide the content of these two files generated by the execution of the *Simple* java application.

Figure 9: runtime.log generated by the execution of the Simple java application

Running COMPSs with **log level debug** generates the same files as the info log level but with more detailed information. Additionally, the *jobs* folder contains two files per **submitted** job; one for the *stdout* and another for the *stderr*. In the other hand, the COMPSs Runtime state is printed out on the *stdout*. Figure 11 shows the logs generated by the same execution than the previous cases but with **debug** mode.

The runtime.log and the resources.log files generated in this mode can be **extremely** large. Consequently, the users should take care of their quota and manually and erase these files if needed.

When running Python applications a *pycompss.log* file will appear inside the *base log* folder containing debug information about the specific calls to PyCOMPSs.

Figure 10: resources.log generated by the execution of the Simple java application

```
.COMPSs/

[4.0K] simple.Simple_03

[4.0K] jobs

[0] job1_NEW.err

[380] job1_NEW.out

[612] resources.log

[70K] runtime.log

[4.0K] tmpFiles
```

Figure 11: Structure of the logs folder for the Simple java application in **debug** mode

Furthermore, when running other runcompss flags (such as monitoring or tracing) additional folders will appear inside the *base log folder*. The meaning of the files inside these folders is explained in Section 4.

4 COMPSs Tools

4.1 Application graph

At the end of the application execution a dependency graph can be generated representing the order of execution of each type of task and their dependencies. To allow the final graph generation the runcompss command must be run with the -g flag and the final graph will appear at the $base_log_folder/monitor/complete_graph$.dot at the end of the execution.

Figure 12 shows a dependency graph example of a SparseLU java application. The graph can be visualized by running the following command:

compss@bsc:~\$ gengraph ~/.COMPSs/sparseLU.arrays.SparseLU_01/monitor/complete_graph.dot




Figure 12: The dependency graph of the SparseLU application

4.2 COMPSs Monitor

The COMPSs Framework exposes a Web Service with a graphical interface that can be used to monitor either finished and running applications. COMPSs Monitor is installed as a service and can be easily managed by running any of the following commands:

```
compss@bsc:~$ sudo service compss-monitor usage
Usage: /usr/sbin/service compss-monitor
{start | stop | reload | restart | try-restart | force-reload | status}
```

4.2.1 Service configuration

The COMPSs Monitor service can be configured by editing the /opt/COMPSs/Tools/monitor/apache-tomcat/conf/compss-monitor.conf file which contains one line per property:

- IT_MONITOR Default directory to retrieve monitored applications.
- COMPSs_MONITOR_PORT Port where to run the compss-monitor web service.
- \bullet $COMPSs_MONITOR_TIMEOUT$ Web page timeout between browser and server.

By default, the $IT_MONITOR$ points to the .COMPSs folder inside the root user, opens the web service in the port 8080 and has a 20s timeout.

4.2.2 Usage

In order to use the COMPSs Monitor users need to start the service as shown in Figure 13.

```
compss@bsc:-$ /etc/init.d/compss-monitor start

* Starting COMPs Monitor

* Checking JAVA Installation...
Warning: JRE_HOME not defined
Info: JAVA_HOME found.
Loading JRE_HOME from JAVA_HOME
Success

* Checking IT_HOME...
MARNING: IT_HOME...
MARNING: IT_HOME...
MARNING: IT_HOME...
MARNING: IT_HOME...

* Checking IT_MONITOR...

IT_MONITOR-/home/compss/.COMPSs/
Success

* Checking COMPSs Monitor Port...
Warning: COMPSs_MONITOR_PORT not defined.
Loading from configuration file.

COMPSs_MONITOR_PORT=8888

Success

* Checking COMPSs Monitor Timeout...
Warning: COMPSs_MONITOR_TORE TIMEOUT not defined.
Loading from configuration file.
COMPSs_MONITOR_TIMEOUT not defined.
Loading from configuration file.
COMPSs_MONITOR_TIMEOUT_20808

Success

* Configuring COMPSs Monitor service...
Success

* Configuring COMPSs Monitor service...
Success

Using CATALINA_BASE: /opt/COMPSs/Tools/monitor/apache-tomcat
Using CATALINA_HOME: /opt/COMPSs/Tools/monitor/apache-tomcat/temp
Using CATALINA_HOME: /usr/lib/jwn/java-7-penjkk-anded/jre
Using CATALINA_TRPDIR: /opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/COMPSs/Tools/monitor/apache-tomcat/bin/bootstrap.jar:/opt/comps/comps/comps/comps/comps/comps/comps/comps/comps/comps/com
```

Figure 13: COMPSs Monitor start command

And use a web browser to open the specific URL:

```
compss@bsc:~$ firefox http://localhost:8080/compss-monitor &
```

The COMPSs Monitor allows to monitor applications from different users and thus, users need to login first to grant access to their applications. Once done, as shown in Figure 14, the users can select any of their executed or on-going COMPSs applications and display it.




Figure 14: COMPSs monitoring interface

To enable **all** the COMPSs Monitor features, applications must run the runcompss command with the -m flag. This flag allows the COMPSs Runtime to store special information inside inside the log base folder under the monitor folder (see Figures 15 and 16). Only advanced users should modify or delete any of these files. If the application that a user is trying to monitor has not been executed with this flag, some of the COMPSs Monitor features will be disabled.

Figure 15: Execution of the Simple java application with the monitoring flag enabled

```
compss@bsc:~$ cd .COMPSs/
compss@bsc:~/.COMPSs$ tree

simple.Simple_01

jobs

job1_NEW.err

job1_NEW.out

monitor

complete_graph.dot

COMPSS_state.xml

current_graph.dot

resources.log

runtime.log

tmpFiles
```

Figure 16: Logs generated by the Simple java application with the monitoring flag enabled

4.2.3 Graphical Interface features

Next we provide a summary of the COMPSs Monitor supported features available through the graphical interface:

• Resources information

Provides information about the resources used by the application

• Tasks information

Provides information about the tasks definition used by the application

• Current tasks graph

Shows the tasks dependency graph currently stored into the COMPSs Runtime

• Complete tasks graph

Shows the complete tasks dependecy graph of the application

• Load chart

Shows different dynamic charts representing the evolution over time of the resources

load and the tasks load

• Runtime log

Shows the runtime log

• Execution Information

Shows specific job information allowing users to easily select failed or uncompleted jobs

• Statistics

Shows application statistics such as the accumulated cloud cost.

Attention: To enable all the COMPSs Monitor features applications must run with the -m flag.

The webpage also allows users to configure some performance parameters of the monitoring service by accessing the *Configuration* button at the top-right corner of the web page.

For specific COMPSs Monitor feature configuration please check our FAQ section at the top-right corner of the web page.

4.3 Application tracing

COMPSs Runtime can generate a post-execution trace of the distributed execution of the application. This trace is useful for performance analysis and diagnosis.

A trace file may contain different events to determine the COMPSs master state, the task execution state or the file-transfers. Despite the fact that in the current release we do not support file-transfers, we intend to support them in a near future release.

During the execution of the application, an XML file is created at worker nodes to keep track of these events. At the end of the execution, all the XML files are merged to get a final trace file.

In the following sections we explain the command used for tracing, how the events are registered, in a process called instrumentation, how to visualize the trace file and make a good analysis of performance based on the data shown in the trace.

4.3.1 Trace Command

In order to obtain a post-execution trace file the option **-t** must be added to the runcompss command. Next we provide an example of the command execution with the tracing option enabled for the Hmmer java application.

```
compss@bsc:~$ runcompss -t --classpath=/home/compss/workspace_java/hmmerobj/jar/hmmerobj.
jar
hmmerobj.HMMPfam
/sharedDisk/Hmmer/smart.HMMs.bin /sharedDisk/Hmmer/256seq
/home/compss/out.txt 2 8 -A 222
```

4.3.2 Application Instrumentation

The instrumentation is the process that intercepts different events of the application execution and keeps log of them. This will cause an overhead in the execution time of the application that the user should take into account, but the collected data will be extremely useful for performance analysis and diagnosis.

COMPSs Runtime uses the *Extrae* tool to dynamically instrument the application and the *Paraver* tool to visualize the obtained tracefiles. Both tools are developped at *BSC* and are available in its webpage http://bsc.es.

At the worker nodes, in background, Extrae keeps track of the events in an intermediate format file (with .mpit extension). Inside the master node, at the end of the execution, Extrae merges the intermediate files to get the final trace file, a Paraver format file (.prv). See the visualization section 4.3.3 in this manual for further information about the Paraver tool.

When instrumenting the application *Extrae* will output several messages. At the master node, *Extrae* will show up its initialization at the begining of the execution and the merging process and the paraver generation at the end of the execution. At the worker nodes *Extrae* will inform about the intermediate files generation every time a task is executed. Next we provide a summary of the *stdout* generated by Hmmer java application execution with the trace flag enabled.

```
-- Executing hmmerobj.HMMPfam --
WARNING: IT Properties file is null. Setting default values
Welcome to Extrae 3.1.1rc (revision 3360 based on extrae/trunk)
Extrae: Warning! EXTRAE_HOME has not been defined!.
Extrae: Generating intermediate files for Paraver traces.
Extrae: Intermediate files will be stored in /home/compss/workspace_java/hmmerobj/jar
Extrae: Tracing buffer can hold 500000 events
Extrae: Tracing mode is set to: Detail.
Extrae: Successfully initiated with 1 tasks
Extrae: Warning! API tries to initialize more than once
                 Previous initialization was done by API
    API] - Starting COMPSs Runtime v1.3 (build 20150821-1134.rnull)
    APIl
            No more tasks for app 1
         - Getting Result Files 1
    API1
         - Execution Finished
Extrae: Intermediate raw trace file created : /home/compss/workspace_java/hmmerobj/jar/
   set -0/TRACE@bsc.0000031637000000000000.mpit
Extrae: Intermediate raw sym file created : /home/compss/workspace_java/hmmerobj/jar/set
    -0/TRACE@bsc.0000031637000000000000.sym
Extrae: Deallocating memory.
Extrae: Application has ended. Tracing has been terminated.
merger: Output trace format is: Paraver
merger: Extrae 3.1.1rc (revision 3360 based on extrae/trunk)
mpi2prv: Checking for target directory existance... exists, ok!
mpi2prv: Selected output trace format is Paraver
mpi2prv: Stored trace format is Paraver
mpi2prv: Parsing intermediate files
mpi2prv: Removing temporal files... done
```

```
mpi2prv: Congratulations! ./trace/hmmerobj.HMMPfam_compss_trace_1440151114.prv has been generated.
```

For further information about *Extrae* please visit the following site:

http://www.bsc.es/computer-science/extrae

4.3.3 Trace Visualization

Paraver is the BSC tool for trace visualization. Trace events are encoded in Paraver format (.prv) by the Extrae tool (see previous section). Paraver is a powerful tool that allows users to show many views of the trace data by means of different configuration files. Users can manually load, edit or create configuration files to obtain different trace data views.

In the following subsections we will explain how to load a trace file into *Paraver*, open the task events view by means of an already predefined configuration file, and how to adjust the view to properly display the data.

For further information about *Paraver* please visit the following site:

http://www.bsc.es/computer-sciences/performance-tools/paraver

4.3.3.1 Trace Loading

The final trace file in Paraver format (.prv) can be found at the base log folder of the application execution inside the trace folder. The fastest way to open it is calling directly the Paraver binary using the trace-file name as arugment.

compss@bsc:~\$ wxparaver /home/compss/.COMPSs/hmmerobj.HMMPfam_01/trace/*.prv

4.3.3.2 Configuration File

In order to open a view with the task events of the application, an already predefined configuration file is provided. To open it, just go in the main window to the "Load Configuration" option in the menu "File". The configuration file is under the following path /opt/COMPSs/Dependencies/paraver/cfgs/tasks.cfg. After accepting the load of the configuration file, another window will appear to show the view. Figures 17 and 18 show an example of this process.

4.3.3.3 View Adjustment

In a *Paraver* view, a red exclamation sign may appear on the bottom-left corner (see last Figure 18 in previous section). This means that some little adjustments must be done to view the trace correctly:

• Fit window: this will give a better color scale to identify events.



Figure 17: Paraver menu



Figure 18: Trace file

- Right click on the trace window
- Chose the option Fit Semantic Scale / Fit Both
- View Event Flags: This will put a flag whenever an event starts/ends.



Figure 19: Paraver view adjustment: Fit window

- Right click on the trace window
- Chose the option View / Event Flags




Figure 20: Paraver view adjustment: View Event Flags

- Show Info Panel: This will show an information panel. In the tab "Colors" we can see the legend of the colors shown in the view.
 - Right click on the trace window
 - Check the Info Panel option
 - Select the Colors tab in the panel
- Zoom: In order to understand a trace view better, sometimes it's a worth thing to zoom into it a little.
 - Select a region in the trace window to see that region in detail
 - And repeat the previous step as many times as needed
 - The undo-zoom option is in the right click panel




Figure 21: Paraver view adjustment: Show info panel




Figure 22: Paraver view adjustment: Zoom configuration




Figure 23: Paraver view adjustment: Zoom configuration

4.3.4 Trace Interpretation

In this section we will explain how to interpret a trace view once it has been adjusted as described in the previous section.

• The trace view has in its horizontal axis the execution time and in the vertical axis

one line for the master at the top, and below it, one line for each of the workers.

- In a line, the light blue color means idle state, in the sense that there is no event at that time.
- Whenever an event starts or ends a flag is shown.
- In the middle of an event, the line shows a different color. Colors are assigned depending on the event type.
- In the info panel the legend of assigned color to event type is provided.




Figure 24: Trace interpretation

4.3.5 Trace Analysis

In this section, we will give some tips to analyse a COMPSs trace from two different points of view: graphically and numerically.

4.3.5.1 Graphical Analysis

The main concept is that computational events, the task events in this case, must be well distributed among all workers to have a good parallelism, and the duration of task events should be also balanced, this means, the duration of computational bursts.

In the previous trace view, all the tasks of type "hmmpfam" in dark blue appear to be well distributed among the four workers, each worker executes four "hmmpfam" tasks.

But some workers finish earlier than the others, worker 1.2.3 finish the first and worker 1.2.1 the last. So there is an imbalance in the duration of "hmmpfam" tasks. The




Figure 25: Caption.

programmer should analyse then whether all the tasks process the same amount of input data and do the same thing in order to find out the reason of such imbalance.

Another thing to highlight is that tasks of type "scoreRatingSameDB" are not equal distributed among all the workers. There are workers that execute more tasks of this type than the others. To understand better what happens here, let's take a look to the execution graph and also zoom in the last part of the trace.




Figure 26: Caption.

There is only one task of type "scoreRatingSameSeq". This task appears in red in the trace (and in light-green in the graph). With the help of the graph we see that the




Figure 27: Caption.

"scoreRatingSameSeq" task has dependences on tasks of type "scoreRatingSameDB", in white (or yellow).

When the last task of type "hmmpfam" (in dark blue) ends, the last dependences are solved, and if we look at the graph, this means going across a path of three dependences of type "scoreRatingSameDB" (in yellow). And because of these are sequential dependences (one depends on the previous) no more than a worker can be used at the same time to execute the tasks. This is the reason of why the last three task of type "scoreRatingSameDB" (in white) are executed in worker 1.2.1 sequentially.

4.3.5.2 Numerical Analysis

Here we show another trace from a different parallel execution of the Hmmer program.




Figure 28: Caption.

Paraver offers the possibility of having different histograms of the trace events. For it just click the "New Histogram" button in the main window and accept the default options in the "New Histogram" window that will appear.



Figure 29: Paraver Menu - New Histogram

After that, the following table is shown. In this case for each worker, the time spent executing each type of task is shown. Task names appear in the same color than in the trace view. The color of a cell in a row corresponding to a worker goes in a scale from a

light-green for lower values to a dark-blue for higher ones. This conforms a color based histogram.

	hmmpfam	scoreRatingSameDB	scoreRatingSameSeq	0
THREAD 1.1.1	174	·-	-	
THREAD 1.2.1	99,150.88 ms	573.96 ms		
THREAD 1.2.2	98,464.85 ms	1,222.91 ms	-	
THREAD 1.2.3	95,356.19 ms	4,384.48 ms		
THREAD 1.2.4	99,477.27 ms	1,055.47 ms	735.85 ms	
Total	392,449.19 ms	7,236.83 ms	735.85 ms	=
Average	98,112.30 ms	1,809.21 ms	735.85 ms	
Maximum	99,477.27 ms	4,384.48 ms	735.85 ms	
Minimum	95,356.19 ms	573.96 ms	735.85 ms	
StDev	1,632.65 ms	1,505.80 ms	0 ms	
Avg/Max	0.99	0.41	1	

Figure 30: Hmmpfam histogram

The previous table also gives, at the end of each column, some extra statistical information for each type of tasks (as the total, average, maximum or minimum values, etc.).

In the window properties of the main window we can change the semantic of the statistics to see other factors rather than the time, for example, the number of bursts.




Figure 31: Paraver histogram options menu

In the same way as before, the following table shows for each worker the number of bursts for each type of task, this is, the number or tasks executed of each type. Notice the gradient scale from light-green to dark-blue changes with the new values.



Figure 32: Hmmpfam histogram with the number of bursts

4.3.6 Other Trace examples

To end this section, let's present some other examples of COMPSs traces. COMPSs traces can be much complex as the number of workers or tasks grows. Just to illustrate this, the following pictures show traces with a greater number of workers and tasks.




Figure 33: Examples of complex traces

4.4 COMPSs IDE

COMPSs IDE is an Integrated Development Environment to develop, compile, deploy and execute COMPSs applications. It is available through the *Eclipse Market* as a plugin and provides an even easier way to work with COMPSs.

For further information please check the $COMPSs\ IDE\ User\ Guide$ available at our webpage: http://compss.bsc.es .

5 Common Issues

This section provides answers for the most common issues that users encounter while beginning to execute COMPSs applications. Nevertheless, if your specific issues are not covered through this section, please do not hesitate to contact us at:

support-compss@bsc.es

5.1 How to debug

When the application does not behave as expected the first thing users must do is to run it in **debug** mode. We remember that the runcompss command allows to introduce a -d flag to enable the debug log level.

Once done, application execution will produce the following files:

- runtime.log
- resources.log
- jobs folder

Firstly, users should check the last lines of the runtime.log. If the file-transfers or the tasks are failing an error message will appear in this file. Secondly, if the file-transfers are successfully and the jobs are submitted, users should check the jobs folder and look at the error messages produced inside each job. Users should notice that if there are _RESUBMITTED files something inside the job is failing.

5.2 Tasks are not executed

If the tasks remain in **Blocked** state means that there are no existing resources matching the specific task constraints. This error can be potentially caused by two facts: in one hand, because the resources are not correctly loaded into the runtime and, in the other hand, because the task constraints do not really match with any resource.

In the first case, users should take a look at the *resouces.log* and check that all the resources defined in the *project.xml* file are available for the runtime. In the second case users should re-define the task constraints taking into account the resources capabilities defined into the *resources.xml* and *project.xml* files.

5.3 Jobs sistematically fail

If all the application tasks fail because all the submited jobs fail, it is probably due to the fact that there is a resource missconfiguration. In most of the cases, the resource that the application is trying to access has no passwordless access through the configured user. Users can try if this is their case by executing the following steps:

• Open the project.xml that the application is using. Remember that the default file is stored under /opt/COMPSs/Runtime/configuration/xml/projects/project.xml

- For each resource annotate its name and the value inside the *User* tag. Remember that if there is no *User* tag COMPSs will try to connect this resource with the same username than the one that launches the main application.
- For each annotated resourceName user please try *ssh user@resourceName*. If the connection asks for a password then there has been a passwordless missconfiguration.

If there has been a passwordless missconfiguration you can solve it by running the following commands:

```
compss@bsc:~$ scp ~/.ssh/id_dsa.pub user@resourceName:./mydsa.pub
compss@bsc:~$ ssh user@resourceName "cat mydsa.pub >> ~/.ssh/authorized_keys; rm ./mydsa.
    pub"
```

These commands are a quick solution, for further details please check the *Additional Configuration* section inside the *COMPSs Installation Manual* available at our website http://compss.bsc.es.

5.4 Compilation error: @Method not found

When trying to compile java applications users get some of the following compilation errors:

```
error: package integratedtoolkit.types.annotations does not exist
import integrated toolkit.types.annotations.Constraints;
error: package integrated toolkit.types.annotations does not exist
import integratedtoolkit.types.annotations.Method;
error: package integrated toolkit.types.annotations does not exist
import integratedtoolkit.types.annotations.Parameter;
error: package integratedtoolkit.types.annotations.Parameter does not exist
{\tt import\ integrated toolk it.types.annotations.Parameter.Direction;}
error: package integratedtoolkit.types.annotations.Parameter does not exist
import integratedtoolkit.types.annotations.Parameter.Type;
error: cannot find symbol
@Parameter(type = Type.FILE, direction = Direction.INOUT)
 symbol: class Parameter
 location: interface APPLICATION_Itf
error: cannot find symbol
@Constraints(processorCoreCount = 2)
 symbol: class Constraints
 location: interface APPLICATION_Itf
error: cannot find symbol
@Method(declaringClass = "application.ApplicationImpl")
 symbol: class Method
 location: interface APPLICATION_Itf
```

All these errors are raised because the *compss-engine.jar* is not available in the CLASS-PATH. The default COMPSs installation automatically inserts this package into the CLASSPATH but some users may have overwriten or deleted it. Please check that your environment variable CLASSPATH containts the *compss-engine.jar* location by running the following command:

```
$ echo $CLASSPATH | grep compss-engine
```

If the result of the previous command is empty it means that you are missing the *compss-engine.jar* package in your classpath.

The easiest solution comes up by manually exporting the CLASSPATH variable into the user session:

```
$ export CLASSPATH=$CLASSPATH:/opt/COMPSs/Runtime/compss-engine.jar
```

However, you will need to remember to export this variable every time you log out and back in again. Consequently, we recomend to add this export to the *.bashrc* file:

```
$ echo "# COMPSs variables for Java compilation" >> ~/.bashrc
$ echo "export CLASSPATH=$CLASSPATH:/opt/COMPSs/Runtime/compss-engine.jar" >> ~/.bashrc
```

Attention: The *compss-engine.jar* is installed inside the COMPSs installation directory. If you have performed a custom installation, the path of the package may be different.

Please find more details on the COMPSs framework at

http://compss.bsc.es