ENGG1003 - Tuesday Week 2

Calculating Pi C Arithmetic Datatypes

Brenton Schulz

University of Newcastle

February 27, 2019



Before we start...

- ► Today's lecture is information overload
 - It is a long list of "stuff" to rote learn
 - Half of programming is just "playing with Lego" with this "stuff"
 - There is a lot to learn before we can solve interesting problems
- It will probably push you out of your comfort zone
- Lab experience will rebuild your confidence
 - Much of this content will be used in every lab
- But first, a problem for motivation...



Case Study: Calulating π


- Computers are really good at repetitive things
- Lets use this fact to calculate π using a "monte-carlo" method
 - Informally, these are methods which solve problems by repeating the same thing with different inputs until patterns emerge
 - It could repeat millions or billions of times
 - Name comes from the Monaco Principality's high concentration of casinos
- Algorithm pseudocode will be written before an implementation in C



Case Study: Calulating π


Consider a quadrant of a unit circle (r = 1) with a square around it:

- Area of the square $A_1 = 1$
- Area of the circle quadrant $A_2 = \frac{\pi r^2}{4} = \frac{\pi}{4}$
- ▶ Ratio of areas $\frac{A_2}{A_1} = \frac{\pi}{4}$
- ► Therefore $\pi = 4 \times \frac{A2}{A1}$



Case Study: Calulating π

- We can't calculate the area ratio without knowing π
- Estimate it by:
 - Randomly picking many points inside the square
 - Test if the point is inside the circle with $x^2 + y^2 < 1$



 $\pi \approx 4 \times \frac{\text{Number of points which land inside circle}}{\text{Total number of points tested}} = 4 \times \frac{9}{12} = 3$

- How can the above mathematics be turned into an algorithm?
 - ▶ NB: You only have to understand the algorithm
- The algorithm needs to repeat the same thing multiple times
 - This implies use of a loop
 - ▶ The loop's *exit condition* needs to be defined
- As the loop repeats, we need to keep track of the following variables:
 - ▶ The number of points tested
 - ► The number of points which landed inside the circle
 - ▶ The (x,y) coordinates of the point under test



- ► The number of points tested will be an integer, we will call it countTotal
- The number of points found to be inside the circle is also an integer, we will call it countInside
- Before these variables are used they should be initialised
 - ▶ ie: The algorithm will explicitly include countTotal = 0 and countInside = 0
 - So-called uninitialised variables have undefined (or random) values



- Incrementing the countInside variable is conditional on the values of x and y
 - ► This implies IF...ENDIF flow control
- The condition on incrementing countInside is $x^2 + y^2 < 1$
- Incrementing a variable in pseudocode takes the form:
 - variable = variable + 1
 - This can be read as "variable becomes variable plus 1"
 - Maths people would write: $x_{n+1} = x_n + 1$



- The point under test needs two "real" variables: x and y
 - "Real" comes from mathematics: any number with integer and fractional components. Eg: 1.45
- These values take new random values each loop
- The pseudocode doesn't need to describe how a random number is generated
 - Stating: "x = a random number between
 0 and 1" is totally acceptable
- At the end of the algorithm the final step will be $\pi=4 \times \frac{\text{countInside}}{\text{countTotal}}$



```
BEGIN
  integer countTotal = 0
  integer countInside = 0
  WHILE countTotal < A large number
    x = random number between 0 and 1
    v = random number between 0 and 1
    countTotal = countTotal + 1
    IF x*x + y*y < 1
      countInside = countInside + 1
    ENDIF
  ENDWHILE
  pi = 4*countInside/countTotal
  PRINT pi
END
```

Missing Knowledge for C Implementation

- More information about arithmetic
 - ► Relational operators (less/greater-than) look useful
 - Is there a neat way to do count=count+1?
 - countInside and countTotal are both integers. What happens when we divide?
- Datatypes and how they are handled in arithmetic statements
- ▶ How do we generate random numbers?
- Syntax for WHILE loops and IF statements



- Basic arithmetic was seen in the lab
 - ► You all did the lab, right?

Operation	C Symbol
Addition	+
Subtraction	_
Multiplication	*
Division	/

Table: Basic arithmetic operators in C

 Complex expressions can be built from these operators and parentheses

Examples:

$$z=x^2+5(y+b)$$
 $z=x*x+5*(y+b);$ $u=\frac{x+1}{x-1}$ $u=(x+1)/(x-1);$ $v=z^3+\frac{5(y+b)}{2}$ $v=z*z*z+(5*(y+b))/2;$

- Multiplication is not assumed. If you write 5 (y+b) the compiler will generate a syntax error.
- ➤ To be valid C expressions the semicolon is required.



- C supports two time-saving unary operators:
 - Very useful in loops.

Operation	C Syntax	Replaces		
Increment	x++; or ++x;	x = x + 1;		
Decrement	x; orx;	x = x - 1;		

It also supports the following shorthand syntax:

What's the difference between x++ and ++x?

- x++ is a post-increment
- ++x is a pre-increment
- ▶ If they appear in an arithmetic expression, pre-increment is processed before the variable is used and post-increment is processed after it is used.
- ▶ In isolation there is no difference



Increment Example

```
#include <stdio.h>
int main() {
  int x = 0;
  int y = 0;
  int z = 0;
  y = ++x + 10;
  printf("Pre-increment: %d\n", y);
  y = z++ + 10;
  printf("Post-increment: %d\n", y);
  return 0;
}
```

Listing 1: increment.c

Pre/post-inc/decrements have many applications, more details in coming weeks.

Modulus

- Integer division ignores (truncates) any fractional component
- ► The modulus operator provides the remainder after division
 - ► C uses the % character
 - "a % b" means "remainder of a / b"
- **Example:**
 - **▶** 10 / 3 = 3
 - ▶ 10 % 3 = 1



Modulus Example 1 - Printing Every *nth* Loop

```
1 #include <stdio.h>
2 int main() {
  int x = 0;
   while (x < 1000)
5
      // Presumably something useful is done with x
6
      // inside this loop
7
      if(x%100 == 0)
8
        printf("%d\n", x);
9
    }
11
    return 0;
12 }
```

Listing 2: loopmod.c

Modulus Example 2 - Factor Testing

```
1 #include <stdio.h>
2 int main() {
    int x, y;
    printf("Enter an integer: ");
    scanf("%d", &x);
5
    printf("Enter another integer: ");
    scanf("%d", &y);
7
    if(x % y == 0) { // ie: if the remainder is zero}
8
      printf("%d is a factor of %d\n", y, x);
9
    } else {
10
      printf("%d is NOT a factor of %d\n", y, x);
    return 0;
13
14 }
```

Listing 3: factorTest.c

Modulus Example 3 - Finding Factors

```
#include <stdio.h>
2 int main() {
    int input, x;
    printf("Enter an integer to factorise: ");
    scanf("%d", &input);
5
    x = input;
    while (x > 0) {
7
      if (input % x == 0) // ie: if the remainder is
8
     zero
        printf("%d is a factor of %d\n", x, input);
9
      x--;
10
    return 0;
12
13 }
```

Listing 4: factors.c

Relational Operators

C supports six relational operators:

Operation	C Symbol
Less than	<
Less than or equal to	<=
Greater than	>
Greater than or equal to	>=
Equal to	==
Not equal to	! =

Relational Operators

- ▶ The result of a relational operation is 0 or 1
 - C treats 0 as Boolean FALSE and non-zero as TRUE
- They are typically used as flow control conditions
 - ▶ if(condition) {statements}
 - ▶ while (condition) {statements}
- While we're here: the above is the correct syntax for IF and WHILE flow control in C



Boolean Operators

- We discussed Boolean algebra last week
- It has three operators: AND, OR, NOT
- In C, these are implemented with:

Operator	C Characters
AND	& &
OR	
NOT	!

- I know the | character as a "pipe" symbol or "vertical slash"
 - Ask your demonstrator to find it on the keyboard

Conditions

- We have seen that if() and while() statements need conditions
- A condition can be any combination of variables, operators, and literals (numbers, defined later)
- The following are all valid:
 - \rightarrow if (x > 29)
 - \rightarrow if (x == 2)
 - ightharpoonup if (! (x == y))
 - \triangleright if ((x > 5) && (x < 20))
 - \triangleright if (x = y + z)
 - Evaluates (y + z), assigns to x, uses result as if() condition.

C Arithmetic Operator Precedence

- C has an "order of operations"
- ▶ eg: 1+5 * 2 evaluates to 11
 - ► You remember BODMAS / PEDMAS, right?
- Multiplication and division first
- Addition and subtraction second
- Relational operators somewhere below that
- If in doubt: force order with parentheses
 - This makes the code more readable
 - It doesn't cost you anything
 - C compilers understand algebra and will optimise inefficient expressions automatically



Variable Declaration

- In C, all variables are declared before use
- Declaration specifies the variable's:
 - Datatype
 - Name
 - An initialisation value (optional)
 - Always assume uninitialised variables have random values! Behaviour varies between compilers and target platforms.
 - eg: int counter = 0;
 - ► Type is int
 - ▶ Name is counter
 - Initial value is 0 (optional)
- C is a "strongly-typed" language
 - Every variable has a fixed type



Variable Naming Rules

- Variable names:
 - Are case sensitive
 - Must not be a C keywoard (eg: int, char, while, etc)
 - ► Must **not** contain special characters (*-+/, etc)
 - Must begin with a letter
 - Can contain numbers
 - Can contain underscores
- What you do with those rules is up to you
- Modern practice encourages:
 - camelCaseVariableNames
 - names_with_underscores



Diversion: Binary Nomenclature

- ► The value range is a result of the underlying binary storage mechanism
- A single binary digit is called a bit
- ► There are 8 bits in a *byte*
- In programming we use the "power of two" definitions of kB, MB, etc:
 - ▶ 1 kilobyte is $2^{10} = 1024$ bytes
 - ▶ 1 Megabyte is $2^{20} = 1048576$ bytes
 - ▶ 1 Gigabyte is $2^{30} = 1073741824$ bytes
 - ► (Advanced) These numbers look better in hex: 0x3FF, 0xFFFFF, etc.



Diversion: Binary Nomenclature

- Observe that kilobyte, Megabyte, Gigabyte, etc use scientific prefixes
- ▶ These *normally* mean a power of 10:
 - ightharpoonup kilo- = 10^3
 - Mega- $= 10^6$
 - Giga- $= 10^9$
 - ...etc (see the inside cover of a physics text)
- Computer science stole these terms and re-defined them



Diversion: Binary Nomenclature

- This has made some people illogically angry
- Instead, we can use a more modern standard:
 - $ightharpoonup 2^{10}$ bytes = 1 kibiByte (KiB)
 - $ightharpoonup 2^{20}$ bytes = 1 Mebibyte (MiB)
 - \triangleright 2³⁰ bytes = 1 Gibibyte (GiB)
 - ...etc
- Generally speaking, KB (etc) implies:
 - powers of two to engineers
 - powers of ten to marketing
 - The number is smaller
 - ► Hard drive manufacturers, ISPs, etc like this



Integer Data Types

- There are several integer data types
- They vary by their:
 - Size
 - Support for negative numbers
- C integer types can be 1, 2, 4, or 8 bytes long
 - int and long sizes vary by platform
 - Larger sizes store larger numbers, use more RAM
- Each type can be signed or unsigned
 - Unsigned numbers are always positive but you get double the value range



Integer Data Types

- ► The integer data type ranges can be calculated from the data type's size in bits
- ► For unsigned numbers of bit length *n*:

$$\max = 2^n - 1 \tag{1}$$

For signed numbers of bit length *n*:

$$\max = 2^{(n-1)} - 1 \tag{2}$$

$$\min = -2^{(n-1)} \tag{3}$$

Signed numbers are stored in two's complement format, covered in ELEC1710

Integer Data Types

- C includes the sizeof() expression so that a program can discover the size of a data type on a given platform
- On a modern 64-bit Linux desktop machine:

Type	Bytes	Bits	Value Range
char	1	8	-128, +127
short	2	16	-32768, 32767
int	4	32	-2147483648, 2147483647
long	8	64	-9223372036854775808,

Unsigned Integers

- Unsigned integers are always positive
- They are the same size as their signed counterparts
- ► The unsigned keyword placed before the data type makes that variable unsigned
- eg: unsigned char is 1 byte and has a value range of 0 to 255

Unambiguous Integer Data Types

- Because the standard int and long data types don't have fixed size unambiguous types exist
- Under OnlineGDB (ie: Linux with gcc) these are defined in stdint.h (#include it)
- You will see them used commonly in embedded systems programming (eg: Arduino code)
- ▶ The types are:
 - ▶ int8_t
 - ▶ uint8_t
 - ▶ int16 t
 - ...etc



Why Care About Data Types?

- You may be thinking "why not make everything a long?"
- Answer: speed and memory
- Smaller types use less RAM
- Arithmetic on a type larger than the target platform's native size is slow
- Matters if you store millions of the same type
- Makes a huge difference on embedded targets
 - Don't declare 32-bit variables on an 8-bit AVR microcontroller unless you have to



Overflow

- Overflow occurs when the result of a calculation is too big to fit into the target type
- \triangleright Example: 127 + 1 = -128

```
1 #include <stdio.h>
2 int main() {
3    char x = 127;
4    printf("%d\n", x);
5    x++;
6    printf("%d\n", x);
7    return 0;
8 }
```

Listing 5: overflow.c

Overflow

- Message: make variables as small you can, but no smaller
 - Or just use long everywhere are cop the performance hit
- Quite often you need to take a guess at how big a variable needs to be
- Typically a good idea to document software limits due to variable choice



Floating Point Data Types

- To store real numbers C has several floating point data types
- As with integers, try to use the smallest you can get away with
- Quad precision (__float128) is supported in gcc but very slow
 - Not used in this course
- Run benchmark demonstration

Type	Size	Range	Precision
float	4	$1.2 \times 10^{-38} \text{ to } 3.4 \times 10^{38}$	6 dp
double	8	2.3×10^{-308} to 1.7×10^{308}	15 dp



Floating Point Problems

- Q: Why not always use float or double?
- A: Floating point arithmetic is NOT exact
- Example 1: Does this code exit?

```
1 #include <stdio.h>
2 int main() {
3   float x = 16000000.0;
4   while(x < 17000000.0) {
5      x = x + 1.0;
6      printf("%f\n", x);
7   }
8 }</pre>
```

Listing 6: floatLoop.c

Floating Point Problems

- **Example** 2: $tan\left(\frac{\pi}{2}\right)$ is undefined
- ▶ But using floating point π can't be represented exactly, so C produces a result anyway

```
#include <stdio.h>
#include <math.h>
int main() {
   double pi = 3.141592653589793238;
   printf("%f\n", tan(pi/2.0));
   printf("%f\n", ftanf((float)pi/2.0));
}
```

Listing 7: taninf.c

Literals

- ► A *literal* is any number written in the code
- ▶ Why not "constant"?
 - That word means something different
- Examples:
 - \triangleright x = 5; // 5 is a literal int
 - \triangleright y = 2.0 / z; // 2.0 is a literal double
- By default:
 - An integer literal is stored as an int data type
 - ▶ ie: has the value range and arithmetic limits of int
 - ▶ A floating point literal is stored as double



Literals

- Integer literals can be in:
 - Decimal: 123
 - ► Hexadecimal: 0xA34 // Zero-x
 - ▶ Octal: 0125 // Capital letter 0
 - (Hex and octal are covered in ELEC1710)
- Integer literals can be specified as unsigned with the u suffix:
 - 93811
- They can also be declared long with the l suffix:
 - > 37264841
 - The compiler will issue a warning if a literal is too big for int



Literals

- Floating point literals can be written in many ways:
 - ▶ 1.0f // f suffix forces float
 - ▶ (float)2.3 // Forces float
 - ▶ 1.0 // Default to double
 - ▶ 1e2 // Double, 1 times 10^2
- 1e2 is known as "e-notation"
 - \triangleright XeY = X × 10^{Y}
 - ▶ I will use it all the time
- Forcing literals to float is frequently necessary in embedded systems which lack double precision hardware



Mixing Data Types

- C supports arithmetic between different types
- Changing a data type is called casting
- When types are mixed two things can happen:
 - Types get upgraded automatically (implicit type casting)
 - ▶ Upgrade path is roughly: short/char int long - long long - float - double
 - Types get specified manually by the programmer (explicit type casting)



Explicit Type Casting

- ► The data type of a variable (or literal) can be forced to change using type casting
- Write the desired type in parentheses before the variable or constant
- Examples:

```
\triangleright x = (float)y / k;
```

```
\triangleright y = (unsigned int)y + 32;
```

Format Specifiers

- A format specifier controls how printf(); converts numerical (or textual) data to a series of ASCII characters
- Full details are complex, for now just use:
 - %d for integer types
 - %f for "fixed decimal place" floating point
 - %e for e-notation floating point
 - Cast inside printf() to suppress compiler warnings



Format Specifiers

Casting example:

```
long i;
// ...
printf("%d\n", (int)i); //Breaks when i>2^31
```

- %.df produces d decimal places of precision
 - eg:

```
1 float x = 1.23456;
2 printf("%.2f", x); // Prints 1.23
```

Integer Division Example

With all that out of the way, what is the output of each printf() statement?

```
1 #include <stdio.h>
2 int main() {
3    printf("%d\n", 9/10);
4    printf("%f\n", 9/10);
5    printf("%f\n", 9.0/10);
6    printf("%f\n", 9/10.0);
7    printf("%f\n", (float) 9/10);
8    return 0;
9 }
```

Listing 8: intdiv.c

- ► In C there is a *standard library function* which generates random numbers
- We will study functions in more detail later
- To use a library function:
 - Read the function's documentation
 - #include the correct header file
 - ► Take note of the return value data type
 - ► Add any *compiler flags* (beyond ENGG1003)
 - Use the function in your code
- Demonstration: read the rand() man page
 - Click here



▶ Observe that rand(); requires

```
#include <stdlib.h>
```

- ▶ Observe that it returns an int between 0 and RAND_MAX which, in gcc, is $2^{31} 1$
- Note that is has <u>limits</u> (advanced discussion, beyond ENGG1003)
- ► For us, using the % operator:

```
x = rand() % (RANGE+1);
```

produces a *good enough* random number between zero and RANGE



Using the above information, we can roll a standard die with:

```
int dieRoll;
dieRoll = rand() % 7;
```

Or, if you're a D&D fan, roll a D20 with:

```
int D20Roll;
2 D20Roll = rand() % 21;
```

- ► RAND_MAX is a constant defined in stdlib.h
- We can try to generate a floating point number from 0 to 1 with a division:

```
float num;
num = rand()/RAND_MAX; // This is broken
```

- Problem: rand() is an integer, RAND_MAX is a (large) integer
 - ► The integer division result will always be zero!
- Solution: use an explicit cast so that a floating point division occurs:

```
double num;
num = (double) rand()/RAND_MAX;
```

Probably out of time by now, lets implement a π calculator in the lab... *In theory* you have enough information by now.