Contents

1	Introduction			3
	1.1	2D Euclidean Space and $U(1)$		3
		1.1.1	Geometric Algebra of Euclidean 2-Space	3
		1.1.2	U(1) as a Geometric Algebra	5
	1.2 3D Euclidean Space and $SU(2)$			6
		1.2.1	Geometric Algebra of Euclidean 2-Space	6
		1.2.2	SU(2) as a Geometric Algebra	7
	1.3	Minko	wski Spacetime	7
2	Derivatives, Integrals, and Geometric Calculus			
	2.1	The G	Geometric Derivative	9
		2.1.1	Euclidean 2-Space	9
		2.1.2	Euclidean 3-Space	10
		2.1.3	Minkowski Spacetime	10
	2.2	Cauch	y's Integral Theorem and Formula	10
3	Yang-Mills Theories		11	
4	Fey	nman	Path Integrals	13

2 CONTENTS

Introduction

The objects of a geometric algebra are called *multivectors*. Multivectors generalize objects like directed lines, planes, and volumes. An important property of multivectors is they have *orientation*, i.e., a sense of up/down, inside/outside, etc. The following sections introduce examples of geometric algebras and the operations on their multivectors.

1.1 2D Euclidean Space and U(1)

1.1.1 Geometric Algebra of Euclidean 2-Space

Multivectors are composed of *basis one-vectors*. In Euclidean 2-space, these are unit factors along the positive x and y axes. They are denoted by e_1 and e_2 , respectively (the use of e here is shorthand for Euclidean. Different symbols may be used for bases in other algebras, as will be seen later).

The most important operation between multivectors is the geometric product. If a and b are multivectors, the geometric product of a and b is written ab. The geometric product is the sum of two simpler products, the dot (inner) and wedge (outer) products. In Euclidean 2-space, these are equivalent to the familiar dot and cross products of vector algebra. The dot product of a and b is written $a \cdot b$ and the wedge product is written $a \wedge b$. The geometric product, then, is written

$$ab = a \cdot b + a \wedge b.$$

The inner products of basis one-vectors amongst themselves defines the signature

of an algebra,

$$e_1 \cdot e_1 = 1$$

$$e_2 \cdot e_2 = 1$$

$$e_1 \cdot e_2 = 0$$

Basis one-vectors represent directed unit lines. An oriented plane can be made by wedging the one-vectors together to form a basis *bivector*.

$$e_1 \wedge e_2 = x$$
- y plane, counterclockwise orientation $e_1 \wedge e_1 = 0$ $e_2 \wedge e_2 = 0$

The plane can be flipped by reversing the wedge product.

$$e_2 \wedge e_1 = -e_1 \wedge e_2 = x$$
-y plane, clockwise orientation

More generally, dot products are symmetric and wedge products are antisymmetric

$$\frac{1}{2}(ab+ba) = \frac{1}{2}(a \cdot b + a \wedge b + b \cdot a + b \wedge a) = a \cdot b,$$
$$\frac{1}{2}(ab-ba) = \frac{1}{2}(a \cdot b + a \wedge b - b \cdot a - b \wedge a) = a \wedge b.$$

Since unit vectors are orthogonal,

$$\begin{aligned} e_i e_j &= e_i \cdot e_j + e_i \wedge e_j = 1 \\ e_i e_j &= e_i \cdot e_j + e_i \wedge e_j = e_i \wedge e_j \end{aligned} \qquad (i = j)$$

explicit dots and wedges are unnecessary when writing basis vectors. We simply write e_1e_2 instead of $e_1 \wedge e_2$.

The basis vector formed by multiplying all basis one-vectors is called the *unit* pseudoscalar and is denoted by I. In 2-space, $I = e_1 e_2$. This is in direct analogy to $i = \sqrt{-1}$ from complex numbers, as shown below.

A basis zero-vector is a scalar.

A general multivector m in Euclidean 2-space is a linear combination of basis vectors,

$$m = s + a_1 e_1 + a_2 e_2 + b e_1 e_2.$$

The following formula is seldom used¹, but for completeness, the product of two general multivectors,

$$m = s + a_1e_1 + a_2e_2 + be_1e_2,$$

 $n = r + c_1e_1 + c_2e_2 + de_1e_2$

 $^{^1{\}rm One}$ application is coding computer algebra systems.

is

$$mn = (rs + a_1b_1 + a_2b_2 - bd)$$

$$+ (ra_1 + sc_1 - a_2d + c_2b)e_1$$

$$+ (ra_2 + sc_2 + a_1d - c_1b)e_2$$

$$+ (a_1c_2 - a_2c_1)e_1e_2.$$

Often, we'll be interested in *even* multivectors, i.e., linear combinations of zero-vectors, bivectors, four-vectors, etc. The product of even multivectors

$$m = a + be_1e_2 = a + bI,$$

 $n = c + de_1e_2 = c + dI$

is

$$mn = (ac - bd) + (ad + bc)I.$$

The correspondence to complex numbers is clear. From this perspective, the i from complex algebra can be thought of as a counterclockwise-oriented plane.

Unit psuedoscalars satisfy $I^2 = -1$. For this, we define the *reverse* operator on multivectors, which reverses the order of basis vectors. The reverse of I is

$$\tilde{I} = e_3 e_2 e_1 = -I.$$

The square of a multivector is defined by multiplying a multivector by its reverse. For example,

$$I^2 = \tilde{I}I = e_3e_2e_1(e_1e_2e_3) = -1.$$

We can use I to compute the dual of a multivector simply by multiplying. The dual M of a multivector m is

$$M = Im$$
.

For example,

$$Ie_2 = (e_1e_2)e_2 = e_1.$$

If m spans a subspace of Euclidean 2-space, its dual spans the remaining subspace needed to fill out 2-space. This is the same as the orthogonal complement in linear algebra.

1.1.2 U(1) as a Geometric Algebra

In later chapters, we'll discuss the implications of symmetries in field theories. Some of these symmetries will involve unitary groups, so we show how unitary groups can be represented with geometric algebras.

Unitary groups U(n) are groups of $n \times n$ unitary matrices, i.e., matrices U where $U^{\dagger}U = I$. For n = 1, this is the group of unit complex numbers. As shown above, this group equivalent to the group of even multivectors in Euclidean 2-space of unit magnitude.

1.2 3D Euclidean Space and SU(2)

1.2.1 Geometric Algebra of Euclidean 2-Space

Multivectors are composed of basis 1-vectors. In three-dimensional Euclidean space, these are unit factors along the positive x, y, and z axes. They are denoted by e_1 , e_2 , and e_3 , respectively (the use of e is shorthand for Euclidean. Different symbols will be used for bases in other algebras).

The most important operation between multivectors is the geometric product. If a and b are multivectors, the geometric product of a and b is written ab. The geometric product is the sum of two simpler products, the dot (inner) and wedge (outer) products. In three-dimensional Euclidean space, these are equivalent to the familiar dot and cross products of vector algebra. The dot product of a and b is written $a \cdot b$ and the wedge product is written $a \wedge b$. The geometric product, then, is written

$$ab = a \cdot b + a \wedge b$$
.

The inner products of basis one-vectors amongst themselves defines the *signature* of an algebra. In Euclidean 3-space, the basis vectors are *orthogonal*,

$$e_1 \cdot e_1 = 1$$

 $e_2 \cdot e_2 = 1$
 $e_3 \cdot e_3 = 1$
 $e_1 \cdot e_2 = 0$
 $e_2 \cdot e_3 = 0$
 $e_3 \cdot e_2 = 0$.

Basis one-vectors represent directed unit lines. Directed planes can be made by wedging one-vectors together to form basis *bivectors*.

$$e_1 \wedge e_2 = x$$
-y plane, normal along $+z$
 $e_2 \wedge e_3 = y$ -z plane, normal along $+x$
 $e_3 \wedge e_1 = z$ -x plane, normal along $+y$
 $e_1 \wedge e_1 = 0$
 $e_2 \wedge e_2 = 0$
 $e_3 \wedge e_2 = 0$

Planes can be flipped by reversing the wedge product.

$$e_2 \wedge e_1 = -e_1 \wedge e_2 = x$$
-y plane, normal along $-z$
 $e_3 \wedge e_2 = -e_2 \wedge e_3 = y$ -z plane, normal along $-x$
 $e_1 \wedge e_3 = -e_3 \wedge e_1 = z$ -x plane, normal along $-y$.

7

Since unit vectors are orthogonal,

$$\begin{aligned} e_i e_j &= e_i \cdot e_j + e_i \wedge e_j = 1 \\ e_i e_j &= e_i \cdot e_j + e_i \wedge e_j = e_i \wedge e_j \end{aligned} \qquad (i = j)$$

explicit dots and wedges are unnecessary when writing basis vectors, e.g., we simply write e_1e_2 instead of $e_1 \wedge e_2$.

The unit volume is the wedge product of all three basis one-vectors,

$$e_1e_2e_3=e_1\wedge e_2\wedge e_3.$$

As with bivectors, permuting the order of vectors in the product changes orientation. Every swap changes the orientation by a minus sign,

$$e_1e_2e_3 = -e_1e_3e_2 = -e_2e_1e_3 = e_2e_3e_1 = -e_3e_2e_1 = e_3e_1e_2.$$

A general multivector m in Euclidean 3-space is a scalar plus a linear combination of basis vectors,

$$m = s + a_1e_1 + a_2e_2 + a_3e_3 + b_1e_2e_3 + b_2e_3e_1 + b_3e_1e_2 + ce_1e_2e_3.$$

1.2.2 SU(2) as a Geometric Algebra

1.3 Minkowski Spacetime

Derivatives, Integrals, and Geometric Calculus

2.1 The Geometric Derivative

Geometric Algebra is extended to Geometric Calculus by adding geometric derivatives and integrals. The geometric derivative is denoted by ∇ and acts on multivector-valued functions over a given domain. In summation notation, the geometric derivative of a function F is:

$$\nabla F(x) = e_i \partial_i F(x) .$$

The following sections demonstrate the geometric derivative in example spaces.

2.1.1 Euclidean 2-Space

Real-valued Functions

Consider a real-valued function f over x and y in Euclidean 2-space. Its geometric derivative is

$$\nabla f = (\partial_x f) e_1 + (\partial_y f) e_2,$$

i.e., the geometric derivative of a real-valued function is its gradient.

10CHAPTER 2. DERIVATIVES, INTEGRALS, AND GEOMETRIC CALCULUS

Vector-valued Functions

Now consider a vector-valued function $g(x,y) = u(x,y)e_1 + v(x,y)e_2$. It's derivative is

$$\nabla g = (e_1 \partial_x + e_2 \partial_y) (ue_1 + ve_2)$$
$$= (\partial_x u + \partial_y v) + (\partial_x v - \partial_y u) e_1 e_2,$$

i.e., the derivative of a vector-valued function in Euclidean 2-space is the complex derivative. From this example, we see that geometric derivatives have inner and outer products,

$$\nabla F = \nabla \cdot F + \nabla \wedge F.$$

The geometric derivative contains both divergence and curl from traditional vector calculus.

2.1.2 Euclidean 3-Space

Real-valued Functions

The geometric derivative acting on a real-valued function f in 3-space is

$$\nabla f = (\partial_x f) e_1 + (\partial_y f) e_2 + (\partial_z f) e_3.$$

Again, this is simply the gradient of f.

Vector-valued Functions

2.1.3 Minkowski Spacetime

2.2 Cauchy's Integral Theorem and Formula

Yang-Mills Theories

Feynman Path Integrals