Analysis of a GRTS Survey Design for an Area Resource

Thomas Kincaid

September 20, 2013

Contents

1	Freimmaries	1
2	Read the survey design and analytical variables data file	2
3	Analysis of site status evaluation variables	5
4	Analysis of estuary condition variables	8
5	Analysis of estuary condition variables correcting for population size	9
6	Analysis of quantitative variables	11

1 Preliminaries

This document presents analysis of a GRTS survey design for an area resource. The area resource used in the analysis is estuaries in South Carolina. Although a stratified survey design was used to sample estuaries, analyses will be conducted as if the design was unstratified. Instead, strata will be used to define subpopulations for analysis. The strata employed in the survey were: (1) open water and (2) tidal creeks. The analysis will include calculation of three types of population estimates: (1) estimation of proportion and size (area of estuaries) for site evaluation status categorical variables; (2) estimation of proportion and size for estuary condition categorical variables; and (3) estimation of the cumulative distribution function (CDF) and percentiles for quantitative variables. Testing for difference between CDFs from subpopulations also will be presented.

The initial step is to use the library function to load the spsurvey package. After the package is loaded, a message is printed to the R console indicating that the spsurvey package was

loaded successfully.

Load the spsurvey package.

```
> # Load the spsurvey package
> library(spsurvey)
>
```

Version 2.5 of the spsurvey package was loaded successfully.

2 Read the survey design and analytical variables data file

The next step is to read the data file, which includes both survey design variables and analytical variables. The read delim function is used to read the tab-delimited file and assign it to a data frame named SC_estuaries. The nrow function is used to determine the number of rows in the SC_estuaries data frame, and the resulting value is assigned to an object named nr. Finally, the initial six lines and the final six lines in the SC_estuaries data frame are printed using the head and tail functions, respectively.

Read the survey design and analytical variables data file.

```
> # Read the data file and determine the number of rows in the file
> SC_estuaries <- read.delim("SC_estuaries.tab")
> nr <- nrow(SC_estuaries)
>
```

Display the initial six lines in the data file.

Good

2

4.6

> # Display the initial six lines in the data file
> head(SC_estuaries)

```
siteID xcoord ycoord
                                  wgt
                                          Stratum Status IBI_score IBI_status
1 EEOW00-001 1549286 1263060 10.47516 Open Water Sampled
                                                                3.5
                                                                          Good
2 EEOW00-002 1487515 1226790 10.47516 Open Water Sampled
                                                                4.0
                                                                          Good
3 EE0W00-003 1442800 1159806 10.47516 Open Water Sampled
                                                                4.0
                                                                          Good
4 EEOW00-004 1425120 1148898 10.47516 Open Water Sampled
                                                                4.5
                                                                          Good
5 EEOW00-005 1432141 1140626 10.47516 Open Water Sampled
                                                                4.5
                                                                          Good
6 EEOW00-006 1540516 1280598 10.47516 Open Water Sampled
                                                                2.5
                                                                          Mrgn
  WQ_score WQ_status
       4.3
1
                Good
```

```
3 5.0 Good
4 5.0 Good
5 5.0 Good
6 4.2 Good
```

>

Display the final six lines in the data file.

- > # Display the final six lines in the data file
- > tail(SC_estuaries)

	siteID	xcoord	ycoord	wgt	St	tratum	Status	IBI_score
130	EETC99-035	1441803	1151432	1.41106	Tidal	Creek	NonTarget	NA
131	EETC99-036	1535415	1247815	1.41106	Tidal	${\tt Creek}$	Sampled	3.5
132	EETC99-037	1500847	1225230	1.41106	Tidal	${\tt Creek}$	Sampled	2.5
133	EETC99-038	1440701	1147436	1.41106	Tidal	${\tt Creek}$	Sampled	3.0
134	EETC99-039	1468472	1179318	1.41106	Tidal	${\tt Creek}$	Sampled	4.0
135	EETC99-040	1430639	1151724	1.41106	Tidal	${\tt Creek}$	Sampled	2.5
	${\tt IBI_status}$	WQ_score	e WQ_stat	cus				
130	<na></na>	NA	/ <1	JA>				
131	Good	4.3	G G	ood				
132	Mrgn	3.0) Po	oor				
133	Good	3.7	r Mı	rgn				
134	Good	4.3	G G	ood				
135	Mrgn	3.7	r Mı	rgn				

>

The location of sample sites in South Carolina estuaries is displayed in Figure 1. The sites for each stratum are displayed using a unique color.




Figure 1: Location of estuaries that were sampled in South Carolina by the U.S. Environmental Protection Agency during the National Lakes Assessment (NLA) conducted in 1999 and 2000.

3 Analysis of site status evaluation variables

The first analysis that will be examined is calculation of extent estimates for a site status evaluation variable. Extent is measured both by the proportion of the resource in status evaluation categories and by size of the resource in each category. For an area resource like estuaries, size refers to the area of estuaries in a category. For calculating extent estimates (and for all of the analyses we will consider), the survey design weights are incorporated into the calculation process. The site status variable named status will be examined, which classifies estuaries into two evaluation categories: "Sampled" and "NonTarget". The table and addmargins functions are used to create tables displaying the count for each code (level) of the status variable.

> addmargins(table(SC_estuaries\$Status))

A table displaying the number of values for each level of the status variable follows:

NonTarget Sampled Sum 19 116 135

The cat.analysis function in the spsurvey package will be used to calculate extent estimates. Four data frames constitute the primary input to the cat.analysis function. The first column (variable) in the four data frames provides the unique identifier (site ID) for each sample site and is used to connect records among the data frames. The siteID variable in the SC_estuaries data frame is assigned to the siteID variable in the data frames. The four data frames that will be created are named as follows: sites, subpop, design, and data.cat. The sites data frame identifies sites to use in the analysis and contains two variables: (1) site ID - site ID values and (2) Use - a logical vector indicating which sites to use in the analysis. The rep (repeat) function is used to assign the value TRUE to each element of the Use variable. Recall that nr is an object containing the number of rows in the SC_estuaries data frame. The subpop data frame defines populations and, optionally, subpopulations for which estimates are desired. Unlike the sites and design data frames, the subpop data frame can contain an arbitrary number of columns. The first variable in the subpop data frame identifies site ID values and each subsequent variable identifies a type of population, where the variable name is used to identify type. A type variable identifies each site with a character value. If the number of unique values for a type variable is greater than one, then the set of values represent subpopulations of that type. When a type variable consists of a single unique value, then the type does not contain subpopulations. For this analysis, the subpop data frame contains three variables: (1) siteID - site ID values, (2) All_Estuaries - which will be used to calculate estimates for all of the sample sites combined, and (3) Estuary_Type - which will be used to calculate estimates for each stratum individually. The stratum variable in the SC_estuaries data frame is assigned to the Estuary_Type variable in the subpop data frame. The design data frame consists of survey design variables. For

the analysis under consideration, the design data frame contains the following variables: (1) siteID - site ID values; (2) wgt - final, adjusted, survey design weights; (3) xcoord - x-coordinates for location; and (4) ycoord - y-coordinates for location. The wgt, xcoord, and ycoord variables in the design data frame are assigned values using variables with the same names in the SC_estuaries data frame. Like the subpop data frame, the data.cat data frame can contain an arbitrary number of columns. The first variable in the data.cat data frame identifies site ID values and each subsequent variable identifies a response variable. The response variable is Status, which is assigned the status variable in the SC_estuaries data frame. Missing data (NA) is allowed for the response variables, which are the only variables in the input data frames for which NA values are allowed.

Create the sites data frame.

```
> sites <- data.frame(siteID=SC_estuaries$siteID,
+ Use=rep(TRUE, nr))</pre>
```

Create the subpop data frame.

```
> subpop <- data.frame(siteID=SC_estuaries$siteID,
+ All_Estuaries=rep("All Estuaries", nr),
+ Estuary_Type=SC_estuaries$Stratum)</pre>
```

Create the design data frame.

Create the data.cat data frame.

Use the cat.analysis function to calculate extent estimates for the site status evaluation variables.

```
> # Calculate extent estimates for the site status evaluation variables
> Extent_Estimates <- cat.analysis(sites, subpop, design, data.cat)
>
```

The extent estimates are displayed using the print function. The object produced by cat.analysis is a data frame containing thirteen columns. The first five columns identify

the population (Type), subpopulation (Subpopulation), response variable (Indicator), levels of the response variable (Category), and number of values in a category (NResp). A category labeled "Total" is included for each combination of population, subpopulation, and response variable. The next four columns in the data frame provide results for the proportion estimates: the proportion estimate (Estimate.P), standard error of the estimate (StdError.P), lower confidence bound (LCB95Pct.P), and upper confidence bound (UCB95Pct.P). Argument conf for cat.analysis allows control of the confidence bound level. The default value for conf is 95, hence the column names for confidence bounds contain the value 95. Supplying a different value to the conf argument will be reflected in the confidence bound names. Confidence bounds are obtained using the standard error and the Normal distribution multiplier corresponding to the confidence level. The final four columns in the data frame provide results for the size (units) estimates: the units estimate (Estimate.U), standard error of the estimate (StdError.U), lower confidence bound (LCB95Pct.U), and upper confidence bound (UCB95Pct.U).

> # Print the extent estimates

> print(Extent_Estimates)

>

```
Category NResp Estimate.P StdError.P
           Type Subpopulation Indicator
1 All_Estuaries All Estuaries
                                  Status NonTarget
                                                       19
                                                             4.885243
                                                                         1.333584
2 All_Estuaries All Estuaries
                                  Status
                                            Sampled
                                                      116
                                                            95.114757
                                                                        1.333584
3 All_Estuaries All Estuaries
                                  Status
                                              Total
                                                      135 100.000000
                                                                        0.000000
  Estuary_Type
                    Open Water
                                  Status NonTarget
                                                         1
                                                             1.666667
                                                                        1.443982
5
                                                       59
  Estuary_Type
                    Open Water
                                  Status
                                            Sampled
                                                            98.333333
                                                                        1.443982
6
  Estuary_Type
                    Open Water
                                  Status
                                              Total
                                                       60 100.000000
                                                                        0.000000
7
  Estuary_Type
                  Tidal Creek
                                  Status NonTarget
                                                       18
                                                            24.000000
                                                                        3.913876
                                            Sampled
                                                            76.000000
  Estuary_Type
                  Tidal Creek
                                  Status
                                                       57
                                                                        3.913876
9
  Estuary_Type
                  Tidal Creek
                                              Total
                                                       75 100.000000
                                                                        0.00000
                                  Status
  LCB95Pct.P UCB95Pct.P Estimate.U
                                       StdError.U LCB95Pct.U UCB95Pct.U
1
    2.271467
               7.499019
                           35.87423 9.425042e+00
                                                    17.40149
                                                                54.34698
2
  92.500981
              97.728533
                          698.46457 4.378451e+01
                                                   612.64850
                                                               784.28063
3 100.000000 100.000000
                                                   651.88141
                          734.33880 4.207087e+01
                                                               816.79619
4
    0.000000
               4.496819
                           10.47516 9.075561e+00
                                                     0.00000
                                                                28.26293
5
  95.503181 100.000000
                          618.03415 9.075561e+00
                                                   600.24637
                                                               635.82192
6 100.000000 100.000000
                          628.50930 3.304215e-14
                                                   628.50930
                                                               628.50930
7
   16.328944
              31.671056
                           25.39908 4.142035e+00
                                                    17.28084
                                                                33.51732
                                                    72.31218
   68.328944
              83.671056
                           80.43042 4.142035e+00
                                                                88.54866
9 100.000000 100.000000
                          105.82950 4.561382e-15
                                                   105.82950
                                                               105.82950
```

The write.csv function is used to store the extent estimates as a comma-separated value (csv) file. Files in csv format can be read by programs such as Microsoft Excel.

```
> write.csv(Extent_Estimates, file="Extent_Estimates.csv")
```

4 Analysis of estuary condition variables

The second analysis that will be examined is estimating resource proportion and size for estuary condition variables. Two estuary condition variables will be examined: (1) IBL_Status, which classifies estuaries by benthic IBI (index of biotic integrity) status categories and (2) WQ_Status, which classifies estuaries by WQ (water quality) status categories. The table and addmargins functions are used to create tables displaying the count for each level of the two estuary condition variables.

```
> addmargins(table(SC_estuaries$IBI_status))
```

A table displaying the number of values for each level of the IBI status variable follows:

```
Good Mrgn Poor Sum
99 14 3 116
```

```
> addmargins(table(SC_estuaries$WQ_status))
```

A table displaying the number of values for each level of the WQ status variable follow

```
Good Mrgn Poor Sum
83 29 4 116
```

As for extent estimates, the cat.analysis function will be used to calculate condition estimates. The sites data frame for this analysis differs from the one used to calculate extent estimates. The Use logical variables in sites is set equal to the value "Sampled", so that only sampled sites are used in the analysis. The subpop and design data frames created in the prior analysis can be reused for this analysis. The data.cat data frame contains the two estuary condition variables: IBL_Status and WQ_Status. Variables IBL_status and WQ_status in the SC_estuaries data frame are assigned to IBL_Status and WQ_Status, respectively.

Create the sites data frame.

Create the data.cat data frame.

Use the cat.analysis function to calculate estimates for the estuary condition variables.

```
> # Calculate estimates for the categorical variables
> Condition_Estimates <- cat.analysis(sites, subpop, design, data.cat)
>
```

Print the estuary condition estimates for all sites combined.

```
> # Print the condition estimates for all basins combined
> print(Condition_Estimates[c(1:4, 13:16),])
```

```
Type Subpopulation Indicator Category NResp Estimate.P StdError.P
  All_Estuaries All Estuaries IBI_Status
                                             Good
                                                         86.1838689
                                                                      3.054977
  All_Estuaries All Estuaries IBI_Status
                                                     14 11.9123445
                                             Mrgn
                                                                      3.101725
3 All_Estuaries All Estuaries IBI_Status
                                             Poor
                                                          1.9037866
                                                                      1.349820
4 All_Estuaries All Estuaries IBI_Status
                                            Total
                                                    116 100.0000000
                                                                      0.000000
13 All_Estuaries All Estuaries WQ_Status
                                                                      3.454680
                                             Good
                                                     83
                                                         82.9514988
14 All_Estuaries All Estuaries
                               WQ_Status
                                                     29
                                                        16.2404087
                                                                      3.443841
                                             Mrgn
15 All_Estuaries All Estuaries
                               WQ_Status
                                             Poor
                                                          0.8080925
                                                                      0.364253
16 All_Estuaries All Estuaries
                               WQ_Status
                                            Total
                                                    116 100.0000000
                                                                      0.000000
    LCB95Pct.P UCB95Pct.P Estimate.U StdError.U LCB95Pct.U UCB95Pct.U
   80.19622370 92.171514 601.96379 41.403906 520.8136211
                                                             683.11395
1
2
    5.83307547 17.991613
                            83.20351 22.101079 39.8861870
                                                             126.52082
3
    0.00000000
                4.549386
                            13.29728
                                      9.383106
                                                  0.0000000
                                                              31.68783
  100.00000000 100.000000 698.46457 39.709481 620.6354124
                                                            776.29372
   76.18045106 89.722546 579.38683 43.296215 494.5278028
                                                            664.24585
                           113.43350 24.285825 65.8341570
14
    9.49060367 22.990214
                                                            161.03284
15
    0.09416982
                 1.522015
                             5.64424
                                       2.463364
                                                  0.8161351
                                                              10.47234
16 100.0000000 100.00000 698.46457 39.709481 620.6354124 776.29372
```

Use the write.csv function to write the condition estimates as a csv file.

>

```
> write.csv(Condition_Estimates, file="Condition_Estimates.csv")
```

5 Analysis of estuary condition variables correcting for population size

The frame is a data structure containing spatial location data in addition to other attributes regarding a resource of interest and is used to create a survey design. A frame often takes

the form of a shapefile. The frame can be used to obtain size values (e.g., area of estuaries) for the populations and subpopulations examined in an analysis. Examination of the Estimates. U column in the Condition_Estimates data frame produced by cat.analysis reveals that the estimated Total value for both condition variables and each combination of population value and subpopulation value does not sum to the corresponding frame size value. For example, the Total entry in the Estimate. U column for the IBL status variable, population "All_Estuaries" and subpopulation "All Estuaries" is 698 square kilometers (rounded to a whole number). The corresponding frame size value is 734 square kilometers. The popsize (population size) argument to cat. analysis provides a mechanism for forcing the Total category to equal a desired value. First, the c (combine) function is used to create a named vector of frame size values for each basin. Output from the c function is assigned to an object named framesize. The popsize argument is a list, which is a particular type of R object. The population type included in the subpop data frame, i.e., All_Estuaries and Estuary_Type for this analysis. The sum function applied to framesize is assigned to the All-Estuaries entry in the popsize list. Recall that the Estuary_Type population contains subpopulations, i.e., stratum categories. When a population type contains subpopulations, the entry in the population is a list. The as list function is applied to framesize, and the result is assigned to the Estuary_Type entry in the popsize list.

Assign frame size values.

```
> framesize <- c("Open Water"=628.509298, "Tidal Creek"=105.829522)
```

Use the cat.analysis function to calculate estimates for the estuary condition variables.

```
> Condition_Estimates_popsize <- cat.analysis(sites, subpop, design, data.cat,
+ popsize=list(All_Estuaries=sum(framesize),</pre>
```

+ Estuary_Type=as.list(framesize)))

Print the estuary condition estimates for IBI status.

```
> # Print the estuary condition estimates for all sites combined
> print(Condition_Estimates_popsize[c(1:4, 13:16),])
```

```
Estimate.P StdError.P
            Type Subpopulation Indicator Category NResp
  All_Estuaries All Estuaries IBI_Status
                                               Good
                                                       99
                                                           86.1838689
                                                                         3.054977
2
  All_Estuaries All Estuaries IBI_Status
                                                           11.9123445
                                               Mrgn
                                                       14
                                                                         3.101725
3
  All_Estuaries All Estuaries IBI_Status
                                               Poor
                                                        3
                                                             1.9037866
                                                                         1.349820
  All_Estuaries All Estuaries IBI_Status
                                              Total
                                                      116 100.0000000
                                                                               NΑ
13 All_Estuaries All Estuaries
                                WQ_Status
                                               Good
                                                       83
                                                           82.9514988
                                                                         3.454680
14 All_Estuaries All Estuaries
                                 WQ_Status
                                               Mrgn
                                                       29
                                                           16.2404087
                                                                         3.443841
15 All_Estuaries All Estuaries
                                WQ_Status
                                               Poor
                                                        4
                                                            0.8080925
                                                                         0.364253
```

```
16 All_Estuaries All Estuaries WQ_Status
                                                       116 100.0000000
                                                                                NA
                                              Total
    LCB95Pct.P UCB95Pct.P Estimate.U StdError.U
                                                  LCB95Pct.U UCB95Pct.U
  80.19622370 92.171514 632.881606
                                       22.433883 588.9120028
                                                               676.85121
2
    5.83307547
                17.991613
                           87.476970
                                       22.777170
                                                   42.8345376
                                                               132.11940
3
    0.0000000
                 4.549386
                                        9.912255
                                                    0.000000
                            13.980244
                                                                33.40791
                        NA 734.338820
            NA
                                               NA
                                                           NA
                                                                       NA
                89.722546 609.145057
                                       25.369054 559.4226254
                                                               658.86749
13 76.18045106
    9.49060367
                22.990214 119.259626
                                       25.289464
                                                  69.6931870
                                                               168.82606
                             5.934137
15
    0.09416982
                 1.522015
                                        2.674851
                                                    0.6915255
                                                                11.17675
                        NA 734.338820
                                                                       NA
16
            NA
                                               NA
                                                           NA
```

>

Use the write.csv function to write the condition estimates as a csv file.

> write.csv(Condition_Estimates_popsize, file="Condition_Estimates_popsize.csv")

6 Analysis of quantitative variables

The third analysis that will be examined is estimating the CDF and percentiles for quantitative variables. Two quantitative variables will be examined: (1) IBI_score - IBI score and (2) WQ_score - WQ score. The summary function is used to summarize the data structure of the two quantitative variables.

```
> summary(SC_estuaries$IBI_score)
```

Summarize the data structure of the IBI score variable:

```
Min. 1st Qu. Median Mean 3rd Qu. Max. NA's 1.000 3.000 3.500 3.612 4.125 5.000 19
```

> summary(SC_estuaries\$WQ_score)

Summarize the data structure of the WQ score variable:

```
Min. 1st Qu. Median Mean 3rd Qu. Max. NA's 2.700 4.000 4.600 4.407 5.000 5.000 19
```

The cont.analysis function will be used to calculate estimates for quantitative variables. Input to the cont.analysis function is the same as input for the cat.analysis function except that the data frame containing response variables is named cont.data rather than cat.data. The sites, subpop, and design data frames created in the analysis of estuary condition variables can be reused for this analysis. The data.cont data frame contains the two quantitative variables: IBL_Score and WQ_Score, which contain the numeric scores for the IBI and WQ variables, respectively. Variables IBL_score and WQ_score in the SC_estuaries data frame are assigned to IBL_Score and WQ_Score, respectively. The popsize argument is included in the call to cont.analysis.

Create the data.cont data frame.

Use the cont. analysis function to calculate CDF and percentile estimates for the quantitative variables.

The object produced by cont.analysis is a list containing two objects: (1) CDF, a data frame containing the CDF estimates and (2) Pct, a data frame containing percentile estimates plus estimates of population values for mean, variance, and standard deviation. Format for the CDF data frame is analogous to the data frame produced by cat.analysis. For the CDF data frame, however, the fourth column is labeled Value and contains the value at which the CDF was evaluated. Unlike the data frames produced by the other analysis functions we have examined, the Pct data frame contains only nine columns since there is a single set of estimates rather than two sets of estimates. In addition, the fourth column is labeled Statistic and identifies either a percentile or the mean, variance, or standard deviation. Finally, since percentile estimates are obtained by inverting the CDF estimate, the percentile estimates do not have a standard error value associated with them.

Use the write.csv function to write the CDF estimates as a csv file.

```
> write.csv(CDF_Estimates$CDF, file="CDF_Estimates.csv")
```

The cont.cdfplot function in spsurvey can be used to produce a PDF file containing plots of the CDF estimates. The primary arguments to cont.cdfplot are a character string containing a name for the PDF file and the CDF data frame in the CDF_Estimates object.

Produce a PDF file containing plots of the CDF estimates.

```
> cont.cdfplot("CDF_Estimates.pdf", CDF_Estimates$CDF)
>
```

Print the percentile estimates for IBI score for all sites combined.

> # Print the percentile estimates for IBI score for all sites combined
> print(CDF_Estimates\$Pct[1:10,])

```
Type Subpopulation Indicator
                                               Statistic NResp
                                                                Estimate
  All_Estuaries All Estuaries IBI_Score
                                                    5Pct
                                                              3 1.9835561
1
                                                              6 2.2809551
  All_Estuaries All Estuaries IBI_Score
                                                   10Pct
3
  All_Estuaries All Estuaries IBI_Score
                                                   25Pct
                                                            17 2.8823748
  All_Estuaries All Estuaries IBI_Score
                                                   50Pct
                                                            60 3.5875846
  All_Estuaries All Estuaries IBI_Score
                                                   75Pct
                                                            87 4.1208723
6
  All_Estuaries All Estuaries IBI_Score
                                                            87 4.4496095
                                                   90Pct
7
  All_Estuaries All Estuaries IBI_Score
                                                   95Pct
                                                            110 4.6753552
8
  All_Estuaries All Estuaries IBI_Score
                                                            116 3.7144320
                                                    Mean
  All_Estuaries All Estuaries IBI_Score
                                                Variance
                                                           116 0.6908874
10 All_Estuaries All Estuaries IBI_Score Std. Deviation
                                                           116 0.8311964
             StdError LCB95Pct UCB95Pct
                      1.5616016 2.1490377
1
2
                      2.0408270 2.5125581
3
                      2.6707797 3.0788808
4
                      3.3703757 3.7707670
5
                      3.9331037 4.3110103
6
                      4.2521696 4.9356565
7
                      4.4428288 5.0000000
8
  0.0718189615220735 3.5736694 3.8551946
  0.0865446486737272 0.5212630 0.8605118
10 0.0520602901032027 0.7291601 0.9332327
```

Use the write.csv function to write the percentile estimates as a csv file.

>

```
> write.csv(CDF_Estimates$Pct, file="Percentile_Estimates.csv")
```

The cont.cdftest function in spsurvey can be used to test for statistical difference between the CDFs from subpopulations. For this analysis we will use the cont.cdftest function to test for statistical difference between the CDFs from the two strata. Arguments to cont.cdftest are the same as arguments to cont.analysis. Since we are interested only in testing among strata, the subpop data frame is subsetted to include only the siteID and Estuary_Type variables. Note that the popsize argument was modified from prior examples to include only the entry for Estuary_Type.

```
> CDF_Tests <- cont.cdftest(sites, subpop[,c(1,3)], design, data.cont,
+ popsize=list(Estuary_Type=as.list(framesize)))</pre>
```

The print function is used to display results for IBI score of the statistical tests for difference between CDFs for strata. The object produced by cont.cdftest is a data frame containing eight columns. The first column (Type) identifies the population. The second and third columns (Subpopulation_1 and Subpopulation_2) identify the subpopulations. The fourth column (Indicator) identifies the response variable. Column five contains values of the test statistic. Six test statistics are available, and the default statistic is an F-distribution version of the Wald statistic, which is identified in the data frame as "Wald-F". The default statistic is used in this analysis. For further information about the test statistics see the help file for the cdf.test function in spsurvey, which includes a reference for the test for differences in CDFs. Columns six and seven (Degrees_of_Freedom_1 and Degrees_of_Freedom_2) provide the numerator and denominator degrees of freedom for the Wald test. The final column (p_Value) provides the p-value for the test.

```
> # Print results of the statistical tests for difference between strata CDFs for
> # IBI score and WQ score
> print(CDF_Tests, digits=3)
```

```
Type Subpopulation_1 Subpopulation_2 Indicator Wald_F
1 Estuary_Type
                    Open Water
                                    Tidal Creek IBI_Score
                                                            2.98
2 Estuary_Type
                    Open Water
                                    Tidal Creek WQ_Score
                                                           14.61
 Degrees_of_Freedom_1 Degrees_of_Freedom_2 p_Value
1
                     2
                                         109 5.50e-02
2
                     2
                                         109 2.39e-06
```

>

Use the write.csv function to write CDF test results as a csv file.

```
> # Write CDF test results as a csv file
> write.csv(CDF_Tests, file="CDF_Tests.csv")
>
```