## Open Watcom C Library Reference



Version 2.0



### **Notice of Copyright**

Copyright © 2002-2025 the Open Watcom Contributors. Portions Copyright © 1984-2002 Sybase, Inc. and its subsidiaries. All rights reserved.

Any part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of anyone.

For more information please visit https://github.com/open-watcom/open-watcom-v2.

### **Preface**

This manual describes the Open Watcom C Library. It includes the Standard C Library (as defined in the ISO/ANSI C Standard) plus many additional library routines which make application development for personal computers much easier.

### Acknowledgements

This book was produced with the Open Watcom GML electronic publishing system, a software tool developed by WATCOM. In this system, writers use an ASCII text editor to create source files containing text annotated with tags. These tags label the structural elements of the document, such as chapters, sections, paragraphs, and lists. The Open Watcom GML software, which runs on a variety of operating systems, interprets the tags to format the text into a form such as you see here. Writers can produce output for a variety of printers, including laser printers, using separately specified layout directives for such things as font selection, column width and height, number of columns, etc. The result is type-set quality copy containing integrated text and graphics.

July, 1997.

### Trademarks Used in this Manual

IBM is a registered trademark of International Business Machines Corp.

Intel is a registered trademark of Intel Corp.

Microsoft, MS, MS-DOS, Windows, Win32, Win32s, Windows NT and Windows 2000 are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

NetWare, NetWare 386, and Novell are registered trademarks of Novell, Inc.

UNIX is a registered trademark of The Open Group.

WATCOM is a trademark of Sybase, Inc. and its subsidiaries.

Open Watcom C Library Reference
1 C Library Overview
1.1 Classes of Functions
1.1.1 Character Manipulation Functions
1.1.2 Wide Character Manipulation Functions
1.1.3 Multibyte Character Manipulation Functions
1.1.4 Memory Manipulation Functions
1.1.5 String Manipulation Functions
1.1.6 Wide String Manipulation Functions
1.1.7 Multibyte String Manipulation Functions
1.1.8 Conversion Functions
1.1.9 Memory Allocation Functions
1.1.10 Heap Functions
1.1.11 Math Functions
1.1.12 Searching Functions
1.1.13 Time Functions
1.1.14 Variable-length Argument Lists
1.1.15 Stream I/O Functions
1.1.16 Wide Character Stream I/O Functions
1.1.17 Process Primitive Functions
1.1.18 Process Environment
1.1.19 Directory Functions
1.1.20 Operating System I/O Functions
1.1.21 File Manipulation Functions
1.1.22 Console I/O Functions
1.1.23 Default Windowing Functions
1.1.24 BIOS Functions
1.1.25 DOS-Specific Functions
1.1.26 Intel 80x86 Architecture-Specific Functions
1.1.27 Intel Pentium Multimedia Extension Functions
1.1.28 Miscellaneous Functions2
1.1.29 DOS LFN aware Functions
1.2 Header Files
1.2.1 Header Files in /watcom/h
1.2.2 Header Files in /watcom/h/sys
1.3 Global Data
1.4 The TZ Environment Variable
1.5 The OS/2 TZ Environment Variable
2 Graphics Library
2.1 Graphics Functions
2.2 Graphics Adapters
2.3 Classes of Graphics Functions
2.3.1 Environment Functions 4
2.3.2 Coordinate System Functions
2.3.3 Attribute Functions
2.3.4 Drawing Functions 4
2.3.5 Text Functions 4
2.3.6 Graphics Text Functions
2.3.7 Image Manipulation Functions
2.3.8 Font Manipulation Functions

2.	3.9 Presentation Graphics Functions
	2.3.9.1 Display Functions
	2.3.9.2 Analyze Functions
	2.3.9.3 Utility Functions
2.4 G	raphics Header Files
3 DOS C	onsiderations
3.1 D	OS Devices
3.2 D	OS Directories
	OS File Names
	OS Files
	OS Commands
	OS Interrupts
	OS Processes
4 Library	Functions and Macros
. Liorary	abort
	abort_handler_s
	abs
	access, _access, _waccess
	acos
	acosh
	alloca
	_arc, _arc_w, _arc_wxy
	asctime Functions
	asctime_s, _wasctime_s
	asin
	asinh
	assert
	atan
	atan2
	atanh
	atexit
	atof, _wtof
	atoi, _wtoi
	atol, _wtol
	atoll, _wtoll
	_atouni
	basename
	bdos
	_beginthread, _beginthreadex
	Bessel Functions
	bcmp
	bcopy
	_bfreeseg
	_bgetcmd
	_bheapseg
	_bios_disk
	_bios_equiplist
	bios_keybrd
	_bios_memsize
	bios printer

_bios_serialcom
_bios_timeofday
_bprintf, _bwprintf
oreak Functions
ork
osearch
osearch_s
otowc
ozero
eabs
ealloc Functions
ebrt
eil
gets
chain_intr
chair_inti
chdrive
chmod, _chmod, _wchmod
chsize, chsize
_clear87
clearenv
clearerr
_clearscreen
clock
clock_getres
clock_gettime
clock_nanosleep
clock_settime
clone
close, _close
closedir, _wclosedir
cmdname
commit
control87
controlfp
copysign
cos
cosh
eprintf
printi
creat, _creat, _wcreat
escanf
etime Functions
ctime_s, _wctime_s
ewait, _cwait
lelay
_dieeetomsbin
lifftime
lirname
_disable
_displaycursor
liv

_dmsbintoieee	185
_dos_allocmem	187
_dos_close	189
_dos_commit	190
_dos_creat	191
_dos_creatnew	193
dosexterr	195
	197
dos freemem	200
dos_getdate	202
	203
· ·	205
	206
-	208
	210
- <i>-</i>	211
=	213
1	21. 214
	216
	$\frac{217}{216}$
	219
= " - =	221
	222
	224
	226
	228
<del>-</del> -	230
dup, _dup	231
dup2, _dup2	233
_dwDeleteOnClose	235
_dwSetAboutDlg	236
_dwSetAppTitle	237
_dwSetConTitle	238
	239
	241
	242
· — · · —	244
	 246
_	248
	249
	250
	251
1	251 252
	252 253
	255 257
	257
	258
	259
= 7= -	264
	266
1	267
avn)	260

expm1	26
expand Functions	27
abs	27
close	27
closeall	27
cvt, _fcvt, _wfcvt	27
dim	27
dopen, _fdopen, _wfdopen	27
eclearexcept	28
edisableexcept,fedisableexcept	28
eenableexcept,feenableexcept	28
egetenv	28
egetexceptflag	28
egetround	28
eholdexcept	28
eof	28
eraiseexcept	28
error	28
esetenv	29
esetexceptflag	29
esetround	29
etestexcept	29
eupdateenv	29
flush	29
fs	29
getc, fgetwc	29
getchar, _fgetchar, _fgetwchar	29
getpos	30
gets, fgetws	30
fieeetomsbin	30
_filelength, _filelengthi64, filelength	30
FILENAME_MAX	30
ïleno	30
_findclose	30
	31
findnext, _findnexti64, _wfindnext, _wfindnexti64	31
finite	31
_floodfill, _floodfill_w	31
loor	31
flushall, flushall	31
ma	32
max	32
min	32
mod	32
fmsbintoieee	32
nmatch	32
Open, _wfopen	32
open_s, _wfopen_s	3.
FP_OFF	33
FP_SEG	3.
Pclassify	33
fpreset	34

fprintf, fwprintf	341
fprintf_s, fwprintf_s	343
fputc, fputwc	345
fputchar, _fputchar, _fputwchar	. 346
fputs, fputws	348
fread	
free Functions	
_freect	
freopen, _wfreopen	
freopen_s, _wfreopen_s	
frexp	
fscanf, fwscanf	
fscanf_s, fwscanf_s	
fseek	
fsetpos	
1	
_fsopen, _wfsopen	
fstat, _fstat, _fstati64	
fsync	
ftell	
ftime	
_fullpath, _wfullpath	
fwide	
fwrite	38
gcvt, _gcvt, _wgcvt	. 38
_getactivepage	38.
_getarcinfo	38:
_getbkcolor	. 38′
getc, getwc	38
getch	39
getchar, getwchar	. 39
getche	39
_getcliprgn	
getcmd	
_getcolor	
getcwd, _wgetcwd	
_getdcwd, _wgetdcwd	
getdelim	40
_getdiskfree	
getdrive	
<u> </u>	
getegid	
getenv, _wgetenv	
getenv_s	
geteuid	
_getfillmask	
_getfontinfo	
getgid	
_getgtextextent	
_getgtextvector	
gethostbyaddr	41
gethostbyname	41
gethostent	420

_getimage, _getimage_w, _getimage_wxy	
getline	
_getlinestyle	
_getmbcp	
getnetbyaddr	
getnetbyname	
getnetent	
getopt	
_get_osfhandle	
getpgrp	
_getphyscoord	
getpid, _getpid	
_getpixel, _getpixel_w	
_getplotaction	
getppid	
getprotobyname	
getprotobynumber	
getprotoent	
getpwent	
getpwnam	
getpwuid	
gets, _getws	
gets_s	
getservbyname	
getservbyport	
getservent	
_gettextcolor	
_gettextcursor	
_gettextextent	
_gettextposition	
_gettextsettings	
_gettextwindow	
gettid	
getuid	
_getvideoconfig	
_getviewcoord, _getviewcoord_w, _getviewcoord_wxy	
_getvisualpage	
_getw	
_getwindowcoord	
gmtime Functions	
gmtime_s	
_grow_handles	
_grstatus	
_grtext, _grtext_w	
halloc	
_harderr, _hardresume, _hardretn	
_hdopen	
_heapchk Functions	
_heapenable	
_heapgrow Functions	
_heapmin Functions	
_heapset Functions	

_heapshrink Functions	•••••
_heapwalk Functions	
nfree	
1ypot	
gnore_handler_s	
logb	
imagesize, _imagesize_w, _imagesize_wxy	
maxabs	
maxdiv	
np	
inpd	
npw	
nt386	
nt386x	
int86	
nt86x	
ntdos	
ntdosx	
ntr	
ntrf	
salnum, iswalnum	
salpha, iswalpha	
sascii,isascii, iswascii	•••••
satty, _isatty	
sblank, iswblank	
scntrl, iswcntrl	
scsym,iscsym,iswcsym	
scsymf,iscsymf,iswcsymf	
sdigit, iswdigit	
sfinite	
sgraph, iswgraph	
sinf	
sleadbyte	
slower, iswlower	
_ismbbalnum	
ismbbalpha	
_ismbbgraph	
ismbbkalnum	••••••
ismbbkana	•••••
_ismbbkalphaismbbkarint	
_ismbbkprint	
_ismbbkpunct	
_ismbblead	
_ismbbprint	
_ismbbpunct	
_ismbbtrail	
_ismbcalnum	
_ismbcalpha	
_ismbccntrl	
_ismbcdigit	
ismbcgraph	
_101110VS1up11	

ismbekata	589
ismbcl0	591
ismbcl1	593
ismbcl2	595
ismbelegal	597
ismbelower	599
ismberint	601
ismbepunet	603
ismbcspace	605
ismbesymbol	607
ismbcupper	609
ismbexdigit	611
isnan	613
	614
snormal	
sprint, iswprint	615
spunct, iswpunct	617
sspace, iswspace	619
supper, iswupper	621
swctype	623
sxdigit, iswxdigit	625
toa, _itoa, _itow	627
kbhit, _kbhit	629
abs	630
dexp	631
div	632
find	633
gamma	635
gamma_r	636
_lineto, _lineto_w	637
labs	639
ldiv	640
ocaleconv	641
ocaltime Functions	645
ocaltime_s	647
ock	649
ocking, _locking	651
log	653
log10	654
log1p	655
log2	656
logb	657
longjmp	658
lrotl	660
_lrotr	661
search	662
Iseek, _lseek, _lseeki64	664
lltoa, _lltoa, _ltow	667
toa, _ltoa, _ltow	669
main, wmain, WinMain, wWinMain	671
_makepath, _wmakepath	675
malloc Functions	677
natherr	679

max 6
_mbbtombc6
_mbbtype6
_mbccmp, _fmbccmp6
_mbccpy, _fmbccpy
_mbcicmp, _fmbcicmp
_mbcjistojms 6
_mbcjmstojis 6
_mbctolower6
_mbctoupper
mbctohira
_mbctokata
mblen, _fmblen
_mbputchar, _fmbputchar
mbrlen, _fmbrlen
mbrtowc, _fmbrtowc
_mbsbtype, _fmbsbtype
_mbsdec, _fmbsdec, _strdec, _wcsdec
_mbsinc, _fmbsinc, _strinc, _wesinc
_mbsnbcat, _fmbsnbcat
_mbsnbcmp, _fmbsnbcmp
_mbsnbcpy, _fmbsnbcpy
_mbsnbicmp, _fmbsnbicmp
_mbsnbset, _fmbsnbset
_mbsnbcnt, _fmbsnbcnt, _mbsnccnt, _fmbsnccnt, _strncnt, _wcsncnt
_mbsnextc, _fmbsnextc, _strnextc, _wcsnextc
_mbsnine, _fmbsnine, _strnine, _wesnine
mbsrtowes, _fmbsrtowes
mbsrtowcs_s, _fmbsrtowcs_s
_mbsspnp, _fmbsspnp, _strspnp, _wcsspnp
mbstowcs, _fmbstowcs
mbstowcs_s, _fmbstowcs_s
_mbterm, _fmbterm
mbtowc, _fmbtowc
_mbvtop, _fmbvtop
_memavl
memccpy, _fmemccpy, _memccpy
memchr, _fmemchr, wmemchr
memcmp, _fmemcmp, wmemcmp
memcpy, _fmemcpy, wmemcpy
memcpy_s, wmemcpy_s
_memicmp, _fmemicmp, memicmp
_memmax
memmove, _fmemmove, wmemmove
memmove_s, wmemmove_s
_m_empty
memset, _fmemset, wmemset
_m_from_int
III 11 VIII 111t

min
mkdir, _mkdir, _wmkdir
MK_FP
mkstemp
_mktemp, _wmktemp
mktime
mlock
mlockall
mmap
modf
movedata
_moveto, _moveto_w
 _m_packsswb
_m_packuswb
_m_paddb
_m_paddd
_m_paddsb
_m_paddsw
_m_paddusb
_m_paddusw
<b>_</b> _
_m_paddw
_m_pand
_m_pandn82
_m_pcmpeqb
_m_pcmpeqd82
_m_pcmpeqw
_m_pcmpgtb
_m_pcmpgtd83
_m_pcmpgtw
_m_pmaddwd
_m_pmulhw
_m_pmullw
_m_por
mprotect
_m_pslld
_m_pslldi
_m_psllq
_m_psllqi
_m_psllw
_m_psllwi
_m_psrad
_m_psradi
 _m_psrawi84
 _m_psrld
r _m_psrldi
_m_psrlq
_m_psrlqi
_m_psrlw
_m_psrlwi
_m_psubb
222 POWCO

_m_psubd	. 85
_m_psubsb	. 85
_m_psubsw	. 86
_m_psubusb	. 86
_m_psubusw	. 86
_m_psubw	. 86
_m_punpckhbw	
r _m_punpckhdq	
r _r _m_punpcklbw	
_m_punpckldq	
_m_punpcklwd	
_m_pxor	
_msize Functions	
msync	
_m_to_int	
munlock	
munlockall	
munmap	
nan	
nearbyint	
nextafter	
nl_langinfo	
nosound	
offsetof	. 89
_onexit, onexit	. 89
open, _open, _wopen	89
opendir, _wopendir	90
_open_osfhandle	. 90
_os_handle	. 90
_outgtext	. 90
_ outmem	
outpd	
outpw	
_outtext	
pclose	
_pclose	. 9
perror, _wperror	
· ·	
_pg_analyzechart, _pg_analyzechartms	
_pg_analyzepie	
_pg_analyzescatter, _pg_analyzescatterms	
_pg_chart, _pg_chartms	
_pg_chartpie	
_pg_chartscatter, _pg_chartscatterms	
_pg_defaultchart	
_pg_getchardef	
_pg_getpalette	
_pg_getstyleset	. 9
_pg_hlabelchart	. 9
pg_initchart	. 9
_pg_resetpalette	. 95

_pg_resetstyleset	954
_pg_setchardef	950
_pg_setpalette	958
_pg_setstyleset	961
_pg_vlabelchart	964
_pie, _pie_w, _pie_wxy	966
_pipe	969
_polygon, _polygon_w, _polygon_wxy	973
popen	975
_popen, _wpopen	977
pow	979
printf, wprintf	980
printf_s, wprintf_s	986
putc, putwc	988
putch	989
putchar, putwchar	990
putenv, _putenv	992
_putimage, _putimage_w	995
puts, _putws	997
_putw	998
qsort	999
•	1001
•	1003
	1005
	1000
· <del>-</del> · ·	1008
· <del>-</del>	1012
	1012
	1015
	1018
· ·	1019
	1020
_ 11	1022
	1024
	1025
	1026
· <del>-</del>	1027
	1029
- , ,	1030
	1031
	1032
	1033
	1034
	1036
	1037
<del>- /</del>	1043
=6 1	1045
	1046
	1047
<i>=</i> €	1048
	1049
cahad catheren	1050

sched_setscheduler	05
sched_yield1	052
_scrolltextwindow	053
_searchenv, _wsearchenv 1	055
segread	057
	058
	060
·	061
	062
	063
•	064
·	065
	066
	068
• •	070
	071
	$071 \\ 072$
	074
- 16	076
_	077
	078
_	080
_	082
- <i>6</i>	084
sethostent	085
J 1	086
_setlinestyle1	088
setlocale, _wsetlocale	090
_set_matherr	092
_setmbcp 1	094
_setmode, setmode	095
setnetent	097
set_new_handler, _set_new_handler	098
	100
	101
•	103
· •	104
	105
	100
-·····································	108
	110
_	112
_	114
_ <u> </u>	116
_ 1	
	117
	119
	121
	123
	127
= 0	128
=·····································	129
catvicualnoga 1	120

_setwindow 1	13
signal	13
signbit	13
sin	13
	13
	14
	14
	14
	14
	14
	15
	15
<u> </u>	15
-1 1 ·- 1 1	16
1 . 1	16
1 - · 1 -	16
•	16
	16
	16
sscanf_s, swscanf_s	17
stackavail, _stackavail	17
	17 17
	18
•	18
	18
	18
1 - 1 - 1	18
1 ' 1	18
· · · · · · · · · · · · · · · · · · ·	19
	19
17 - 7 - 17 -	19
	19
_strdate, _wstrdate1	19
strdup, _strdup, _fstrdup, wcsdup, _mbsdup, _fmbsdup 1	19
strerror, _wcserror	20
strerror_s, _wcserror_s	20
strerrorlen_s, _wcserrorlen_s	20
	20
	20
	21
	21
	21
	21
	21
	21
•	21
	22
	.22
	.22
	22
strncpy, _fstrncpy, wcsncpy, _mbsncpy, _fmbsncpy	22

strncpy_s, wcsncpy_s
_strnicmp, _fstrnicmp, _wcsnicmp, _mbsnicmp, _fmbsnicmp, strnicmp
_strnicoll, _wcsnicoll, _mbsnicoll
_strnset, _fstrnset, _wcsnset, _mbsnset, _fmbsnset, strnset, wcsnset
strpbrk, _fstrpbrk, wcspbrk, _mbspbrk, _fmbspbrk
strrchr, _fstrrchr, wesrchr, _mbsrchr, _fmbsrchr
_strrev, _fstrrev, _wcsrev, _mbsrev, _fmbsrev, strrev
_strset, _fstrset, _wcsset, _mbsset, _fmbsset, strset
strspn, _fstrspn, wcsspn, _mbsspn, _fmbsspn
strspnp, _fstrspnp
strstr, _fstrstr, wcsstr, _mbsstr, _fmbsstr
_strtime, _wstrtime
strtod, westod
strtok, strtok_r, _fstrtok_r, wcstok, _mbstok, _mbstok_r, _fmbstok, _fmbstok_r
strtok_s, westok_sstrtok_s, ristrok_s r
— ·       — ·
strtol, westol
strtoll, westoll
strtoimax, westoimax
strtoul, westoul
strtoull, westoull
strtoumax, wcstoumax
_strupr, _fstrupr, _wcsupr, _mbsupr, _fmbsupr, strupr
strxfrm, wcsxfrm
swab
sysconf
sysinfo
system, _wsystem
tan
tanh
_tell, _telli64, tell
_tempnam, _wtempnam
tgamma
time
timer_create
timer_delete
timer_gettime
timer_settime
timer_getoverrun
tmpfile
tmpfile_s
tmpnam_s, _wtmpnam_s
tmpnam, _wtmpnam
tolower, _tolower, towlower
toupper, _toupper towupper
towctrans
trunc
ttyname, ttyname_r
tzset
ulltoa, _ulltow
ultoa, _ultoa, _ultow
umask, _umask
ungetc. ungetwc

ungetch	
unlink, _unlink, _wunlink	
unlock	
_unregisterfonts	
unsetenv, _wunsetenv	
utime, _utime, _wutime	
utoa, _utoa, _utow	
va_arg	133
va_end	133
va_start	
_vbprintf, _vbwprintf	133
vcprintf	
vcscanf	
vfprintf, vfwprintf	
vfprintf_s, vfwprintf_s	
vfscanf, vfwscanf	
vfscanf_s, vfwscanf_s	
vprintf, vwprintf	
vprintf_s, vwprintf_s	
vscanf, vwscanf	
vscanf_s, vwscanf_s	
_vsnprintf, _vsnwprintf	
vsnprintf, vsnwprintf	
vsnprintf_s, vsnwprintf_s	
vsprintf, vswprintf	
vsprintf_s, vswprintf_s	
vsscanf, vswscanf	
vsscanf_s, vswscanf_s	
wait	
wertomb, _fwertomb	
wertomb_s, _fwertomb_s	
westombs, _fwestombs	
wcsrtombs_s, _fwcsrtombs_s	
westombs, _fwestombs	
wcstombs_s, _fwcstombs_s	
wctob	
wctomb, _fwctomb	
wctomb_s, _fwctomb_s	
wetrans	
wctype	
_wrapon	
write, _write, writev	
5 December 15 and 15 and 15	140
5 Re-entrant Functions	
Appendices	
A. Implementation-Defined Behavior of the C Library	141
A.1 NULL Macro	
A.2 Diagnostic Printed by the assert Function	141
	14

A.4 Domain Errors	1412
A.5 Underflow of Floating-Point Values	1412
A.6 The fmod Function	1412
A.7 The signal Function	1412
A.8 Default Signals	1413
A.9 The SIGILL Signal	1413
A.10 Terminating Newline Characters	1413
A.11 Space Characters	1413
A.12 Null Characters	1414
A.13 File Position in Append Mode	1414
A.14 Truncation of Text Files	1414
A.15 File Buffering	1414
A.16 Zero-Length Files	1414
A.17 File Names	1414
A.18 File Access Limits	1415
A.19 Deleting Open Files	1415
A.20 Renaming with a Name that Exists	1415
A.21 Printing Pointer Values	1415
A.22 Reading Pointer Values	1415
A.23 Reading Ranges	1416
A.24 File Position Errors	1416
A.25 Messages Generated by the perror Function	1416
A.26 Allocating Zero Memory	1416
A.27 The abort Function	1417
A.28 The atexit Function	1417
A.29 Environment Names	1417
A.30 The system Function	1417
A.31 The strerror Function	1417
A.32 The Time Zone	1418
A.33 The clock Function	1418

# Open Watcom C Library Reference

## 1 C Library Overview

The C library provides much of the power usually associated with the C language. This chapter introduces the individual functions (and macros) that comprise the Open Watcom C library. The chapter *Library Functions and Macros* describes each function and macro in complete detail.

Library functions are called as if they had been defined within the program. When the program is linked, the code for these routines is incorporated into the program by the linker.

Strictly speaking, it is not necessary to declare most library functions since they return int values for the most part. It is preferred, however, to declare all functions by including the header files found in the synopsis section with each function. Not only does this declare the return value, but also the type expected for each of the arguments as well as the number of arguments. This enables the Open Watcom C and C++ compilers to check the arguments coded with each function call.

### 1.1 Classes of Functions

The functions in the Open Watcom C library can be organized into a number of classes:

#### **Character Manipulation Functions**

These functions deal with single characters.

#### Wide Character Manipulation Functions

These functions deal with wide characters.

#### Multibyte Character Manipulation Functions

These functions deal with multibyte characters.

#### **Memory Manipulation Functions**

These functions manipulate blocks of memory.

#### String Manipulation Functions

These functions manipulate strings of characters. A character string is an array of zero or more adjacent characters followed by a null character  $(' \setminus 0')$  which marks the end of the string.

#### Wide String Manipulation Functions

These functions manipulate strings of wide characters. A wide character string is an array of zero or more adjacent wide characters followed by a null wide character ( $L' \setminus 0'$ ) which marks the end of the wide string.

#### Multibyte String Manipulation Functions

These functions manipulate strings of multibyte characters. A multibyte character is either a single-byte or double-byte character. The Chinese, Japanese and Korean character sets are examples of character sets containing both single-byte and double-byte characters.

What determines whether a character is a single-byte or double-byte character is the value of the lead byte in the sequence. For example, in the Japanese DBCS (double-byte character set), double-byte characters are those in which the first byte falls in the range 0x81 - 0x9F or 0xE0 - 0xFC and the second byte falls in the range 0x40 - 0x7E or 0x80 - 0xFC. A string of multibyte characters must be scanned from the first byte (index 0) to the last byte (index n) in sequence in order to determine if a particular byte is part of a double-byte character. For example, suppose that a multibyte character string contains the following byte values.

```
0x31 \ 0x40 \ 0x41 \ 0x81 \ 0x41 \ // "1@A.." where .. is a DB char
```

Among other characters, it contains the letter "A" (the first 0x41) and a double-byte character (0x81 0x41). The second 0x41 is not the letter "A" and that could only be determined by scanning from left to right starting with the first byte (0x31).

#### Conversion Functions

These functions convert values from one representation to another. Numeric values, for example, can be converted to strings.

#### **Memory Allocation Functions**

These functions are concerned with allocating and deallocating memory.

#### **Heap Functions**

These functions provide the ability to shrink and grow the heap, as well as, find heap related problems.

#### **Math Functions**

The mathematical functions perform mathematical computations such as the common trigonometric calculations. These functions operate on double values, also known as floating-point values.

#### Searching Functions

These functions provide searching and sorting capabilities.

#### Time Functions

These functions provide facilities to obtain and manipulate times and dates.

#### Variable-length Argument Lists

These functions provide the capability to process a variable number of arguments to a function.

#### Stream I/O Functions

These functions provide the "standard" functions to read and write files. Data can be transmitted as characters, strings, blocks of memory or under format control.

#### Wide Character Stream I/O Functions

These functions provide the "standard" functions to read and write files of wide characters. Data can be transmitted as wide characters, wide character strings, blocks of memory or under format control.

#### **Process Primitive Functions**

These functions deal with process creation, execution and termination, signal handling, and timer operations.

#### 4 Classes of Functions

#### **Process Environment**

These functions deal with process identification, user identification, process groups, system identification, system time and process time, environment variables, terminal identification, and configurable system variables.

#### **Directory Functions**

These functions provide directory services.

#### Operating System I/O Functions

These "non-standard" file operations are more primitive than the "standard" functions in that they are directly interfaced to the operating system. They are included to provide compatibility with other C implementations and to provide the capability to directly use operating-system file operations.

#### File Manipulation Functions

These functions operate directly on files, providing facilities such as deletion of files.

#### Console I/O Functions

These functions provide the capability to directly read and write characters from the console.

#### **Default Windowing Functions**

These functions provide the capability to manipulate various dialog boxes in Open Watcom's default windowing system.

#### **BIOS Functions**

This set of functions allows access to services provided by the BIOS.

#### **DOS-Specific Functions**

This set of functions allows access to DOS-specific functions.

#### Intel 80x86 Architecture-Specific Functions

This set of functions allows access to Intel 80x86 processor-related functions.

#### Intel Pentium Multimedia Extension Functions

This set of functions allows access to Intel Architecture Multimedia Extensions (MMX).

#### Miscellaneous Functions

This collection consists of the remaining functions.

#### **DOS LFN** aware Functions

These functions are DOS LFN capable.

The following subsections describe these function classes in more detail. Each function in the class is noted with a brief description of its purpose. The chapter *Library Functions and Macros* provides a complete description of each function and macro.

### 1.1.1 Character Manipulation Functions

These functions operate upon single characters of type char. The functions test characters in various ways and convert them between upper and lowercase. The following functions are defined:

isalnum

test for letter or digit

### Open Watcom C Library Reference

isalpha test for letter

isasciitest for ASCII characterisblanktest for blank characteriscntrltest for control character

\_\_iscsym test for letter, underscore or digit test for letter or underscore

isdigit test for digit

isgraph test for printable character, except space

islower test for letter in lowercase

isprint test for printable character, including space

ispuncttest for punctuation charactersisspacetest for "white space" charactersisuppertest for letter in uppercaseisxdigittest for hexadecimal digittolowerconvert character to lowercasetoupperconvert character to uppercase

### 1.1.2 Wide Character Manipulation Functions

These functions operate upon wide characters of type wchar\_t. The functions test wide characters in various ways and convert them between upper and lowercase. The following functions are defined:

iswalnum test for letter or digit

iswalpha test for letter

iswasciitest for ASCII characteriswblanktest for blank characteriswcntrltest for control character

\_\_iswcsym test for letter, underscore or digit test for letter or underscore

iswdigit test for digit

iswgraph test for printable character, except space

iswlower test for letter in lowercase

iswprint test for printable character, including space

iswpuncttest for punctuation charactersiswspacetest for "white space" charactersiswuppertest for letter in uppercaseiswxdigittest for hexadecimal digit

wctype construct a property value for a given "property"

iswctype test a character for a specific property

towlowerconvert character to lowercasetowupperconvert character to uppercase

wctrans construct mapping value for a given "property" towctrans convert a character based on a specific property

### 1.1.3 Multibyte Character Manipulation Functions

These functions operate upon multibyte characters. The functions test wide characters in various ways and convert them between upper and lowercase. The following functions are defined:

\_fmbccmp compare one multibyte character with another

*\_fmbccpy* copy one multibyte character from one string to another

\_fmbcicmp compare one multibyte character with another (case insensitive)

\_fmbclen return number of bytes comprising multibyte character

*\_fmblen* determine length of next multibyte character

\_fmbgetcode get next single-byte or double-byte character from far string store single-byte or double-byte character into far string

\_fmbrlen determine length of next multibyte character
\_fmbrtowc convert far multibyte character to wide character
\_fmbsbtype return type of byte in multibyte character string
\_fmbtowc convert far multibyte character to wide character

\_ismbbalnum test for isalnum or \_ismbbkalnum \_ismbbalpha test for isalpha or \_ismbbkalpha \_ismbbgraph test for isgraph or \_ismbbkprint

ismbbkalnum test for non-ASCII text symbol other than punctuation

\_ismbbkana test for single-byte Katakana character

\_ismbbkalpha test for non-ASCII text symbol other than digits or punctuation test for non-ASCII text or non-ASCII punctuation symbol

\_ismbbkpunct test for non-ASCII punctuation character test for valid first byte of multibyte character

*\_ismbbprint* test for isprint or \_ismbbkprint *\_ismbbpunct* test for ispunct or \_ismbbkpunct

*\_ismbbtrail* test for valid second byte of multibyte character

\_ismbcalnum test for \_ismbcalpha or \_ismbcdigit test for a multibyte alphabetic character \_ismbccntrl test for a multibyte control character

*\_ismbcdigit* test for a multibyte decimal-digit character '0' through '9' test for a printable multibyte character except space

\_ismbchira test for a double-byte Hiragana character \_ismbckata test for a double-byte Katakana character \_ismbcl0 test for a double-byte non-Kanji character \_ismbcl1 test for a JIS level 1 double-byte character \_ismbcl2 test for a JIS level 2 double-byte character

*\_ismbclegal* test for a valid multibyte character

*\_ismbclower* test for a valid lowercase multibyte character

ismbcprint test for a printable multibyte character including space

*\_ismbcpunct* test for any multibyte punctuation character *\_ismbcspace* test for any multibyte space character

\_ismbcsymbol test for valid multibyte symbol (punctuation and other special graphics)

\_ismbcupper test for valid uppercase multibyte character
\_ismbcxdigit test for any multibyte hexadecimal-digit character
\_mbbtombc return double-byte equivalent to single-byte character

*\_mbbtype* determine type of byte in multibyte character *\_mbccmp* compare one multibyte character with another

\_mbccpy copy one multibyte character from one string to another compare one multibyte character with another (case insensitive)

*\_mbcjistojms* convert JIS code to shift-JIS code *\_mbcjmstojis* convert shift-JIS code to JIS code

*\_mbclen* return number of bytes comprising multibyte character

*\_mbctolower* convert double-byte uppercase character to double-byte lowercase character convert double-byte lowercase character to double-byte uppercase character convert double-byte lowercase character to double-byte uppercase character

*\_mbctohira* convert double-byte Katakana character to Hiragana character *\_mbctokata* convert double-byte Hiragana character to Katakana character

*\_mbctombb* return single-byte equivalent to double-byte character get next single-byte or double-byte character from string

*mblen* determine length of next multibyte character

*\_mbputchar* store single-byte or double-byte character into string

### Open Watcom C Library Reference

mbrlendetermine length of next multibyte charactermbrtowcconvert multibyte character to wide character\_mbsbtypereturn type of byte in multibyte character string

mbsinit determine if mbstate\_t object describes an initial conversion state

mbtowc convert multibyte character to wide character

### 1.1.4 Memory Manipulation Functions

These functions manipulate blocks of memory. In each case, the address of the memory block and its size is passed to the function. The functions that begin with "\_f" accept far pointers as their arguments allowing manipulation of any memory location regardless of which memory model your program has been compiled for. The following functions are defined:

\_fmemccpy copy far memory block up to a certain character search far memory block for a character value compare any two memory blocks (near or far) copy far memory block, overlap not allowed compare far memory, case insensitive copy far memory block, overlap allowed

\_fmemset set any memory block (near of far) to a character memccpy copy memory block up to a certain character memchr search memory block for a character value

*memcmp* compare memory blocks

memcpycopy memory block, overlap not allowed\_memicmpcompare memory, case insensitivememmovecopy memory block, overlap allowedmemsetset memory block to a character

movedata copy memory block, with segment information

swab swap bytes of a memory block

wmemchr search memory block for a wide character value

wmemcmp compare memory blocks

wmemcpycopy memory block, overlap not allowedwmemmovecopy memory block, overlap allowedwmemsetset memory block to a wide character

See the section "String Manipulation Functions" for descriptions of functions that manipulate strings of data. See the section "Wide String Manipulation Functions" for descriptions of functions that manipulate wide strings of data.

### 1.1.5 String Manipulation Functions

A *string* is an array of characters (with type char) that is terminated with an extra null character ('\0'). Functions are passed only the address of the string since the size can be determined by searching for the terminating null character. The functions that begin with "\_f" accept far pointers as their arguments allowing manipulation of any memory location regardless of which memory model your program has been compiled for. The following functions are defined:

bcmp \*\* deprecated \*\* compare two byte strings bcopy \*\* deprecated \*\* copy a byte string

\_bprintf formatted transmission to fixed-length string

bzero \*\* deprecated \*\* zero a byte string

\_fstrcat concatenate two far strings

*\_fstrchr* locate character in far string *\_fstrcmp* compare two far strings

*\_fstrcpy* copy far string

\_fstrcspn get number of string characters not from a set of characters

\_fstricmp compare two far strings with case insensitivity

\_fstrlen length of a far string

\_fstrlwr convert far string to lowercase

\_fstrncat concatenate two far strings, up to a maximum length compare two far strings up to maximum length copy a far string, up to a maximum length

\_fstrnicmp compare two far strings with case insensitivity up to a maximum length

\_fstrnset fill far string with character to a maximum length
\_fstrpbrk locate occurrence of a string within a second string
\_fstrrchr locate last occurrence of character from a character set

\_fstrrev reverse a far string in place \_fstrset fill far string with a character

\_fstrspn find number of characters at start of string which are also in a second string

\_fstrstr find first occurrence of string in second string

\_fstrtok get next token from a far string
\_fstrupr convert far string to uppercase
sprintf formatted transmission to string
sscanf scan from string under format control

strcatconcatenate stringstrchrlocate character in stringstrcmpcompare two strings

\*\* deprecated \*\* compare two strings with case insensitivity

\*\* deprecated \*\* compare two strings with case insensitivity

compare two strings using "locale" collating sequence

strcpy copy a string

strcspn get number of string characters not from a set of characters

\_strdec returns pointer to the previous character in string

strdupallocate and duplicate a stringstrerrorget error message as string

\_stricmp compare two strings with case insensitivity
\_strinc return pointer to next character in string
strlcat concatenate string into a bounded buffer
strlcpy copy string into a bounded buffer

strlen string length

\_strlwr convert string to lowercase

strncatconcatenate two strings, up to a maximum lengthstrncmpcompare two strings up to maximum length\_strncntcount the number of characters in the first "n" bytes

strncpy copy a string, up to a maximum length

\_strnextc return integer value of the next character in string

strnicmp compare two strings with case insensitivity up to a maximum length

\_strninc increment character pointer by "n" characters
\_strnset fill string with character to a maximum length
strpbrk locate occurrence of a string within a second string
strrchr locate last occurrence of character from a character set

\_strrev reverse a string in place \_strset fill string with a character

strspn find number of characters at start of string which are also in a second string

*\_strspnp* return pointer to first character of string not in set *strstr* find first occurrence of string in second string

strtok get next token from string

### Open Watcom C Library Reference

*\_strupr* convert string to uppercase

strxfrmtransform string to locale's collating sequence\_vbprintfsame as "\_bprintf" but with variable argumentsvsscanfsame as "sscanf" but with variable arguments

For related functions see the sections *Conversion Functions* (conversions to and from strings), *Time Functions* (formatting of dates and times), and *Memory Manipulation Functions* (operate on arrays without terminating null character).

### 1.1.6 Wide String Manipulation Functions

A wide string is an array of wide characters (with type wchar\_t) that is terminated with an extra null wide character (L'\0'). Functions are passed only the address of the string since the size can be determined by searching for the terminating null character. The functions that begin with "\_f" accept far pointers as their arguments allowing manipulation of any memory location regardless of which memory model your program has been compiled for. The following functions are defined:

\_bwprintf formatted wide character transmission to fixed-length wesing

swprintf formatted wide character transmission to string
 swscanf scan from wide character string under format control
 \_vbwprintf same as "\_bwprintf" but with variable arguments
 vswscanf same as "swscanf" but with variable arguments

wcscatconcatenate stringwcschrlocate character in stringwcscmpcompare two strings

wcscmpi \*\* deprecated \*\* compare two strings with case insensitivity wcscoll compare two strings using "locale" collating sequence

wcscpy copy a string

wescspn get number of string characters not from a set of characters

\_wcsdec returns pointer to the previous character in string

wcsdup allocate and duplicate a string get error message as string

\_wcsicmp compare two strings with case insensitivity \_wcsinc return pointer to next character in string wcslcat concatenate string into a bounded buffer wcslcpy copy string into a bounded buffer

wcslen string length

\_wcslwr convert string to lowercase

wcsncatconcatenate two strings, up to a maximum lengthwcsncmpcompare two strings up to maximum length\_wcsncntcount the number of characters in the first "n" bytes

wcsncpy copy a string, up to a maximum length

\_wcsnextc return integer value of the next multi-byte character in string compare two strings with case insensitivity up to a maximum length

\_wcsninc increment wide character pointer by "n" characters
\_wcsnset fill string with character to a maximum length
wcspbrk locate occurrence of a string within a second string
wcsrchr locate last occurrence of character from a character set

\_wcsrev reverse a string in place \_wcsset fill string with a character

wcsspn find number of characters at start of string which are also in a second string

\_wcsspnp return pointer to first character of string not in set wcsstr find first occurrence of string in second string wcstok get next token from string \_wcsupr convert string to uppercase

wcsxfrm transform string to locale's collating sequence

For related functions see the sections *Conversion Functions* (conversions to and from strings), *Time Functions* (formatting of dates and times), and *Memory Manipulation Functions* (operate on arrays without terminating null character).

### 1.1.7 Multibyte String Manipulation Functions

A wide string is an array of wide characters (with type wchar\_t) that is terminated with an extra null wide character (L'\0'). Functions are passed only the address of the wide string since the size can be determined by searching for the terminating null character. The functions that begin with "\_f" accept far pointers as their arguments allowing manipulation of any memory location regardless of which memory model your program has been compiled for. The following functions are defined:

btowc return wide character version of single-byte character

\_fmbscat concatenate two far strings
\_fmbschr locate character in far string
\_fmbscmp compare two far strings

*\_fmbscpy* copy far string

\_fmbscspn get number of string characters not from a set of characters
\_fmbsdec returns far pointer to the previous character in far string

\_fmbsdup allocate and duplicate a far string

\_fmbsicmp compare two far strings with case insensitivity \_fmbsinc return far pointer to next character in far string

\_fmbslen length of a far string

*\_fmbslwr* convert far string to lowercase

*\_fmbsnbcat* append up to "n" bytes of string to another string

\_fmbsnbcmp compare up to "n" bytes in two strings

\_fmbsnbcnt count the number of characters in the first "n" bytes

\_fmbsnbcpy copy up to "n" bytes of a string

\_fmbsnbicmp compare up to "n" bytes in two strings with case insensitivity

*\_fmbsnbset* fill string with up to "n" bytes

\_fmbsncat concatenate two far strings, up to a maximum length count the number of characters in the first "n" bytes compare two far strings up to maximum length fmbsncpy copy a far string, up to a maximum length

\_fmbsnextc return integer value of the next multi-byte character in far string compare two far strings with case insensitivity up to a maximum length

\_fmbsninc increment wide character far pointer by "n" characters
\_fmbsnset fill far string with character to a maximum length
\_fmbspbrk locate occurrence of a string within a second string
\_fmbsrchr locate last occurrence of character from a character set

*\_fmbsrev* reverse a far string in place

*\_fmbsrtowcs* convert multibyte character string to wide character string

*\_fmbsset* fill far string with a character

\_fmbsspn find number of characters at start of string which are also in a second string

fmbsspnp return far pointer to first character of far string not in set

\_fmbsstr find first occurrence of string in second string

\_fmbstok get next token from a far string

\_fmbstowcs convert multibyte character string to wide character string

*\_fmbsupr* convert far string to uppercase

### Open Watcom C Library Reference

fmbterm determine if next multibyte character in string is null

*\_fmbvtop* store multibyte character into far string

fwcrtomb convert wide character to multibyte character and store

\_fwcsrtombs convert far wide character string to far multibyte character string convert far wide character string to far multibyte character string

\_fwctomb convert wide character to multibyte character

\_mbscat concatenate string
\_mbschr locate character in string
\_mbscmp compare two strings

*\_mbscoll* compare two strings using "locale" collating sequence

\_mbscpy copy a string

mbscspn get number of string characters not from a set of characters

*\_mbsdec* returns pointer to the previous character in string

mbsdup allocate and duplicate a string

\_mbsicmp compare two strings with case insensitivity \_mbsinc return pointer to next character in string

mbsinit determine if mbstate\_t object describes an initial conversion state

*\_mbslen* string length

*\_mbslwr* convert string to lowercase

*\_mbsnbcat* append up to "n" bytes of string to another string

*\_mbsnbcmp* compare up to "n" bytes in two strings

*\_mbsnbcnt* count the number of characters in the first "n" bytes

*\_mbsnbcpy* copy up to "n" bytes of a string

\_mbsnbicmp compare up to "n" bytes in two strings with case insensitivity

*\_mbsnbset* fill string with up to "n" bytes

*\_mbsncat* concatenate two strings, up to a maximum length *\_mbsnccnt* count the number of characters in the first "n" bytes

\_mbsncmp compare two strings up to maximum length copy a string, up to a maximum length

\_mbsnextc return integer value of the next multi-byte character in string compare two strings with case insensitivity up to a maximum length

\_mbsninc increment wide character pointer by "n" characters
\_mbsnset fill string with up to "n" multibyte characters
\_mbspbrk locate occurrence of a string within a second string
\_mbsrchr locate last occurrence of character from a character set

*\_mbsrev* reverse a string in place

mbsrtowcs convert multibyte character string to wide character string

*\_mbsset* fill string with a character

*\_mbsspn* find number of characters at start of string which are also in a second string

\_mbsspnp return pointer to first character of string not in set \_mbsstr find first occurrence of string in second string

*\_mbstok* get next token from string

mbstowcs convert multibyte character string to wide character string

*\_mbsupr* convert string to uppercase

\_mbterm determine if next multibyte character in string is null

*\_mbvtop* store multibyte character into string

wcrtombconvert wide character to multibyte character and storewcsrtombsconvert wide character string to multibyte character stringwcstombsconvert wide character string to multibyte character stringwctobreturn single-byte character version of wide character

wctomb convert wide character to multibyte character

For related functions see the sections *Conversion Functions* (conversions to and from strings), *Time Functions* (formatting of dates and times), and *Memory Manipulation Functions* (operate on arrays without terminating null character).

#### 1.1.8 Conversion Functions

These functions perform conversions between objects of various types and strings. The following functions are defined:

```
atof
                           string to "double"
atoi
                           string to "int"
atol
                           string to "long int"
atoll
                           string to "long long int"
                           "double" to E-format string
ecvt
                           "double" to F-format string
fcvt
                           "double" to string
gcvt
itoa
                           "int" to string
                           "long long int" to string
lltoa
                           "long int" to string
ltoa
strtod
                           string to "double"
                           string to "long int"
strtol
                           string to "long long int"
strtoll
                           string to "unsigned long int"
strtoul
strtoull
                           string to "unsigned long long int"
ulltoa
                           "unsigned long long int" to string
ultoa
                           "unsigned long int" to string
utoa
                           "unsigned int" to string
```

These functions perform conversions between objects of various types and wide character strings. The following functions are defined:

```
"int" to wide character string
_itow
_lltow
                          "long long int" to wide character string
_ltow
                          "long int" to wide character string
_ulltow
                          "unsigned long long int" to wide character string
_ultow
                          "unsigned long int" to wide character string
                          "unsigned int" to wide character string
_utow
wcstod
                         wide character string to "double"
                         wide character string to "long int"
westol
wcstoll
                         wide character string to "long long int"
wcstoul
                         wide character string to "unsigned long int"
                         wide character string to "unsigned long long int"
wcstoull
                         wide character string to "double"
wtof
                         wide character string to "int"
_wtoi
_wtol
                         wide character string to "long int"
_wtoll
                         wide character string to "long long int"
```

See also tolower, towlower, \_mbctolower, toupper, towupper, \_mbctoupper, \_strlwr, \_wcslwr, \_mbslwr, \_strupr, \_wcsupr and \_mbsupr which convert the cases of characters and strings.

### 1.1.9 Memory Allocation Functions

These functions allocate and de-allocate blocks of memory.

Unless you are running your program in 32-bit protect mode, where segments have a limit of 4 gigabytes, the default data segment has a maximum size of 64K bytes. It may be less in a machine with insufficient memory or when other programs in the computer already occupy some of the memory. The \_nmalloc function allocates space within this area while the \_fmalloc function allocates space outside the area (if it is available).

In a small data model, the malloc, calloc and realloc functions use the \_nmalloc function to acquire memory; in a large data model, the \_fmalloc function is used.

It is also possible to allocate memory from a based heap using \_bmalloc. Based heaps are similar to far heaps in that they are located outside the normal data segment. Based pointers only store the offset portion of the full address, so they behave much like near pointers. The selector portion of the full address specifies which based heap a based pointer belongs to, and must be passed to the various based heap functions.

It is important to use the appropriate memory-deallocation function to free memory blocks. The \_nfree function should be used to free space acquired by the \_ncalloc, \_nmalloc, or \_nrealloc functions. The \_ffree function should be used to free space acquired by the \_fcalloc, \_fmalloc, or \_frealloc functions. The \_bfree function should be used to free space acquired by the \_bcalloc, \_bmalloc, or \_brealloc functions.

The free function will use the \_nfree function when the small data memory model is used; it will use the \_ffree function when the large data memory model is being used.

It should be noted that the \_fmalloc and \_nmalloc functions can both be used in either data memory model. The following functions are defined:

allocate auto storage from stack

\_bcalloc allocate and zero memory from a based heap \_bexpand expand a block of memory in a based heap \_bfree free a block of memory in a based heap

\_bfreeseg free a based heap \_bheapseg allocate a based heap

*\_bmalloc* allocate a memory block from a based heap

*\_bmsize* return the size of a memory block

\_brealloc re-allocate a memory block in a based heap

brkset allocation "break" positioncallocallocate and zero memory\_expandexpand a block of memory

\_fcalloc allocate and zero a memory block (outside default data segment)
\_fexpand expand a block of memory (outside default data segment)

\_ffree free a block allocated using "\_fmalloc"

\_fmalloc allocate a memory block (outside default data segment)

*\_fmsize* return the size of a memory block

\_frealloc re-allocate a memory block (outside default data segment)
free free a block allocated using "malloc", "calloc" or "realloc"

\_freect return number of objects that can be allocated

halloc allocate huge array
hfree free huge array

malloc allocate a memory block (using current memory model)

\_memavl return amount of available memory
\_memmax return largest block of memory available
\_msize return the size of a memory block

\_ncalloc allocate and zero a memory block (inside default data segment)
\_nexpand expand a block of memory (inside default data segment)

\_nfree free a block allocated using "\_nmalloc"

\_nmalloc allocate a memory block (inside default data segment)

*\_nmsize* return the size of a memory block

\_nrealloc re-allocate a memory block (inside default data segment)

realloc re-allocate a block of memory sbrk set allocation "break" position

stackavail determine available amount of stack space

## 1.1.10 Heap Functions

These functions provide the ability to shrink and grow the heap, as well as, find heap related problems. The following functions are defined:

\_heapchk perform consistency check on the heap
\_bheapchk perform consistency check on a based heap
\_fheapchk perform consistency check on the far heap
\_nheapchk perform consistency check on the near heap

\_heapgrow grow the heap \_fheapgrow grow the far heap

\_nheapgrow grow the near heap up to its limit of 64K \_heapmin shrink the heap as small as possible \_bheapmin shrink a based heap as small as possible \_fheapmin shrink the far heap as small as possible shrink the near heap as small as possible \_nheapmin \_heapset fill unallocated sections of heap with pattern \_bheapset fill unallocated sections of based heap with pattern \_fheapset fill unallocated sections of far heap with pattern \_nheapset fill unallocated sections of near heap with pattern

\_heapshrink shrink the heap as small as possible \_fheapshrink shrink the far heap as small as possible \_bheapshrink shrink a based heap as small as possible nheapshrink shrink the near heap as small as possible \_heapwalk walk through each entry in the heap \_bheapwalk walk through each entry in a based heap \_fheapwalk walk through each entry in the far heap \_nheapwalk walk through each entry in the near heap

## 1.1.11 Math Functions

These functions operate with objects of type double, also known as floating-point numbers. The Intel 8087 processor (and its successor chips) is commonly used to implement floating-point operations on personal computers. Functions ending in "87" pertain to this specific hardware and should be isolated in programs when portability is a consideration. The following functions are defined:

absolute value of an object of type "int"

acos arccosine

acosh inverse hyperbolic cosine

asin arcsine

asinhinverse hyperbolic sineatanarctangent of one argumentatan2arctangent of two argumentsatanhinverse hyperbolic tangent

Bessel Functions bessel functions j0, j1, jn, y0, y1, and yn

cabs absolute value of complex number

cbrt cubed root of a number ceil ceiling function

\_clear87 clears floating-point status

*\_control87* sets new floating-point control word copysign copies the sign of one number to another

cos cosine

cosh hyperbolic cosine

div compute quotient, remainder from division of an "int" object

*erf* computes the error function

*erfc* computes the complementary error function

*exp* exponential function *exp2* two raised to a value

expm1 exponential of a number minus one

fabs absolute value of "double"

fdim positive difference of two numbers

\_finite determines whether floating-point value is valid

floor floor function fma fused multiply-add

fmaxreturns larger of two numbersfminreturns smaller of two numbers

fmod modulus function

\_fpreset initializes for floating-point operations

frexpfractional exponenthypotcompute hypotenuse

ilogb retrieve the exponent of a "double"

imaxabs get quotient, remainder from division of object of maximum-size integer type

imaxdiv absolute value of an object of maximum-size integer type

j0return Bessel functions of the first kind (described under Bessel)j1return Bessel functions of the first kind (described under Bessel)jnreturn Bessel functions of the first kind (described under Bessel)

labs absolute value of an object of type "long int"

*ldexp* multiply by a power of two

ldivget quotient, remainder from division of object of type "long int"lgammanatural logarithm of the absolute value of the Gamma function

lgamma\_r natural logarithm of the absolute value of the Gamma function (thread-safe)

log natural logarithm log10 logarithm, base 10

log1p natural logarithm of one plus the argument

log2 logarithm, base 2

logbretrieve the exponent of a "double"matherrhandles error from math functionsmaxreturn maximum of two argumentsminreturn minimum of two argumentsmodfget integral, fractional parts of "double"

nearbyint returns nearest integer based on rounding mode

nextafter returns next machine-representable floating point value

pow raise to power rand random integer

remainder retrieves the remainder of a division operation rint returns nearest integer based on rounding mode

rounds to the nearest integer

scalbn compute a "double" times two raised to a power

\_set\_matherr specify a math error handler

sin sine

sinhhyperbolic sinesqrtsquare root

srand set starting point for generation of random numbers using "rand" function

\_status87 gets floating-point status

tan tangent

tanh hyperbolic tangent

tgamma compute the Gamma function trunc truncate a floating point value

y0 return Bessel functions of the second kind (described under Bessel)
y1 return Bessel functions of the second kind (described under Bessel)
yn return Bessel functions of the second kind (described under Bessel)

## 1.1.12 Searching Functions

These functions provide searching and sorting capabilities. The following functions are defined:

bsearch find a data item in an array using binary search lfind find a data item in an array using linear search lsearch linear search array, add item if not found

qsort sort an array

### 1.1.13 Time Functions

These functions are concerned with dates and times. The following functions are defined:

asctimemakes time string from time structure\_asctimemakes time string from time structure\_wasctimemakes time string from time structure\_wasctimemakes time string from time structure

 clock
 gets time since program start

 ctime
 gets calendar time string

 \_ctime
 gets calendar time string

 \_wctime
 gets calendar time string

 \_wctime
 gets calendar time string

difftimecalculate difference between two timesftimereturns the current time in a "timeb" structure

gmtime convert calendar time to Coordinated Universal Time (UTC)
\_gmtime convert calendar time to Coordinated Universal Time (UTC)

localtimeconvert calendar time to local time\_localtimeconvert calendar time to local timemktimemake calendar time from local time

\_strdate return date in buffer strftime format date and time wcsftime format date and time

wstrftime ms format date and time \_strtime return time in buffer wstrtime return time in buffer get current calendar time time

set global variables to reflect the local time zone tzset

return date in buffer \_wstrdate

# 1.1.14 Variable-length Argument Lists

Variable-length argument lists are used when a function does not have a fixed number of arguments. These macros provide the capability to access these arguments. The following functions are defined:

va arg get next variable argument

complete access of variable arguments va\_end start access of variable arguments va start

## 1.1.15 Stream I/O Functions

A stream is the name given to a file or device which has been opened for data transmission. When a stream is opened, a pointer to a FILE structure is returned. This pointer is used to reference the stream when other functions are subsequently invoked.

There are two modes by which data can be transmitted:

binary Data is transmitted unchanged.

text On input, carriage-return characters are removed before following linefeed characters. On

output, carriage-return characters are inserted before linefeed characters.

These modes are required since text files are stored with the two characters delimiting a line of text, while the C convention is for only the linefeed character to delimit a text line.

When a program begins execution, there are a number of streams already open for use:

stdin Standard Input: input from the console

stdout Standard Output: output to the console

stderr Standard Error: output to the console (used for error messages)

stdaux Standard Auxiliary: auxiliary port, available for use by a program (not available in some

Windows platforms)

stdprn Standard Printer: available for use by a program (not available in some Windows

platforms)

These standard streams may be re-directed by use of the freopen function.

See also the section *File Manipulation Functions* for other functions which operate upon files.

The functions referenced in the section *Operating System I/O Functions* may also be invoked (use the fileno function to obtain the file handle). Since the stream functions may buffer input and output, these functions should be used with caution to avoid unexpected results.

#### The following functions are defined:

clear end-of-file and error indicators for stream

fclose close stream

fcloseall close all open streams fdopen open stream, given handle

feoftest for end of fileferrortest for file errorfflushflush output buffer

fgetc get next character from file

\_fgetchar equivalent to "fgetc" with the argument "stdin"

fgetpos get current file position

fgets get a string

\_flushall flush output buffers for all streams

fopenopen a streamfprintfformat outputfputcwrite a character

\_fputchar write a character to the "stdout" stream

fputs write a string

fread read a number of objects re-open re-opens a stream

fscanfscan input according to formatfseekset current file position, relativefsetposset current file position, absolute

\_fsopen open a shared stream
ftell get current file position
fwrite write a number of objects

getc read character

getchar get next character from "stdin"

gets get string from "stdin"
\_getw read int from stream file

perror write error message to "stderr" stream

printfformat output to "stdout"putcwrite character to fileputcharwrite character to "stdout"putswrite string to "stdout"\_putwwrite int to stream filerewindposition to start of file

scan input from "stdin" under format control

setbufset buffersetvbufset buffering

tmpfile create temporary file

ungetc push character back on input stream

vfprintfsame as "fprintf" but with variable argumentsvfscanfsame as "fscanf" but with variable argumentsvprintfsame as "printf" but with variable argumentsvscanfsame as "scanf" but with variable arguments

See the section Directory Functions for functions which are related to directories.

## 1.1.16 Wide Character Stream I/O Functions

The previous section describes some general aspects of stream input/output. The following describes functions dealing with streams containing multibyte character sequences.

After a stream is associated with an external file, but before any operations are performed on it, the stream is without orientation. Once a wide character input/output function has been applied to a stream without orientation, the stream becomes *wide-oriented*. Similarly, once a byte input/output function has been applied to a stream without orientation, the stream becomes *byte-oriented*. Only a successful call to freopen can otherwise alter the orientation of a stream (it removes any orientation). You cannot mix byte input/output functions and wide character input/output functions on the same stream.

A file positioning function can cause the next wide character output function to overwrite a partial multibyte character. This can lead to the subsequent reading of a stream of multibyte characters containing an invalid character.

When multibyte characters are read from a stream, they are converted to wide characters. Similarly, when wide characters are written to a stream, they are converted to multibyte characters.

The following functions are defined:

fgetwc get next wide character from file

*\_fgetwchar* equivalent to "fgetwc" with the argument "stdin"

fgetws get a wide character string

fprintf "C" and "S" extensions to the format specifier

fputwc write a wide character

\_fputwchar write a character to the "stdout" stream

fputws write a wide character string

fscanf "C" and "S" extensions to the format specifier

fwprintf formatted wide character output

fwscanf scan wide character input according to format

getwc read wide character

getwchar get next wide character from "stdin"

\_getws get wide character string from "stdin"

putwc write wide character to file write wide character to "stdout" putwchar \_putws write wide character string to "stdout" ungetwc push wide character back on input stream vfwprintf same as "fwprintf" but with variable arguments vfwscanf same as "fwscanf" but with variable arguments vswprintf same as "swprintf" but with variable arguments vwprintf same as "wprintf" but with variable arguments same as "wscanf" but with variable arguments vwscanf

\_wfdopen open stream, given handle using a wide character "mode"

\_wfopen open a stream using wide character arguments
\_wfreopen re-opens a stream using wide character arguments
\_wfsopen open a shared stream using wide character arguments

\_wperror write error message to "stderr" stream
wprintf format wide character output to "stdout"

wscanf scan wide character input from "stdin" under format control

See the section *Directory Functions* for functions which are related to directories.

### 1.1.17 Process Primitive Functions

These functions deal with process creation, execution and termination, signal handling, and timer operations.

When a new process is started, it may replace the existing process

- P\_OVERLAY is specified with the spawn... functions
- the exec... routines are invoked

or the existing process may be suspended while the new process executes (control continues at the point following the place where the new process was started)

- P\_WAIT is specified with the spawn... functions
- system is used

The following functions are defined:

abort immediate termination of process, return code 3

alarm send calling process SIGALRM signal after specified time

atexit register exit routine

\_beginthread start a new thread of execution
cwait wait for a child process to terminate
\_cwait wait for a child process to terminate
delay delay for number of milliseconds

\_endthread
 execl
 end the current thread
 chain to program
 chain to program

execle chain to program, pass environment chain to program, pass environment

execlpchain to program\_execlpchain to program

execlpe chain to program, pass environment\_execlpe chain to program, pass environment

execv chain to program \_execv chain to program

*execve* chain to program, pass environment *\_execve* chain to program, pass environment

execvpchain to program\_execvpchain to program

*execvpe* chain to program, pass environment *\_execvpe* chain to program, pass environment

 exit
 exit process, set return code

 \_Exit
 exit process, set return code

 \_exit
 exit process, set return code

fork create a new process

kill send a signal to specified process

*\_onexit* register exit routine

pausesuspend calling process until signalraisesignal an exceptional condition

sigaction examine or specify action for specific signal

sigaddsetadd specified signal to setsigdelsetdelete specified signal from set

sigemptysetinitialize signal set to exclude certain signalssigfillsetinitialize signal set to include certain signalssigismembertest whether signal is a member of a setsignalset handling for exceptional condition

sigpending store set of pending signals

sigprocmask examine or change process's signal mask

sigsuspend replace process's signal mask and then suspend process

sleep delay for number of seconds

spawnl create process
\_spawnl create process

spawnle create process, set environment create process, set environment

spawnlp create process \_spawnlp create process

spawnlpe create process, set environment \_spawnlpe create process, set environment

spawnv create process \_spawnv create process

*spawnve* create process, set environment *\_spawnve* create process, set environment

*spawnvp* create process *\_spawnvp* create process

spawnvpecreate process, set environment\_spawnvpecreate process, set environmentsystemexecute system command

wait wait for any child process to terminate waitpid wait for a child process to terminate

\_wexecl chain to program

\_wexecle chain to program, pass environment

\_wexeclp chain to program

\_wexeclpe chain to program, pass environment

\_wexecv chain to program

\_wexecve chain to program, pass environment

\_wexecvp chain to program

\_wexecvpe chain to program, pass environment

\_wspawnl create process

*\_wspawnle* create process, set environment

*\_wspawnlp* create process

\_wspawnlpe create process, set environment

*\_wspawnv* create process

\_wspawnve create process, set environment

\_wspawnvp create process

\_wspawnvpe create process, set environment \_wsystem execute system command

There are eight spawn... and exec... functions each. The "..." is one to three letters:

- "l" or "v" (one is required) to indicate the way the process parameters are passed
- "p" (optional) to indicate whether the **PATH** environment variable is searched to locate the program for the process

• "e" (optional) to indicate that the environment variables are being passed

## 1.1.18 Process Environment

These functions deal with process identification, process groups, system identification, system time, environment variables, and terminal identification. The following functions are defined:

\_bgetcmd get command line

clearenv delete environment variables

confstrget configuration-defined string valuesctermidreturn name of controlling terminalcuseridgenerate login name of process owner

getcmd get command line

getegid get effective group ID of calling process

getenv get environment variable value

geteuid get effective user ID

getgidget real group ID of calling processgetgroupsget supplementary group IDsgetloginget user's login name

getlogin get user's login getnid get netword ID

getpgrpget process group ID of calling processgetpidget process ID of calling process\_getpidget process ID of calling processgetppidget parent process ID of calling process

gettid get thread ID of current thread

getuid get real user ID

*isatty* determine if file descriptor associated with a terminal

putenv add, change or delete environment variable
\_searchenv search for a file in list of directories
searchenv search for a file in list of directories

setegid set the effective group ID

setenv add, change or delete environment variable

seteuid set the effective user ID

setgidset real group ID, effective group IDsetpgidset process group ID for job control

setsid create a new session and set process group ID

set real user ID, effective user ID

sysconf determine value of configurable system limit or option

times return time-accounting information

ttyname return pointer to string containing pathname of terminal associated with file

descriptor argument

uname return operating system identification

unsetenvdelete environment variable\_wgetenvget environment variable value

\_wputenv add, change or delete environment variable

\_wsearchenv search for a file in list of directories

\_wsetenv add, change or delete environment variable

\_wunsetenv delete environment variable

# 1.1.19 Directory Functions

These functions pertain to directory manipulation. The following functions are defined:

chdirchange current working directoryclosedirclose opened directory filegetcwdget current working directory\_getdcwdget current directory on drivemkdirmake a new directory

mkdir make a new directory opendir open directory file

readdir read file name from directory rewinddir reset position of directory stream

rmdir remove a directory

\_wchdir change current working directory wclosedir close opened directory file get current working directory get current working directory get current directory on drive

\_wmkdir make a new directory open directory file

\_wreaddir read file name from directory
\_wrewinddir reset position of directory stream

\_wrmdir remove a directory

# 1.1.20 Operating System I/O Functions

These functions operate at the operating-system level and are included for compatibility with other C implementations. It is recommended that the functions used in the section *File Manipulation Functions* be used for new programs, as these functions are defined portably and are part of the ISO/ANSI standard for the C language.

The functions in this section reference opened files and devices using a *file handle* which is returned when the file is opened. The file handle is passed to the other functions.

The following functions are defined:

*\_chsize* change the size of a file

*close* close file

*\_commit* commit changes to disk

create a file

dupduplicate file handle, get unused handle numberdup2duplicate file handle, supply new handle number

\_eof test for end of file control over an open file fdatasync write queued file data to disk

\_filelength get file size

fileno get file handle for stream file

fstat get file status

fsync write queued file and filesystem data to disk

hdopen get POSIX handle from OS handle

linkcreate new directory entrylocklock a section of a filelockinglock/unlock a section of a file

*lseek* set current file position

*ltrunc* truncate a file

mkfifo make a FIFO special file mknod make a filesystem entry point

mount a filesystem

open open a file

\_os\_handle get OS handle from POSIX handle

\_pclose close a pipe pclose close a pipe

pipe create an inter-process channel

\_popen open a pipe
popen open a pipe
read read a record

readlink read a symbolic link

read records placing them into a specified number of buffers

select synchronous I/O multiplexing

*\_setmode* set file mode

\_sopen open a file for shared access
symlink create a symbolic link
sync sync the filesystem
\_tell get current file position
umask set file permission mask
umount unmount a filesystem

unlink delete a file

unlock unlock a section of a file

write write a record

writev write several records from a specified number of buffers

\_wcreat create a file \_wopen open a file \_wpopen open a pipe

\_wsopen open a file for shared access

\_wunlink delete a file

# 1.1.21 File Manipulation Functions

These functions operate directly with files. The following functions are defined:

access test file or directory for mode of access

chmod change permissions for a file

chown change owner user ID and group ID of the specified file

fchmod change the permissions for the file associated with the specified file descriptor to

the specified mode

fchown change the user ID and group ID of the file associated with the specified file

descriptor to the specified numeric values

fpathconf determine value of configurable limit associated with a file or directory

*lstat* get file status

pathconf determine value of configurable limit associated with a file or directory

removedelete a filerenamerename a filestatget file status

tmpnamcreate name for temporary fileutimeset modification time for a file

\_waccess test file or directory for mode of access

wchmod change permissions for a file

\_wremove delete a file \_wrename rename a file \_wstat get file status

\_wtmpnam create name for temporary file \_wutime set modification time for a file

## 1.1.22 Console I/O Functions

These functions provide the capability to read and write data from the console. Data is read or written without any special initialization (devices are not opened or closed), since the functions operate at the hardware level.

The following functions are defined:

cgets get a string from the console cprintf print formatted string to the console

cputs write a string to the console

cscanfscan formatted data from the consolegetchget character from console, no echogetcheget character from console, echo it

kbhit test if keystroke available putch write a character to the console

ungetch push back next character from console

# 1.1.23 Default Windowing Functions

These functions provide the capability to manipulate attributes of various windows created by Open Watcom's default windowing system for Microsoft Windows and IBM OS/2.

The following functions are defined:

\_dwDeleteOnClose delete console window upon close \_dwSetAboutDlg set about dialogue box title and contents \_dwSetAppTitle set main window's application title

\_dwSetConTitle set console window's title

\_dwShutDown shut down default windowing system \_dwYield yield control to other processes

## 1.1.24 BIOS Functions

This set of functions allows access to services provided by the BIOS. The following functions are defined:

\_bios\_disk provide disk access functions \_bios\_equiplist determine equipment list

\_bios\_keybrd provide low-level keyboard access

bios memsize determine amount of system board memory

\_bios\_printer provide access to printer services \_bios\_serialcom provide access to serial services \_bios\_timeofday get and set system clock

# 1.1.25 DOS-Specific Functions

These functions provide the capability to invoke DOS functions directly from a program. The following functions are defined:

bdos DOS call (short form)

dosexterrextract DOS error information\_dos\_allocmemallocate a block of memory

\_dos\_close close a file

\_dos\_findfirst find first file matching a specified pattern
\_dos\_findnext find the next file matching a specified pattern

\_dos\_freemem free a block of memory
\_dos\_getdate get current system date
\_dos\_getdiskfree get information about disk
\_dos\_getdrive get the current drive
\_dos\_getfileattr get file attributes

\_dos\_getftime get file's last modification time get the current system time get contents of interrupt vector

\_dos\_keep install a terminate-and-stay-resident program

\_dos\_open open a file

\_dos\_read read data from a file

\_dos\_setblock change the size of allocated block \_dos\_setdate change current system date \_dos\_setdrive change the current default drive \_dos\_setfileattr set the attributes of a file

\_dos\_setftime set a file's last modification time
\_dos\_settime set the current system time
\_dos\_setvect set an interrupt vector
\_dos\_write write data to a file
intdos cause DOS interrupt

intdosx cause DOS interrupt, with segment registers

\_wdos\_findclose close find file matching

\_wdos\_findfirst file matching a specified pattern
\_wdos\_findnext find the next file matching a specified pattern

# 1.1.26 Intel 80x86 Architecture-Specific Functions

These functions provide the capability to invoke Intel 80x86 processor-related functions directly from a program. Functions that apply to the Intel 8086 CPU apply to that family including the 80286, 80386, 80486 and Pentium processors. The following functions are defined:

\_chain\_intr chain to the previous interrupt handler

\_disable disable interrupts
\_enable enable interrupts

FP\_OFF get offset part of far pointer
FP\_SEG get segment part of far pointer
inp get one byte from hardware port

*inpw* get two bytes (one word) from hardware port *int386* cause 386/486/Pentium CPU interrupt

int386x cause 386/486/Pentium CPU interrupt, with segment registers

int86 cause 8086 CPU interrupt

int86x cause 8086 CPU interrupt, with segment registers cause 8086 CPU interrupt, with segment registers

intrf cause 8086 CPU interrupt, with segment registers and CPU flags

*MK\_FP* make a far pointer from the segment and offset values

nosound turn off the speaker

outp write one byte to hardware port

outpw write two bytes (one word) to hardware port

segread read segment registers

sound turn on the speaker at specified frequency

## 1.1.27 Intel Pentium Multimedia Extension Functions

This set of functions allows access to Intel Architecture Multimedia Extensions (MMX). These functions are implemented as in-line intrinsic functions. The general format for most functions is:

```
mm_result = mm_function( mm_operand1, mm_operand2 );
```

These functions provide a simple model for use of Intel Multimedia Extension (MMX). More advanced use of MMX can be implemented in much the same way that these functions are implemented. See the <mmintrin.h> header file for examples. The following functions are defined:

*\_m\_empty* empty multimedia state

\_m\_from\_int form 64-bit MM value from unsigned 32-bit integer value

\_m\_packssdw pack and saturate 32-bit double-words from two MM elements into signed 16-bit

words

\_m\_packsswb pack and saturate 16-bit words from two MM elements into signed bytes

\_m\_packuswb pack and saturate signed 16-bit words from two MM elements into unsigned bytes

*\_m\_paddb* add packed bytes

\_m\_padddadd packed 32-bit double-words\_m\_paddsbadd packed signed bytes with saturation\_m\_paddswadd packed signed 16-bit words with saturation\_m\_paddusbadd packed unsigned bytes with saturation\_m\_padduswadd packed unsigned 16-bit words with saturation

*\_m\_paddw* add packed 16-bit words

*\_m\_pand* AND 64 bits of two MM elements

\_m\_pandn invert the 64 bits in MM element, then AND 64 bits from second MM element

*\_m\_pcmpeqb* compare packed bytes for equality

\_m\_pcmpeqd compare packed 32-bit double-words for equality \_m\_pcmpeqw compare packed 16-bit words for equality

\_m\_pcmpgtb compare packed bytes for greater than relationship

\_m\_pcmpgtd compare packed 32-bit double-words for greater than relationship compare packed 16-bit words for greater than relationship multiply packed 16-bit words, then add 32-bit results pair-wise

\_m\_pmulhw multiply the packed 16-bit words of two MM elements, then store high-order 16

bits of results

\_m\_pmullw multiply the packed 16-bit words of two MM elements, then store low-order 16

bits of results

*\_m\_por* OR 64 bits of two MM elements

\_m\_pslld shift left each 32-bit double-word by amount specified in second MM element

_m_pslldi	shift left each 32-bit double-word by amount specified in constant value
 _m_psllq	shift left each 64-bit quad-word by amount specified in second MM element
_m_psllqi	shift left each 64-bit quad-word by amount specified in constant value
_m_psllw	shift left each 16-bit word by amount specified in second MM element
_m_psllwi	shift left each 16-bit word by amount specified in constant value
_m_psrad	shift right (with sign propagation) each 32-bit double-word by amount specified in
	second MM element
_m_psradi	shift right (with sign propagation) each 32-bit double-word by amount specified in constant value
_m_psraw	shift right (with sign propagation) each 16-bit word by amount specified in second MM element
_m_psrawi	shift right (with sign propagation) each 16-bit word by amount specified in constant value
_m_psrld	shift right (with zero fill) each 32-bit double-word by an amount specified in second MM element
_m_psrldi	shift right (with zero fill) each 32-bit double-word by an amount specified in
	constant value
_m_psrlq	shift right (with zero fill) each 64-bit quad-word by an amount specified in second MM element
_m_psrlqi	shift right (with zero fill) each 64-bit quad-word by an amount specified in
	constant value
_m_psrlw	shift right (with zero fill) each 16-bit word by an amount specified in second MM element
_m_psrlwi	shift right (with zero fill) each 16-bit word by an amount specified in constant value
_m_psubb	subtract packed bytes in MM element from second MM element
_m_psubd	subtract packed 32-bit dwords in MM element from second MM element
_m_psubsb	subtract packed signed bytes in MM element from second MM element with
psese	saturation
_m_psubsw	subtract packed signed 16-bit words in MM element from second MM element
	with saturation
_m_psubusb	subtract packed unsigned bytes in MM element from second MM element with saturation
_m_psubusw	subtract packed unsigned 16-bit words in MM element from second MM element with saturation
_m_psubw	subtract packed 16-bit words in MM element from second MM element
_m_punpckhbw	interleave bytes from the high halves of two MM elements
_m_punpckhdq	interleave 32-bit double-words from the high halves of two MM elements
_m_punpckhwd	interleave 16-bit words from the high halves of two MM elements
_m_punpcklbw	interleave bytes from the low halves of two MM elements
_m_punpckldq	interleave 32-bit double-words from the low halves of two MM elements
_m_punpcklwd	interleave 16-bit words from the low halves of two MM elements
_m_pxor	XOR 64 bits from two MM elements
_m_to_int	retrieve low-order 32 bits from MM value
- <b>-</b> -	

# 1.1.28 Miscellaneous Functions

The following functions are defined:

assert test an assertion and output a string upon failure

\_fullpath return full path specification for file \_getmbcp get current multibyte code page

getopt a command-line parser that can be used by applications that follow guidelines

outlined in the Single UNIX Specification

\_harderr critical error handler \_hardresume critical error handler resume

 localeconv
 obtain locale specific conversion information

 longjmp
 return and restore environment saved by "setjmp"

\_lrotl rotate an "unsigned long" left
\_lrotr rotate an "unsigned long" right
main the main program (user written)
offsetof get offset of field in structure
\_rotl rotate an "unsigned int" left
rotr rotate an "unsigned int" right

setjmp save environment for use with "longjmp" function \_makepath make a full filename from specified components

setlocale set locale category

\_setmbcp set current multibyte code page

sigsetjmp save environment and process's signal mask for use with "siglongjmp" function siglongjmp return and restore environment and process's signal mask saved by "sigsetjmp"

\_splitpath split a filename into its components \_splitpath2 split a filename into its components \_wfullpath return full path specification for file

\_wmakepath make a full filename from specified components

\_wsetlocale set locale category

\_wsplitpath split a filename into its components \_wsplitpath2 split a filename into its components

## 1.1.29 DOS LFN aware Functions

These functions deal with DOS Long File Name if an application is compiled with -D\_WATCOM\_LFN\_ option and DOS LFN support is available on host system. The following functions are defined:

accesstest file or directory for mode of accesschdirchange current working directorychmodchange permissions for a file

\_dos\_findfirst find first file matching a specified pattern

\_dos\_getfileattr get file attributes \_dos\_open open a file

\_dos\_setfileattr set the attributes of a file

\_findfirst find first file matching a specified pattern
\_fullpath return full path specification for file

getcwd get current working directory get current directory on drive

*lstat* get file status mkdir make a new directory

openopen a fileopendiropen directory fileremovedelete a filerenamerename a filermdirremove a directory

\_sopen open a file for shared access

stat get file status

tmpnam create name for temporary file

unlink delete a file

utime set modification time for a file

\_waccess test file or directory for mode of access \_wchdir change current working directory \_wchmod change permissions for a file

\_wcreat create a file

\_wdos\_findfirst find first file matching a specified pattern
\_wfindfirst find first file matching a specified pattern
\_wfullpath return full path specification for file

\_wgetcwd get current working directory \_wgetdcwd get current directory on drive

*\_wmkdir* make a new directory

\_wopen open a file
\_wopendir open directory file
\_wremove delete a file
\_wrename rename a file
\_wrmdir remove a directory

\_wsopen open a file for shared access

\_wstat get file status

\_wtmpnam create name for temporary file

\_wunlink delete a file

\_wutime set modification time for a file

# 1.2 Header Files

The following header files are supplied with the C library. As has been previously noted, when a library function is referenced in a source file, the related header files (shown in the synopsis for that function) should be included into that source file. The header files provide the proper declarations for the functions and for the number and types of arguments used with them. Constant values used in conjunction with the functions are also declared. The files can be included multiple times and in any order.

## 1.2.1 Header Files in /watcom/h

The following header files are provided with the software. The header files that are located in the \WATCOM\H directory are described first.

assert.h This ISO C90 header file is required when an assert macro is used. These assertions

will be ignored when the identifier NDEBUG is defined.

*bios.h* This header file declares all BIOS related functions.

*conio.h* This header file declares console and Intel 80x86 port input/output functions.

ctype.h This ISO C90 header file declares functions that perform character classification and case

conversion operations. Similar functions for wide characters are declared in <wctype.h>.

direct.h This header file declares functions related to directories and the type DIR which describes

an entry in a directory.

dos.h This header file declares functions that interact with DOS and defines the following structures: \_DOSERROR, dosdate\_t, dostime\_t, find\_t, \_wfind\_t

env.h This POSIX header file declares environment string functions.

This ISO C90 header file provides the extern declaration for error variable errno and errno.h provides the symbolic names for error codes that can be placed in the error variable.

fcntl.h This POSIX header file defines the flags used by the open and \_sopen functions. The function declarations for these functions are found in the <io.h> header file.

fenv.h This ISO C99 header file defines several types and declares several functions that give access to the floating point environment. These functions can be used to control status flags and control modes in the floating point processor.

float.h This ISO C90 header file declares constants related to floating-point numbers, declarations for low-level floating-point functions, and the declaration of the floating-point exception codes.

fnmatch.h This header file declares the pattern matching function fnmatch

graph.h This header file contains structure definitions and function declarations for the Open Watcom C Graphics library functions.

i86.h This header file is used with functions that interact with the Intel architecture. It defines the structs and unions used to handle the input and output registers for the Intel 80x86 and 80386/80486 interrupt interface routines. It includes prototypes for the interrupt functions, definitions for the FP\_OFF, FP\_SEG and MK\_FP macros, and definitions for the following structures and unions:

> REGS describes the CPU registers for Intel 8086 family.

**SREGS** describes the segment registers for the Intel 8086 family.

REGPACK describes the CPU registers and segment registers for Intel 8086 family.

**INTPACK** describes the input parameter to an "interrupt" function.

inttypes.h This ISO C99 header file includes <stdint.h> and expands on it by definition macros for printing and scanning specific sized integer types. This header also declares several functions for manipulating maximum sized integers.

> Note that the format macros are not visible in C++ programs unless the macro \_\_\_STDC\_FORMAT\_MACROS is defined.

io.h This header file declares functions that perform input/output operations at the operating system level. These functions use file handles to reference files or devices. The function fstat is declared in the <sys/stat.h> header file.

limits.h This ISO C90 header file contains constant declarations for limits or boundary values for ranges of integers and characters.

locale.h This ISO C90 header file contains declarations for the categories (LC...) of locales which can be selected using the setlocale function which is also declared.

malloc.h This header file declares the memory allocation and deallocation functions.

math.h This ISO/ANSI header file declares the mathematical functions (which operate with floating-point numbers) and the structures:

**exception** describes the exception structure passed to the matherr function;

symbolic constants for the types of exceptions are included

complex declares a complex number

mmintrin.h This header file declares functions that interact with the Intel Architecture Multimedia Extensions. It defines the datatype used to store multimedia values:

\_m64 describes the 64-bit multimedia data element. Note: the underlying implementation details of this datatype are subject to change. Other compilers may implement a similar datatype in a different manner.

It also contains prototypes for multimedia functions and pragmas for the in-line generation of code that operates on multimedia registers.

process.h This header file declares the spawn... functions, the exec... functions, and the system function. The file also contains declarations for the constants P\_WAIT, P\_NOWAITO, and P\_OVERLAY.

search.h This header file declares the functions lfind and lsearch

stdint.h

setjmp.h This ISO C90 header file declares the set jmp and long jmp functions.

share.h This header file defines constants for shared access to files using the \_sopen function.

signal.h This ISO C90 header file declares the signal and raise functions.

stdarg.h This ISO C90 header file defines the macros which handle variable argument lists.

This ISO C99 header file defines the macro bool and the macros true and false for use in C programs. If this header is included in a C++ program there is no effect. The C++ reserved words will not be redefined. However the definition of bool, true, and false used in a C program will be compatible with their C++ counterparts. In particular, a C function declared as taking a bool parameter and a structure containing a bool member can both be shared between C and C++ without error.

stddef.h This ISO C90 header file defines a few popular constants and types including NULL (null pointer), size\_t (unsigned size of an object), and ptrdiff\_t (difference between two pointers). It also contains a declaration for the offsetof macro.

This ISO C99 header file defines numerous type names for integers of various sizes. Such type names provide a reasonably portable way to refer to integers with a specific number of bits. This header file also defines macros that describe the minimum and maximum values for these types (similar to the macros in limits.h), and macros for writing integer constants with specific sized types.

Note that in C++ programs the limit macros are not visible unless the macro \_\_STDC\_LIMIT\_MACROS is defined. Similarly the constant writing macros are not visible unless the macro \_\_STDC\_CONSTANT\_MACROS is defined.

stdio.h This ISO C90 header file declares the standard input/output functions. Files, devices and

directories are referenced using pointers to objects of the type FILE.

stdlib.h This ISO C90 header file declares many standard functions excluding those declared in

other header files discussed in this section.

string.h This ISO C90 header file declares functions that manipulate strings or blocks of memory.

time.h This ISO/ANSI header file declares functions related to times and dates and defines the

structure struct tm.

varargs.h This UNIX System V header file provides an alternate way of handling variable argument

lists. The equivalent ISO/ANSI header file is <stdarg.h>.

wchar.h This ISO C99 header file defines several data types including wchar\_t, size\_t,

mbstate\_t (an object that can hold conversion state information necessary to convert between multibyte characters and wide characters), wctype\_t (a scalar type that can hold values which represent locale-specific character classification), and wint\_t which is an integral type that can hold any wchar\_t value as well as WEOF (a character that is not in the set of "wchar\_t" characters and that is used to indicate *end-of-file* on an input stream). The functions that are declared in this header file are grouped as follows:

Wide character classification and case conversion.

• Input and output of wide characters, or multibyte characters, or both.

• Wide string numeric conversion.

• Wide string manipulation.

• Wide string data and time conversion.

• Conversion between multibyte and wide character sequences.

wetype.h This ISO C99 header file declares functions that perform characater classification and case

conversion operations on wide characters. Similar functions for ordinary characters are declared in <ctype.h>.

# 1.2.2 Header Files in /watcom/h/sys

The following header files are present in the sys subdirectory. Their presence in this directory indicates that they are system-dependent header files.

sys/locking.h This header file contains the manifest constants used by the locking function.

sys/stat.h This POSIX header file contains the declarations pertaining to file status, including

definitions for the fstat and stat functions and for the structure:

stat describes the information obtained for a directory, file or device

sys/timeb.h This header file describes the timeb structure used in conjunction with the ftime

function.

sys/types.h This POSIX header file contains declarations for the types used by system-level calls to

obtain file status or time information.

sys/utime.h This POSIX header file contains a declaration for the utime function and for the

structured type utimbuf used by it.

# 1.3 Global Data

Certain data items are used by the Open Watcom C/C++ run-time library and may be inspected (or changed in some cases) by a program. The defined items are:

\_amblksiz Prototype in <stdlib.h>.

This unsigned int data item contains the increment by which the "break" pointer for memory allocation will be advanced when there is no freed block large enough to satisfy a request to allocate a block of memory. This value may be changed by a program at any

time.

\_\_argc Prototype in <stdlib.h>.

This int item contains the number of arguments passed to main.

\_argv Prototype in <stdlib.h>.

This char \*\* item contains a pointer to a vector containing the actual arguments passed

to main.

daylight Prototype in <time.h>.

This unsigned int has a value of one when daylight saving time is supported in this locale and zero otherwise. Whenever a time function is called, the tzset function is called to set the value of the variable. The value will be determined from the value of the

TZ environment variable.

\_doserrno Prototype in <stdlib.h>.

This int item contains the actual error code returned when a DOS, Windows or OS/2

function fails.

environ Prototype in <stdlib.h>.

This char \*\* \_\_near data item is a pointer to an array of character pointers to the

environment strings.

*errno* Prototype in <errno.h>.

This int item contains the number of the last error that was detected. The run-time library never resets error to 0. Symbolic names for these errors are found in the <erro.h>

header file. See the descriptions for the perror and strerror functions for

information about the text which describes these errors.

**fltused\_** The C compiler places a reference to the fltused\_symbol into any module that uses a

floating-point library routine or library routine that requires floating-point support (e.g., the

use of a float or double as an argument to the printf function).

**\_fmode** Prototype in <stdlib.h>.

This data item contains the default type of file (text or binary) translation for a file. It will

contain a value of either

O BINARY indicates that data is transmitted to and from streams unchanged.

O TEXT

indicates that carriage return characters are added before linefeed characters on output operations and are removed on input operations when they precede linefeed characters.

These values are defined in the <fcntl.h> header file. The value of \_fmode may be changed by a program to change the default behavior of the open, fopen, creat and \_sopen functions. The default setting of \_fmode is O\_TEXT, for text-mode translation. O\_BINARY is the setting for binary mode. You can change the value of \_fmode in either of two ways:

- You can include the object file BINMODE.OBJ when linking your application. This object file contains code to change the initial setting of \_fmode to O\_BINARY, causing all files except stdin, stdout, and stderr to be opened in binary mode.
- You can change the value of \_fmode directly by setting it in your program.

#### \_\_MaxThreads

There is a limit to the number of threads an application can create under 16-bit OS/2 and 32-bit NetWare. The default limit is 32. This limit can be adjusted by statically initializing the unsigned global variable \_\_MaxThreads.

Under 32-bit OS/2, there is no limit to the number of threads an application can create. However, due to the way in which multiple threads are supported in the Open Watcom libraries, there is a small performance penalty once the number of threads exceeds the default limit of 32 (this number includes the initial thread). If you are creating more than 32 threads and wish to avoid this performance penalty, you can redefine the threshold value of 32. You can statically initialize the global variable \_\_\_MaxThreads.

By adding the following line to your multi-threaded application, the new threshold value will be set to 48.

```
unsigned ___MaxThreads = { 48 };
```

minreal

Prototype in <stdlib.h>.

This data item contains the minimum amount of real memory (below 640K) to reserve when running a 32-bit DOS extended application.

optarg

Prototype in <unistd.h>.

This char \* variable contains a pointer to an option-argument parsed by the getopt function.

opterr

Prototype in <unistd.h>.

This int variable controls whether the getopt function will print error messages. The default value is non-zero and will cause the getopt function to print error messages on the console.

optind

Prototype in <unistd.h>.

This int variable holds the index of the argument array element currently processed by the getopt function.

optopt

Prototype in <unistd.h>.

This int variable contains the unrecognized option character in case the getopt function returns an error.

\_osmajor

Prototype in <stdlib.h>.

This unsigned char variable contains the major number for the version of Operating System executing on the computer. By example, if current running DOS version is 3.20, then the value will be 3.

osminor

Prototype in <stdlib.h>.

This unsigned char variable contains the minor number for the version of Operating System executing on the computer. By example, if current running DOS version is 3.20, then the value will be 20.

osbuild

(Win32 only) Prototype in <stdlib.h>.

This unsigned short variable contains the operating system build number for the version of Windows executing on the computer.

\_osver

(Win32 only) Prototype in <stdlib.h>.

This unsigned int variable contains the operating system build number for the version of Windows executing on the computer.

On Win32s or Windows 95/98 platforms, the high bit of the low-order 16-bit word is turned on. Windows 95/98 do not have build numbers.

Note that the Win32 GetVersionEx function is the preferred method for obtaining operating system version number information.

\_osmode

(16-bit only) Prototype in <stdlib.h>.

This unsigned char variable contains either the value DOS\_MODE which indicates the program is running in real address mode, or it contains the value OS2\_MODE which indicates the program is running in protected address mode.

\_psp

Prototype in <stdlib.h>.

This data item contains the segment value for the DOS Program Segment Prefix. Consult the technical documentation for your DOS system for the process information contained in the Program Segment Prefix.

\_stacksize

On 16-bit 80x86 systems, this unsigned int value contains the size of the stack for a TINY memory model program. Changing the value of this item during the execution of a program will have no effect upon the program, since the value is used when the program starts execution. To change the size of the stack to be 8K bytes, a statement such as follows can be included with the program.

```
unsigned int _stacksize = { 8 * 1024 };
```

stdaux

Prototype in <stdio.h>.

This variable (with type FILE \*) indicates the standard auxiliary port (not available in some Windows platforms).

stderr Prototype in <stdio.h>.

This variable (with type FILE \*) indicates the standard error stream (set to the console by

default).

stdin Prototype in <stdio.h>.

This variable (with type FILE \*) indicates the standard input stream (set to the console

by default).

stdout Prototype in <stdio.h>.

This variable (with type FILE \*) indicates the standard output stream (set to the console

by default).

stdprn Prototype in <stdio.h>.

This variable (with type FILE \*) indicates the standard printer. (not available in some

Windows platforms).

sys\_errlist Prototype in <stdlib.h>.

This variable is an array of pointers to character strings for each error code defined in the

<errno.h> header file.

sys\_nerr Prototype in <stdlib.h>.

This int variable contains the number of messages declared in sys\_errlist.

\_threadid Prototype in <stddef.h>.

This variable/function may be used to obtain the id of the current thread which is an int. In the 32-bit libraries, \_threadid is a function that returns a pointer to an int. In the 16-bit libraries, \_threadid is a far pointer to an int. Note that the value stored where \_threadid points does not necessarily change when a thread context switch occurs (so do not make a copy of the pointer ... it may change). To obtain the current thread

do not make a copy of the pointer ... it may change). To obtain the current three identifier, simply code:

int tid = \*\_threadid;

*timezone* Prototype in <time.h>.

This long int contains the number of seconds of time that the local time zone is earlier than Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time (GMT)). Whenever a time function is called, the tzset function is called to set the value

of the variable. The value will be determined from the value of the TZ environment

variable.

*tzname* Prototype in <time.h>.

This array of two pointers to character strings indicates the name of the standard abbreviation for the time zone and the name of the abbreviation for the time zone when daylight saving time is in effect. Whenever a time function is called, the tzset function is called to set the values in the array. These values will be determined from the value of

the TZ environment variable.

\_\_wargc Prototype in <stdlib.h>.

This int item contains the number of arguments passed to wmain.

\_\_wargv Prototype in <stdlib.h>.

This wchar\_t \*\* item contains a pointer to a vector containing the actual arguments passed to wmain.

#### \_wenviron

Prototype in <stdlib.h>.

This wchar\_t \*\* \_\_near data item is a pointer to an array of wide character pointers to the wide character equivalents of the environment strings.

#### \_\_win\_alloc\_flags

Prototype in <stdlib.h>.

This unsigned long int variable contains the flags to be used when allocating memory in Windows.

#### \_\_win\_realloc\_flags

Prototype in <stdlib.h>.

This unsigned long int variable contains the flags to be used when reallocating memory in Windows.

#### \_winmajor

(Windows only) Prototype in <stdlib.h>.

This unsigned int (Win32) or unsigned char (Win16) variable contains the operating system major version number for the version of Windows executing on the computer. For example, the major version number of the Daytona release of Windows NT is 3.

Note that the Win32 GetVersionEx function is the preferred method for obtaining operating system version number information.

#### \_winminor

(Window only) Prototype in <stdlib.h>.

This unsigned int (Win32) or unsigned char (Win16) variable contains the operating system minor version number for the version of Windows executing on the computer. For example, the minor version number of the Daytona release of Windows NT is 5.

Note that the Win32 GetVersionEx function is the preferred method for obtaining operating system version number information.

#### \_winver

(Windows only) Prototype in <stdlib.h>.

This unsigned int variable contains the operating system version number for the version of Windows executing on the computer. The low-order byte contains the minor version number (see also \_winminor). The next byte contains the major version number (see also \_winmajor). The high-order word contains no useful information.

Note that the Win32 GetVersionEx function is the preferred method for obtaining operating system version number information.

## 1.4 The TZ Environment Variable

The TZ environment variable is used to establish the local time zone. The value of the variable is used by various time functions to compute times relative to Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time (GMT)).

The time on the computer should be set to the local time. Use the DOS time command and the DOS date command if the time is not automatically maintained by the computer hardware.

The TZ environment variable can be set (before the program is executed) by using the DOS set command as follows:

```
SET TZ=PST8PDT
```

or (during the program execution) by using the setenv or putenv library functions:

```
setenv( "TZ", "PST8PDT", 1 );
putenv( "TZ=PST8PDT" );
```

The value of the variable can be obtained by using the getenv function:

```
char *tzvalue;
...
tzvalue = getenv( "TZ" );
```

The tzset function processes the TZ environment variable and sets the global variables daylight (indicates if daylight saving time is supported in the locale), timezone (contains the number of seconds of time difference between the local time zone and Coordinated Universal Time (UTC)), and tzname (a vector of two pointers to character strings containing the standard and daylight time-zone names).

The value of the TZ environment variable should be set as follows (spaces are for clarity only):

#### std offset dst offset, rule

On the OS/2 platform, an alternate format is also supported. Please refer to the following section for details.

The expanded format is as follows:

#### stdoffset[dst[offset][,start[/time],end[/time]]]

std, dst

three or more letters that are the designation for the standard (std) or summer (dst) time zone. Only std is required. If dst is omitted, then summer time does not apply in this locale. Upper- and lowercase letters are allowed. Any characters except for a leading colon (:), digits, comma (,), minus (-), plus (+), and ASCII NUL ( $\$ 0) are allowed.

offset

indicates the value one must add to the local time to arrive at Coordinated Universal Time (UTC). The *offset* has the form:

#### hh[:mm[:ss]]

The minutes (mm) and seconds (ss) are optional. The hour (hh) is required and may be a single digit. The offset following std is required. If no offset follows dst, summer time is assumed to be one hour ahead of standard time. One or more digits may be used; the value is always interpreted as a decimal number. The hour may be between 0 and 24, and the minutes (and seconds) - if present - between 0 and 59. If preceded by a "-", the time zone will be east of the Prime Meridian; otherwise it will be west (which may be indicated by an optional preceding "+").

rule

indicates when to change to and back from summer time. The *rule* has the form:

#### date/time,date/time

where the first *date* describes when the change from standard to summer time occurs and the second *date* describes when the change back happens. Each *time* field describes when, in current local time, the change to the other time is made.

The format of *date* may be one of the following:

Jn The Julian day n ( $1 \le n \le 365$ ). Leap days are not counted. That is, in all years - including leap years - February 28 is day 59 and March 1 is day 60. It is impossible to explicitly refer to the occasional February 29.

*n* The zero-based Julian day  $(0 \le n \le 365)$ . Leap years are counted, and it is possible to refer to February 29.

**Mm.n.d** The d'th day  $(0 \le d \le 6)$  of week n of month m of the year  $(1 \le n \le 5, 1 \le m \le 12)$ , where week 5 means "the last d day in month m" which may occur in the fourth or fifth week). Week 1 is the first week in which the d'th day occurs. Day zero is Sunday.

The *time* has the same format as *offset* except that no leading sign ("+" or "-") is allowed. The default, if *time* is omitted, is 02:00:00.

Whenever ctime, \_ctime, localtime, \_localtime or mktime is called, the time zone names contained in the external variable tzname will be set as if the tzset function had been called. The same is true if the %Z directive of strftime is used.

Some examples are:

TZ=EST5EDT Eastern Standard Time is 5 hours earlier than Coordinated Universal Time (UTC). Standard time and daylight saving time both apply to this locale. By default, Eastern Daylight Time (EDT) is one hour ahead of standard time (i.e., EDT4). Since it is not specified, daylight saving time starts on the first Sunday of April at 2:00 A.M. and ends on the last Sunday of October at 2:00 A.M. This is the default when the TZ variable is not set.

#### TZ=EST5EDT4,M4.1.0/02:00:00,M10.5.0/02:00:00

This is the full specification for the default when the TZ variable is not set. Eastern Standard Time is 5 hours earlier than Coordinated Universal Time (UTC). Standard time and daylight saving time both apply to this locale. Eastern Daylight Time (EDT) is one hour ahead of standard time. Daylight saving time starts on the first (1) Sunday (0) of April (4) at 2:00 A.M. and ends on the last (5) Sunday (0) of October (10) at 2:00 A.M.

**TZ=PST8PDT** Pacific Standard Time is 8 hours earlier than Coordinated Universal Time (UTC). Standard time and daylight saving time both apply to this locale. By default, Pacific Daylight Time is one hour ahead of standard time (i.e., PDT7). Since it is not specified, daylight saving time starts on the first Sunday of April at 2:00 A.M. and ends on the last Sunday of October at 2:00 A.M.

#### TZ=NST3:30NDT1:30

Newfoundland Standard Time is 3 and 1/2 hours earlier than Coordinated Universal Time (UTC). Standard time and daylight saving time both apply to this locale. Newfoundland Daylight Time is 1 and 1/2 hours earlier than Coordinated Universal Time (UTC).

#### TZ=Central Europe Time-2:00

Central European Time is 2 hours later than Coordinated Universal Time (UTC). Daylight saving time does not apply in this locale.

# 1.5 The OS/2 TZ Environment Variable

On the OS/2 platform, an alternate format of the TZ environment variable is supported, in addition to the standard format described in the preceding section. The value of the OS/2 TZ environment variable should be set as follows (spaces are for clarity only):

#### std offset dst, rule

This format will be used if after scanning the standard format there are additional fields or the format has not been identified as standard.

The standard format is identified if an offset follows dst; characters J, M, /, or : are found in rule; or some fields are empty.

The alternate expanded format is as follows (fields may not be empty):

#### stdoffsetdst,sm,sw,sd,st,em,ew,ed,et,shift

std, dst

three or more letters that are the designation for the standard (*std*) and summer (*dst*) time zone. Upper- and lowercase letters are allowed. Any characters except for a leading colon (:), digits, comma (,), minus (-), plus (+), and ASCII NUL (\0) are allowed.

offset

indicates the value one must add to the local time to arrive at Coordinated Universal Time (UTC). The *offset* has the form:

#### hh[:mm[:ss]]

The minutes (*mm*) and seconds (*ss*) are optional. The hour (*hh*) is required and may be a single digit. The value is always interpreted as a decimal number. The hour may be between 0 and 24, and the minutes (and seconds) - if present - between 0 and 59. If preceded by a "-", the time zone will be east of the *Prime Meridian*; otherwise it will be west (which may be indicated by an optional preceding "+").

rule

indicates when to change to and back from summer time and the time shift for summer time. The *rule* has the form:

#### sm,sw,sd,st,em,ew,ed,et,shift

where *sm,sw,sd,st* describe when the change from standard to summer time occurs and *em,ew,ed,et* describe when the change back happens.

sm and em specify the starting and ending month (1 - 12) of the summer time.

sw and ew specify the starting and ending week of the summer time. You can specify the last week of the month (-1), or week 1 to 4. Week 0 has a special meaning for the day field (sd or ed).

sd/ed Starting/ending day of dst,

0 - 6 (weekday Sun to Sat ) if sw/ew is not zero,

1 - 31 (day of the month) if sw/ew is zero

st/et Starting/ending time (in seconds after midnight) of the summer time.

shift Amount of time change (in seconds).

An example of the default setting is:

#### TZ=EST5EDT,4,1,0,7200,10,-1,0,7200,3600

This is the full specification for the default when the TZ variable is not set. Eastern Standard Time is 5 hours earlier than Coordinated Universal Time (UTC). Standard time and daylight saving time both apply to this locale. Eastern Daylight Time (EDT) is one hour ahead of standard time. Daylight saving time starts on the first (1) Sunday (0) of April (4) at 2:00 A.M. and ends on the last (-1) Sunday (0) of October (10) at 2:00 A.M.

# 2 Graphics Library

The Open Watcom C Graphics Library consists of a large number of functions that provide graphical image support under DOS and QNX. This chapter provides an overview of this support. The following topics are discussed.

- Graphics Functions
- · Graphics Adapters
- Classes of Graphics Functions
  - 1. Environment Functions
  - 2. Coordinate System Functions
  - 3. Attribute Functions
  - 4. Drawing Functions
  - 5. Text Functions
  - 6. Graphics Text Functions
  - 7. Image Manipulation Functions
  - 8. Font Manipulation Functions
  - 9. Presentation Graphics Functions

Display Functions Analyze Functions Utility Functions

• Graphics Header Files

# 2.1 Graphics Functions

Graphics functions are used to display graphical images such as lines and circles upon the computer screen. Functions are also provided for displaying text along with the graphics output.

# 2.2 Graphics Adapters

Support is provided for both color and monochrome screens which are connected to the computer using any of the following graphics adapters:

- IBM Monochrome Display/Printer Adapter (MDPA)
- IBM Color Graphics Adapter (CGA)
- IBM Enhanced Graphics Adapter (EGA)
- IBM Multi-Color Graphics Array (MCGA)

- IBM Video Graphics Array (VGA)
- Hercules Monochrome Adapter
- SuperVGA adapters (SVGA) supplied by various manufacturers

# 2.3 Classes of Graphics Functions

The functions in the Open Watcom C Graphics Library can be organized into a number of classes:

#### **Environment Functions**

These functions deal with the hardware environment.

#### Coordinate System Functions

These functions deal with coordinate systems and mapping coordinates from one system to another.

#### Attribute Functions

These functions control the display of graphical images.

#### **Drawing Functions**

These functions display graphical images such as lines and ellipses.

#### **Text Functions**

These functions deal with displaying text in both graphics and text modes.

#### **Graphics Text Functions**

These functions deal with displaying graphics text.

#### Image Manipulation Functions

These functions store and retrieve screen images.

#### Font Manipulation Functions

These functions deal with displaying font based text.

#### **Presentation Graphics Functions**

These functions deal with displaying presentation graphics elements such as bar charts and pie charts.

The following subsections describe these function classes in more detail. Each function in the class is noted with a brief description of its purpose.

## 2.3.1 Environment Functions

These functions deal with the hardware environment. The \_getvideoconfig function returns information about the current video mode and the hardware configuration. The \_setvideomode function selects a new video mode.

Some video modes support multiple pages of screen memory. The visual page (the one displayed on the screen) may be different than the active page (the one to which objects are being written).

The following functions are defined:

\_getactivepage get the number of the current active graphics page
\_getvideoconfig get information about the graphics configuration
\_getvisualpage get the number of the current visual graphics page

*\_grstatus* get the status of the most recently called graphics library function *\_setactivepage* set the active graphics page (the page to which graphics objects are

drawn

\_settextrows set the number of rows of text displayed on the screen

\_setvideomode select the video mode to be used

\_setvideomoderows select the video mode and the number of text rows to be used \_setvisualpage set the visual graphics page (the page displayed on the screen)

# 2.3.2 Coordinate System Functions

These functions deal with coordinate systems and mapping coordinates from one system to another. The Open Watcom C Graphics Library supports three coordinate systems:

- 1. Physical coordinates
- 2. View coordinates
- 3. Window coordinates

Physical coordinates match the physical dimensions of the screen. The physical origin, denoted (0,0), is located at the top left corner of the screen. A pixel to the right of the origin has a positive x-coordinate and a pixel below the origin will have a positive y-coordinate. The x- and y-coordinates will never be negative values.

The view coordinate system can be defined upon the physical coordinate system by moving the origin from the top left corner of the screen to any physical coordinate (see the \_setvieworg function). In the view coordinate system, negative x- and y-coordinates are allowed. The scale of the view and physical coordinate systems is identical (both are in terms of pixels)

The window coordinate system is defined in terms of a range of user-specified values (see the \_setwindow function). These values are scaled to map onto the physical coordinates of the screen. This allows for consistent pictures regardless of the resolution (number of pixels) of the screen.

The following functions are defined:

*\_getcliprgn* get the boundary of the current clipping region *\_getphyscoord* get the physical coordinates of a point in view coordinates

\_getphyscoord get the physical coordinates of a point in view coordinates
\_getviewcoord\_w get the view coordinates of a point in physical coordinates
\_getviewcoord\_w get the view coordinates of a point in window coordinates
\_getviewcoord\_wxy get the view coordinates of a point in window coordinates
\_getwindowcoord get the window coordinates of a point in view coordinates

\_setcliprgn set the boundary of the clipping region

\_setvieworg set the position to be used as the origin of the view coordinate system \_setviewport set the boundary of the clipping region and the origin of the view

coordinate system

\_setwindow define the boundary of the window coordinate system

## 2.3.3 Attribute Functions

These functions control the display of graphical images such as lines and circles. Lines and figures are drawn using the current color (see the \_setcolor function), the current line style (see the \_setlinestyle function), the current fill mask (see the \_setfillmask function), and the current plotting action (see the \_setplotaction function).

The following functions are defined:

\_getarcinfo get the endpoints of the most recently drawn arc get the background color \_getbkcolor \_getcolor get the current color \_getfillmask get the current fill mask \_getlinestyle get the current line style \_getplotaction get the current plotting action \_remapallpalette assign colors for all pixel values \_remappalette assign color for one pixel value \_selectpalette select a palette \_setbkcolor set the background color \_setcolor set the current color \_setfillmask set the current fill mask \_setlinestyle set the current line style \_setplotaction set the current plotting action

# 2.3.4 Drawing Functions

These functions display graphical images such as lines and ellipses. Functions exist to draw straight lines (see the \_lineto function), rectangles (see the \_rectangle function), polygons (see the \_polygon function), ellipses (see the \_ellipse function), elliptical arcs (see the \_arc function) and pie-shaped wedges from ellipses (see the \_pie function).

These figures are drawn using the attributes described in the previous section. The functions ending with \_w or \_wxy use the window coordinate system; the others use the view coordinate system.

The following functions are defined:

arc draw an arc draw an arc using window coordinates \_arc\_w \_arc\_wxy draw an arc using window coordinates \_clearscreen clear the screen and fill with the background color \_ellipse draw an ellipse draw an ellipse using window coordinates \_ellipse\_w ellipse wxy draw an ellipse using window coordinates fill an area of the screen with the current color \_floodfill floodfill w fill an area of the screen in window coordinates with the current color get the coordinates of the current output position \_getcurrentposition \_getcurrentposition\_w get the window coordinates of the current output position \_getpixel get the color of the pixel at the specified position \_getpixel\_w get the color of the pixel at the specified position in window draw a line from the current position to a specified position

\_lineto

lineto w draw a line from the current position to a specified position in window

coordinates

moveto set the current output position

\_moveto\_w set the current output position using window coordinates

\_pie draw a wedge of a "pie"

\_pie\_w draw a wedge of a "pie" using window coordinates
\_pie\_wxy draw a wedge of a "pie" using window coordinates

\_polygon draw a polygon

\_polygon\_w draw a polygon using window coordinates \_polygon\_wxy draw a polygon using window coordinates

*\_rectangle* draw a rectangle

\_rectangle\_w draw a rectangle using window coordinates
\_rectangle\_wxy draw a rectangle using window coordinates
\_setpixel set the color of the pixel at the specified position

\_setpixel\_w set the color of the pixel at the specified position in window coordinates

## 2.3.5 Text Functions

These functions deal with displaying text in both graphics and text modes. This type of text output can be displayed in only one size.

This text is displayed using the \_outtext and \_outmem functions. The output position for text follows the last text that was displayed or can be reset (see the \_settextposition function). Text windows can be created (see the \_settextwindow function) in which the text will scroll. Text is displayed with the current text color (see the \_settextcolor function).

The following functions are defined:

\_clearscreen clear the screen and fill with the background color

\_displayeursor determine whether the cursor is to be displayed after a graphics function

completes execution

\_getbkcolorget the background color\_gettextcolorget the color used to display text\_gettextcursorget the shape of the text cursor\_gettextpositionget the current output position for text\_gettextwindowget the boundary of the current text window\_outmendisplay a text string of a specified length

\_outtext display a text string

\_scrolltextwindow scroll the contents of the text window

\_setbkcolor set the background color set the color used to display text settextcursor set the shape of the text cursor settextposition set the output position for text

*\_settextwindow* set the boundary of the region used to display text *\_wrapon* permit or disallow wrap-around of text in a text window

# 2.3.6 Graphics Text Functions

These functions deal with displaying graphics text. Graphics text is displayed as a sequence of line segments, and can be drawn in different sizes (see the \_setcharsize function), with different orientations (see the \_settextorient function) and alignments (see the \_settextalign function).

The functions ending with \_w use the window coordinate system; the others use the view coordinate system.

The following functions are defined:

*\_gettextextent* get the bounding rectangle for a graphics text string

\_gettextsettings get information about the current settings used to display graphics text

\_grtext display graphics text

*\_grtext\_w* display graphics text using window coordinates *\_setcharsize* set the character size used to display graphics text

\_setcharsize\_w set the character size in window coordinates used to display graphics

text

\_setcharspacing set the character spacing used to display graphics text

\_setcharspacing\_w set the character spacing in window coordinates used to display

graphics text

\_settextalign set the alignment used to display graphics text
\_settextorient set the orientation used to display graphics text
\_settextpath set the path used to display graphics text

# 2.3.7 Image Manipulation Functions

These functions are used to transfer screen images. The \_getimage function transfers a rectangular image from the screen into memory. The \_putimage function transfers an image from memory back onto the screen. The functions ending with \_w or \_wxy use the window coordinate system; the others use the view coordinate system.

The following functions are defined:

\_getimage store an image of an area of the screen into memory

\_getimage\_w store an image of an area of the screen in window coordinates into

memory

\_getimage\_wxy store an image of an area of the screen in window coordinates into

memory

*\_imagesize* get the size of a screen area

\_imagesize\_w get the size of a screen area in window coordinates get the size of a screen area in window coordinates get the size of a screen area in window coordinates display an image from memory on the screen

\_putimage\_w display an image from memory on the screen using window coordinates

# 2.3.8 Font Manipulation Functions

These functions are for the display of fonts compatible with Microsoft Windows. Fonts are contained in files with an extension of .FON. Before font based text can be displayed, the fonts must be registered with the \_registerfonts function, and a font must be selected with the \_setfont function.

The following functions are defined:

\_getfontinfo get information about the currently selected font

*\_getgtextextent* get the length in pixels of a text string

\_getgtextvector get the current value of the font text orientation vector

\_outgtext display a string of text in the current font \_registerfonts initialize the font graphics system

\_setfont select a font from among the registered fonts

\_setgtextvector set the font text orientation vector

\_unregisterfonts frees memory allocated by the font graphics system

### 2.3.9 Presentation Graphics Functions

These functions provide a system for displaying and manipulating presentation graphics elements such as bar charts and pie charts. The presentation graphics functions can be further divided into three classes:

### Display Functions

These functions are for the initialization of the presentation graphics system and the displaying of charts.

#### Analyze Functions

These functions calculate default values for chart elements without actually displaying the chart.

### **Utility Functions**

These functions provide additional support to control the appearance of presentation graphics elements.

The following subsections describe these function classes in more detail. Each function in the class is noted with a brief description of its purpose.

### 2.3.9.1 Display Functions

These functions are for the initialization of the presentation graphics system and the displaying of charts. The \_pg\_initchart function initializes the system and should be the first presentation graphics function called. The single-series functions display a single set of data on a chart; the multi-series functions (those ending with ms) display several sets of data on the same chart.

The following functions are defined:

*\_pg\_chart* display a bar, column or line chart

\_pg\_chartms display a multi-series bar, column or line chart

*\_pg\_chartpie* display a pie chart *\_pg\_chartscatter* display a scatter chart

*\_pg\_chartscatterms* display a multi-series scatter chart

\_pg\_defaultchart initialize the chart environment for a specific chart type

pg initchart initialize the presentation graphics system

### 2.3.9.2 Analyze Functions

These functions calculate default values for chart elements without actually displaying the chart. The functions ending with ms analyze multi-series charts; the others analyze single-series charts.

The following functions are defined:

\_pg\_analyzechart analyze a bar, column or line chart

\_pg\_analyzechartms analyze a multi-series bar, column or line chart

*\_pg\_analyzepie* analyze a pie chart *\_pg\_analyzescatter* analyze a scatter chart

\_pg\_analyzescatterms analyze a multi-series scatter chart

### 2.3.9.3 Utility Functions

These functions provide additional support to control the appearance of presentation graphics elements.

The following functions are defined:

\_pg\_getchardef get bit-map definition for a specific character

\_pg\_getpalette get presentation graphics palette (colors, line styles, fill patterns and

plot characters)

\_pg\_getstyleset get presentation graphics style-set (line styles for window borders and

grid lines)

\_pg\_hlabelchart display text horizontally on a chart

*\_pg\_resetpalette* reset presentation graphics palette to default values *\_pg\_resetstyleset* reset presentation graphics style-set to default values

*\_pg\_setchardef* set bit-map definition for a specific character

\_pg\_setpalette set presentation graphics palette (colors, line styles, fill patterns and plot

characters)

\_pg\_setstyleset set presentation graphics style-set (line styles for window borders and

grid lines)

\_pg\_vlabelchart display text vertically on a chart

## 2.4 Graphics Header Files

All program modules which use the Graphics Library should include the header file graph.h. This file contains prototypes for all the functions in the library as well as the structures and constants used by them.

Modules using the presentation graphics functions should also include the header file pgchart.h.

# 3 DOS Considerations

For the most part, DOS (Disk Operating System) for your personal computer can be ignored, unless an application is highly dependent upon the hardware or uses specialized functions from the operating system. In this section, some of these aspects will be addressed. For a more detailed explanation, the technical documentation for the DOS that you are using should be consulted.

## 3.1 DOS Devices

Most of the hardware devices attached to your computer have names which are recognized by DOS. These names cannot be used as the names of files. Some examples are:

CON the console (screen)
AUX the serial (auxiliary) port

COM1 serial port 1COM2 serial port 2

PRN the printer on the parallel port
 LPT1 the printer on the first parallel port
 LPT2 the printer on the second parallel port
 LPT3 the printer on the third parallel port

**NUL** a non-existent device, which accepts (and discards) output

Disks (such as diskette drives and hard disks) are specified as single letters, starting with the letter A. A colon character (:) follows the letter for the drive. Either uppercase or lowercase letters can be used. Some examples are:

A: the first disk drive

a: the first disk drive

e: the fifth disk drive

### 3.2 DOS Directories

Each disk drive is conceptually divided into directories. Each directory is capable of containing files and/or other directories. The initial directory, called the *root directory*, is not named; all other directories are named and can be accessed with a *path* specification. A path is either absolute or relative to the current working directory. Some examples are:

**b:\** the root directory of the second disk drive

\ the root directory of the current disk drive

#### \outer\middle\inner

directory inner which is contained within directory middle which is contained within directory outer which is contained within the root directory of the current disk drive.

Directory names are separated by backslash characters (\). The initial backslash character informs DOS that the path starts with the root directory. When the first character is not a backslash, the path starts with the current working directory on the indicated device.

The DOS CHDIR (CD) command can be used to change the current working directory for a device. Suppose that the following DOS commands were issued:

```
chdir a:\apps\payroll
chdir c:\mydir
```

Then, the following path specifications are:

Relative Path Absolute Path

a:xxx\ya:\apps\payroll\xxx\yc:zzzzzc:\mydir\zzzzz

When no drive is specified, DOS uses the current disk drive.

## 3.3 DOS File Names

The name of a file within a directory has the format filename.ext where the required filename portion is up to eight characters in length and the optional ext portion is up to three characters in length. A period character (.) separates the two names when the ext portion is present.

More than eight characters can be given in the filename. DOS truncates the name to eight characters when a longer filename is given. This may lead to erroneous results in some cases, since the files MYBIGDATAFILE and MYBIGDATES both refer to the file MYBIGDAT.

The characters used in file names may be letters, digits as well as some other characters documented in your DOS technical documentation. Most people restrict their file names to contain only letters and digits. Uppercase and lowercase letters are treated as being equivalent (file names are case insensitive). Thus, the files

```
MYDATA.NEW mydata.new MyData.New
```

all refer to the same file.

You cannot use a DOS device name (such as CON or PRN, for example) for a file name. See the section *DOS Devices* for a list of these reserved names.

A complete file designation has the following format:

```
drive:\path\filename.ext
```

where:

drive: is an optional disk drive specification. If omitted, the default drive is used. Some

examples are:

A: (first disk drive) c: (third disk drive)

**path**\ is the path specification for the directory containing the desired file. Some examples

are:

\mylib\
\apps\payroll\

*filename.ext* is the name of the file.

Suppose that the current working directories are as follows:

Drive Directory

A: \payroll
B: \ (root directory)
C: \source\c

and that the default disk drive is C:. Then, the following file designations will result in the indicated file references:

Designation Actual File

pgm.c C:\SOURCE\C\PGM.C C:\BASIC.DAT

paypgm\outsep.c C:\SOURCE\C\PAYPGM\OUTSEP.C

b:data B:\DATA

a:employee A:\PAYROLL\EMPLOYEE a:\deduct\yr1988 A:\DEDUCT\YR1988

### 3.4 DOS Files

DOS files are stored within directories on disk drives. Most software, including Open Watcom C/C++, treats files in two representations:

**BINARY** These files can contain arbitrary data. It is the responsibility of the software to recognize

records within the file if they exist.

**TEXT** These files contain lines of "printable" characters. Each line is delimited by a carriage

return character followed by a linefeed character.

Since the conceptual view of text files in the C and C++ languages is that lines are terminated by only linefeed characters, the Open Watcom C library will remove carriage returns on input and add them on output, provided the mode is set to be *text*. This mode is set upon opening the file or with the \_setmode function.

## 3.5 DOS Commands

DOS commands are documented in the technical documentation for your DOS system. These may be invoked from a C or C++ program with the system function.

# 3.6 DOS Interrupts

DOS interrupts and 8086 interrupts are documented in the technical documentation for your DOS system. These may be generated from a C or C++ program by calling the bdos, intdos, intdosx, intr, intrf, int386, int386x, int86 and int86x functions.

## 3.7 DOS Processes

Currently, DOS has the capability to execute only one process at a time. Thus, when a process is initiated with the <code>spawn...</code> parameter <code>P\_WAIT</code>, the new process will execute to completion before control returns to the initiating program. Otherwise, the new task replaces the initial task. Tasks can be started by using the <code>system</code>, <code>exec...</code> and <code>spawn...</code> functions.

# 4 Library Functions and Macros

Each of the functions or macros in the C Library is described in this chapter. Each description consists of a number of subsections:

Synopsis:

This subsection gives the header files that should be included within a source file that references the function or macro. It also shows an appropriate declaration for the function or for a function that could be substituted for a macro. This declaration is not included in your program; only the header file(s) should be included.

When a pointer argument is passed to a function and that function does not modify the item indicated by that pointer, the argument is shown with const before the argument. For example,

const char \*string

indicates that the array pointed at by string is not changed.

Constraints: This subsection describes Runtime-constraints for Safer C Library functions.

Safer C: This subsection points to the Safer C version of the described "unsafe" function.

**Description:** This subsection is a description of the function or macro.

**Returns:** This subsection describes the return value (if any) for the function or macro.

*Errors:* This subsection describes the possible errno values.

ISO C

**ISO C99** 

See Also: This optional subsection provides a list of related functions or macros.

**Example:** This optional subsection consists of one or more examples of the use of the function. The examples are often just fragments of code (not complete programs) for illustration purposes.

*Classification:* This subsection provides an indication of where the function or macro is commonly found. The following notation is used:

	9899:1989.
ISO C90	These functions or macros are defined by the ISO/ANSI C standard ISO/IEC 9899:1990.
ISO C95	These functions or macros are defined by the ISO/ANSI C standard ISO/IEC 9899:1990/AMD 1:1995.

These functions or macros are defined by the ISO/ANSI C standard ISO/IEC

These functions or macros are defined by the ISO/ANSI C standard ISO/IEC

9899:1999.

**POSIX 1003.1** The functions or macros are not defined by the ISO C standard. These functions are

specified in the document IEEE Standard Portable Operating System Interface for

Computer Environments (IEEE Draft Standard 1003.1-1990).

**POSIX 1003.2** These functions or macros are not defined by the ISO C standard. These functions are

specified in the document *Shell and Utility Application Interface for Computer Operating System Environments* (IEEE Computer Society Working Group 1003.2).

**POSIX 1003.4** These functions or macros are not defined by the ISO C standard. These functions are

specified in the document Realtime Extensions for Computer Operating System

Environments (IEEE Computer Society Working Group 1003.4).

**Intel** These functions or macros are neither ISO C nor POSIX. It performs a function

related to the Intel x86 architecture. It may be found in other implementations of C for personal computers using Intel chips. Use these functions with caution, if

portability is a consideration.

BIOS These functions access a service of the BIOS found in IBM Personal Computers and

compatibles. These functions should not be used if portability is a consideration.

**DOS** These functions or macros are neither ISO C nor POSIX. They perform a function

related to DOS. They may be found in other implementations of C for personal computers with DOS. Use these functions with caution, if portability is a

consideration.

OS/2 These functions are specific to OS/2.

**PC Graphics** These functions are part of the PC graphics library.

**Windows** These functions are specific to Microsoft Windows.

WATCOM These functions or macros are neither ISO C nor POSIX. They may be found in other

implementations of the C language, but caution should be used if portability is a

consideration.

TR 24731 These functions are "safer" versions of normal C library functions. They perform

more checks on parameters and should be used in preference over their "unsafe"

version.

Systems: This subsection provides an indication of where the function or macro is supported. The following notation

is used:

All This function is available on all systems (we do not include RDOS, Linux, Netware or

DOS/PM in this category).

**DOS** This function is available on both 16-bit DOS and 32-bit extended DOS.

**DOS/16** This function is available on 16-bit, real-mode DOS.

**DOS/32** This function is available on 32-bit, protected-mode extended DOS.

**DOS/PM** This 16-bit DOS protected-mode function is supported under Phar Lap's

286|DOS-Extender "RUN286". The function is found in one of Open Watcom's

16-bit protected-mode DOS libraries (DOSPM\*.LIB under the 16-bit OS2

subdirectory).

**Linux** This function is available on the Linux operating system for Intel 80386 and upwards

compatible systems.

**MACRO** This function is implemented as a macro (#define) on all systems.

**Math** This function is a math function. Math functions are available on all systems.

**Netware** This function is available on the 32-bit Novell Netware operating system.

OS/2 1.x This function is available on IBM OS/2 1.x, a 16-bit protected-mode system for Intel

80286 and upwards compatible systems.

When "(MT)" appears after OS/2, it refers to the CLIBMTL library which supports

multi-threaded applications.

When "(DL)" appears after OS/2, it refers to the CLIBDLL library which supports

creation of Dynamic Link Libraries.

When "(all)" appears after "OS/2 1", it means all versions of the OS/2 1.x libraries.

If a function is missing from the OS/2 library, it may be found in Open Watcom's

16-bit protected-mode DOS libraries (DOSPM\*.LIB) for Phar Lap's

286 DOS-Extender (RUN286).

OS/2-32 This function is available on 32-bit IBM OS/2, a protected-mode system for Intel

80386 and upwards compatible systems.

**RDOS** This function is available on RDOS operating system.

**QNX** This function is available on QNX Software Systems' 16 or 32-bit operating systems.

**QNX/16** This function is available on QNX Software Systems' 16-bit operating system.

QNX/32 This function is available on QNX Software Systems' 32-bit operating system.

**Windows** This function is available on 16-bit, protected-mode Windows 3.x.

Win386 This function is available on Microsoft Windows 3.x, using Open Watcom's

Windows Extender for 32-bit protected-mode applications running on Intel 386 or

upward compatible systems.

Win32 This function is available on 32-bit Microsoft Windows platforms (Windows 95,

Windows 98, Windows NT, Windows 2000, etc.). It may also be available for

Windows 3.x using Win32s support.

Open Watcom C Library Reference								
		<del></del>						

Synopsis: #include <stdlib.h>
 void abort( void );

**Description:** The abort function raises the signal SIGABRT. The default action for SIGABRT is to terminate

program execution, returning control to the process that started the calling program (usually the operating system). The status *unsuccessful termination* is returned to the invoking process by means of the function call raise (SIGABRT). The exit code returned to the invoking process is

EXIT\_FAILURE which is defined in the <stdlib.h> header file.

**Returns:** The abort function does not return to its caller.

See Also: atexit, \_bgetcmd, exec..., exit, \_Exit, \_exit, getcmd, getenv, main, putenv,

spawn..., system, \_wsystem

Example: #include <stdlib.h>

```
void main()
{
   int major_error = 1;
   if( major_error )
       abort();
}
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

```
#define __STDC_WANT_LIB_EXT1__ 1
Synopsis:
            #include <stdlib.h>
            void abort_handler_s(
                     const char * restrict msg,
                     void * restrict ptr,
                     errno_t error );
           The abort_handler_s function may be passed as an argument to the
Description:
            set_constraint_handler_s function. It writes a message on the standard error stream in the
            following format:
                Runtime-constraint violation: <msg>
            The abort_handler_s function then calls the abort function.
Returns:
            The abort_handler_s function does not return to its caller.
See Also:
            ignore_handler_s, set_constraint_handler_s
            #define __STDC_WANT_LIB_EXT1__ 1
Example:
            #include <stdlib.h>
            #include <stdio.h>
            void main( void )
                constraint_handler_t old_handler;
                old_handler = set_constraint_handler_s( abort_handler_s );
                if( getenv_s( NULL, NULL, 0, NULL ) ) {
                     printf( "getenv_s failed\n" );
                set_constraint_handler_s( old_handler );
            }
            produces the following:
            Runtime-constraint violation: getenv_s, name == NULL.
            ABNORMAL TERMINATION
Classification: TR 24731
            All, Linux, RDOS, Netware
Systems:
```

```
Synopsis: #include <stdlib.h>
int abs(int j);
```

**Description:** The abs function returns the absolute value of its integer argument j.

**Returns:** The abs function returns the absolute value of its argument.

```
See Also: labs, llabs, imaxabs, fabs
```

produces the following:

5 0 5

Classification: ISO C90

**Systems:** All, Linux, RDOS, Netware

#### Synopsis:

```
#include <io.h>
int access( const char *path, int mode );
int _access( const char *path, int mode );
int _waccess( const wchar_t *path, int mode );
```

#### **Description:**

The access function determines if the file or directory specified by *path* exists and if it can be accessed with the file permission given by *mode*.

When the value of *mode* is zero, only the existence of the file is verified. The read and/or write permission for the file can be determined when *mode* is a combination of the bits:

Bit	Meaning
$R\_OK$	test for read permission
W_OK	test for write permission
X_OK	test for execute permission
F_OK	test for existence of file

chmod, fstat, open, \_sopen, stat

With DOS, all files have read permission; it is a good idea to test for read permission anyway, since a later version of DOS may support write-only files.

The \_access function is identical to access. Use \_access for ANSI naming conventions.

The \_waccess function is a wide character version of access that operates with wide character strings.

### **Returns:**

The access function returns zero if the file or directory exists and can be accessed with the specified mode. Otherwise, -1 is returned and errno is set to indicate the error.

#### Errors:

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning
EACCES	Access denied because the file's permission does not allow the specified access.
ENOENT	Path or file not found.

### Example:

See Also:

```
#include <stdio.h>
#include <stdlib.h>
#include <io.h>

void main( int argc, char *argv[] )
   {
    if( argc != 2 ) {
        fprintf( stderr, "Use: check <filename>\n" );
        exit( 1 );
    }
}
```

```
if( access( argv[1], F_OK ) == 0 ) {
    printf( "%s exists\n", argv[1] );
} else {
    printf( "%s does not exist\n", argv[1] );
    exit( EXIT_FAILURE );
}
if( access( argv[1], R_OK ) == 0 ) {
    printf( "%s is readable\n", argv[1] );
}
if( access( argv[1], W_OK ) == 0 ) {
    printf( "%s is writeable\n", argv[1] );
}
if( access( argv[1], X_OK ) == 0 ) {
    printf( "%s is executable\n", argv[1] );
}
exit( EXIT_SUCCESS );
}
```

### Classification: POSIX 1003.1

\_access conforms to ANSI naming conventions

Systems: access - All, Linux, RDOS, Netware

\_access - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS \_waccess - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

Synopsis: #include <math.h>

double acos ( double x );

**Description:** The acos function computes the principal value of the arccosine of x. A domain error occurs for

arguments not in the range [-1,1].

**Returns:** The acos function returns the arccosine in the range  $[0,\pi]$ . When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: asin, atan, atan2, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
     {
        printf( "%f\n", acos(.5) );
     }
}
```

produces the following:

1.047197

Classification: ISO C

Synopsis: #include <math.h>

double acosh ( double x );

**Description:** The acosh function computes the inverse hyperbolic cosine of x. A domain error occurs if the value of

x is less than 1.0.

**Returns:** The acosh function returns the inverse hyperbolic cosine value. When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: asinh, atanh, cosh, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", acosh( 1.5 ) );
}
```

produces the following:

0.962424

**Classification:** WATCOM

Synopsis: #include <malloc.h>
 void \*alloca( size\_t size );

**Description:** The alloca function allocates space for an object of *size* bytes from the stack. The allocated space is

automatically discarded when the current function exits. The alloca function should not be used in

an expression that is an argument to a function.

Returns: The alloca function returns a pointer to the start of the allocated memory. The return value is NULL

if there is insufficient stack space available.

See Also: calloc, malloc, stackavail

Example: #include <stdio.h>
#include <string.h>

}

#include <malloc.h>
FILE \*open\_err\_file( char \* );

{
 FILE \*fp;

void main()

if( fp == NULL ) {
 printf( "Unable to open error file\n" );
} else {
 fclose( fp );

fp = open\_err\_file( "alloca" );

FILE \*open\_err\_file( char \*name )
 {
 char \*buffer;

/\* allocate temp buffer for file name \*/
buffer = (char \*) alloca( strlen(name) + 5 );
if( buffer ) {
 sprintf( buffer, "%s.err", name );
 return( fopen( buffer, "w" ) );

}
return( (FILE \*) NULL );
}

**Classification: WATCOM** 

**Systems:** MACRO

### **Synopsis:**

#### **Description:**

The \_arc functions draw elliptical arcs. The \_arc function uses the view coordinate system. The \_arc\_w and \_arc\_wxy functions use the window coordinate system.

The center of the arc is the center of the rectangle established by the points (x1,y1) and (x2,y2). The arc is a segment of the ellipse drawn within this bounding rectangle. The arc starts at the point on this ellipse that intersects the vector from the centre of the ellipse to the point (x3,y3). The arc ends at the point on this ellipse that intersects the vector from the centre of the ellipse to the point (x4,y4). The arc is drawn in a counter-clockwise direction with the current plot action using the current color and the current line style.

The following picture illustrates the way in which the bounding rectangle and the vectors specifying the start and end points are defined.



When the coordinates (x1, y1) and (x2, y2) establish a line or a point (this happens when one or more of the x-coordinates or y-coordinates are equal), nothing is drawn.

The current output position for graphics output is set to be the point at the end of the arc that was drawn.

**Returns:** The \_arc functions return a non-zero value when the arc was successfully drawn; otherwise, zero is

returned.

 $\textbf{See Also:} \qquad \texttt{\_ellipse}, \texttt{\_pie}, \texttt{\_rectangle}, \texttt{\_getarcinfo}, \texttt{\_setcolor}, \texttt{\_setlinestyle},$ 

\_setplotaction

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    _setvideomode( _VRES16COLOR );
    _arc( 120, 90, 520, 390, 500, 20, 450, 460 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

Systems: \_arc - DOS \_arc\_w - DOS

\_arc\_wxy - DOS

		_arc Functions

### **Synopsis:**

**Safer C:** The Safer C Library extension provides the asctime\_s function which is a safer alternative to asctime.

**Description:** 

The **asctime** functions convert the time information in the structure pointed to by *timeptr* into a string containing exactly 26 characters. This string has the form shown in the following example:

```
Sat Mar 21 15:58:27 1987\n\0
```

All fields have a constant width. The new-line character ' $\n'$  and the null character ' $\n'$  occupy the last two positions of the string.

The ISO C function **asctime** places the result string in a static buffer that is re-used each time **asctime** or ctime is called. The non-ISO C function \_asctime places the result string in the buffer pointed to by *buf*.

The \_wasctime and \_\_wasctime functions are identical to their asctime and \_asctime counterparts except that they deal with wide character strings.

**Returns:** The **asctime** functions return a pointer to the character string result.

**See Also:** asctime\_s, clock, ctime Functions, ctime\_s, difftime, gmtime\_s, localtime, localtime\_s, mktime, strftime, time, tzset

Example:

```
#include <stdio.h>
#include <time.h>

void main()
{
    struct tm time_of_day;
    time_t ltime;
    auto char buf[26];
```

### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <time.h>
errno_t asctime_s( char * s,
                               rsize_t maxsize,
                                const struct tm * timeptr);
errno_t _wasctime_s( wchar_t * s,
                                   rsize_t maxsize,
                                    const struct tm * timeptr);
struct tm {
  int tm_sec; /* seconds after the minute -- [0,61] */
int tm_min; /* minutes after the hour -- [0,59] */
int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
   int tm_year; /* years since 1900 */
int tm_wday; /* days since Sunday -- [0,6] */
int tm_yday; /* days since January 1 -- [0,365]*/
   int tm_isdst; /* Daylight Savings Time flag
};
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and asctime\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither s nor timeptr shall be a null pointer. maxsize shall not be less than 26 and shall not be greater than RSIZE\_MAX. The broken-down time pointed to by timeptr shall be normalized. The calendar year represented by the broken-down time pointed to by timeptr shall not be less than calendar year 0 and shall not be greater than calendar year 9999. If there is a runtime-constraint violation, there is no attempt to convert the time, and s[0] is set to a null character if s is not a null pointer and maxsize is not zero and is not greater than RSIZE\_MAX.

### **Description:**

The asctime\_s function converts the normalized broken-down time in the structure pointed to by timeptr into a 26 character (including the null character) string in the form

```
Sun Sep 16 01:03:52 1973\n\0
```

The fields making up this string are (in order):

1. The name of the day of the week represented by timeptr->tm\_wday using the following three character weekday names:

```
Sun, Mon, Tue, Wed, Thu, Fri, and Sat.
```

- 2. The character space.
- The name of the month represented by timeptr->tm\_mon using the following three character month names:

```
Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, and Dec.
```

- 4. The character space.
- 5. The value of *timeptr->tm\_mday* as if printed using the fprintf format "%2d".

- 6. The character space.
- 7. The value of timeptr->tm\_hour as if printed using the fprintf format "%.2d".
- 8. The character colon.
- 9. The value of *timeptr->tm\_min* as if printed using the fprintf format "%.2d".
- 10. The character colon.
- 11. The value of *timeptr->tm\_sec* as if printed using the fprintf format "%.2d".
- 12. The character space.
- 13. The value of *timeptr->tm\_year + 1900* as if printed using the fprintf format "%4d".
- 14. The character new line.
- 15. The null character.

The \_wasctime\_s function is a wide character version of asctime\_s that operates with wide character strings.

**Returns:** The asctime\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

**See Also:** asctime Functions, clock, ctime Functions, ctime\_s, difftime, gmtime\_s, localtime, localtime\_s, mktime, strftime, time, tzset

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <time.h>

void main()
{
    struct tm time_of_day;
    time_t ltime;
    auto char buf[26];

    time( &ltime );
    _localtime( &ltime, &time_of_day );
    asctime_s( buf, sizeof( buf ), &time_of_day );
    printf( "Date and time is: %s\n", buf );
}
```

produces the following:

Date and time is: Mon Jan 30 11:32:45 2006

Classification: TR 24731

\_wasctime\_s is WATCOM

Systems: asctime\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware

\_wasctime\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux

Synopsis: #include <math.h>

double asin( double x);

**Description:** The asin function computes the principal value of the arcsine of x. A domain error occurs for

arguments not in the range [-1,1].

**Returns:** The asin function returns the arcsine in the range  $[-\pi/2,\pi/2]$ . When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: acos, atan, atan2, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
     {
        printf( "%f\n", asin(.5) );
     }
}
```

produces the following:

0.523599

**Classification:** ISO C

**Description:** The asinh function computes the inverse hyperbolic sine of x.

**Returns:** The asinh function returns the inverse hyperbolic sine value.

See Also: acosh, atanh, sinh, matherr

```
Example: #include <stdio.h>
#include <math.h>

void main()
{
    printf( "%f\n", asinh( 0.5 ) );
}
```

produces the following:

0.481212

**Classification:** WATCOM

Synopsis: #include <assert.h>
 void assert(int expression);

**Description:** 

The assert macro prints a diagnostic message upon the stderr stream and terminates the program if expression is false (0). The diagnostic message has the form

Assertion failed: expression, file filename, line linenumber

where *filename* is the name of the source file and *linenumber* is the line number of the assertion that failed in the source file. *Filename* and *linenumber* are the values of the preprocessing macros \_\_\_FILE\_\_ and \_\_LINE\_\_ respectively. No action is taken if *expression* is true (non-zero).

The assert macro is typically used during program development to identify program logic errors. The given *expression* should be chosen so that it is true when the program is functioning as intended. After the program has been debugged, the special "no debug" identifier NDEBUG can be used to remove assert calls from the program when it is re-compiled. If NDEBUG is defined (with any value) with a -d command line option or with a #define directive, the C preprocessor ignores all assert calls in the program source.

**Returns:** The assert macro does not return a value.

**Example:** 

```
#include <stdio.h>
#include <assert.h>

void process_string( char *string )
{
    /* use assert to check argument */
    assert( string != NULL );
    assert( *string != '\0' );
    /* rest of code follows here */
}

void main()
{
    process_string( "hello" );
    process_string( "" );
}
```

**Classification:** ISO C

**Systems:** MACRO

**Description:** The atan function computes the principal value of the arctangent of x.

**Returns:** The atan function returns the arctangent in the range  $(-\pi/2, \pi/2)$ .

See Also: acos, asin, atan2

Example: #include <stdio.h>
#include <math.h>

void main()
{
 printf( "%f\n", atan(.5) );
}

produces the following:

0.463648

Classification: ISO C

Synopsis: #include <math.h>

double at an 2 ( double y, double x );

**Description:** The atan2 function computes the principal value of the arctangent of y/x, using the signs of both

arguments to determine the quadrant of the return value. A domain error occurs if both arguments are

zero.

**Returns:** The atan2 function returns the arctangent of y/x, in the range  $(-\pi,\pi)$ . When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: acos, asin, atan, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", atan2( .5, 1. ) );
}
```

produces the following:

0.463648

**Classification:** ISO C

Synopsis: #include <math.h>

double atanh ( double x );

**Description:** The atanh function computes the inverse hyperbolic tangent of x. A domain error occurs if the value

of x is outside the range (-1,1).

**Returns:** The atanh function returns the inverse hyperbolic tangent value. When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: acosh, asinh, matherr, tanh

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", atanh( 0.5 ) );
}
```

produces the following:

0.549306

**Classification:** WATCOM

```
Synopsis: #include <stdlib.h>
    int atexit( void (*func) (void) );
```

**Description:** The atexit function is passed the address of function *func* to be called when the program terminates

normally. Successive calls to atexit create a list of functions that will be executed on a "last-in, first-out" basis. No more than 32 functions can be registered with the atexit function.

The functions have no parameters and do not return values.

**Returns:** The atexit function returns zero if the registration succeeds, non-zero if it fails.

```
See Also: abort, _Exit, _exit, exit
```

```
Example:
```

```
#include <stdio.h>
#include <stdlib.h>
void main()
  {
    extern void func1(void), func2(void), func3(void);
    atexit( func1 );
    atexit (func2);
    atexit (func3);
    printf( "Do this first.\n" );
  }
void func1(void) { printf( "last.\n" ); }
void func2(void) { printf( "this " ); }
void func3(void) { printf( "Do " ); }
produces the following:
Do this first.
Do this last.
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

Synopsis: #include <stdlib.h>

double atof( const char \*ptr );
double \_wtof( const wchar\_t \*ptr );

**Description:** The atof function converts the string pointed to by *ptr* to double representation. It is equivalent to

```
strtod( ptr, (char **)NULL )
```

The \_wtof function is a wide character version of atof that operates with wide character strings. It is equivalent to

```
wcstod( ptr, (wchar_t **)NULL )
```

**Returns:** 

The atof function returns the converted value. Zero is returned when the input string cannot be converted. In this case, errno is not set. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: sscanf, strtod

Example: #include <stdlib.h>

```
void main()
{
    double x;

    x = atof( "3.1415926" );
}
```

Classification: ISO C

Systems: atof - Math \_wtof - Math

```
Synopsis:
             #include <stdlib.h>
             int atoi( const char *ptr );
             int _wtoi( const wchar_t *ptr );
Description:
             The atoi function converts the string pointed to by ptr to int representation.
             The _wtoi function is a wide character version of atoi that operates with wide character strings.
Returns:
             The atoi function returns the converted value.
See Also:
             atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull,
             strtoimax, strtoumax, ultoa, ulltoa, utoa
Example:
             #include <stdlib.h>
             void main()
                  int x;
```

**Classification:** ISO C

Systems: atoi - All, Linux, RDOS, Netware \_wtoi - All, Linux, RDOS

x = atoi("-289");

**Library Functions and Macros** 

```
Synopsis:
             #include <stdlib.h>
             long int atol( const char *ptr );
             long int _wtol( const wchar_t *ptr );
Description:
            The atol function converts the string pointed to by ptr to long int representation.
             The _wtol function is a wide character version of atol that operates with wide character strings.
Returns:
             The atol function returns the converted value.
See Also:
             atoi, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull,
             strtoimax, strtoumax, ultoa, ulltoa, utoa
Example:
             #include <stdlib.h>
             void main()
                  long int x;
                 x = atol("-289");
Classification: ISO C
Systems:
             atol - All, Linux, RDOS, Netware
             _wtol - All, Linux, RDOS
```

```
Synopsis:
             #include <stdlib.h>
             long long int atoll( const char *ptr );
             long long int _wtoll( const wchar_t *ptr );
Description:
            The atoll function converts the string pointed to by ptr to long long int representation.
            The _wtoll function is a wide character version of atoll that operates with wide character strings.
Returns:
             The atoll function returns the converted value.
See Also:
             atoi, atol, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull,
             strtoimax, strtoumax, ultoa, ulltoa, utoa
Example:
             #include <stdlib.h>
             void main()
                 long int x;
                 x = atoll("-289356768201");
Classification: ISO C
Systems:
             atoll - All, Linux, RDOS, Netware
            _wtoll - All, Linux, RDOS
```

```
Synopsis: #include <stdlib.h>
    wchar_t *_atouni( wchar_t *wcs, const char *sbcs );
```

**Description:** The \_atouni function converts the string pointed to by *sbcs* to a wide character string and places it in

the buffer pointed to by wcs.

The conversion ends at the first null character.

**Returns:** The \_atouni function returns the first argument as a result.

See Also: atoi, atol, itoa, ltoa, strtod, strtol, strtoul, ultoa, utoa

Example: #include <stdlib.h>

void main()
{
 wchar\_t wcs[12];
 \_atouni( wcs, "Hello world" );

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

#### **Description:**

The basename function returns a pointer to the final component of a pathname pointed to by the *path* argument, deleting trailing path separators.

If the string pointed to by *path* consists entirely of path separators, a string consisting of single path separator is returned.

If path is a null pointer or points to an empty string, a pointer to the string "." is returned.

The basename function may modify the string pointed to by *path* and may return a pointer to static storage that may be overwritten by a subsequent call to basename

The basename function is not re-entrant or thread-safe.

**Returns:** The basename function returns a pointer to the final component of *path*.

See Also: dirname

### **Example:**

```
#include <stdio.h>
#include <libgen.h>

int main( void )
{

   puts( basename( "/usr/lib" ) );
   puts( basename( "//usr//lib//" ) );
   puts( basename( "//" ) );
   puts( basename( "foo" ) );
   puts( basename( NULL ) );
   return( 0 );
}
```

produces the following:

lib lib / foo

Classification: POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

Synopsis: #include <dos.h>

int bdos( int dos\_func, unsigned dx, unsigned char al );

**Description:** 

The bdos function causes the computer's central processor (CPU) to be interrupted with an interrupt number hexadecimal 21 (0x21), which is a request to invoke a specific DOS function. Before the interrupt, the DX register is loaded from dx, the AH register is loaded with the DOS function number from  $dos\_func$  and the AL register is loaded from al. The remaining registers are passed unchanged to DOS.

You should consult the technical documentation for the DOS operating system you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The bdos function returns the value of the AX register after the interrupt has completed.

See Also: int386, int386x, int86, int86x, intdos, intdosx, intr, intrf, segread

Example: #include <dos.h>

```
#define DISPLAY_OUTPUT 2

void main()
{
   int rc;

   rc = bdos( DISPLAY_OUTPUT, 'B', 0 );
   rc = bdos( DISPLAY_OUTPUT, 'D', 0 );
   rc = bdos( DISPLAY_OUTPUT, 'O', 0 );
   rc = bdos( DISPLAY_OUTPUT, 'S', 0 );
}
```

Classification: DOS

**Systems:** DOS, Windows, Win386, DOS/PM

### **Synopsis:**

```
#include <process.h>
#if defined(__386__)
   define FAR
#else
   define FAR ___far
#endif
#if defined(__NT___)
unsigned long _beginthread(
        void (*start_address) (void *),
        unsigned stack_size,
        void
               *arglist);
unsigned long _beginthreadex(
        void *security,
        unsigned stack_size,
        unsigned (__stdcall *start_address) (void *),
        void *arglist,
        unsigned initflag,
        unsigned *thrdid );
#else
int FAR _beginthread(
        void (FAR *start_address) (void FAR *),
        void FAR *stack_bottom,
        unsigned stack_size,
        void FAR *arglist );
#endif
```

### **Description:**

The \_beginthread function is used to start a new thread of execution at the function identified by *start\_address* with a single parameter identified by *arglist*.

For each operating environment under which \_beginthread is supported, the \_beginthread function uses the appropriate system call to begin a new thread of execution.

The new thread will use the memory identified by *stack\_bottom* and *stack\_size* for its stack.

Note for 16-bit applications: If the stack is not in DGROUP (i.e., the stack pointer does not point to an area in DGROUP) then you must compile your application with the "zu" option. For example, the pointer returned by malloc in a large data model may not be in DGROUP. The "zu" option relaxes the restriction that the SS register contains the base address of the default data segment, "DGROUP". Normally, all data items are placed into the group DGROUP and the SS register contains the base address of this group. In a thread, the SS register will likely not contain the base address of this group. When the "zu" option is selected, the SS register is volatile (assumed to point to another segment) and any global data references require loading a segment register such as DS with the base address of DGROUP.

*Note for OS/2 32-bit applications:* Memory for a stack need not be provided by the application. The *stack\_bottom* may be NULL in which case the run-time system will provide a stack. You must specify a non-zero *stack\_size* for this stack.

*Note for Win32 applications:* Memory for a stack is provided by the run-time system. The size of the stack is determined by *stack\_size* and must not be zero.

The \_beginthreadex function can be used to create a new thread, in a running or suspended state specified by *initflag*, with security attributes specified by *security*.

The initial state of the new thread (running or suspended) is specified by the *initflag* argument. If the CREATE\_SUSPENDED flag (WINBASE.H) is specified, the thread is created in a suspended state, and will not run until the Win32 ResumeThread function is called with the thread handle as an argument. If this value is zero, the thread runs immediately after creation.

The security descriptor for the new thread is specified by the *security* argument. This is a pointer to a Win32 SECURITY\_ATTRIBUTES structure (see Microsoft's *Win32 Programmer's Reference* for more information). For default behaviour, the security structure pointer can be NULL.

The thread identifier is returned in the location identified by the *thrdid* argument.

The thread ends when it exits from its main function or calls exit, \_Exit, \_exit, \_endthread or \_endthreadex.

The variable/function \_threadid which is defined in <stddef.h> may be used by the executing thread to obtain its thread ID. In the 16-bit libraries, \_threadid is a far pointer to an int. In the 32-bit libraries, it is a function that returns an int.

There is no limit to the number of threads an application can create under Win32 platforms.

There is a limit to the number of threads an application can create under 16-bit OS/2 and 32-bit NetWare. The default limit is 32. This limit can be adjusted by statically initializing the unsigned global variable \_\_MaxThreads.

Under 32-bit OS/2, there is no limit to the number of threads an application can create. However, due to the way in which multiple threads are supported in the Open Watcom libraries, there is a small performance penalty once the number of threads exceeds the default limit of 32 (this number includes the initial thread). If you are creating more than 32 threads and wish to avoid this performance penalty, you can redefine the threshold value of 32. You can statically initialize the global variable \_\_MaxThreads.

By adding the following line to your multi-threaded application, the new threshold value will be set to 48.

```
unsigned __MaxThreads = { 48 };
```

**Returns:** 

Under Win32, the \_beginthread function returns the thread handle for the new thread if successful; otherwise it returns -1 to indicate that the thread could not be started.

Under all other systems that support the \_beginthread function (OS/2, Netware and QNX), it returns the thread ID for the new thread if successful; otherwise it returns -1 to indicate that the thread could not be started.

The \_beginthreadex function returns the thread handle for the new thread if successful; otherwise it returns 0 to indicate that the thread could not be started.

When the thread could not be started, the value of errno could be set to EAGAIN if there are too many threads, or to EINVAL if the argument is invalid or the stack size is incorrect, or to ENOMEM if there is not enough available memory.

See Also: \_endthread

# **Example:**

```
#include <stdio.h>
#include <stdlib.h>
#include <stddef.h>
#include <malloc.h>
#include cess.h>
#include <dos.h>
#if defined(__386__)
  #define FAR
  #define STACK_SIZE
                       8192
#else
  #define FAR
                        __far
                       4096
  #define STACK_SIZE
#endif
static volatile int
                       WaitForThread;
void FAR child( void FAR *parm )
   char * FAR *argv = (char * FAR *) parm;
    int i;
    printf( "Child thread ID = %x\n", *_threadid );
    for( i = 0; argv[i]; i++ ) {
     printf( "argv[%d] = %s\n", i, argv[i] );
   WaitForThread = 0;
    _endthread();
```

```
void main()
 {
    char
                   *args[3];
#if defined(__NT___)
    unsigned long tid;
#else
    char
                   *stack;
    int
                    tid;
#endif
    args[0] = "child";
    args[1] = "parm";
    args[2] = NULL;
    WaitForThread = 1;
#if defined(__NT__)
    tid = _beginthread( child, STACK_SIZE, args );
    printf( "Thread handle = lx \n", tid );
#else
  #if defined(__386__)
    stack = (char *) malloc( STACK_SIZE );
    stack = (char *) _nmalloc( STACK_SIZE );
  #endif
    tid = _beginthread( child, stack, STACK_SIZE, args );
    printf( "Thread ID = %x\n", tid );
#endif
    while( WaitForThread ) {
        sleep( 0 );
  }
```

# **Classification:** WATCOM

Systems: \_beginthread - Win32, OS/2 1.x(MT), OS/2 1.x(DL), OS/2-32, Linux, RDOS, Netware \_beginthreadex - Win32

**Description:** Functions j0, j1, and jn return Bessel Functions of the first kind.

Functions y0, y1, and yn return Bessel Functions of the second kind. The argument x must be positive. If x is negative, will be called to print a DOMAIN error message to stderr, set errno to EDOM, and return the value  $-HUGE\_VAL$ . This error handling can be modified by using the matherr routine.

**Returns:** These functions return the result of the desired Bessel Function of x.

See Also: matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
{
    double x, y, z;

    x = j0(2.4);
    y = y1(1.58);
    z = jn(3, 2.4);
    printf("j0(2.4) = %f, y1(1.58) = %f\n", x, y);
    printf("jn(3,2.4) = %f\n", z);
}
```

**Classification:** WATCOM

**Systems:** j0 - Math

j1 - Math jn - Math y0 - Math y1 - Math yn - Math Synopsis: \*\* deprecated \*\*

#include <strings.h>
int bcmp(const void \*s1, const void \*s2, size\_t n);

**Description:** 

The bcmp function compares the byte string pointed to by s1 to the string pointed to by s2. The number of bytes to compare is specified by n. Null characters may be included in the comparision.

Note that this function is similar to the ISO C memcmp function but just tests for equality (new code should use the ISO C function).

**Returns:** The bcmp function returns zero if the byte strings are identical; otherwise it returns 1.

See Also: bcopy, bzero, memcmp, strcmp

**Example:** 

```
#include <stdio.h>
#include <strings.h>

void main()
{
   if( bcmp( "Hello there", "Hello world", 6 ) ) {
      printf( "Not equal\n" );
   } else {
      printf( "Equal\n" );
   }
}
```

produces the following:

Equal

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Description:** The bcopy function copies the byte string pointed to by *src* (including any null characters) into the

array pointed to by dst. The number of bytes to copy is specified by n. Copying of overlapping objects

is guaranteed to work properly.

Note that this function is similar to the ISO C memmove function but the order of arguments is different (new code should use the ISO C function).

**Returns:** The bcopy function has no return value.

See Also: bcmp, bzero, memmove, strcpy

Example: #include <stdio.h>
#include <strings.h>

void main()
{
 auto char buffer[80];

 bcopy( "Hello ", buffer, 6 );
 bcopy( "world", &buffer[6], 6 );
 printf( "%s\n", buffer );
}

produces the following:

Hello world

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

```
Synopsis:
           #include <malloc.h>
           int _bfreeseg( __segment seg );
Description:
           The _bfreeseg function frees a based-heap segment.
           The argument seg indicates the segment returned by an earlier call to _bheapseg.
Returns:
           The _bfreeseg function returns 0 if successful and -1 if an error occurred.
See Also:
           _bcalloc, _bexpand, _bfree, _bheapseg, _bmalloc, _brealloc
Example:
           #include <stdio.h>
           #include <stdlib.h>
           #include <malloc.h>
           struct list {
                struct list __based(__self) *next;
                                               value;
           };
           void main()
              {
                int
                             i;
                __segment
                           seg;
                struct list __based(seg) *head;
                struct list __based(seg) *p;
                /* allocate based heap */
                seg = \_bheapseg(1024);
                if( seg == _NULLSEG ) {
                  printf( "Unable to allocate based heap\n" );
                  exit(1);
                /* create a linked list in the based heap */
                head = 0;
                for (i = 1; i < 10; i++) {
                  p = _bmalloc( seg, sizeof( struct list ) );
                  if( p == _NULLOFF ) {
                    printf( "_bmalloc failed\n" );
                    break;
                  p->next = head;
                  p->value = i;
                  head = p;
                /* traverse the linked list, printing out values */
                for( p = head; p != 0; p = p->next ) {
                  printf( "Value = dn, p->value );
```

```
/* free all the elements of the linked list */
for(; p = head; ) {
  head = p->next;
  _bfree( seg, p );
}
/* free the based heap */
  _bfreeseg( seg );
}
```

**Classification:** WATCOM

**Systems:** DOS/16, Windows, OS/2 1.x(all)

**Synopsis:** #include cess.h> int \_bgetcmd( char \*cmd\_line, int len );

**Description:** The \_bget cmd function causes the command line information, with the program name removed, to be

copied to cmd\_line. The argument len specifies the size of cmd\_line. The information is terminated with a null character. This provides a method of obtaining the original parameters to a program unchanged (with the white space intact).

This information can also be obtained by examining the vector of program parameters passed to the main function in the program.

**Returns:** The number of bytes required to store the entire command line, excluding the terminating null character,

is returned.

See Also: abort, atexit, exec..., exit, \_Exit, \_exit, getcmd, getenv, main, putenv,

spawn..., system, \_wsystem

**Example:** Suppose a program were invoked with the command line

```
myprog arg-1 ( my
                    stuff ) here
```

where that program contains

```
#include <stdio.h>
#include <stdlib.h>
#include cess.h>
void main( void )
   char *cmdline;
    int
         cmdlen;
    cmdlen = _bgetcmd( NULL, 0 ) + 1;
    cmdline = malloc( cmdlen );
    if( cmdline != NULL ) {
        cmdlen = _bgetcmd( cmdline, cmdlen );
       printf( "%s\n", cmdline );
```

produces the following:

```
arg-1 ( my
            stuff ) here
```

**Classification: WATCOM** 

**Systems:** All, Linux, RDOS, Netware

_bgetcmd			

**Synopsis:** #include <malloc.h> \_\_segment \_bheapseg( size\_t size );

**Description:** The \_bheapseg function allocates a based-heap segment of at least *size* bytes.

> The argument size indicates the initial size for the heap. The heap will automatically be enlarged as needed if there is not enough space available within the heap to satisfy an allocation request by \_bcalloc, \_bexpand, \_bmalloc, or \_brealloc.

The value returned by \_bheapseg is the segment value or selector for the based heap. This value must be saved and used as an argument to other based heap functions to indicate which based heap to operate upon.

Each call to \_bheapseg allocates a new based heap.

**Returns:** 

The value returned by \_bheapseg is the segment value or selector for the based heap. This value must be saved and used as an argument to other based heap functions to indicate which based heap to operate upon. A special value of \_NULLSEG is returned if the segment could not be allocated.

See Also: \_bfreeseg, \_bcalloc, \_bexpand, \_bmalloc, \_brealloc

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
#include <malloc.h>
struct list {
    struct list __based(__self) *next;
                                value;
};
void main()
  {
   int
                i;
   __segment seq;
    struct list __based(seg) *head;
    struct list __based(seg) *p;
    /* allocate based heap */
    seg = \_bheapseg(1024);
    if( seg == _NULLSEG ) {
     printf( "Unable to allocate based heap\n" );
      exit(1);
```

```
/* create a linked list in the based heap */
head = 0;
for(i = 1; i < 10; i++) {
  p = _bmalloc( seg, sizeof( struct list ) );
  if( p == \_NULLOFF ) {
    printf( "_bmalloc failed\n" );
    break;
  }
  p->next = head;
  p->value = i;
  head = p;
/* traverse the linked list, printing out values */
for( p = head; p != 0; p = p->next ) {
  printf( "Value = %d\n", p->value );
/* free all the elements of the linked list */
for( ; p = head; ) {
  head = p->next;
  _bfree( seg, p );
/* free the based heap */
_bfreeseg( seg );
```

**Classification:** WATCOM

**Systems:** DOS/16, Windows, OS/2 1.x(all)

### **Synopsis:**

```
#include <bios.h>
unsigned short _bios_disk( unsigned service,
                        struct diskinfo_t *diskinfo );
                     /* disk parameters */
struct diskinfo_t {
   unsigned drive; /* drive number
                                          */
   unsigned head;
                     /* head number
                                          */
   unsigned track; /* track number
                                          */
   unsigned sector; /* sector number
                                          */
   unsigned nsectors; /* number of sectors */
   void __far *buffer; /* buffer address
};
```

### **Description:**

The \_bios\_disk function uses INT 0x13 to provide access to the BIOS disk functions. Information for the desired service is passed the diskinfo\_t structure pointed to by diskinfo. The value for service can be one of the following values:

Value	Meaning
_DISK_RESET	Forces the disk controller to do a reset on the disk. This request does not use the <i>diskinfo</i> argument.
_DISK_STATUS	Obtains the status of the last disk operation.
_DISK_READ	Reads the specified number of sectors from the disk. This request uses all of the information passed in the <i>diskinfo</i> structure.
_DISK_WRITE	Writes the specified amount of data to the disk. This request uses all of the information passed in the <i>diskinfo</i> structure.
_DISK_VERIFY	Checks the disk to be sure the specified sectors exist and can be read. A CRC (cyclic redundancy check) test is performed. This request uses all of the information passed in the <i>diskinfo</i> structure except for the <i>buffer</i> field.
_DISK_FORMAT	Formats the specified track on the disk. The <i>head</i> and <i>track</i> fields indicate the track to be formatted. Only one track can be formatted per call. The <i>buffer</i> field points to a set of sector markers, whose format depends on the type of disk drive. This service has no return value.

This function is not supported by DOS/4GW (you must use the Simulate Real-Mode Interrupt DPMI call).

### **Returns:**

The \_bios\_disk function returns status information in the high-order byte when service is \_DISK\_STATUS, \_DISK\_READ, \_DISK\_WRITE, or \_DISK\_VERIFY. The possible values are:

Value	Meaning
0x00	Operation successful
0x01	Bad command
0x02	Address mark not found
0x03	Attempt to write to write-protected disk
0x04	Sector not found
0x05	Reset failed

```
0x06
                           Disk changed since last operation
             0x07
                           Drive parameter activity failed
             0x08
                          DMA overrun
             0x09
                           Attempt to DMA across 64K boundary
             0x0A
                           Bad sector detected
             0x0B
                           Bad track detected
             0x0C
                           Unsupported track
             0x10
                          Data read (CRC/ECC) error
             0x11
                          CRC/ECC corrected data error
             0x20
                          Controller failure
             0x40
                           Seek operation failed
                           Disk timed out or failed to respond
             0x80
             0xAA
                           Drive not ready
             0xBB
                           Undefined error occurred
             0xCC
                           Write fault occurred
             0xE0
                           Status error
             0xFF
                           Sense operation failed
Example:
             #include <stdio.h>
             #include <bios.h>
             void main()
               {
                  struct diskinfo_t di;
                  unsigned short status;
                  di.drive = di.head = di.track = di.sector = 0;
                  di.nsectors = 1;
                  di.buffer = NULL;
                  status = _bios_disk( _DISK_VERIFY, &di );
                  printf( "Status = 0x%4.4X\n", status );
                }
```

**Classification: BIOS** 

**Systems:** DOS, Windows, Win386

**Synopsis:** #include <bios.h>

Bit

unsigned short \_bios\_equiplist( void );

**Description:** The  $\_$ bios $\_$ equiplist function uses INT 0x11 to determine what hardware and peripherals are

installed on the machine.

**Returns:** The \_bios\_equiplist function returns a set of bits indicating what is currently installed on the

machine. Those bits are defined as follows:

Meaning

	<u> </u>
bit 0	Set to 1 if system boots from disk
bit 1	Set to 1 if a math coprocessor is installed
bits 2-3	Indicates motherboard RAM size
bits 4-5	Initial video mode
bits 6-7	Number of diskette drives
bit 8	Set to 1 if machine does not have DMA
bits 9-11	Number of serial ports
bit 12	Set to 1 if a game port is attached
bit 13	Set to 1 if a serial printer is attached
bits 14-15	Number of parallel printers installed
#include	<stdio.h></stdio.h>
#include	 <bios.h></bios.h>
void mair	n ()
{ unsiq	gned short equipment;
	<pre>pment = _bios_equiplist(); tf( "Equipment flags = 0x%4.4X\n", equipment );</pre>

**Classification:** BIOS

**Example:** 

**Systems:** DOS, Windows, Win386 **Synopsis:** #include <bios.h>

unsigned short \_bios\_keybrd( unsigned service );

**Description:** The \_bios\_keybrd function uses INT 0x16 to access the BIOS keyboard services. The possible

values for service are the following constants:

Constant Meaning \_KEYBRD\_READ Reads the next character from the keyboard. The function will wait until a character has been typed. Checks to see if a character has been typed. If there is one, then its value \_KEYBRD\_READY will be returned, but it is not removed from the input buffer. **\_KEYBRD\_SHIFTSTATUS** Returns the current state of special keys. \_NKEYBRD\_READ Reads the next character from an enhanced keyboard. The function will wait until a character has been typed. \_NKEYBRD\_READY Checks to see if a character has been typed on an enhanced keyboard. If

input buffer.

there is one, then its value will be returned, but it is not removed from the

\_NKEYBRD\_SHIFTSTATUS Returns the current state of special keys on an enhanced keyboard.

**Returns:** The return value depends on the *service* requested.

> The \_KEYBRD\_READ and \_NKEYBRD\_READ services return the character's ASCII value in the low-order byte and the character's keyboard scan code in the high-order byte.

The \_KEYBRD\_READY and \_NKEYBRD\_READY services return zero if there was no character available, otherwise it returns the same value returned by \_KEYBRD\_READ and \_NKEYBRD\_READ.

The shift status is returned in the low-order byte with one bit for each special key defined as follows:

	Bit	Meaning	
	bit 0 (0x01)	Right SHIFT key is pressed	
	bit 1 (0x02)	Left SHIFT key is pressed	
	bit 2 (0x04)	CTRL key is pressed	
	$bit \ 3 \ (0x08)$	ALT key is pressed	
	$bit\ 4\ (0x10)$	SCROLL LOCK is on	
	bit $5 (0x20)$	NUM LOCK is on	
	bit 6 (0x40)	CAPS LOCK is on	
	bit 7 (0x80)	Insert mode is set	
Example:	<pre>#include <stdio.h> #include <bios.h>  void main() {</bios.h></stdio.h></pre>		
	unsigned short key_state		

```
key_state = _bios_keybrd( _KEYBRD_SHIFTSTATUS );
    if( key_state & 0x10 )
        printf( "SCROLL LOCK is on\n" );
    if( key_state & 0x20 )
        printf( "NUM LOCK is on\n" );
    if( key_state & 0x40 )
        printf( "CAPS LOCK is on\n" );
  }
produces the following:
```

NUM LOCK is on

**Classification:** BIOS

**Systems:** DOS, Windows, Win386 Synopsis: #include <bios.h>
 unsigned short \_bios\_memsize( void );

**Description:** The  $\_$ bios $\_$ memsize function uses INT 0x12 to determine the total amount of memory available.

**Returns:** The \_bios\_memsize function returns the total amount of 1K blocks of memory installed (maximum

640).

The total amount of memory is: 640K

**Classification:** BIOS

**Systems:** DOS, Windows, Win386

**Synopsis:** #include <bios.h>

unsigned short \_bios\_printer( unsigned service, unsigned port, unsigned data );

**Description:** 

The \_bios\_printer function uses INT 0x17 to perform printer output services to the printer specified by *port*. The values for service are:

Value Meaning

**\_PRINTER\_WRITE** Sends the low-order byte of *data* to the printer specified by *port*.

**\_PRINTER\_INIT** Initializes the printer specified by *port*.

\_PRINTER\_STATUS Get the status of the printer specified by port.

**Returns:** The \_bios\_printer function returns a printer status byte defined as follows:

#### Bit Meaning Printer timed out bit 0 (0x01)bits 1-2 Unused bit 3 (0x08) I/O error Printer selected bit 4 (0x10) bit 5 (0x20) Out of paper bit 6 (0x40) Printer acknowledge bit 7 (0x80) Printer not busy #include <stdio.h> #include <bios.h>

```
void main()
   unsigned short status;
   status = _bios_printer( _PRINTER_STATUS, 1, 0 );
   printf( "Printer status: 0x%2.2X\n", status );
```

**Classification:** BIOS

**Example:** 

**Systems:** DOS, Windows, Win386 Synopsis: #include <bios.h>

**Description:** The \_bios\_serialcom function uses INT 0x14 to provide serial communications services to the

serial port specified by serial\_port. 0 represents COM1, 1 represents COM2, etc. The values for

service are:

Value Meaning
 \_COM\_INIT Initializes the serial port to the parameters specified in data.
 \_COM\_SEND Transmits the low-order byte of data to the serial port.
 \_COM\_RECEIVE Reads an input character from the serial port.
 \_COM\_STATUS Returns the current status of the serial port.

The value passed in *data* for the \_COM\_INIT service can be built using the appropriate combination of the following values:

Value	Meaning
_COM_110	110 baud
_COM_150	150 baud
_COM_300	300 baud
_COM_600	600 baud
_COM_1200	1200 baud
_COM_2400	2400 baud
_COM_4800	4800 baud
_COM_9600	9600 baud
_COM_NOPARITY	No parity
_COM_EVENPARITY	Even parity
_COM_ODDPARITY	Odd parity
_COM_CHR7	7 data bits
_COM_CHR8	8 data bits
_COM_STOP1	1 stop bit
_COM_STOP2	2 stop bits

**Returns:** 

The \_bios\_serialcom function returns a 16-bit value with the high-order byte containing status information defined as follows:

Bit	Meaning
bit 15 (0x8000)	Timed out
bit 14 (0x4000)	Transmit shift register empty
bit 13 (0x2000)	Transmit holding register empty

bit 12 (0x1000)	Break detected
bit 11 (0x0800)	Framing error
bit 10 (0x0400)	Parity error
bit 9 $(0x0200)$	Overrun error
bit 8 $(0x0100)$	Data ready

The low-order byte of the return value depends on the value of the *service* argument.

When service is \_COM\_SEND, bit 15 will be set if the data could not be sent. If bit 15 is clear, the return value equals the byte sent.

When service is \_COM\_RECEIVE, the byte read will be returned in the low-order byte if there was no error. If there was an error, at least one of the high-order status bits will be set.

When service is \_COM\_INIT or \_COM\_STATUS the low-order bits are defined as follows:

bit 0 (0x01)	Clear to send (CTS) changed
$bit \ 1 \ (0x02)$	Data set ready changed
$bit \ 2 \ (0x04)$	Trailing-edge ring detector
bit $3(0x08)$	Receive line signal detector changed
bit 4 (0x10)	Clear to send
bit $5(0x20)$	Data-set ready
bit 6 (0x40)	Ring indicator
bit 7 (0x80)	Receive-line signal detected
<pre>#include <std #include="" <bio<="" pre=""></std></pre>	<del></del>
<pre>void main() {     unsigned</pre>	short status;
	_bios_serialcom( _COM_STATUS, 1, 0 ); Serial status: 0x%2.2X\n", status );

Meaning

**Classification:** BIOS

**Example:** 

**Systems:** DOS, Windows, Win386

}

Bit

Synopsis: #include <bios.h>

unsigned short \_bios\_timeofday( int service, long \*timeval );

**Description:** The \_bios\_timeofday function uses INT 0x1A to get or set the current system clock value. The

values for service are:

Value Meaning

\_TIME\_GETCLOCK Places the current system clock value in the location pointed to by timeval. The

function returns zero if midnight has not passed since the last time the system

clock was read or set; otherwise, it returns 1.

\_TIME\_SETCLOCK Sets the system clock to the value in the location pointed to by timeval.

**Returns:** A value of -1 is returned if neither \_TIME\_GETCLOCK nor \_TIME\_SETCLOCK were specified;

otherwise 0 is returned.

Example: #include <stdio.h>

#include <bios.h>

void main()
 {
 long time\_of\_day;

\_bios\_timeofday( \_TIME\_GETCLOCK, &time\_of\_day );
printf( "Ticks since midnight: %lu\n", time\_of\_day );
}

produces the following:

Ticks since midnight: 762717

**Classification:** BIOS

**Systems:** DOS, Windows, Win386

**Synopsis:** 

```
#include <stdio.h>
int _bprintf( char *buf, size_t bufsize,
              const char *format, ...);
int _bwprintf( wchar_t *buf, size_t bufsize,
               const wchar_t *format, ...);
```

**Description:** 

The \_bprintf function is equivalent to the sprintf function, except that the argument bufsize specifies the size of the character array buf into which the generated output is placed. A null character is placed at the end of the generated character string. The format string is described under the description of the printf function.

The \_bwprintf function is a wide character version of \_bprintf. It accepts a wide character string argument for format and produces wide character output. The argument buf specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream.

**Returns:** 

The \_bprintf function returns the number of characters written into the array, not counting the terminating null character. The \_bwprintf function returns the number of wide characters written into the array, not counting the terminating null character. An error can occur while converting a value for output. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

**Example:** 

```
void main( int argc, char *argv[] )
{
    char file_name[9];
   char file_ext[4];
   _bprintf(file_name, 9, "%s", argv[1]);
   _bprintf( file_ext, 4, "%s", argv[2] );
   printf( "%s.%s\n", file_name, file_ext );
}
```

**Classification:** WATCOM

**Systems:** 

```
_bprintf - All, Linux, RDOS, Netware
_bwprintf - All, Linux
```

#include <stdio.h>

```
Synopsis:
             #include <stdlib.h>
             void break_off( void );
             void break_on( void );
Description:
            The break_off function can be used with DOS to restrict break checking (Ctrl+C, Ctrl+Break) to
             screen output and keyboard input. The break_on function can be used with DOS to add break
             checking (Ctrl+C, Ctrl+Break) to other activities such as disk file input/output.
Returns:
             The break_off and break_on functions to not return anything.
See Also:
             signal
Example:
             #include <stdio.h>
             #include <stdlib.h>
             void main()
               {
                 long i;
                 FILE *tmpf;
                 tmpf = tmpfile();
                 if( tmpf != NULL ) {
                    printf( "Start\n" );
                    break_off();
                    for( i = 1; i < 100000; i++)
                      fprintf( tmpf, "%ld\n", i );
                    break_on();
                    printf( "Finish\n" );
Classification: DOS
Systems:
             break_off - DOS, Windows, Win386
             break_on - DOS, Windows, Win386
```

**Synopsis:** #include <stdlib.h>

int brk( void \_\_near \*addr );

**Description:** Change data segment size, the "break" value. The "break" value is the address of the first byte of

> unallocated memory. When a program starts execution, the break value is placed following the code and constant data for the program. As memory is allocated, this pointer will advance when there is no freed block large enough to satisfy an allocation request. The brk function can be used to set a new

"break" value for the program.

This value may be changed by a program at any time.

**Returns:** If the call to brk succeeds, "break" value is set to new value and 0 is returned. If the call to brk fails,

-1 is returned. When an error has occurred, errno contains a value indicating the type of error that has

been detected.

See Also: calloc Functions, \_expand Functions, free Functions, halloc, hfree, malloc Functions,

\_msize Functions, realloc Functions, sbrk

**Example:** 

**Classification:** WATCOM

**Systems:** Linux Safer C: The Safer C Library extension provides the bsearch\_s function which is a safer alternative to bsearch.

**Description:** The bsearch function performs a binary search of a sorted array of *num* elements, which is pointed to by *base*, for an item which matches the object pointed to by *key*. Each element in the array is *width* bytes in size. The comparison function pointed to by *compar* is called with two arguments that point to elements in the array. The first argument *pkey* points to the same object pointed to by *key*. The second argument *pbase* points to a element in the array. The comparison function shall return an integer less than, equal to, or greater than zero if the *key* object is less than, equal to, or greater than the element in the array.

const void \*pbase) );

**Returns:** The bsearch function returns a pointer to the matching member of the array, or NULL if a matching object could not be found. If there are multiple values in the array which are equal to the *key*, the return value is not necessarily the first occurrence of a matching value when the array is searched linearly.

See Also: bsearch\_s, lfind, lsearch, qsort\_s

```
Example:
           #include <stdio.h>
           #include <stdlib.h>
           #include <string.h>
           static const char *keywords[] = {
                   "auto",
                    "break",
                    "case",
                    "char",
                    /* . */
                    /* . */
                    /* . */
                    "while"
             } ;
           #define NUM_KW sizeof(keywords) / sizeof(char *)
           int kw_compare( const void *p1, const void *p2 )
               const char *p1c = (const char *) p1;
               const char **p2c = (const char **) p2;
```

return( strcmp( p1c, \*p2c ) );

```
int keyword_lookup( const char *name )
    const char **key;
    key = (char const **) bsearch( name, keywords, NUM_KW,
                    sizeof( char * ), kw_compare );
    if ( key == NULL ) return (-1);
    return key - keywords;
}
void main()
    printf( "%d\n", keyword_lookup( "case" ) );
    printf( "%d\n", keyword_lookup( "crigger" ) );
printf( "%d\n", keyword_lookup( "auto" ) );
//******* Sample program output *******
//2
//-1
//0
produces the following:
2
-1
0
```

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware

#### **Synopsis:**

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and bsearch\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *nmemb* nor *size* shall be greater than RSIZE\_MAX. If *nmemb* is not equal to zero, then none of *key*, *base*, or *compar* shall be a null pointer. If there is a runtime-constraint violation, the bsearch\_s function does not search the array.

## **Description:**

The bsearch\_s function searches an array of *nmemb* objects, the initial element of which is pointed to by *base*, for an element that matches the object pointed to by *key*. The size of each element of the array is specified by *size*. The comparison function pointed to by *compar* is called with three arguments. The first two point to the key object and to an array element, in that order. The function shall return an integer less than, equal to, or greater than zero if the key object is considered, respectively, to be less than, to match, or to be greater than the array element. The array shall consist of: all the elements that compare less than, all the elements that compare equal to, and all the elements that compare greater than the key object, in that order. The third argument to the comparison function is the *context* argument passed to bsearch\_s The sole use of context by bsearch\_s is to pass it to the comparison function.

### **Returns:**

The bsearch\_s function returns a pointer to a matching element of the array, or a null pointer if no match is found or there is a runtime-constraint violation. If two elements compare as equal, which element is matched is unspecified.

See Also:

bsearch, lfind, lsearch, qsort, qsort\_s

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdlib.h>
#include <string.h>

static const char *keywords[] = {
    "auto",
    "break",
    "case",
    "char",
    /* . */
    /* . */
    /* . */
    "while"
};
static void * context = NULL;
#define NUM_KW sizeof(keywords) / sizeof(char *)
```

```
int kw_compare( const void *p1, const void *p2, void *context )
    const char *p1c = (const char *) p1;
    const char **p2c = (const char **) p2;
   return( strcmp( p1c, *p2c ) );
int keyword_lookup( const char *name )
    const char **key;
   key = (char const **) bsearch_s( name, keywords, NUM_KW,
                   sizeof( char * ), kw_compare, context );
    if ( key == NULL ) return (-1);
    return key - keywords;
}
int main()
   printf( "%d\n", keyword_lookup( "case" ) );
   printf( "%d\n", keyword_lookup( "crigger" ) );
   printf( "%d\n", keyword_lookup( "auto" ) );
    return 0;
//****** Sample program output *******
//2
//-1
//0
produces the following:
2
-1
```

Classification: TR 24731

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <wchar.h>
 wint\_t btowc(int c);

**Description:** The btowc function determines whether c is a valid single-byte character in the initial shift state.

**Returns:** The btowc function returns WEOF if c has the value EOF or if (unsigned char)c does not constitute a

valid single-byte character in the initial shift state. Otherwise, btowc returns the wide character

representation of that character.

See Also: \_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira,

\_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb,

wctomb\_s

Example: #include <stdio.h>

#include <wchar.h>

void main( void )
{
 printf( "EOF is %sa valid single-byte character\n",
 btowc( EOF ) == WEOF ? "not " : "" );
}

produces the following:

EOF is not a valid single-byte character

**Classification:** ISO C

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

**Synopsis:** \*\* deprecated \*\* #include <strings.h> void bzero( void \*dst, size\_t n );

**Description:** The bzero function fills the first *n* bytes of the object pointed to by *dst* with zero (null) bytes.

Note that this function is similar to the ISO C memset function (new code should use the ISO C

function).

**Returns:** The bzero function has no return value.

See Also: memcmp, memcpy, memset, \_strset

**Example:** #include <strings.h> void main() char buffer[80]; bzero( buffer, 80 );

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

```
#include <math.h>
double cabs( struct complex value );

struct _complex {
    double x; /* real part */
    double y; /* imaginary part */
};
```

**Description:** The cabs function computes the absolute value of the complex number *value* by a calculation which is

equivalent to

```
sqrt( (value.x*value.x) + (value.y*value.y) )
```

In certain cases, overflow errors may occur which will cause the matherr routine to be invoked.

**Returns:** The absolute value is returned.

Example: #include <stdio.h>
#include <math.h>

produces the following:

5.000000

Classification: WATCOM

**Systems:** Math

### **Synopsis:**

```
#include <stdlib.h> For ISO C compatibility (calloc only)
#include <malloc.h> Required for other function prototypes
void *calloc( size_t n, size_t size );
void __based(void) *_bcalloc( __segment seg,
                              size_t n,
                              size_t size );
void __far *_fcalloc( size_t n, size_t size );
void __near *_ncalloc( size_t n, size_t size );
```

### **Description:**

The **calloc** functions allocate space for an array of *n* objects, each of length *size* bytes. Each element is initialized to 0.

Each function allocates memory from a particular heap, as listed below:

Function	Неар
calloc	Depends on data model of the program
_bcalloc	Based heap specified by seg value
_fcalloc	Far heap (outside the default data segment)
_ncalloc	Near heap (inside the default data segment)

In a small data memory model, the **calloc** function is equivalent to the \_ncalloc function; in a large data memory model, the **calloc** function is equivalent to the \_fcalloc function.

A block of memory allocated should be freed using the appropriate free function.

### **Returns:**

The calloc functions return a pointer to the start of the allocated memory. The return value is NULL (\_NULLOFF for \_bcalloc) if there is insufficient memory available or if the value of the size argument is zero.

See Also:

\_expand Functions, free Functions, halloc, hfree, malloc Functions, \_msize Functions, realloc Functions, sbrk

# **Example:**

```
void main()
    char *buffer;
    buffer = (char *)calloc( 80, sizeof(char) );
  }
```

### Classification: ISO C

#include <stdlib.h>

### **Systems:**

```
calloc - All, Linux, RDOS, Netware
_bcalloc - DOS/16, Windows, OS/2 1.x(all)
_fcalloc - DOS/16, Windows, OS/2 1.x(all)
_ncalloc - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

calloc Functions			

**Synopsis:** #include <math.h>

double cbrt( double x );

**Description:** The cbrt function computes the cubed root of the argument x.

**Returns:** The cubed root of the value.

**Example:** #include <stdio.h> #include <math.h>

```
void main()
   printf( "%f\n", cbrt( 8.0 ) );
```

produces the following:

2.000000

Classification: ISO C99

**Systems:** Math

```
Synopsis:
             #include <math.h>
             double ceil( double x);
Description:
            The ceil function (ceiling function) computes the smallest integer not less than x.
Returns:
             The ceil function returns the smallest integer not less than x, expressed as a double.
See Also:
             floor
Example:
             #include <stdio.h>
             #include <math.h>
             void main()
               {
                 printf( "%f %f %f %f %f %f\n", ceil( -2.1 ), ceil( -2. ),
                      ceil( 0.0 ), ceil( 2. ), ceil( 2.1 ) );
             produces the following:
             -2.000000 -2.000000 0.000000 2.000000 3.000000
Classification: ISO C
```

**Systems:** Math

**Synopsis:** #include <conio.h> char \*cgets( char \*buf );

**Description:** 

The cgets function gets a string of characters directly from the console and stores the string and its length in the array pointed to by buf. The first element of the array buf[0] must contain the maximum length in characters of the string to be read. The array must be big enough to hold the string, a terminating null character, and two additional bytes.

The cgets function reads characters until a carriage-return line-feed combination is read, or until the specified number of characters is read. The string is stored in the array starting at buf[2]. The carriage-return line-feed combination, if read, is replaced by a null character. The actual length of the string read is placed in buf[1].

**Returns:** The cgets function returns a pointer to the start of the string which is at buf[2].

See Also: fgets, getch, getche, gets

**Example:** #include <conio.h>

```
void main()
  {
    char buffer[82];
   buffer[0] = 80;
    cgets( buffer );
    cprintf( "%s\r\n", &buffer[2] );
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware **Synopsis:** #include <dos.h> void \_chain\_intr( void (\_\_interrupt \_\_far \*func)() ); **Description:** The \_chain\_intr function is used at the end of an interrupt routine to start executing another interrupt handler (usually the previous handler for that interrupt). When the interrupt handler designated by func receives control, the stack and registers appear as though the interrupt just occurred. **Returns:** The \_chain\_intr function does not return to its caller. See Also: \_dos\_getvect, \_dos\_keep, \_dos\_setvect **Example:** #include <stdio.h> #include <dos.h> volatile int clock\_ticks; void (\_\_interrupt \_\_far \*prev\_int\_1c)(); #define BLIP\_COUNT (5\*18) /\* 5 seconds \*/ void \_\_interrupt \_\_far timer\_rtn() { ++clock\_ticks; \_chain\_intr( prev\_int\_1c ); int delays = 0;int compile\_a\_line() if ( delays > 15 ) return ( 0 ); delay( 1000 ); /\* delay for 1 second \*/ printf( "Delayed for 1 second\n" ); delays++; return(1); } void main() {  $prev_int_1c = _dos_getvect( 0x1c );$ \_dos\_setvect( 0x1c, timer\_rtn ); while( compile\_a\_line() ) { if( clock\_ticks >= BLIP\_COUNT ) { putchar( '.' ); clock\_ticks -= BLIP\_COUNT; \_dos\_setvect( 0x1c, prev\_int\_1c );

**Classification:** WATCOM

Systems: DOS, Windows

	_chain_intr

### **Synopsis:**

```
#include <sys/types.h>
#include <direct.h>
int chdir( const char *path );
int _chdir( const char *path );
int _wchdir( const wchar_t *path );
```

### **Description:**

The chdir function changes the current directory on the specified drive to the specified *path*. If no drive is specified in *path* then the current drive is assumed. The *path* can be either relative to the current directory on the specified drive or it can be an absolute path name.

Each drive under DOS, OS/2 or Windows has a current directory. The current working directory is the current directory of the current drive. If you wish to change the current drive, you must use the \_dos\_setdrive function.

The \_chdir function is identical to chdir. Use \_chdir for ANSI naming conventions.

The \_wchdir function is a wide character version of chdir that operates with wide character strings.

**Returns:** 

The chdir function returns zero if successful. Otherwise, -1 is returned, errno is set to indicate the error, and the current working directory remains unchanged.

**Errors:** 

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

Constant Meaning

**ENOENT** 

The specified *path* does not exist or *path* is an empty string.

See Also:

chmod, \_dos\_setdrive, getcwd, mkdir, rmdir, stat, umask

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
#include <direct.h>

void main( int argc, char *argv[] )
{
   if( argc != 2 ) {
      fprintf( stderr, "Use: cd <directory>\n" );
      exit( 1 );
   }

   if( chdir( argv[1] ) == 0 ) {
      printf( "Directory changed to %s\n", argv[1] );
      exit( 0 );
   } else {
      perror( argv[1] );
      exit( 1 );
   }
}
```

Classification: POSIX 1003.1

\_chdir conforms to ANSI naming conventions

**Systems:** 

```
chdir - All, Linux, RDOS, Netware
_chdir - All, RDOS, Netware
```

\_wchdir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

Synopsis: #include <direct.h>
 int \_chdrive( int drive );

**Description:** The \_chdrive function changes the current working drive to the one specified by *drive*. A value of 1

is drive A, 2 is drive B, 3 is drive C, etc.

**Returns:** The \_chdrive function returns zero if drive is successfully changed. Otherwise, -1 is returned.

See Also: \_\_dos\_getdrive, \_dos\_setdrive, \_getdrive

produces the following:

Changed the current drive to C

**Classification:** DOS

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS, DOS/PM

#### **Synopsis:** #include <sys/types.h>

#include <sys/stat.h>

#include <io.h>

int chmod( const char \*path, mode\_t permission ); int \_chmod( const char \*path, mode\_t permission ); int \_wchmod( const wchar\_t \*path, mode\_t permission );

# **Description:**

The chmod function changes the permissions for a file specified by path to be the settings in the mode given by permission. The access permissions for the file or directory are specified as a combination of bits (defined in the <sys/stat.h> header file).

The following bits define permissions for the owner.

Permission	Meaning
S_IRWXU	Read, write, execute/search
S_IRUSR	Read permission
S_IWUSR	Write permission
S_IXUSR	Execute/search permission

The following bits define permissions for the group.

Permission	Meaning
S_IRWXG	Read, write, execute/search
S_IRGRP	Read permission
S_IWGRP	Write permission
S_IXGRP	Execute/search permission

The following bits define permissions for others.

Permission	Meaning
S_IRWXO	Read, write, execute/search
S_IROTH	Read permission
S_IWOTH	Write permission
S_IXOTH	Execute/search permission

The following bits define miscellaneous permissions used by other implementations.

Permission	Meaning
S_IREAD	is equivalent to S_IRUSR (read permission)
S_IWRITE	is equivalent to S_IWUSR (write permission)
S_IEXEC	is equivalent to S_IXUSR (execute/search permission)

Upon successful completion, the chmod function will mark for update the st\_ctime field of the file.

The \_chmod function is identical to chmod. Use \_chmod for ANSI naming conventions.

The \_wchmod function is a wide character version of chmod that operates with wide character strings.

**Returns:** The chmod returns zero if the new settings are successfully made; otherwise, -1 is returned and errno

is set to indicate the error.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning

**EACCES** Search permission is denied for a component of *path*.

**ENOENT** The specified *path* does not exist or *path* is an empty string.

See Also: fstat, open, \_sopen, stat

```
Example:
```

```
/*
 * change the permissions of a list of files
 * to be read/write by the owner only
#include <stdio.h>
#include <stdlib.h>
#include <sys/types.h>
#include <sys/stat.h>
#include <io.h>
void main( int argc, char *argv[] )
    int i;
    int ecode = 0;
    for(i = 1; i < argc; i++) {
      if( chmod( argv[i], S_IRUSR | S_IWUSR ) == -1 ) {
        perror( argv[i] );
        ecode++;
      }
    exit( ecode );
  }
```

Classification: POSIX 1003.1

\_chmod conforms to ANSI naming conventions

```
Systems: chmod - All, Linux, RDOS, Netware
```

\_chmod - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS \_wchmod - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

```
Synopsis:
           #include <io.h>
           int _chsize( int handle, long size );
           ** deprecated **
           int chsize (int handle, long size);
```

**Description:** 

The \_chsize function changes the size of the file associated with handle by extending or truncating the file to the length specified by size. If the file needs to be extended, the file is padded with NULL ('\0') characters.

The chsize function is deprecated, use \_chsize instead.

**Returns:** The \_chsize function returns zero if successful. A return value of -1 indicates an error, and errno is set to indicate the error.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

> Constant Meaning **EACCES** The specified file is locked against access. **EBADF** Invalid file handle. **ENOSPC** Not enough space left on the device to extend the file.

See Also: close, creat, open

{

}

```
Example:
           #include <stdio.h>
           #include <io.h>
           #include <fcntl.h>
           #include <sys/stat.h>
           void main()
```

```
int handle;
handle = open( "file", O_RDWR | O_CREAT,
            S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
if ( handle !=-1 ) {
  if( _chsize( handle, 32 * 1024L ) != 0 ) {
      printf( "Error extending file\n" );
  close( handle );
```

**Classification:** WATCOM

```
Systems:
           _chsize - All, Linux, RDOS, Netware
           chsize - All, Linux, RDOS, Netware
```

_chsize, chsize			

**Synopsis:** #include <float.h> unsigned int \_clear87( void );

**Description:** The \_clear87 function clears the floating-point status word which is used to record the status of

8087/80287/80387/80486 floating-point operations.

**Returns:** The \_clear 87 function returns the old floating-point status. The description of this status is found in

the <float.h> header file.

See Also: \_control87, \_controlfp, \_finite, \_fpreset, \_status87

**Example:** #include <stdio.h> #include <float.h>

```
void main()
  {
    unsigned int fp_status;
    fp_status = _clear87();
    printf( "80x87 status =" );
    if( fp_status & SW_INVALID )
        printf( " invalid" );
    if( fp_status & SW_DENORMAL )
        printf( " denormal" );
    if( fp_status & SW_ZERODIVIDE )
        printf( " zero_divide" );
    if( fp_status & SW_OVERFLOW )
        printf( " overflow" );
    if( fp_status & SW_UNDERFLOW )
        printf( " underflow" );
    if( fp_status & SW_INEXACT )
        printf( " inexact_result" );
    printf( "\n" );
```

Classification: Intel

**Systems:** Math Synopsis: #include <env.h>

int clearenv( void );

**Description:** The clearenv function clears the process environment area. No environment variables are defined

immediately after a call to the clearenv function. Note that this clears the PATH, COMSPEC, and TZ

environment variables which may then affect the operation of other library functions.

The clearenv function may manipulate the value of the pointer environ.

**Returns:** The clearenv function returns zero upon successful completion. Otherwise, it will return a non-zero

value and set errno to indicate the error.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning

**ENOMEM** Not enough memory to allocate a control structure.

See Also: exec..., \_wexec..., getenv, getenv\_s, putenv, \_searchenv, setenv, unsetenv,

 $\verb|_wgetenv, \_wputenv, \_wsearchenv, \_wsetenv, \_wunsetenv, spawn..., \_wspawn...,$ 

system, \_wsystem

**Example:** The following example clears the entire environment area and sets up a new TZ environment variable.

```
#include <env.h>
void main()
{
   clearenv();
   setenv( "TZ", "EST5EDT", 0 );
}
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <stdio.h> void clearerr( FILE \*fp );

The clearerr function clears the end-of-file and error indicators for the stream pointed to by fp. **Description:** 

These indicators are cleared only when the file is opened or by an explicit call to the clearerr or

rewind functions.

**Returns:** The clearerr function returns no value.

See Also: feof, ferror, perror, strerror

**Example:** #include <stdio.h>

```
void main()
   FILE *fp;
    int c;
    c = 'J';
    fp = fopen( "file", "w" );
    if( fp != NULL ) {
      fputc( c, fp );
      if( ferror( fp ) ) { /* if error
        clearerr( fp ); /* clear the error */
        fputc( c, fp ); /* and retry it
      }
    }
  }
```

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <graph.h>

void \_FAR \_clearscreen( short area );

**Description:** The \_clearscreen function clears the indicated *area* and fills it with the background color. The

area argument must be one of the following values:

**\_GCLEARSCREEN** area is entire screen

\_GVIEWPORT area is current viewport or clip region

**\_GWINDOW** area is current text window

**Returns:** The \_clearscreen function does not return a value.

See Also: \_setbkcolor, \_setviewport, \_setcliprgn, \_settextwindow

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    _setvideomode( _VRES16COLOR );
    _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
    getch();
    _setviewport( 200, 200, 440, 280 );
    _clearscreen( _GVIEWPORT );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: DOS

**Synopsis:** #include <time.h> clock\_t clock(void);

**Description:** The clock function returns the number of clock ticks of processor time used by program since the

program started executing. This can be converted to seconds by dividing by the value of the macro

CLOCKS\_PER\_SEC.

Note that under DOS and OS/2, the clock tick counter will reset to 0 for each subsequent 24 hour

interval that elapses.

void compute( void )

**Returns:** The clock function returns the number of clock ticks that have occurred since the program started

executing.

See Also: asctime Functions, asctime\_s, ctime Functions, ctime\_s, difftime, gmtime\_s,

localtime, localtime\_s, mktime, strftime, time, tzset

**Example:** #include <stdio.h> #include <math.h> #include <time.h>

> int i, j; double x; x = 0.0;for ( i = 1;  $i \le 100$ ; i++ ) for(  $j = 1; j \le 100; j++$ ) x += sqrt((double) i \* j);printf( "%16.7f\n", x ); }

clock\_t start\_time, end\_time; start\_time = clock(); compute(); end\_time = clock(); printf( "Execution time was %lu seconds\n", (end\_time - start\_time) / CLOCKS\_PER\_SEC );

Classification: ISO C

All, Linux, RDOS, Netware **Systems:** 

}

void main()

{

clock			

**Synopsis:** #include <time.h>

```
int clock_getres(clockid_t clockid, struct timespec *ts);
struct timespec {
   time_t tv_sec;
   long tv_nsec;
```

};

**Description:** The clock\_getres function retrieves the minimum resolution of the clock specified by clockid in

the ts pointer.

**Returns:** If successful, the function will return zero. If the call fails, the return value is the negation of the

appropriate errno value as specified below. This implementation will also set errno appropriately

on failures.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EINVAL** The value of *clockid* is invalid.

See Also: clock\_settime, clock\_gettime, clock\_nanosleep

Classification: POSIX 1003.1

**Systems:** Linux Synopsis: #include <time.h>

int clock\_gettime(clockid\_t clockid, struct timespec \*ts);

struct timespec {
 time\_t tv\_sec;
 long tv\_nsec;
};

**Description:** The clock\_gettime function retrieves the time for the clock specified by *clockid* in the *ts* pointer.

**Returns:** If successful, the function will return zero. If the call fails, the return value is the negation of the

appropriate errno value as specified below. This implementation will also set errno appropriately

on failures.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EINVAL** The value of *clockid* is invalid.

See Also: clock\_settime, clock\_getres, clock\_nanosleep

Classification: POSIX 1003.1

**Systems:** Linux

### **Synopsis:**

```
#include <time.h>
int clock_nanosleep(clockid_t clockid, int flags,
                    const struct timespec *request,
                    struct timespec *remains);
struct timespec {
   time_t tv_sec;
   long tv_nsec;
};
```

### **Description:**

The clock\_nanosleep function causes the current thread to be suspended until the time period specified by request has elapsed according to the clock specified by clockid if the flags do not contain the value TIMER\_ABSTIME.

If flags does contain TIMER\_ABSTIME, the clock\_nanosleep function causes the current thread to be suspended until the absolute time specified by request has been reached according to the clock specified by clockid if the flags.

If remains is not NULL, the structure will contain the amount of time remaining to be slept if clock\_nanosleep is interrupted by a signal.

### **Returns:**

If successful and uninterrupted, the function will return zero. If the call fails or is interrupted, the return value is the negation of the appropriate errno value as specified below. This implementation will also set errno appropriately on failures.

# **Errors:**

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

# **Constant Meaning**

**EINTR** The sleep was interrupted by a signal.

**EINVAL** The value of *clockid*, *request*, or *flags* is invalid.

**ENOTSUP** The specified clock does not support this function.

See Also:

clock\_gettime, clock\_getres, clock\_settime

Classification: POSIX 1003.1

**Systems:** 

Linux

Synopsis: #include <time.h>

```
int clock_settime(clockid_t clockid, const struct timespec *ts);
struct timespec {
    time_t tv_sec;
    long tv_nsec;
};
```

**Description:** 

The clock\_settime function sets the time for the clock specified by *clockid* to the time contained in the *ts* pointer. Depending on the value of *clockid*, the function may fail if the user has insufficient privileges.

Values of ts that specify significance beyond the clock's resolution will be truncated.

**Returns:** 

If successful, the function will return zero. If the call fails, the return value is the negation of the appropriate errno value as specified below. This implementation will also set errno appropriately on failures.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EINVAL** The value of *clockid* is invalid, or the value of *ts* exceeds the range of this clock.

**EPERM** The user does not have sufficient privileges to modify the specified clock.

See Also: clock\_gettime, clock\_getres, clock\_nanosleep

Classification: POSIX 1003.1

**Systems:** Linux

**Synopsis:** #include <sched.h>

```
pid_t clone( int (*fn) (void *), void *child_stack,
              int flags, void *args, ...);
            /* pid_t *ppid, void *tls, pid_t *ctid */
```

# **Description:**

The clone function creates a "clone" of the currently running process that shares the address space of the original, parent process, and starts execution within the clone process at the fn function. The child function is called with args as its argument, and, once complete, with will terminate with the return value of fn as its exit code. This function provides a wrapper around the Linux kernel's SYS\_clone system call.

The child\_stack argument points to a user-allocated memory block within the process's heap for use as the cloned process's new stack space. Because the stack will grow in the direction of descending address, the *child\_stack* argument should refer to the highest address in the allocated memory.

The *flags* argument may be one of the following values:

Constant	Meaning
CLONE_VM	Virtual memory should be shared across processes
CLONE_FS	File system information should be shared across processes
CLONE_FILES	File handles should be shared across processes
CLONE_SIGHAND	Signal handlers and blocked signals should be shared across processes
CLONE_PTRACE	Allow tracing within the child process (if enabled in the parent)
CLONE_VFORK	The child can wake the parent via mm_release
CLONE_PARENT	The new child should share the same parent as the cloning process
CLONE_THREAD	The new process is to be considered a thread, and should be grouped in the same thread group as the parent
CLONE_NEWNS	The child process is provided a new mount namespace
CLONE_SYSVSEM	The child process shares all System V semaphores
CLONE_SETTLS	The thread-local storage, an optional argument, should be passed and set appropriately. The user must specify the <i>tls</i> argument if this flag is set.
CLONE_PARENT_SETTID	Store the thread ID of the parent in the <i>ptid</i> argument. The user must specify the optional <i>ptid</i> argument if this flag is set.
CLONE_CHILD_CLEARTID	Clear the thread ID stored in <i>ctid</i> argument. The user must specify the optional <i>ctid</i> argument if this flag is set.

**CLONE\_UNTRACED** The parent process cannot force tracing on the child process

**CLONE\_CHILD\_SETTID** Store the thread ID of the child process in the *ctid* argument. The

user must specify the optional ctid argument if this flag is set.

**CLONE\_NEWUTS** The child process has a new UTS namespace

**CLONE\_NEWIPC** The child process has a new IPC namespace

CLONE\_NEWUSER The child process has a new user namespace

CLONE\_NEWPID The child process has a new PID namespace

CLONE\_NEWNET The child process has a new network namespace

CLONE\_IO The parent and child share io contexts

This function provides a low-level threading interface that is normally meant for designing higher level thread libraries.

**Returns:** If successful, the function will return the process ID of the child process. If the system call fails, the

return value will be -1, and errno will be set appropriately.

**Classification:** WATCOM

**Systems:** Linux

**Synopsis:** #include <io.h>

> int close( int handle ); int \_close( int handle );

**Description:** 

The close function closes a file at the operating system level. The handle value is the file handle returned by a successful execution of one of the creat, dup, dup2, open or \_sopen functions.

The \_close function is identical to close. Use \_close for ANSI naming conventions.

**Returns:** 

The close function returns zero if successful. Otherwise, it returns -1 and errno is set to indicate the

error.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant

Meaning

**EBADF** 

The *handle* argument is not a valid file handle.

See Also:

creat, dup, dup2, open, \_sopen

**Example:** 

```
#include <fcntl.h>
#include <io.h>
void main()
  {
    int handle;
    handle = open( "file", O_RDONLY );
    if ( handle !=-1 ) {
      /* process file */
      close( handle );
  }
```

Classification: POSIX 1003.1

\_close conforms to ANSI naming conventions

**Systems:** 

```
close - All, Linux, RDOS, Netware
_close - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

```
Synopsis: #include <direct.h>
    int closedir( DIR *dirp );
    int _wclosedir( WDIR *dirp );
```

**Description:** The closedir function closes the directory specified by *dirp* and frees the memory allocated by

opendir.

The \_wclosedir function is identical to closedir except that it closes a directory of wide

character filenames opened by \_wopendir.

**Returns:** The closedir function returns zero if successful, non-zero otherwise.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning

**EBADF** The argument *dirp* does not refer to an open directory stream.

See Also: \_dos\_find..., opendir, readdir, rewinddir, \_wopendir, \_wreaddir, \_wrewinddir

**Example:** To get a list of files contained in the directory \watcom\h on your default disk:

```
#include <stdio.h>
#include <direct.h>
typedef struct {
   unsigned short twosecs : 5; /* seconds / 2 */
   unsigned short minutes : 6;
    unsigned short hours : 5;
} ftime_t;
typedef struct {
   unsigned short day : 5;
   unsigned short month : 4;
   unsigned short year : 7;
} fdate_t;
void main()
   DIR *dirp;
    struct dirent *direntp;
    ftime_t *f_time;
    fdate_t *f_date;
```

```
dirp = opendir( "\\watcom\\h" );
  if( dirp != NULL ) {
    for(;;) {
      direntp = readdir( dirp );
      if( direntp == NULL ) break;
      f_time = (ftime_t *)&direntp->d_time;
      f_date = (fdate_t *)&direntp->d_date;
      printf( "%-12s %d/%2.2d/%2.2d "
              "%2.2d:%2.2d:%2.2d \n",
          direntp->d_name,
          f_date->year + 1980,
          f_date->month,
          f_date->day,
          f_time->hours,
          f_time->minutes,
          f_time->twosecs * 2 );
    closedir( dirp );
  }
}
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

Classification: POSIX 1003.1

```
Systems:
           closedir - All, Linux, RDOS, Netware
           _wclosedir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

**Description:** The \_cmdname function obtains a copy of the executing program's pathname and places it in *buffer*.

**Returns:** If the pathname of the executing program cannot be determined then NULL is returned; otherwise the

address of buffer is returned.

See Also: getcmd

Example: #include <stdio.h>
#include <process.h>

void main()
{
 char buffer[PATH\_MAX];

 printf( "%s\n", \_cmdname( buffer ) );

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <io.h>

int \_commit( int handle );

**Description:** The \_commit function commits changes to the file specified by *handle* to disk immediately.

**Returns:** The \_commit function returns -1 if the changes have been successfully committed. Otherwise, 0 is

returned and errno is set to indicate the error.

**Classification:** WATCOM

**Systems:** DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

```
Synopsis:
            #include <float.h>
            unsigned int _control87( unsigned int newcw,
                                        unsigned int mask );
            The _control87 function updates the control word of the 8087/80287/80387/80486. If mask is zero,
Description:
            then the control word is not updated. If mask is non-zero, then the control word is updated with bits
            from newcw corresponding to every bit that is on in mask.
Returns:
            The _control87 function returns the new control word. The description of bits defined for the
            control word is found in the <float.h> header file.
See Also:
            _clear87, _controlfp, _finite, _fpreset, _status87
Example:
            #include <stdio.h>
            #include <float.h>
            char *status[2] = { "disabled", "enabled" };
            void main()
              {
                unsigned int fp_cw = 0;
                unsigned int fp_mask = 0;
                unsigned int bits;
                fp_cw = _control87( fp_cw,
                                       fp_mask );
                printf( "Interrupt Exception Masks\n" );
                bits = fp_cw & MCW_EM;
                printf( " Invalid Operation exception %s\n",
                          status[ (bits & EM_INVALID) == 0 ] );
                printf( " Denormalized exception %s\n",
                         status[ (bits & EM_DENORMAL) == 0 ] );
                printf( " Divide-By-Zero exception %s\n",
                         status[ (bits & EM_ZERODIVIDE) == 0 ] );
                printf( " Overflow exception %s\n",
                         status[ (bits & EM_OVERFLOW) == 0 ] );
                printf( " Underflow exception %s\n",
                         status[ (bits & EM_UNDERFLOW) == 0 ] );
                printf( " Precision exception %s\n",
                         status[ (bits & EM_PRECISION) == 0 ] );
                printf( "Infinity Control = " );
                bits = fp_cw & MCW_IC;
                                               printf( "affine\n" );
                if( bits == IC_AFFINE )
                if( bits == IC_PROJECTIVE ) printf( "projective\n" );
                printf( "Rounding Control = " );
                bits = fp_cw & MCW_RC;
                if( bits == RC_NEAR )
                                               printf( "near\n" );
                                            printf( "down\n" );
printf( "up\n" );
printf( "chop\n" );
                if( bits == RC_DOWN )
                if( bits == RC_UP )
                if( bits == RC_CHOP )
```

```
printf( "Precision Control = " );
bits = fp_cw & MCW_PC;
                                    printf( "24 bits\n" );
printf( "53 bits\n" );
if ( bits == PC_24 )
if ( bits == PC_53 )
if( bits == PC_64 )
                                    printf( "64 bits\n" );
```

Classification: Intel

**Systems:** All, Linux, RDOS, Netware

```
Synopsis:
            #include <float.h>
            unsigned int _controlfp( unsigned int newcw,
                                        unsigned int mask );
            The _controlfp function updates the control word of the 8087/80287/80387/80486. If mask is zero,
Description:
            then the control word is not updated. If mask is non-zero, then the control word is updated with bits
            from newcw corresponding to every bit that is on in mask.
Returns:
            The _controlfp function returns the new control word. The description of bits defined for the
            control word is found in the <float.h> header file.
See Also:
            _clear87, _control87, _finite, _fpreset, _status87
Example:
            #include <stdio.h>
            #include <float.h>
            char *status[2] = { "disabled", "enabled" };
            void main()
              {
                unsigned int fp_cw = 0;
                unsigned int fp_mask = 0;
                unsigned int bits;
                fp_cw = _controlfp( fp_cw,
                                       fp_mask );
                printf( "Interrupt Exception Masks\n" );
                bits = fp_cw & MCW_EM;
                printf( " Invalid Operation exception %s\n",
                          status[ (bits & EM_INVALID) == 0 ] );
                printf( " Denormalized exception %s\n",
                         status[ (bits & EM_DENORMAL) == 0 ] );
                printf( " Divide-By-Zero exception %s\n",
                         status[ (bits & EM_ZERODIVIDE) == 0 ] );
                printf( " Overflow exception %s\n",
                         status[ (bits & EM_OVERFLOW) == 0 ] );
                printf( " Underflow exception %s\n",
                         status[ (bits & EM_UNDERFLOW) == 0 ] );
                printf( " Precision exception %s\n",
                         status[ (bits & EM_PRECISION) == 0 ] );
                printf( "Infinity Control = " );
                bits = fp_cw & MCW_IC;
                                              printf( "affine\n" );
                if( bits == IC_AFFINE )
                if( bits == IC_PROJECTIVE ) printf( "projective\n" );
                printf( "Rounding Control = " );
                bits = fp_cw & MCW_RC;
                                              printf( "near\n" );
                if( bits == RC_NEAR )
                                           printf( "down\n" );
printf( "up\n" );
printf( "chop\n" );
                if( bits == RC_DOWN )
                if( bits == RC_UP )
                if( bits == RC_CHOP )
```

```
printf( "Precision Control = " );
bits = fp_cw & MCW_PC;
                                    printf( "24 bits\n" );
printf( "53 bits\n" );
if ( bits == PC_24 )
if ( bits == PC_53 )
if( bits == PC_64 )
                                    printf( "64 bits\n" );
```

Classification: Intel

**Systems:** All, Linux, RDOS, Netware **Synopsis:** #include <math.h>

double copysign ( double x, double y );

**Description:** The copysign function returns a value whose absolute value is equal to the absolute value of the

argument x and whose sign matches argument y.

**Returns:** A value of the same magnitude as x and the same sign as y.

**Example:** #include <stdio.h>

```
#include <math.h>
void main()
  {
   printf( \$f\n, copysign( -2.0, 3.0 ) );
```

produces the following:

2.000000

Classification: ISO C99

**Systems:** Math

**Synopsis:** #include <math.h> double cos(double x);

**Description:** The  $\cos$  function computes the cosine of x (measured in radians). A large magnitude argument may

yield a result with little or no significance.

**Returns:** The cos function returns the cosine value.

See Also: acos, sin, tan

**Example:** #include <math.h>

```
void main()
    double value;
   value = \cos(3.1415278);
```

**Classification:** ISO C

**Systems:** Math Synopsis: #include <math.h>

double cosh( double x);

**Description:** The cosh function computes the hyperbolic cosine of x. A range error occurs if the magnitude of x is

too large.

**Returns:** The cosh function returns the hyperbolic cosine value. When the argument is outside the permissible

range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to ERANGE, and print a "RANGE error" diagnostic message using the stderr

stream.

See Also: sinh, tanh, matherr

Example: #include <stdio.h>
#include <math.h>

produces the following:

1.127626

**Classification:** ISO C

**Systems:** Math

```
Synopsis:
           #include <conio.h>
           int cprintf( const char *format, ... );
```

**Description:** The cprintf function writes output directly to the console under control of the argument format. The putch function is used to output characters to the console. The format string is described under the

description of the printf function.

**Returns:** The cprintf function returns the number of characters written.

See Also: \_bprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

**Example:** #include <conio.h>

```
void main()
    char *weekday, *month;
    int day, year;
    weekday = "Saturday";
    month = "April";
    day = 18;
    year = 1987;
    cprintf( "%s, %s %d, %d\n",
          weekday, month, day, year );
  }
```

produces the following:

Saturday, April 18, 1987

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <conio.h>
 int cputs( const char \*buf );

**Description:** The cputs function writes the character string pointed to by *buf* directly to the console using the

putch function. Unlike the puts function, the carriage-return and line-feed characters are not

appended to the string. The terminating null character is not written.

Returns: The cputs function returns a non-zero value if an error occurs; otherwise, it returns zero. When an error

has occurred, errno contains a value indicating the type of error that has been detected.

See Also: fputs, putch, puts

Example: #include <conio.h>

```
void main()
{
    char buffer[82];

    buffer[0] = 80;
    cgets( buffer );
    cputs( &buffer[2] );
    putch( '\r' );
    putch( '\n' );
}
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

### **Synopsis:** #include <sys/types.h>

```
#include <sys/stat.h>
```

#include <io.h>

int creat( const char \*path, mode\_t mode ); int \_creat( const char \*path, mode\_t mode ); int \_wcreat( const wchar\_t \*path, mode\_t mode );

**Description:** The creat function creates (and opens) a file at the operating system level. It is equivalent to:

```
open(path, O_WRONLY | O_CREAT | O_TRUNC, mode);
```

The \_creat function is identical to creat. Use \_creat for ANSI naming conventions.

The \_wcreat function is identical to creat except that it accepts a wide character string argument.

The name of the file to be created is given by path. When the file exists (it must be writeable), it is truncated to contain no data and the preceding mode setting is unchanged.

When the file does not exist, it is created with access permissions given by the *mode* argument. The access permissions for the file or directory are specified as a combination of bits (defined in the <sys/stat.h> header file).

The following bits define permissions for the owner.

Permission	Meaning				
S_IRWXU	Read, write, execute/search				
S_IRUSR	Read permission				
S_IWUSR	Write permission				
S IXUSR	Execute/search permission				

The following bits define permissions for the group.

Permission	Meaning				
S_IRWXG	Read, write, execute/search				
S_IRGRP	Read permission				
S_IWGRP	Write permission				
S IXGRP	Execute/search permission				

The following bits define permissions for others.

Permission	Meaning				
S_IRWXO	Read, write, execute/search				
S_IROTH	Read permission				
S_IWOTH	Write permission				
S_IXOTH	Execute/search permission				

The following bits define miscellaneous permissions used by other implementations.

**Systems:** 

	Permission	Meaning			
	S_IREAD S_IWRITE S_IEXEC	is equivalent to S_IRUSR (read permission) is equivalent to S_IWUSR (write permission) is equivalent to S_IXUSR (execute/search permission)			
	All files are readabl intended for the file	e with DOS; however, it is a good idea to set S_IREAD when read permission is			
Returns:		t returns a handle for the file. When an error occurs while opening the file, -1 is o is set to indicate the error.			
Errors:	When an error has o	occurred, errno contains a value indicating the type of error that has been detected.			
	Constant	Meaning			
	EACCES	Access denied because <i>path</i> specifies a directory or a volume ID, or a read-only file.			
	<b>EMFILE</b>	No more handles available (too many open files).			
	ENOENT	The specified path does not exist or path is an empty string.			
See Also:	_chsize, close, dup, dup2, _eof, exec, fdopen, _filelength, fileno, fstat, _grow_handles, isatty, lseek, open, read, _setmode, _sopen, stat, _tell, write, umask				
Example:	<pre>#include <sys #include="" <io.il<="" pre=""></sys></pre>	/stat.h>			
	<pre>void main() {    int handle</pre>	e <b>;</b>			
		creat( "file", S_IWRITE   S_IREAD ); e != -1 ) {			
	/* proc	ess file */			
	close( ) } }	handle );			
Classification	: POSIX 1003.1 _creat conforms to A	ANSI naming conventions			

\_wcreat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

166 Library Functions and Macros

creat - All, Linux, RDOS, Netware \_creat - All, Linux, RDOS, Netware

creat, _creat, _wcrea

Synopsis: #include <conio.h>
 int cscanf( const char \*format, ...);

**Description:** The cscanf function scans input from the console under control of the argument format. Following

the format string is a list of addresses to receive values. The cscanf function uses the function getche to read characters from the console. The *format* string is described under the description of

the scanf function.

**Returns:** The cscanf function returns EOF when the scanning is terminated by reaching the end of the input

stream. Otherwise, the number of input arguments for which values were successfully scanned and

stored is returned. When a file input error occurs, the errno global variable may be set.

See Also: fscanf, scanf, scanf, vcscanf, vfscanf, vscanf, vscanf, fwscanf, wscanf,

swscanf, vfwscanf, vwscanf, vswscanf

**Example:** To scan a date in the form "Saturday April 18 1987":

Classification: WATCOM

**Systems:** All, Linux, RDOS, Netware

# **Synopsis:**

```
#include <time.h>
char *ctime( const time_t *timer );
char *_ctime( const time_t *timer, char *buf );
wchar_t *_wctime( const time_t *timer );
wchar_t *__wctime( const time_t *timer, wchar_t *buf );
```

Safer C:

The Safer C Library extension provides the ctime\_s function which is a safer alternative to ctime.

**Description:** 

The **ctime** functions convert the calendar time pointed to by *timer* to local time in the form of a string. The **ctime** function is equivalent to

```
asctime( localtime( timer ) )
```

The **ctime** functions convert the time into a string containing exactly 26 characters. This string has the form shown in the following example:

```
Sat Mar 21 15:58:27 1987\n\0
```

All fields have a constant width. The new-line character '\n' and the null character '\0' occupy the last two positions of the string.

The ISO C function **ctime** places the result string in a static buffer that is re-used each time **ctime** or asctime is called. The non-ISO C function \_ctime places the result string in the buffer pointed to by buf.

The \_wctime function is a wide character version of ctime except that it produces a wide character

The \_\_wctime function is a wide character version of \_ctime except that it produces a wide character string.

Whenever the **ctime** functions are called, the tzset function is also called.

The calendar time is usually obtained by using the time function. That time is Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time (GMT)).

The time set on the computer with the DOS time command and the DOS date command reflects the local time. The environment variable TZ is used to establish the time zone to which this local time applies. See the section *The TZ Environment Variable* for a discussion of how to set the time zone.

**Returns:** 

The **ctime** functions return the pointer to the string containing the local time.

See Also:

asctime Functions, asctime\_s, clock, ctime\_s, difftime, gmtime, gmtime\_s, localtime, localtime\_s, mktime, strftime, time, tzset, ctime\_s

**Example:** 

```
#include <stdio.h>
#include <time.h>
void main()
    time_t time_of_day;
    auto char buf[26];
```

```
time_of_day = time( NULL );
    printf( "It is now: %s", _ctime( &time_of_day, buf ) );
}

produces the following:
    It is now: Fri Dec 25 15:58:42 1987

Classification: ISO C

Systems: ctime - All, Linux, RDOS, Netware _ctime - All, Linux, RDOS _wctime - All, Linux _ wctime - All, Linux
```

# **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <time.h>
errno_t ctime_s( char * s,
                 rsize_t maxsize,
                 const time_t * timer);
#include <wchar.h>
errno_t _wctime_s( wchar_t * s,
                   rsize_t maxsize,
                   const time_t * timer);
```

### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and ctime\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither s nor timer shall be a null pointer. maxsize shall not be less than 26 and shall not be greater than RSIZE\_MAX. If there is a runtime-constraint violation, s(0) is set to a null character if s is not a null pointer and *maxsize* is not equal zero and is not greater than *RSIZE\_MAX*.

**Description:** 

The ctime\_s function converts the calendar time pointed to by timer to local time in the form of a string. It is equivalent to

```
asctime_s( s, maxsize, localtime_s( timer ) )
```

# **Recommended practice:**

The strftime function allows more flexible formatting and supports locale-specific behavior. If you do not require the exact form of the result string produced by the ctime\_s function, consider using the strftime function instead.

**Returns:** 

The ctime\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

asctime Functions, asctime\_s, clock, ctime Functions, difftime, gmtime\_s, localtime, localtime\_s, mktime, strftime, time, tzset

**Example:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <time.h>
void main()
    time_t time_of_day;
    auto char buf[26];
    time_of_day = time( NULL );
    ctime_s( buf, sizeof( buf ), &time_of_day );
    printf( "It is now: %s", buf );
produces the following:
```

It is now: Mon Jan 30 14:29:55 2006

Classification: TR 24731

\_wctime\_s is WATCOM

**Systems:** ctime\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux,

RDOS, Netware

 $_{\text{wctime\_s}}$  - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,

Linux

**Synopsis:** #include <process.h>

```
int cwait( int *status, int process_id, int action );
int _cwait( int *status, int process_id, int action );
```

**Description:** 

The cwait function suspends the calling process until the specified process terminates.

If status is not NULL, it points to a word that will be filled in with the termination status word and return code of the terminated child process.

If the child process terminated normally, then the low order byte of the status word will be set to 0, and the high order byte will contain the low order byte of the return code that the child process passed to the DOSEXIT function. The DOSEXIT function is called whenever main returns, or exit, or \_Exit or \_exit are explicity called.

If the child process did not terminate normally, then the high order byte of the status word will be set to 0, and the low order byte will contain one of the following values:

#### Value Meaning

- Hard-error abort
- 2 Trap operation
- 3 SIGTERM signal not intercepted

Note:

This implementation of the status value follows the OS/2 model and differs from the Microsoft implementation. Under Microsoft, the return code is returned in the low order byte and it is not possible to determine whether a return code of 1, 2, or 3 imply that the process terminated normally. For portability to Microsoft compilers, you should ensure that the application that is waited on does not return one of these values. The following shows how to handle the status value in a portable manner.

```
cwait ( &status, process id, WAIT CHILD );
#if defined(__WATCOMC__)
switch( status & 0xff ) {
case 0:
   printf( "Normal termination exit code = %d\n", status >> 8 );
    break;
case 1:
    printf( "Hard-error abort\n" );
case 2:
    printf( "Trap operation\n" );
   break;
case 3:
    printf( "SIGTERM signal not intercepted\n" );
    break;
default:
   printf( "Bogus return status\n" );
#else if defined(_MSC_VER)
switch ( status & 0xff ) {
case 1:
   printf( "Possible Hard-error abort\n" );
   break;
case 2:
   printf( "Possible Trap operation\n" );
    break:
   printf( "Possible SIGTERM signal not intercepted\n" );
    break;
default:
    printf( "Normal termination exit code = %d\n", status );
#endif
```

The *process\_id* argument specifies which process to wait for. Under Win32, any process can wait for any other process for which the process ID is known. Under OS/2, a process can wait for any of its child processes. For example, a process ID is returned by certain forms of the spawn... functions that is used to start a child process.

The *action* argument specifies when the parent process resumes execution. This argument is ignored in Win32, but is accepted for compatibility with OS/2 (although Microsoft handles the *status* value differently from OS/2!). The possible values are:

Walt\_CHILD Wait until the specified child process has ended.
 WAIT\_GRANDCHILD Wait until the specified child process and all of the child processes of that child process have ended.

Under Win32, there is no parent-child relationship.

**Returns:** 

The cwait function returns the (child's) process ID if the (child) process terminated normally. Otherwise, cwait returns -1 and sets errno to one of the following values:

```
Constant
                          Meaning
            EINVAL
                          Invalid action code
            ECHILD
                          Invalid process ID, or the child does not exist.
            EINTR
                          The child process terminated abnormally.
See Also:
            exit, _Exit, _exit, spawn..., wait
Example:
            #include <stdio.h>
            #include cess.h>
            void main()
                        process_id;
                  int
                        status;
                  int
                 process_id = spawnl( P_NOWAIT, "child.exe",
                              "child", "parm", NULL );
                  cwait( &status, process_id, WAIT_CHILD );
Classification: WATCOM
Systems:
            cwait - Win32, OS/2 1.x(all), OS/2-32
            _cwait - Win32, OS/2 1.x(all), OS/2-32
```

Synopsis: #include <i86.h>

void delay( unsigned milliseconds );

**Description:** The delay function suspends execution by the specified number of *milliseconds*.

**Returns:** The delay function has no return value.

See Also: sleep

Example: #include <i86.h>

void main()
{
 sound( 200 );
 delay( 500 ); /\* delay for 1/2 second \*/
 nosound();

**Classification:** WATCOM

**Systems:** All, RDOS, Netware

```
Synopsis:
           #include <math.h>
           extern int _dieeetomsbin( double *src, double *dest );
```

**Description:** The \_dieeetomsbin function loads the double pointed to by src in IEEE format and converts it to Microsoft binary format, storing the result into the double pointed to by dest.

> For \_dieeetomsbin IEEE Nan's and Infinities will cause overflow. IEEE denormals will be converted if within range. Otherwise, they will be converted to 0 in the Microsoft binary format.

The range of Microsoft binary format floats is 2.938736e-39 to 1.701412e+38. The range of Microsoft binary format doubles is 2.938735877056e-39 to 1.701411834605e+38.

Microsoft Binary Format was used by early versions of Microsoft QuickBASIC before coprocessors became standard.

**Returns:** The \_dieeetomsbin function returns 0 if the conversion was successful. Otherwise, it returns 1 if conversion would cause an overflow.

See Also: \_dmsbintoieee, \_fieeetomsbin, \_fmsbintoieee

**Example:** #include <stdio.h> #include <math.h> void main()

{ float fieee, fmsb; double dieee, dmsb; fieee = 0.5; dieee = -2.0; /\* Convert IEEE format to Microsoft binary format \*/ \_fieeetomsbin( &fieee, &fmsb ); \_dieeetomsbin( &dieee, &dmsb ); /\* Convert Microsoft binary format back to IEEE format \*/ \_fmsbintoieee( &fmsb, &fieee ); \_dmsbintoieee( &dmsb, &dieee ); /\* Display results \*/ printf( "fieee = %f, dieee = %f\n", fieee, dieee );

produces the following:

fieee = 0.500000, dieee = -2.000000

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

_dieeetomsbin			

**Synopsis:** #include <time.h> double difftime( time\_t time1, time\_t time0 );

**Description:** The difftime function calculates the difference between the two calendar times:

time1 - time0

**Returns:** The difftime function returns the difference between the two times in seconds as a double.

See Also: asctime Functions, asctime\_s, clock, ctime Functions, ctime\_s, gmtime\_s, localtime, localtime\_s, mktime, strftime, time, tzset

Example: #include <stdio.h>

```
#include <time.h>
void compute( void );
void main()
 {
    time_t start_time, end_time;
    start_time = time( NULL );
    compute();
    end_time = time( NULL );
    printf( "Elapsed time: %f seconds\n",
        difftime( end_time, start_time ) );
  }
void compute( void )
    int i, j;
    for(i = 1; i \le 20; i++) {
      for( j = 1; j \le 20; j++ )
        printf( "%3d ", i * j );
      printf( "\n" );
```

**Classification:** ISO C

**Systems:** Math **Description:** The dirname function takes a pointer to a character string that contains a pathname, and returns a

pointer to a string that is a pathname of the parent directory of that file. Trailing path separators are not

considered as part of the path.

The dirname function may modify the string pointed to by *path* and may return a pointer to static storage that may be overwritten by a subsequent call to dirname

The dirname function is not re-entrant or thread-safe.

**Returns:** The dirname function returns a pointer to a string that is the parent directory of path. If path is a null

pointer or points to an empty string, a pointer to the string "." is returned.

See Also: basename

Example: #include <stdio.h>
#include <libgen.h>

```
int main( void )
{

   puts( dirname( "/usr/lib" ) );
   puts( dirname( "/usr/" ) );
   puts( dirname( "usr" ) );
   puts( dirname( "/" ) );
   puts( dirname( ".." ) );
   return( 0 );
}
```

produces the following:

/usr / . /

Classification: POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <i86.h> void \_disable( void );

**Description:** The \_disable function causes interrupts to become disabled.

> The \_disable function would be used in conjunction with the \_enable function to make sure that a sequence of instructions are executed without any intervening interrupts occurring.

**Returns:** The \_disable function returns no value.

See Also: \_enable

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
#include <i86.h>
struct list_entry {
   struct list_entry *next;
   int
                      data;
};
volatile struct list_entry *ListHead = NULL;
volatile struct list_entry *ListTail = NULL;
void insert( struct list_entry *new_entry )
  {
    /* insert new_entry at end of linked list */
   new_entry->next = NULL;
    _disable();
                     /* disable interrupts */
   if( ListTail == NULL ) {
      ListHead = new_entry;
    } else {
      ListTail->next = new_entry;
   ListTail = new_entry;
   _enable();
               /* enable interrupts now */
  }
void main()
  {
    struct list_entry *p;
    int i;
    for( i = 1; i <= 10; i++ ) {
      p = (struct list_entry *)
          malloc( sizeof( struct list_entry ) );
      if( p == NULL ) break;
     p->data = i;
      insert( p );
  }
```

Classification: Intel

**Systems:** All, Linux, RDOS, Netware

_disable			

**Synopsis:** #include <graph.h> short \_FAR \_displaycursor( short mode );

**Description:** The \_displaycursor function is used to establish whether the text cursor is to be displayed when

graphics functions complete. On entry to a graphics function, the text cursor is turned off. When the function completes, the mode setting determines whether the cursor is turned back on. The mode

argument can have one of the following values:

\_GCURSORON the cursor will be displayed

\_GCURSOROFF the cursor will not be displayed

**Returns:** The \_displaycursor function returns the previous setting for *mode*.

See Also: \_gettextcursor, \_settextcursor

**Example:** #include <stdio.h> #include <graph.h>

```
main()
    char buf[ 80 ];
    _setvideomode( _TEXTC80 );
    _settextposition(2, 1);
    _displaycursor( _GCURSORON );
    _outtext( "Cursor ON\n\nEnter your name >" );
    gets (buf);
   _displaycursor( _GCURSOROFF );
   _settextposition(6, 1);
   _outtext( "Cursor OFF\n\nEnter your name >" );
    gets (buf);
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

DOS **Systems:** 

```
Synopsis:
            #include <stdlib.h>
            div_t div( int numer, int denom );
            typedef struct {
                 int quot; /* quotient */
                                 /* remainder */
                 int rem;
            } div_t;
Description:
            The div function calculates the quotient and remainder of the division of the numerator numer by the
            denominator denom.
Returns:
            The div function returns a structure of type div_t which contains the fields quot and rem.
See Also:
            ldiv, lldiv, imaxdiv
Example:
            #include <stdio.h>
            #include <stdlib.h>
            void print_time( int seconds )
                  div_t min_sec;
                  min_sec = div( seconds, 60 );
                  printf( "It took %d minutes and %d seconds\n",
                           min_sec.quot, min_sec.rem );
            }
            void main( void )
                 print_time( 130 );
            produces the following:
            It took 2 minutes and 10 seconds
Classification: ISO C90
Systems:
            All, Linux, RDOS, Netware
```

**Synopsis:** #include <math.h> extern int \_dmsbintoieee( double \*src, double \*dest );

**Description:** The \_dmsbintoieee function loads the double pointed to by src in Microsoft binary format and converts it to IEEE format, storing the result into the double pointed to by dest.

> The range of Microsoft binary format floats is 2.938736e-39 to 1.701412e+38. The range of Microsoft binary format doubles is 2.938735877056e-39 to 1.701411834605e+38.

Microsoft Binary Format was used by early versions of Microsoft QuickBASIC before coprocessors became standard.

**Returns:** The \_dmsbintoieee function returns 0 if the conversion was successful. Otherwise, it returns 1 if conversion would cause an overflow.

See Also: \_dieeetomsbin, \_fieeetomsbin, \_fmsbintoieee

**Example:** #include <stdio.h> #include <math.h> void main() float fieee, fmsb; double dieee, dmsb;

fieee = 0.5; dieee = -2.0; /\* Convert IEEE format to Microsoft binary format \*/ \_fieeetomsbin(&fieee, &fmsb); \_dieeetomsbin( &dieee, &dmsb ); /\* Convert Microsoft binary format back to IEEE format \*/ \_fmsbintoieee( &fmsb, &fieee ); \_dmsbintoieee( &dmsb, &dieee ); /\* Display results \*/ printf( "fieee = %f, dieee = %f\n", fieee, dieee ); }

produces the following:

fieee = 0.500000, dieee = -2.000000

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

_dmsbintoieee			

**Synopsis:** 

```
#include <dos.h>
#if defined(__NT__) | \
  ( defined(\_OS2\_) && \
        (defined(__386__) | defined(__PPC__))))
unsigned _dos_allocmem( unsigned size,
                        void * *segment);
#else
unsigned _dos_allocmem( unsigned size,
                        unsigned *segment);
#endif
```

**Description:** 

The \_dos\_allocmem function uses system call 0x48 to allocate size paragraphs directly from DOS. The size of a paragraph is 16 bytes. The allocated memory is always paragraph aligned. The segment descriptor for the allocated memory is returned in the word pointed to by segment. If the allocation request fails, the maximum number of paragraphs that can be allocated is returned in this word instead.

For 32-bit DOS applications, it is recommended that the corresponding DPMI services be used.

**Returns:** 

The \_dos\_allocmem function returns zero if successful. Otherwise, it returns an OS error code and sets errno accordingly.

See Also: alloca, calloc, \_dos\_freemem, \_dos\_setblock, halloc, malloc

**Example:** 

```
#include <stdio.h>
#include <dos.h>
void main( void )
#if defined(__NT__) | \
  ( defined(__OS2__) && \
        (defined(__386__) || defined(__PPC__)) )
    void *segment;
#else
    unsigned segment;
#endif
    /* Try to allocate 100 paragraphs, then free them */
    if( _dos_allocmem( 100, &segment ) != 0 ) {
        printf( "_dos_allocmem failed\n" );
        printf( "Only %u paragraphs available\n",
                 segment );
    } else {
        printf( "_dos_allocmem succeeded\n" );
        if( _dos_freemem( segment ) != 0 ) {
            printf( "_dos_freemem failed\n" );
        } else {
            printf( "_dos_freemem succeeded\n" );
    }
```

**Classification:** DOS

**Systems:** DOS, Win32, OS/2 1.x(all), OS/2-32, DOS/PM

_dos_allocmem			

**Synopsis:** #include <dos.h> unsigned \_dos\_close( int handle );

**Description:** The \_dos\_close function uses system call 0x3E to close the file indicated by *handle*. The value for handle is the one returned by a function call that created or last opened the file.

**Returns:** The \_dos\_close function returns zero if successful. Otherwise, it returns an OS error code and sets errno accordingly.

See Also: creat, \_dos\_creat, \_dos\_creatnew, \_dos\_open, dup, fclose, open

**Example:** #include <stdio.h> #include <dos.h> #include <fcntl.h> void main() int handle; /\* Try to open "stdio.h" and then close it \*/ if( \_dos\_open( "stdio.h", O\_RDONLY, &handle ) != 0 ){ printf( "Unable to open file\n" ); } else { printf( "Open succeeded\n" ); if( \_dos\_close( handle ) != 0 ) { printf( "Close failed\n" ); printf( "Close succeeded\n" ); }

**Classification:** DOS

}

DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM **Systems:** 

Synopsis: #include <dos.h>
unsigned \_dos\_commit( int handle );

**Description:** The \_dos\_commit function uses system call 0x68 to flush to disk the DOS buffers associated with the

file indicated by handle. It also forces an update on the corresponding disk directory and the file

allocation table.

**Returns:** The \_dos\_commit function returns zero if successful. Otherwise, it returns an OS error code and sets

errno accordingly.

See Also: \_\_dos\_close, \_dos\_creat, \_dos\_open, \_dos\_write, fflush

Example: #include <stdio.h>

#include <dos.h>
#include <fcntl.h>
void main()

int handle;
if( \_dos\_open( "file", O\_RDONLY, handle ) != 0 ) {

} else {
 if( \_dos\_commit( handle ) == 0 ) {
 printf( "Commit succeeded.\n" );
 }
 \_dos\_close( handle );
}

printf( "Unable to open file\n" );

produces the following:

Commit succeeded.

**Classification:** DOS

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM

```
Synopsis:
           #include <dos.h>
           unsigned _dos_creat( const char *path,
                                 unsigned attribute,
                                 int *handle );
```

**Description:** 

The \_dos\_creat function uses system call 0x3C to create a new file named path, with the access attributes specified by attribute. The handle for the new file is returned in the word pointed to by handle. If the file already exists, the contents will be erased, and the attributes of the file will remain unchanged. The possible values for attribute are:

	Attribute	Meaning					
	_A_NORMAL	Indicates a normal file. File can be read or written without any restrictions.					
	_A_RDONLY	Indicates a read-only file. File cannot be opened for "write".					
	_A_HIDDEN	Indicates a hidden file. This file will not show up in a normal directory search.					
	_A_SYSTEM	Indicates a system file. This file will not show up in a normal directory search.					
Returns:	The _dos_cre	at function returns zero if successful. Otherwise, it returns an OS error code and sets gly.					
See Also:	· — —	creat, _dos_creatnew, _dos_open, _dos_close, open, fdopen, fopen, freopen, _fsopen, _grow_handles, _hdopen, open, _open_osfhandle, _popen, _sopen					
Example:	<pre>#include <stdio.h> #include <dos.h></dos.h></stdio.h></pre>						
	<pre>void main() {    int han</pre>	dle;					
	print } else print	<pre>s_creat( "file", _A_NORMAL, &amp;handle ) != 0 ){ f( "Unable to create file\n" ); { f( "Create succeeded\n" ); close( handle );</pre>					

**Classification:** DOS

**Systems:** DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM

_dos_creat			

**Synopsis:** #include <dos.h>

unsigned \_dos\_creatnew( const char \*path, unsigned attribute, int \*handle );

**Description:** 

The \_dos\_creatnew function uses system call 0x5B to create a new file named path, with the access attributes specified by attribute. The handle for the new file is returned in the word pointed to by handle. If the file already exists, the create will fail. The possible values for attribute are:

Attribute Meaning

A NORMAL Indicates a normal file. File can be read or written without any restrictions.

Indicates a read-only file. File cannot be opened for "write". \_A\_RDONLY

Indicates a hidden file. This file will not show up in a normal directory search. A HIDDEN

\_A\_SYSTEM Indicates a system file. This file will not show up in a normal directory search.

**Returns:** 

The \_dos\_creatnew function returns zero if successful. Otherwise, it returns an OS error code and sets errno. Possible values and their interpretations:

Constant Meaning **EACCES** Access denied because the directory is full, or the file exists and cannot be overwritten. **EEXIST** File already exists **EMFILE** No more handles available (i.e., too many open files)

Path or file not found

See Also:

**ENOENT** 

creat, \_dos\_creat, \_dos\_open, \_dos\_close, open, fdopen, fopen, freopen, \_fsopen, \_grow\_handles, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen

**Example:** 

```
#include <stdio.h>
#include <dos.h>
void main()
    int handle1, handle2;
    if( _dos_creat( "file", _A_NORMAL, &handle1 ) ){
      printf( "Unable to create file\n" );
    } else {
      printf( "Create succeeded\n" );
      if( _dos_creatnew( "file", _A_NORMAL, &handle2 ) ){
        printf( "Unable to create new file\n" );
      _dos_close( handle1 );
    }
  }
```

**Classification:** DOS

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM

```
Synopsis:
          #include <dos.h>
          int dosexterr( struct DOSERROR *err_info );
          struct _DOSERROR {
              int exterror; /* contents of AX register */
              char errclass; /* contents of BH register */
              char action; /* contents of BL register */
                               /* contents of CH register */
                      locus;
          };
```

**Description:** 

The dosexterr function extracts extended error information following a failed DOS function. This information is placed in the structure located by err\_info. This function is only useful with DOS version 3.0 or later.

You should consult the technical documentation for the DOS system on your computer for an interpretation of the error information.

**Returns:** 

The dosexterr function returns an unpredictable result when the preceding DOS call did not result in an error. Otherwise, dosexterr returns the number of the extended error.

See Also: perror

**Example:** 

```
#include <stdio.h>
#include <dos.h>
#include <fcntl.h>
struct _DOSERROR dos_err;
void main()
  {
    int handle;
    /* Try to open "stdio.h" and then close it */
    if( _dos_open( "stdio.h", O_RDONLY, &handle ) != 0 ){
      dosexterr( &dos_err );
      printf( "Unable to open file\n" );
      printf( "exterror (AX) = %d\n", dos_err.exterror );
      printf( "errclass (BH) = %d\n", dos_err.errclass );
      printf( "action (BL) = %d\n", dos_err.action );
      printf( "locus
                        (CH) = dn'', dos_err.locus);
    } else {
      printf( "Open succeeded\n" );
      if( _dos_close( handle ) != 0 ) {
        printf( "Close failed\n" );
      } else {
        printf( "Close succeeded\n" );
    }
  }
```

produces the following:

## dosexterr

```
Unable to open file exterror (AX) = 2 errclass (BH) = 8 action (BL) = 3 locus (CH) = 2
```

**Classification:** DOS

**Systems:** DOS, Windows, Win386, DOS/PM

```
Synopsis:
          #include <dos.h>
          unsigned _dos_findfirst( const char *path,
                                   unsigned attributes,
                                   struct find_t *buffer );
          unsigned _dos_findnext( struct find_t *buffer );
          unsigned _dos_findclose( struct find_t *buffer );
          struct find_t {
              char
                             reserved[21]; /* reserved for use by DOS
                             attrib; /* attribute byte for file
              char
                                                                         */
                                          /* time of last write to file */
              unsigned short wr_time;
                                          /* date of last write to file */
              unsigned short wr_date;
              unsigned long size;
                                          /* length of file in bytes
                                                                         */
          #if defined(__OS2__) | defined(__NT__)
                             name[256]; /* null-terminated filename
                                                                        */
          #else
                                          /* null-terminated filename
                             name[13];
                                                                        * /
              char
          #endif
          };
          unsigned _wdos_findfirst( const wchar_t *path,
                                    unsigned attributes,
                                    struct _wfind_t *buffer );
          unsigned _wdos_findnext( struct _wfind_t *buffer );
          unsigned _wdos_findclose( struct _wfind_t *buffer );
          struct _wfind_t {
              char
                             reserved[21]; /* reserved for use by DOS
                             attrib; /* attribute byte for file
              char
                                                                        */
                                         /* time of last write to file */
              unsigned short wr_time;
                                         /* date of last write to file */
              unsigned short wr_date;
              unsigned long size; /* length of file in bytes
                                                                        */
          #if defined(__OS2__) | defined(__NT__)
                            name[256]; /* null-terminated filename
                                                                        */
              wchar_t
          #else
                                                                        */
                           name[13]; /* null-terminated filename
              wchar_t
          #endif
          };
```

**Description:** 

The \_dos\_findfirst function uses system call 0x4E to return information on the first file whose name and attributes match the path and attributes arguments. The information is returned in a find\_t structure pointed to by buffer. The path argument may contain wildcard characters ('?' and '\*'). The attributes argument may be any combination of the following constants:

Attribute	Meaning
_A_NORMAL	Indicates a normal file. File can be read or written without any restrictions.
_A_RDONLY	Indicates a read-only file. File cannot be opened for "write".
_A_HIDDEN	Indicates a hidden file. This file will not show up in a normal directory search.
_A_SYSTEM	Indicates a system file. This file will not show up in a normal directory search.
_A_VOLID	Indicates a volume-ID.

\_A\_SUBDIR Indicates a sub-directory.

\_A\_ARCH This is the archive flag. It is set whenever the file is modified, and is cleared by the MS-DOS BACKUP command and other backup utility programs.

The attributes argument is interpreted by DOS as follows:

- 1. If \_A\_NORMAL is specified, then normal files are included in the search.
- 2. If any of \_A\_HIDDEN, \_A\_SYSTEM, \_A\_SUBDIR are specified, then normal files and the specified type of files are included in the search.
- 3. If \_A\_VOLID is specified, then volume-ID's are also included in the search. Note: The \_A\_VOLID attribute is not supported on systems other than DOS (e.g. Win32, OS/2).
- 4. \_A\_RDONLY and \_A\_ARCH are ignored by this function.

The format of the wr\_time field is described by the following structure (this structure is not defined in any Open Watcom header file).

```
typedef struct {
   unsigned short twosecs : 5;    /* seconds / 2    */
   unsigned short minutes : 6;    /* minutes (0,59) */
   unsigned short hours : 5;    /* hours (0,23)    */
} ftime_t;
```

The format of the wr\_date field is described by the following structure (this structure is not defined in any Open Watcom header file).

```
typedef struct {
   unsigned short day : 5;     /* day (1,31) */
   unsigned short month : 4;     /* month (1,12) */
   unsigned short year : 7;     /* 0 is 1980 */
} fdate_t;
```

The \_dos\_findnext function uses system call 0x4F to return information on the next file whose name and attributes match the pattern supplied to the \_dos\_findfirst function.

On some systems (e.g. Win32, OS/2), you must call \_dos\_findclose to indicate that you are done matching files. This function deallocates any resources that were allocated by the \_dos\_findfirst function.

The \_wdos\_find... functions are similar to their counterparts but operate on wide character strings.

**Returns:** The \_dos\_find... functions return zero if successful. Otherwise, the \_dos\_findfirst and \_dos\_findnext functions return an OS error code and set errno accordingly.

See Also: opendir, readdir, closedir

Example: #include <stdio.h>
 #include <dos.h>

 void main()
{
 struct find\_t fileinfo;
 unsigned rc; /\* return code \*/

```
/* Display name and size of "*.c" files */
               rc = _dos_findfirst( "*.c", _A_NORMAL, &fileinfo );
               while( rc == 0 ) {
                   printf( "%14s %10ld\n", fileinfo.name,
                                            fileinfo.size );
                   rc = _dos_findnext( &fileinfo );
               #if defined(__OS2__)
               _dos_findclose( &fileinfo );
               #endif
Classification: DOS
           _dos_findclose - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
           DOS/PM
           _dos_findfirst - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
           DOS/PM
           _dos_findnext - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
          DOS/PM
          _wdos_findclose - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

\_wdos\_findfirst - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32 \_wdos\_findnext - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

**Systems:** 

```
Synopsis:
            #include <dos.h>
            #if defined(__NT__) | \
               ( defined(__OS2__) && \
                     (defined(__386__) | defined(__PPC__)))
            unsigned _dos_freemem( void *
                                               segment );
            #else
            unsigned _dos_freemem( unsigned segment );
            #endif
Description:
            The _dos_freemem function uses system call 0x49 to release memory that was previously allocated
            by _dos_allocmem. The value contained in segment is the one returned by a previous call to
            _dos_allocmem.
            For 32-bit DOS applications, it is recommended that the corresponding DPMI services be used.
Returns:
            The _dos_freemem function returns zero if successful. Otherwise, it returns an OS error code and
            sets errno accordingly.
See Also:
            _dos_allocmem, _dos_setblock, free, hfree
Example:
            #include <stdio.h>
            #include <dos.h>
            void main( void )
            #if defined(__NT__) | \
               ( defined(__OS2__) && \
                      (defined(__386__) | defined(__PPC__)) )
                 void *segment;
            #else
                 unsigned segment;
            #endif
                 /* Try to allocate 100 paragraphs, then free them */
                 if( _{dos\_allocmem(100, \&segment)} != 0 ) {
                     printf( "\_dos\_allocmem failed\n" );
                     printf( "Only %u paragraphs available\n",
                                segment );
                 } else {
                     printf( "_dos_allocmem succeeded\n" );
                     if( _dos_freemem( segment ) != 0 ) {
                          printf( "_dos_freemem failed\n" );
                          printf( "_dos_freemem succeeded\n" );
                 }
Classification: DOS
```

DOS, Win32, OS/2 1.x(all), OS/2-32, DOS/PM

**Systems:** 

	_dos_freemem

```
Synopsis:
            #include <dos.h>
            void _dos_getdate( struct dosdate_t *date );
            struct dosdate_t {
                                           /* 1-31
                unsigned char day;
                                           /* 1-12
                                                                 */
                unsigned char month;
                unsigned short year; /* 1980-2099
                                                                 */
                unsigned char dayofweek; /* 0-6 (0=Sunday) */
            };
Description:
           The _dos_getdate function uses system call 0x2A to get the current system date. The date
            information is returned in a dosdate_t structure pointed to by date.
Returns:
           The _dos_getdate function has no return value.
See Also:
            _dos_gettime, _dos_setdate, _dos_settime, gmtime, localtime, mktime, time
Example:
            #include <stdio.h>
            #include <dos.h>
            void main()
              {
                struct dosdate_t date;
                struct dostime_t time;
                /* Get and display the current date and time */
                _dos_getdate( &date );
                _dos_gettime( &time );
                printf( "The date (MM-DD-YYYY) is: %d-%d-%d\n",
                                date.month, date.day, date.year );
                printf( "The time (HH:MM:SS) is: %.2d:\%.2d\n",
                                time.hour, time.minute, time.second );
              }
            produces the following:
            The date (MM-DD-YYYY) is: 12-25-1989
            The time (HH:MM:SS) is: 14:23:57
Classification: DOS
Systems:
           DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM
```

```
unsigned _dos_getdiskfree( unsigned drive,
                                        struct diskfree_t *diskspace );
            struct diskfree_t {
                 unsigned short total_clusters;
                 unsigned short avail_clusters;
                 unsigned short sectors_per_cluster;
                 unsigned short bytes_per_sector;
            };
Description:
            The _dos_getdiskfree function uses system call 0x36 to obtain useful information on the disk
            drive specified by drive. Specify 0 for the default drive, 1 for drive A, 2 for drive B, etc. The
            information about the drive is returned in the structure diskfree_t pointed to by diskspace.
Returns:
            The _dos_getdiskfree function returns zero if successful. Otherwise, it returns a non-zero value
            and sets errno to EINVAL indicating an invalid drive was specified.
See Also:
            _dos_getdrive, _dos_setdrive, _getdiskfree, _getdrive
Example:
            #include <stdio.h>
            #include <dos.h>
            void main()
              {
                 struct diskfree_t disk_data;
                 /* get information about drive 3 (the C drive) */
                 if( _dos_getdiskfree( 3, &disk_data ) == 0 ) {
                   printf( "total clusters: %u\n",
                                        disk_data.total_clusters );
                   printf( "available clusters: %u\n",
                                        disk_data.avail_clusters );
                   printf( "sectors/cluster: %u\n",
                                        disk_data.sectors_per_cluster );
                   printf( "bytes per sector: u\n",
                                        disk_data.bytes_per_sector );
                 } else {
                   printf( "Invalid drive specified\n" );
              }
            produces the following:
            total clusters: 16335
            available clusters: 510
            sectors/cluster: 4
            bytes per sector: 512
Classification: DOS
```

**Synopsis:** 

**Systems:** 

#include <dos.h>

_dos_getdiskfree			

```
Synopsis:
             #include <dos.h>
             void _dos_getdrive( unsigned *drive );
Description:
             The _dos_getdrive function uses system call 0x19 to get the current disk drive number. The
             current disk drive number is returned in the word pointed to by drive. A value of 1 is drive A, 2 is drive
             B, 3 is drive C, etc.
Returns:
             The _dos_getdrive function has no return value.
See Also:
             _dos_getdiskfree, _dos_setdrive, _getdiskfree, _getdrive
Example:
             #include <stdio.h>
             #include <dos.h>
             void main()
                {
                  unsigned drive;
                  _dos_getdrive( &drive );
                  printf( "The current drive is c\n",
                                 'A' + drive - 1 );
                }
             produces the following:
```

**Systems:** 

DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM

The current drive is C

**Returns:** 

**Description:** The \_dos\_getfileattr function uses system call 0x43 to get the current attributes of the file or directory that *path* points to. The possible attributes are:

Attribute Meaning  $\_A\_NORMAL$ Indicates a normal file. File can be read or written without any restrictions. \_A\_RDONLY Indicates a read-only file. File cannot be opened for "write". Indicates a hidden file. This file will not show up in a normal directory search. \_A\_HIDDEN \_A\_SYSTEM Indicates a system file. This file will not show up in a normal directory search. \_A\_VOLID Indicates a volume-ID. \_A\_SUBDIR Indicates a sub-directory. This is the archive flag. It is set whenever the file is modified, and is cleared by the  $\_A\_ARCH$ MS-DOS BACKUP command and other backup utility programs.

The \_dos\_getfileattr function returns zero if successful. Otherwise, it returns an OS error code and sets errno accordingly.

See Also: \_dos\_setfileattr **Example:** #include <stdio.h> #include <dos.h> print\_attribute() { unsigned attribute; \_dos\_getfileattr( "file", &attribute ); printf( "File attribute is %d\n", attribute ); if( attribute & \_A\_RDONLY ) { printf( "This is a read-only file.\n" ); } else { printf( "This is not a read-only file.\n" ); } void main()

handle;

{

int

```
if( _dos_creat( "file", _A_RDONLY, &handle ) != 0 ) {
  printf( "Error creating file\n" );
print_attribute();
_dos_setfileattr( "file", _A_NORMAL );
print_attribute();
_dos_close( handle );
```

Synopsis: #include <dos.h>

**Description:** 

The \_dos\_getftime function uses system call 0x57 to get the date and time that the file associated with *handle* was last modified. The date consists of the year, month and day packed into 16 bits as follows:

Bits	Meaning
bits 0-4	Day (1-31)
bits 5-8	Month (1-12)
bits 9-15	Year (0-119 representing 1980-2099)

The time consists of the hour, minute and seconds/2 packed into 16 bits as follows:

Bits	Meaning
bits 0-4	Seconds/2 (0-29)
bits 5-10	Minutes (0-59)
bits 11-15	Hours (0-23)

gats a mma

The \_dos\_getftime function returns zero if successful. Otherwise, it returns an OS error code and sets errno accordingly.

```
See Also: __dos__setftime
```

```
Example:
```

**Returns:** 

```
if( _dos_open( "file", O_RDONLY, &handle ) != 0 ) {
        printf( "Unable to open file\n" );
    } else {
        printf( "Open succeeded\n" );
        _dos_getftime( handle, &date, &time );
        printf( "The file was last modified on d/d/d",
                MONTH(date), DAY(date), YEAR(date));
        printf( " at %.2d:%.2d:%.2d\n",
                HOUR(time), MINUTE(time), SECOND(time));
        _dos_close( handle );
    }
}
produces the following:
Open succeeded
The file was last modified on 12/29/1989 at 14:32:46
```

```
Synopsis:
            #include <dos.h>
            void _dos_gettime( struct dostime_t *time );
            struct dostime_t {
                unsigned char hour;
                                           /* 0-23
                unsigned char minute; /* 0-59
                                                                     */
                unsigned char second; /* 0-59
                unsigned char hsecond; /* 1/100 second; 0-99 */
            };
Description:
           The _dos_gettime function uses system call 0x2C to get the current system time. The time
            information is returned in a dostime_t structure pointed to by time.
Returns:
           The _dos_gettime function has no return value.
See Also:
            _dos_getdate, _dos_setdate, _dos_settime, gmtime, localtime, mktime, time
Example:
            #include <stdio.h>
            #include <dos.h>
            void main()
              {
                struct dosdate_t date;
                struct dostime_t time;
                /* Get and display the current date and time */
                _dos_getdate( &date );
                _dos_gettime( &time );
                printf( "The date (MM-DD-YYYY) is: %d-%d-%d\n",
                    date.month, date.day, date.year);
                printf( "The time (HH:MM:SS) is: %.2d:\%.2d\n",
                    time.hour, time.minute, time.second );
              }
            produces the following:
            The date (MM-DD-YYYY) is: 12-25-1989
            The time (HH:MM:SS) is: 14:23:57
Classification: DOS
Systems:
           DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, DOS/PM
```

```
Synopsis:
            #include <dos.h>
            void (__interrupt __far *_dos_getvect(unsigned intnum))();
Description:
            The _dos_getvect function gets the current value of interrupt vector number intnum.
Returns:
            The _dos_getvect function returns a far pointer to the current interrupt handler for interrupt number
            intnum.
See Also:
            _chain_intr, _dos_keep, _dos_setvect
Example:
            #include <stdio.h>
            #include <dos.h>
            volatile int clock_ticks;
            void (__interrupt __far *prev_int_1c)();
#define BLIP_COUNT (5*18) /* 5 seconds */
            void __interrupt __far timer_rtn()
                 ++clock_ticks;
                 _chain_intr( prev_int_1c );
            int delays = 0;
            int compile_a_line()
                 if( delays > 15 ) return( 0 );
                 delay( 1000 ); /* delay for 1 second */
                 printf( "Delayed for 1 second\n" );
                delays++;
                 return(1);
              }
            void main()
              {
                 prev_int_1c = _dos_getvect( 0x1c );
                 _dos_setvect( 0x1c, timer_rtn );
                 while( compile_a_line() ) {
                     if( clock_ticks >= BLIP_COUNT ) {
                          putchar( '.' );
                          clock_ticks -= BLIP_COUNT;
                 _dos_setvect( 0x1c, prev_int_1c );
```

**Classification:** WATCOM

**Systems:** DOS, Windows, DOS/PM

_dos_getvect				

**Synopsis:** #include <dos.h> void \_dos\_keep( unsigned retcode, unsigned memsize );

**Description:** The \_dos\_keep function is used to install terminate-and-stay-resident programs ("TSR's") in

memory. The amount of memory kept for the program is memsize paragraphs (a paragraph is 16 bytes) from the Program Segment Prefix which is stored in the variable \_psp. The value of retcode is

returned to the parent process.

**Returns:** The \_dos\_keep function does not return to its caller.

See Also: \_chain\_intr, \_dos\_getvect, \_dos\_setvect

**Example:** #include <dos.h>

```
void permanent()
    /* . */
    /* . */
void transient()
void main()
    /* initialize our TSR */
    transient();
    /*
        now terminate and keep resident
        the non-transient portion
        Note: following calculation only works in .COM files
    _{dos_{keep}(0, (FP_{OFF(transient) + 15)} >> 4);
```

**Classification:** DOS

**Systems:** DOS Synopsis: #include <dos.h>

#include <fcntl.h>
#include <share.h>

**Description:** 

The \_dos\_open function uses system call 0x3D to open the file specified by *path*, which must be an existing file. The *mode* argument specifies the file's access, sharing and inheritance permissions. The access mode must be one of:

Mode	Meaning
O_RDONLY	Read only
$O_{WRONLY}$	Write only
$O_RDWR$	Both read and write

The sharing permissions, if specified, must be one of:

Permission	Meaning		
SH_COMPAT	Set compatibility mode.		
SH_DENYRW	Prevent read or write access to the file.		
SH_DENYWR	Prevent write access of the file.		
SH_DENYRD	Prevent read access to the file.		
SH_DENYNO	Permit both read and write access to the file.		

The inheritance permission, if specified, is:

Permission Meaning

**O\_NOINHERIT** File is not inherited by a child process

**Returns:** 

See Also:

The \_dos\_open function returns zero if successful. Otherwise, it returns an MS-DOS error code and sets error to one of the following values:

Constant	Meaning
EACCES	Access denied because <i>path</i> specifies a directory or a volume ID, or opening a read-only file for write access
EINVAL	A sharing mode was specified when file sharing is not installed, or access-mode value is invalid
<b>EMFILE</b>	No more handles available, (too many open files)
ENOENT	Path or file not found
	os_creat, _dos_creatnew, _dos_read, _dos_write, fdopen, fopen, en, _grow_handles, _hdopen, open, _open_osfhandle, _popen,

\_sopen

```
Example:
           #include <stdio.h>
           #include <dos.h>
           #include <fcntl.h>
           #include <share.h>
           void main()
             {
               int handle;
               if( _{dos\_open}( "file", O_{RDONLY}, &handle ) != 0 ) {
                   printf( "Unable to open file\n" );
               } else {
                   printf( "Open succeeded\n" );
                   _dos_close( handle );
```

**Description:** The \_dos\_read function uses system call 0x3F to read *count* bytes of data from the file specified by *handle* into the buffer pointed to by *buffer*. The number of bytes successfully read will be stored in the

unsigned integer pointed to by bytes.

**Returns:** The \_dos\_read function returns zero if successful. Otherwise, it returns an OS error code and sets

errno accordingly.

See Also: \_\_dos\_close, \_dos\_open, \_dos\_write

Example: #include <stdio.h>
#include <dos.h>
#include <fcntl.h>

```
void main()
{
   unsigned len_read;
   int      handle;
   auto char buffer[80];

   if( _dos_open( "file", O_RDONLY, &handle ) != 0 ) {
      printf( "Unable to open file\n" );
   } else {
      printf( "Open succeeded\n" );
      _dos_read( handle, buffer, 80, &len_read );
      _dos_close( handle );
   }
}
```

**Classification:** DOS

```
Synopsis:
           #include <dos.h>
           unsigned _dos_setblock( unsigned size,
                                     unsigned segment,
                                     unsigned *maxsize );
```

**Description:** The \_dos\_setblock function uses system call 0x4A to change the size of segment, which was previously allocated by \_dos\_allocmem, to size paragraphs. If the request fails, the maximum number of paragraphs that this memory block can be changed to is returned in the word pointed to by maxsize.

For 32-bit DOS applications, it is recommended that the corresponding DPMI services be used.

**Returns:** The \_dos\_setblock function returns zero if successful. Otherwise, it returns an OS error code and sets errno to ENOMEM indicating a bad segment value, insufficient memory or corrupted memory.

See Also: \_dos\_allocmem, \_dos\_freemem, realloc

#if defined(\_\_DOS\_\_\_)

} else {

**Example:** #include <stdio.h> #include <dos.h> void main( void ) #if defined(\_\_NT\_\_) | \ ( defined(\_\_OS2\_\_) && \ (defined(\_\_386\_\_) | defined(\_\_PPC\_\_)))) void \*segment; #else unsigned segment; #endif /\* Try to allocate 100 paragraphs, then free them \*/ if  $(\_dos\_allocmem(100, \&segment) != 0) {$ printf( "\_dos\_allocmem failed\n" ); printf( "Only %u paragraphs available\n", segment); } else { printf( "\_dos\_allocmem succeeded\n" );

{ unsigned maxsize = 0;

#endif

printf( "\_dos\_setblock succeeded\n" );

/\* Try to increase it to 200 paragraphs \*/

if( \_dos\_setblock( 200, segment, &maxsize ) != 0 ) { printf( "\_dos\_setblock failed: max=%u, err=%s\n", maxsize, strerror( errno) );

```
if( _dos_freemem( segment ) != 0 ) {
        printf( "_dos_freemem failed\n" );
} else {
        printf( "_dos_freemem succeeded\n" );
}
}
```

**Systems:** DOS, DOS/PM

```
Synopsis:
           #include <dos.h>
           unsigned _dos_setdate( struct dosdate_t *date );
           struct dosdate_t {
                                               /* 1-31
                                                                  */
                unsigned char
                                 day;
                                                                  */
                unsigned char month;
                                              /* 1-12
                                              /* 1980-2099
                                                                  */
                unsigned short year;
                unsigned char dayofweek;
                                              /* 0-6 (0=Sunday) */
           };
Description:
           The _dos_setdate function uses system call 0x2B to set the current system date. The date
           information is passed in a dosdate_t structure pointed to by date.
Returns:
           The _dos_setdate function returns zero if successful. Otherwise, it returns an OS error code and
           sets errno accordingly.
See Also:
           _dos_getdate, _dos_gettime, _dos_settime, gmtime, localtime, mktime, time
Example:
           #include <stdio.h>
           #include <dos.h>
           void main()
              {
                struct dosdate_t date;
                struct dostime_t time;
                /* Get and display the current date and time */
                dos getdate ( &date );
                _dos_gettime( &time );
                printf( "The date (MM-DD-YYYY) is: %d-%d-%d\n",
                    date.month, date.day, date.year);
                printf( "The time (HH:MM:SS) is: %.2d:\%.2d:\%.2d\n",
                    time.hour, time.minute, time.second );
                /* Change it to the turn of the century */
                date.year = 1999;
                date.month = 12;
                date.day = 31;
                time.hour = 23;
                time.minute = 59;
                _dos_setdate( &date );
                _dos_settime( &time );
                printf( "New date (MM-DD-YYYY) is: %d-%d-%d\n",
                    date.month, date.day, date.year );
                printf( "New time (HH:MM:SS) is: %.2d:%.2d:%.2d\n",
                    time.hour, time.minute, time.second );
              }
           produces the following:
           The date (MM-DD-YYYY) is: 12-25-1989
           The time (HH:MM:SS) is: 14:23:15
           New date (MM-DD-YYYY) is: 12-31-1999
           New time (HH:MM:SS) is: 23:59:16
```

## \_dos\_setdate

Classification: DOS

**Synopsis:** #include <dos.h>

void \_dos\_setdrive( unsigned drive, unsigned \*total );

**Description:** The \_dos\_setdrive function uses system call 0x0E to set the current default disk drive to be the

drive specified by drive, where 1 = drive A, 2 = drive B, etc. The total number of disk drives is returned in the word pointed to by total. For DOS versions 3.0 or later, the minimum number of drives returned

is 5.

**Returns:** The \_dos\_setdrive function has no return value. If an invalid drive number is specified, the

function fails with no error indication. You must use the \_dos\_getdrive function to check that the

desired drive has been set.

See Also: \_dos\_getdiskfree, \_dos\_getdrive, \_getdiskfree, \_getdrive

**Example:** #include <stdio.h> #include <dos.h>

```
void main()
  {
    unsigned drive1, drive2, total;
   _dos_getdrive( &drive1 );
   printf( "Current drive is %c\n", 'A' + drive1 - 1 );
    /* try to change to drive C */
   _dos_setdrive(3, &total);
   _dos_getdrive( &drive2 );
   printf( "Current drive is %c\n", 'A' + drive2 - 1 );
    /* go back to original drive */
   _dos_setdrive( drive1, &total );
   _dos_getdrive( &drivel );
   printf( "Current drive is %c\n", 'A' + drive1 - 1 );
   printf( "Total number of drives is %u\n", total );
```

produces the following:

Current drive is D Current drive is C Total number of drives is 6

**Classification:** DOS

**Returns:** 

**Description:** The \_dos\_setfileattr function uses system call 0x43 to set the attributes of the file or directory that *path* points to. The possible attributes are:

Attribute Meaning  $\_A\_NORMAL$ Indicates a normal file. File can be read or written without any restrictions. \_A\_RDONLY Indicates a read-only file. File cannot be opened for "write". Indicates a hidden file. This file will not show up in a normal directory search. \_A\_HIDDEN \_A\_SYSTEM Indicates a system file. This file will not show up in a normal directory search. \_A\_VOLID Indicates a volume-ID. \_A\_SUBDIR Indicates a sub-directory. This is the archive flag. It is set whenever the file is modified, and is cleared by the  $\_A\_ARCH$ MS-DOS BACKUP command and other backup utility programs.

The \_dos\_setfileattr function returns zero if successful. Otherwise, it returns an OS error code and sets errno accordingly.

See Also: \_\_dos\_getfileattr

Example: #include <stdio.h>
#include <dos.h>

print\_attribute()
{

unsigned attribute;

```
_dos_getfileattr( "file", &attribute );
printf( "File attribute is %x\n", attribute );
if( attribute & _A_RDONLY ) {
    printf( "This is a read-only file\n" );
} else {
    printf( "This is not a read-only file\n" );
}

void main()
{
    int handle;
```

```
if( _dos_creat( "file", _A_RDONLY, &handle ) != 0 ){
  printf( "Error creating file\n" );
print_attribute();
_dos_setfileattr( "file", _A_NORMAL );
print_attribute();
_dos_close( handle );
```

Synopsis: #include <dos.h>

**Description:** 

The \_dos\_setftime function uses system call 0x57 to set the date and time that the file associated with *handle* was last modified. The date consists of the year, month and day packed into 16 bits as follows:

Bits	Meaning
bits 0-4	Day (1-31)
bits 5-8	Month (1-12)
bits 9-15	Year (0-119 representing 1980-2099)

The time consists of the hour, minute and seconds/2 packed into 16 bits as follows:

Bits	Meaning
bits 0-4	Seconds/2 (0-29)
bits 5-10	Minutes (0-59)
bits 11-15	Hours (0-23)

**Returns:** Th

The \_dos\_setftime function returns zero if successful. Otherwise, it returns an OS error code and sets errno accordingly.

```
See Also: _dos_getftime
```

```
Example:
```

```
#include <stdio.h>
#include <dos.h>
#include <fcntl.h>
                  (((t \& 0xFE00) >> 9) + 1980)
#define YEAR(t)
#define MONTH(t) ((t & 0x01E0) >> 5)
#define DAY(t)
                  (t \& 0x001F)
#define HOUR(t)
                  ((t \& 0xF800) >> 11)
\#define MINUTE(t) ((t & 0x07E0) >> 5)
\#define SECOND(t) ((t \& 0x001F) << 1)
void main( void )
{
    int handle;
    unsigned short date, time;
```

```
if( _dos_open( "file", O_RDWR, &handle ) != 0 ) {
        printf( "Unable to open file\n" );
    } else {
      printf( "Open succeeded\n" );
        _dos_getftime( handle, &date, &time );
        printf( "The file was last modified on %d/%d/%d",
                MONTH(date), DAY(date), YEAR(date));
        printf( " at %.2d:%.2d:%.2d\n",
                HOUR(time), MINUTE(time), SECOND(time) );
        /* set the time to 12 noon */
        time = (12 << 11) + (0 << 5) + 0;
        _dos_setftime( handle, date, time );
        _dos_getftime( handle, &date, &time );
        printf( "The file was last modified on %d/%d/%d",
                MONTH(date), DAY(date), YEAR(date));
        printf( " at %.2d:%.2d:%.2d\n",
                HOUR(time), MINUTE(time), SECOND(time) );
        _dos_close( handle );
    }
}
produces the following:
Open succeeded
The file was last modified on 12/29/1989 at 14:32:46
The file was last modified on 12/29/1989 at 12:00:00
```

```
Synopsis:
            #include <dos.h>
            unsigned _dos_settime( struct dostime_t *time );
            struct dostime_t {
                                         /* 0-23
                unsigned char hour;
                                                                   */
                unsigned char minute; /* 0-59
                                                                   */
                                                                   */
                unsigned char second; /* 0-59
                unsigned char hsecond; /* 1/100 second; 0-99 */
            };
Description:
           The _dos_settime function uses system call 0x2D to set the current system time. The time
            information is passed in a dostime_t structure pointed to by time.
Returns:
           The _dos_settime function returns zero if successful. Otherwise, it returns a non-zero value and
            sets errno to EINVAL indicating that an invalid time was given.
See Also:
            _dos_getdate, _dos_setdate, _dos_gettime, gmtime, localtime, mktime, time
Example:
            #include <stdio.h>
            #include <dos.h>
            void main()
              {
                struct dosdate_t date;
                struct dostime t time;
                /* Get and display the current date and time */
                _dos_getdate( &date );
                _dos_gettime( &time );
                printf( "The date (MM-DD-YYYY) is: %d-%d-%d\n",
                     date.month, date.day, date.year );
                printf( "The time (HH:MM:SS) is: %.2d:%.2d:%.2d\n",
                    time.hour, time.minute, time.second );
                /* Change it to the turn of the century */
                date.year = 1999;
                date.month = 12;
                date.day = 31;
                time.hour = 23;
                time.minute = 59;
                _dos_setdate( &date );
                _dos_settime( &time );
                printf( "New date (MM-DD-YYYY) is: %d-%d-%d\n",
                               date.month, date.day, date.year );
                printf( "New time (HH:MM:SS) is: %.2d:%.2d:%.2d\n",
                               time.hour, time.minute, time.second );
              }
            produces the following:
           The date (MM-DD-YYYY) is: 12-25-1989
            The time (HH:MM:SS) is: 14:23:15
            New date (MM-DD-YYYY) is: 12-31-1999
            New time (HH:MM:SS) is: 23:59:16
```

```
Synopsis:
            #include <dos.h>
            void _dos_setvect( unsigned intnum,
                                  void (__interrupt __far *handler)() );
Description:
            The _dos_setvect function sets interrupt vector number intnum to point to the interrupt handling
            function pointed to by handler.
Returns:
            The _dos_setvect function does not return a value.
See Also:
            _chain_intr, _dos_getvect, _dos_keep
Example:
            #include <stdio.h>
            #include <dos.h>
            volatile int clock_ticks;
            void (__interrupt __far *prev_int_1c)();
#define BLIP_COUNT (5*18) /* 5 seconds */
            void __interrupt __far timer_rtn()
              {
                 ++clock_ticks;
                 _chain_intr( prev_int_1c );
            int compile_a_line()
              {
                 static int delays = 0;
                 if ( delays > 15 ) return ( 0 );
                 delay( 1000 ); /* delay for 1 second */
                printf( "Delayed for 1 second\n" );
                 delays++;
                 return(1);
              }
            void main()
              {
                prev_int_1c = _dos_getvect( 0x1c );
                 _dos_setvect( 0x1c, timer_rtn );
                 while( compile_a_line() ) {
                     if( clock_ticks >= BLIP_COUNT ) {
                          putchar( '.' );
                          clock_ticks -= BLIP_COUNT;
                 _dos_setvect( 0x1c, prev_int_1c );
Classification: WATCOM
```

**Systems:** DOS, Windows, DOS/PM

		_dos_setvect

**Description:** The \_dos\_write function uses system call 0x40 to write *count* bytes of data from the buffer pointed to by *buffer* to the file specified by *handle*. The number of bytes successfully written will be stored in

the unsigned integer pointed to by bytes.

**Returns:** The \_dos\_write function returns zero if successful. Otherwise, it returns an OS error code and sets

errno accordingly.

See Also: \_dos\_close, \_dos\_open, \_dos\_read

Example: #include <stdio.h>
#include <dos.h>

void main()

#include <fcntl.h>
char buffer[] = "This is a test for \_dos\_write.";

**Classification:** DOS

}

```
Synopsis:
           #include <io.h>
           int dup( int handle );
           int _dup( int handle );
```

**Description:** 

The dup function duplicates the file handle given by the argument handle. The new file handle refers to the same open file handle as the original file handle, and shares any locks. The new file handle is identical to the original in that it references the same file or device, it has the same open mode (read and/or write) and it will have file position identical to the original. Changing the position with one handle will result in a changed position in the other.

The \_dup function is identical to dup. Use \_dup for ANSI naming conventions.

**Returns:** 

If successful, the new file handle is returned to be used with the other functions which operate on the file. Otherwise, -1 is returned and errno is set to indicate the error.

**Errors:** 

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

**Constant** Meaning

**EBADF** The argument *handle* is not a valid open file handle.

**EMFILE** The number of file handles would exceed {OPEN\_MAX}.

See Also:

\_chsize, close, creat, dup2, \_eof, exec..., fdopen, \_filelength, fileno, fstat, \_grow\_handles, isatty, lseek, open, read, \_setmode, \_sopen, stat, \_tell, write, umask

**Example:** 

```
#include <fcntl.h>
#include <io.h>
void main( void )
    int handle, dup_handle;
    handle = open( "file",
                O_WRONLY | O_CREAT | O_TRUNC | O_TEXT,
                S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
    if (handle !=-1) {
        dup_handle = dup( handle );
        if ( dup_handle != -1 ) {
            /* process file */
            close( dup_handle );
        close( handle );
    }
```

Classification: POSIX 1003.1

}

\_dup conforms to ANSI naming conventions

**Systems:** dup - All, Linux, RDOS, Netware \_dup - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

dup, _dup			

**Synopsis:** #include <io.h>

> int dup2 (int handle, int handle2); int \_dup2( int handle, int handle2 );

**Description:** 

The dup2 function duplicates the file handle given by the argument handle. The new file handle is identical to the original in that it references the same file or device, it has the same open mode (read and/or write) and it will have identical file position to the original (changing the position with one handle will result in a changed position in the other).

The number of the new handle is *handle2*. If a file already is opened with this handle, the file is closed before the duplication is attempted.

The \_dup2 function is identical to dup2. Use \_dup2 for ANSI naming conventions.

**Returns:** 

The dup2 function returns zero if successful. Otherwise, -1 is returned and errno is set to indicate the error.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning **EBADF** The argument *handle* is not a valid open file handle or *handle2* is out of range. **EMFILE** The number of file handles would exceed {OPEN\_MAX}, or no file handles above *handle2* are available.

See Also:

\_chsize, close, creat, dup, \_eof, exec..., fdopen, \_filelength, fileno, fstat, \_grow\_handles, isatty, lseek, open, read, \_setmode, \_sopen, stat, \_tell, write, umask

**Example:** 

```
#include <fcntl.h>
#include <io.h>
void main()
    int handle, dup_handle;
    handle = open( "file",
                O_WRONLY | O_CREAT | O_TRUNC | O_TEXT,
                S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
    if (handle !=-1) {
      dup handle = 4;
      if ( dup2 ( handle, dup_handle ) != -1 ) {
        /* process file */
        close( dup_handle );
      close ( handle );
  }
```

Classification: POSIX 1003.1

\_dup2 conforms to ANSI naming conventions

**Systems:** 

dup2 - All, Linux, RDOS, Netware
\_dup2 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

Synopsis: #include <wdefwin.h>
 int \_dwDeleteOnClose( int handle );

**Description:** The \_dwDeleteOnClose function tells the console window that it should close itself when the

corresponding file is closed. The argument *handle* is the handle associated with the opened console.

The \_dwDeleteOnClose function is one of the support functions that can be called from an application using Open Watcom's default windowing support.

**Returns:** The \_dwDeleteOnClose function returns 1 if it was successful and 0 if not.

See Also: \_\_dwSetAboutDlg, \_dwSetAppTitle, \_dwSetConTitle, \_dwShutDown, \_dwYield

Example: #include <wdefwin.h>
#include <stdio.h>

```
void main()
  {
    FILE *sec;
    _dwSetAboutDlg( "Hello World About Dialog",
                      "About Hello World\n"
                      "Copyright 1994 by WATCOM\n" );
    _dwSetAppTitle( "Hello World Application Title" );
    _dwSetConTitle( 0, "Hello World Console Title" );
    printf( "Hello World\n" );
    sec = fopen("CON", "r+");
    _dwSetConTitle( fileno( sec ),
                      "Hello World Second Console Title" );
    _dwDeleteOnClose( fileno( sec ) );
    fprintf( sec, "Hello to second console\n" ); fprintf( sec, "Press Enter to close this console\n" );
    fflush( sec );
    fgetc( sec );
    fclose( sec );
```

**Classification:** WATCOM

Systems: Windows, Win386, Win32, OS/2-32

Synopsis: #include <wdefwin.h>
 int \_dwSetAboutDlg( const char \*title, const char \*text );

**Description:** The \_dwSetAboutDlg function sets the "About" dialog box of the default windowing system. The

argument *title* points to the string that will replace the current title. If *title* is NULL then the title will not be replaced. The argument *text* points to a string which will be placed in the "About" box. To get multiple lines, embed a new line after each logical line in the string. If *text* is NULL, then the current

text in the "About" box will not be replaced.

The \_dwSetAboutDlg function is one of the support functions that can be called from an application using Open Watcom's default windowing support.

**Returns:** The \_dwSetAboutDlg function returns 1 if it was successful and 0 if not.

See Also: \_\_dwDeleteOnClose, \_dwSetAppTitle, \_dwSetConTitle, \_dwShutDown, \_dwYield

Example: #include <wdefwin.h>
#include <stdio.h>

```
void main()
  {
   FILE *sec;
    _dwSetAboutDlg( "Hello World About Dialog",
                    "About Hello World\n"
                    "Copyright 1994 by WATCOM\n" );
   _dwSetAppTitle( "Hello World Application Title" );
   _dwSetConTitle( 0, "Hello World Console Title" );
   printf( "Hello World\n" );
   sec = fopen("CON", "r+");
   _dwSetConTitle( fileno( sec ),
                    "Hello World Second Console Title" );
    _dwDeleteOnClose( fileno( sec ) );
    fprintf( sec, "Hello to second console\n");
    fprintf( sec, "Press Enter to close this console\n" );
    fflush ( sec );
    fgetc( sec );
    fclose( sec );
```

**Classification:** WATCOM

Systems: Windows, Win386, Win32, OS/2-32

**Synopsis:** #include <wdefwin.h> int \_dwSetAppTitle( const char \*title );

**Description:** The \_dwSetAppTitle function sets the main window's title. The argument *title* points to the string

that will replace the current title.

The \_dwSetAppTitle function is one of the support functions that can be called from an application using Open Watcom's default windowing support.

**Returns:** The \_dwSetAppTitle function returns 1 if it was successful and 0 if not.

See Also: \_dwDeleteOnClose, \_dwSetAboutDlg, \_dwSetConTitle, \_dwShutDown, \_dwYield

**Example:** #include <wdefwin.h> #include <stdio.h>

```
void main()
  {
    FILE *sec;
    _dwSetAboutDlg( "Hello World About Dialog",
                      "About Hello World\n"
                      "Copyright 1994 by WATCOM\n" );
    _dwSetAppTitle( "Hello World Application Title" );
    _dwSetConTitle( 0, "Hello World Console Title" );
    printf( "Hello World\n" );
    sec = fopen("CON", "r+");
    _dwSetConTitle( fileno( sec ),
                      "Hello World Second Console Title" );
    _dwDeleteOnClose( fileno( sec ) );
    fprintf( sec, "Hello to second console\n" ); fprintf( sec, "Press Enter to close this console\n" );
    fflush( sec );
    fgetc( sec );
    fclose( sec );
```

**Classification:** WATCOM

**Systems:** Windows, Win386, Win32, OS/2-32

Library Functions and Macros 237

Synopsis: #include <wdefwin.h>
 int \_dwSetConTitle( int handle, const char \*title );

**Description:** The \_dwSetConTitle function sets the console window's title which corresponds to the handle

passed to it. The argument *handle* is the handle associated with the opened console. The argument *title* 

points to the string that will replace the current title.

The \_dwSetConTitle function is one of the support functions that can be called from an application using Open Watcom's default windowing support.

**Returns:** The \_dwSetConTitle function returns 1 if it was successful and 0 if not.

See Also: \_\_dwDeleteOnClose, \_dwSetAboutDlg, \_dwSetAppTitle, \_dwShutDown, \_dwYield

Example: #include <wdefwin.h>

```
#include <stdio.h>
void main()
  {
   FILE *sec;
   _dwSetAboutDlg( "Hello World About Dialog",
                    "About Hello World\n"
                    "Copyright 1994 by WATCOM\n" );
    _dwSetAppTitle( "Hello World Application Title" );
   _dwSetConTitle( 0, "Hello World Console Title" );
   printf( "Hello World\n" );
   sec = fopen("CON", "r+");
   _dwSetConTitle( fileno( sec ),
                    "Hello World Second Console Title" );
   _dwDeleteOnClose( fileno( sec ) );
    fprintf( sec, "Hello to second console\n");
    fprintf( sec, "Press Enter to close this console\n" );
    fflush ( sec );
    fgetc( sec );
    fclose( sec );
```

**Classification: WATCOM** 

**Systems:** Windows, Win386, Win32, OS/2-32

```
Synopsis:
           #include <wdefwin.h>
           int _dwShutDown( void );
```

**Description:** The \_dwShutDown function shuts down the default windowing I/O system. The application will

continue to execute but no windows will be available for output. Care should be exercised when using

this function since any subsequent output may cause unpredictable results.

When the application terminates, it will not be necessary to manually close the main window.

The \_dwShutDown function is one of the support functions that can be called from an application using Open Watcom's default windowing support.

**Returns:** The \_dwShutDown function returns 1 if it was successful and 0 if not.

See Also: \_dwDeleteOnClose, \_dwSetAboutDlg, \_dwSetAppTitle, \_dwSetConTitle, \_dwYield

```
Example:
           #include <wdefwin.h>
           #include <stdio.h>
           void main()
```

{

```
FILE *sec;
_dwSetAboutDlg( "Hello World About Dialog",
                "About Hello World\n"
                "Copyright 1994 by WATCOM\n" );
_dwSetAppTitle( "Hello World Application Title" );
_dwSetConTitle( 0, "Hello World Console Title" );
printf( "Hello World\n" );
sec = fopen("CON", "r+");
_dwSetConTitle( fileno( sec ),
                "Hello World Second Console Title" );
_dwDeleteOnClose( fileno( sec ) );
fprintf( sec, "Hello to second console\n" );
fprintf( sec, "Press Enter to close this console\n" );
fflush( sec );
fgetc( sec );
fclose( sec );
_dwShutDown();
  do more computing that does not involve
  console input/output
```

**Classification:** WATCOM

**Systems:** Windows, Win386, Win32, OS/2-32

_dwShutDown			

**Synopsis:** #include <wdefwin.h> int \_dwYield( void );

**Description:** The \_dwYield function yields control back to the operating system, thereby giving other processes a

chance to run.

The \_dwYield function is one of the support functions that can be called from an application using Open Watcom's default windowing support.

**Returns:** The \_dwYield function returns 1 if it was successful and 0 if not.

See Also: \_dwDeleteOnClose, \_dwSetAboutDlg, \_dwSetAppTitle, \_dwSetConTitle, \_dwShutDown

**Example:** #include <wdefwin.h> #include <stdio.h>

```
void main()
  {
    int i;
    for(i = 0; i < 1000; i++) {
      /* give other processes a chance to run */
      _dwYield();
      /* do CPU-intensive calculation */
      /*
         . */
```

**Classification:** WATCOM

**Systems:** Windows, Win386, Win32, OS/2-32

### **Synopsis:**

## **Description:**

The ecvt function converts the floating-point number *value* into a character string. The parameter *ndigits* specifies the number of significant digits desired. The converted number will be rounded to *ndigits* of precision.

The character string will contain only digits and is terminated by a null character. The integer pointed to by *dec* will be filled in with a value indicating the position of the decimal point relative to the start of the string of digits. A zero or negative value indicates that the decimal point lies to the left of the first digit. The integer pointed to by *sign* will contain 0 if the number is positive, and non-zero if the number is negative.

The \_ecvt function is identical to ecvt. Use \_ecvt for ANSI naming conventions.

The \_wecvt function is a wide character version of ecvt except that it produces a wide character string.

## **Returns:**

The ecvt function returns a pointer to a static buffer containing the converted string of digits. Note: ecvt and fcvt both use the same static buffer.

See Also:

fcvt, gcvt, printf

#### **Example:**

```
#include <stdio.h>
#include <stdlib.h>

void main()
{
    char *str;
    int dec, sign;

    str = ecvt( 123.456789, 6, &dec, &sign );
    printf( "str=%s, dec=%d, sign=%d\n", str,dec,sign );
}
```

produces the following:

str=123457, dec=3, sign=0

#### **Classification:** WATCOM

\_ecvt conforms to ANSI naming conventions

Systems: ecvt - Math

\_ecvt - Math \_wecvt - Math

### Synopsis:

#### **Description:**

The \_ellipse functions draw ellipses. The \_ellipse function uses the view coordinate system. The \_ellipse\_w and \_ellipse\_wxy functions use the window coordinate system.

The center of the ellipse is the center of the rectangle established by the points (x1, y1) and (x2, y2).

The argument *fill* determines whether the ellipse is filled in or has only its outline drawn. The argument can have one of two values:

GFILLINTERIOR

fill the interior by writing pixels with the current plot action using the current color and the current fill mask

\_GBORDER

leave the interior unchanged; draw the outline of the figure with the current plot action using the current color and line style

When the coordinates (x1, y1) and (x2, y2) establish a line or a point (this happens when one or more of the x-coordinates or y-coordinates are equal), nothing is drawn.

**Returns:** 

The \_ellipse functions return a non-zero value when the ellipse was successfully drawn; otherwise, zero is returned.

See Also:

\_arc,\_rectangle,\_setcolor,\_setfillmask,\_setlinestyle,\_setplotaction

**Example:** 

```
#include <conio.h>
#include <graph.h>

main()
{
    _setvideomode( _VRES16COLOR );
    _ellipse( _GBORDER, 120, 90, 520, 390 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

**Systems:** 

\_ellipse - DOS \_ellipse\_w - DOS \_ellipse\_wxy - DOS

Synopsis: #include <i86.h>
 void \_enable( void );

**Description:** The \_enable function causes interrupts to become enabled.

The \_enable function would be used in conjunction with the \_disable function to make sure that a sequence of instructions are executed without any intervening interrupts occurring.

**Returns:** The \_enable function returns no value.

**See Also:** \_disable

Example: #include <stdio.h>

```
#include <stdlib.h>
#include <i86.h>
struct list_entry {
   struct list_entry *next;
   int
                      data;
};
struct list_entry *ListHead = NULL;
struct list_entry *ListTail = NULL;
void insert( struct list_entry *new_entry )
  {
    /* insert new_entry at end of linked list */
   new_entry->next = NULL;
                     /* disable interrupts */
    _disable();
   if( ListTail == NULL ) {
      ListHead = new_entry;
    } else {
      ListTail->next = new_entry;
   ListTail = new_entry;
   _enable(); /* enable interrupts now */
  }
void main()
  {
   struct list_entry *p;
   int i;
    for( i = 1; i <= 10; i++ ) {
      p = (struct list_entry *)
          malloc( sizeof( struct list_entry ) );
      if( p == NULL ) break;
     p->data = i;
      insert( p );
  }
```

Classification: Intel

**Systems:** All, Linux, RDOS, Netware

			_enable

# endhostent

Synopsis: #include <netdb.h>

void endhostent( void );

**Description:** The endhostent function closes the network host database at /etc/hosts. If the network host database

is not open, this call results in no actions.

See Also: gethostent, sethostent

Classification: POSIX 1003.1

Systems: Linux

**Synopsis:** #include <netdb.h>

void endnetent( void );

**Description:** The endnetent function closes the network database.

This function is not thread-safe. Other calls to this function or to other functions accessing the

hostname database may affect the return value from this function.

See Also: getnetent, setnetent, getnetbyname, getnetbyaddr

Classification: POSIX 1003.1

**Systems:** Linux

# endprotoent

Synopsis: #include <netdb.h>

void endprotoent( void );

**Description:** The endprotoent function explicitly closes the protocol database.

This function is not thread-safe. Other calls to this function or to other functions accessing the protocol

database may affect the return value from this function.

See Also: getprotoent, setprotoent, getprotobyname, getprotobynumber

Classification: POSIX 1003.1

**Systems:** Linux

**Synopsis:** #include <pwd.h> void endpwent( void );

**Description:** The endpwent function closes the system's password database after calls to getpwent are complete.

See Also: setpwent, getpwent, getpwnam, getpwuid

**Example:** The following program will print out each user and their user ID in the system's password database

```
#include <stdio.h>
#include <pwd.h>
void main()
    struct passwd *pw;
    setpwent();
    while((pw = getpwent()) != NULL) {
        printf("User id %d is %s\n", (int)pw->pw_uid, pw->pw_name);
    endpwent();
  }
```

Classification: POSIX 1003.1

**Systems:** Linux

# endservent

Synopsis: #include <netdb.h>

void endservent( void );

**Description:** The endservent function closes the service database.

This function is not thread-safe. Other calls to this function or to other functions accessing the

hostname database may affect the return value from this function.

See Also: getservent, setservent, getservbyname, getservbyport

Classification: POSIX 1003.1

**Systems:** Linux

```
Synopsis:
           #include <process.h>
           void _endthread(void);
           void _endthreadex( unsigned retval );
```

**Description:** The \_endthread function is used to terminate a thread created by \_beginthread. For each operating environment under which \_endthread is supported, the \_endthread function uses the

appropriate system call to end the current thread of execution.

The \_endthreadex function is used to terminate a thread created by \_beginthreadex. The thread exit code *retval* must be specified.

**Returns:** The \_endthread function does not return any value.

See Also: \_beginthread

### **Example:**

```
#include <stdio.h>
#include <stdlib.h>
#include <stddef.h>
#include <malloc.h>
#include cess.h>
#include <dos.h>
#if defined(__386__)
  #define FAR
  #define STACK_SIZE
                        8192
  #define FAR
                          _far
  #define STACK_SIZE
                        4096
#endif
static volatile int
                        WaitForThread;
void FAR child( void FAR *parm )
    char * FAR *argv = (char * FAR *) parm;
    int i;
    printf( "Child thread ID = %x\n", *_threadid );
    for( i = 0; argv[i]; i++) {
      printf( "argv[%d] = %s\n", i, argv[i] );
    WaitForThread = 0;
    _endthread();
  }
```

```
void main()
 {
    char
                   *args[3];
#if defined(__NT___)
    unsigned long tid;
#else
    char
                   *stack;
    int
                   tid;
#endif
    args[0] = "child";
    args[1] = "parm";
    args[2] = NULL;
    WaitForThread = 1;
#if defined(__NT___)
    tid = _beginthread( child, STACK_SIZE, args );
    printf( "Thread handle = lx \n", tid );
#else
  #if defined(__386__)
    stack = (char *) malloc( STACK_SIZE );
    stack = (char *) _nmalloc( STACK_SIZE );
  #endif
    tid = _beginthread( child, stack, STACK_SIZE, args );
    printf( "Thread ID = %x\n", tid );
#endif
    while( WaitForThread ) {
        sleep(0);
  }
```

## **Classification:** WATCOM

```
Systems: __endthread - Win32, OS/2 1.x(MT), OS/2 1.x(DL), OS/2-32, Linux, RDOS, Netware __endthreadex - Win32
```

**Synopsis:** #include <io.h> int \_eof( int handle ); \*\* deprecated \*\* int eof( int handle );

**Description:** 

The \_eof function determines, at the operating system level, if the end of the file has been reached for the file whose file handle is given by handle. Because the current file position is set following an input operation, the \_eof function may be called to detect the end of the file before an input operation beyond the end of the file is attempted.

The eof function is deprecated, use \_eof instead.

**Returns:** 

The \_eof function returns 1 if the current file position is at the end of the file, 0 if the current file position is not at the end. A return value of -1 indicates an error, and in this case errno is set to indicate the error.

**Errors:** 

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

**EBADF** The *handle* argument is not a valid file handle.

See Also: read

**Example:** 

```
#include <stdio.h>
#include <fcntl.h>
#include <io.h>
void main ( void )
    int handle, len;
    char buffer[100];
    handle = open( "file", O_RDONLY );
    if (handle !=-1) {
        while( ! _eof( handle ) ) {
            len = read( handle, buffer, sizeof(buffer) - 1 );
            buffer[ len ] = ' \setminus 0';
            printf( "%s", buffer );
        close( handle );
    }
}
```

**Classification:** WATCOM

**Systems:** 

```
_eof - All, Linux, RDOS, Netware
eof - All, Linux, RDOS, Netware
```

_eof, eof			

**Synopsis:** #include <math.h>

double erf ( double x );

**Description:** The erf function computes the value of the error function, also known as the Gauss error function, for

the argument x.

**Returns:** For non-infinite values of x the function returns the value of the error function. For positive infinity or

negative infinity the function returns positive or negative one respectively. For not-a-number the

function returns NAN.

See Also: erfc

**Example:** #include <stdio.h>

#include <math.h>

```
void main()
    printf( "%f\n", erf( 0.0 ) );
```

produces the following:

0.000000

Classification: ISO C99

**Systems:** Math Synopsis: #include <math.h>

double erfc( double x );

Description: The erfc function computes the value of the complementary error function, also known as the Gauss

error function, for the argument x.

**Returns:** For non-infinite values of x the function returns the value of the error function. For positive infinity or

negative infinity the function returns negative or positive one respectively. For not-a-number the

function returns NAN.

See Also: erf

Example: #include <stdio.h>

#include <math.h>

void main()
{

printf( "%f\n", erfc( 0.0 ) );

produces the following:

0.000000

**Classification:** WATCOM

**Systems:** Math

**Synopsis:** 

```
#include cess.h>
int execl( path, arg0, arg1..., argn, NULL);
int execle( path, arg0, arg1..., argn, NULL, envp );
int execlp( file, arg0, arg1..., argn, NULL);
int execlpe( file, arg0, arg1..., argn, NULL, envp );
int execv( path, argv);
int execve( path, argv, envp);
int execvp( file, argv);
int execvpe( file, argv, envp );
int _execl( path, arg0, arg1..., argn, NULL);
int _execle( path, arg0, arg1..., argn, NULL, envp);
int _execlp( file, arg0, arg1..., argn, NULL );
int _execlpe( file, arg0, arg1..., argn, NULL, envp );
int _execv( path, argv);
int _execve( path, argv, envp);
int _execvp( file, argv );
int _execvpe( file, argv, envp );
 const char *path;
                              /* file name incl. path */
 const char *file;
                              /* file name
 const char *arg0, ..., *argn; /* arguments
 int _wexecl( path, arg0, arg1..., argn, NULL);
int _wexecle( path, arg0, arg1..., argn, NULL, envp);
int _wexeclp( file, arg0, arg1..., argn, NULL);
int _wexeclpe( file, arg0, arg1..., argn, NULL, envp );
int _wexecv( path, argv);
int _wexecve( path, argv, envp );
int _wexecvp( file, argv );
int _wexecvpe( file, argv, envp );
                                 /* file name incl. path */
 const wchar t *path;
                                /* file name
 const wchar_t *file;
 const wchar_t *arg0, ..., *argn;/* arguments
                                                         */
 const wchar_t *const argv[];  /* array of arguments
                                                         */
                                /* environment strings */
 const wchar_t *const envp[];
```

**Description:** 

The **exec...** functions load and execute a new child process, named by *path* or *file*. If the child process is successfully loaded, it replaces the current process in memory. No return is made to the original program.

The program is located by using the following logic in sequence:

- An attempt is made to locate the program in the current working directory if no directory specification precedes the program name; otherwise, an attempt is made in the specified directory.
- If no file extension is given, an attempt is made to find the program name, in the directory indicated in the first point, with . COM concatenated to the end of the program name.
- If no file extension is given, an attempt is made to find the program name, in the directory indicated in the first point, with .EXE concatenated to the end of the program name.
- When no directory specification is given as part of the program name, the execlp, execlpe, execvp, and execvpe functions will repeat the preceding three steps for each of the directories specified by the PATH environment variable. The command

```
path c:\myapps;d:\lib\applns
```

indicates that the two directories

```
c:\myapps
d:\lib\applns
```

are to be searched. The DOS PATH command (without any directory specification) will cause the current path definition to be displayed.

An error is detected when the program cannot be found.

Arguments are passed to the child process by supplying one or more pointers to character strings as arguments in the **exec...** call. These character strings are concatenated with spaces inserted to separate the arguments to form one argument string for the child process. The length of this concatenated string must not exceed 128 bytes for DOS systems.

The arguments may be passed as a list of arguments (execl, execle, execlp, and execlpe) or as a vector of pointers (execv, execve, execvp, and execvpe). At least one argument,  $arg\theta$  or argv[0], must be passed to the child process. By convention, this first argument is a pointer to the name of the program.

If the arguments are passed as a list, there must be a NULL pointer to mark the end of the argument list. Similarly, if a pointer to an argument vector is passed, the argument vector must be terminated by a NULL pointer.

The environment for the invoked program is inherited from the parent process when you use the execl, execlp, execv, and execvp functions. The execle, execlpe, execve, and execvpe functions allow a different environment to be passed to the child process through the *envp* argument. The argument *envp* is a pointer to an array of character pointers, each of which points to a string defining an environment variable. The array is terminated with a NULL pointer. Each pointer locates a character string of the form

```
variable=value
```

that is used to define an environment variable. If the value of *envp* is NULL, then the child process inherits the environment of the parent process.

The environment is the collection of environment variables whose values have been defined with the DOS SET command or by the successful execution of the putenv function. A program may read these values with the getenv function.

The execupe and execlpe functions are extensions to POSIX 1003.1.

The \_wexec... functions are similar to their counterparts but operate on wide character strings.

**Returns:** When the invoked program is successfully initiated, no return occurs. When an error is detected while invoking the indicated program, exec... returns -1 and error is set to indicate the error.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

	Constant	Meaning			
	E2BIG	The argument list exceeds 128 bytes, or the space required for the environment information exceeds 32K.			
	EACCES	The specified file has a locking or sharing violation.			
	<b>EMFILE</b>	Too many files open			
	ENOENT	Path or file not found			
	ENOMEM	Not enough memory is available to execute the child process.			
See Also:	abort, atexit, e	exit, _Exit, _exit, getcmd, getenv, main, putenv, spawn, system			
Example:	#include <stdo< th=""><th></th></stdo<>				
	execl( "myprog" myprog	g", og", "ARG1", "ARG2", NULL );			
	The preceding invok	tes "myprog" as if			
	myprog AR(	G1 ARG2			
	had been entered as a command to DOS. The program will be found if one of				
	myprog. myprog.com myprog.exe				
	is found in the curre	nt working directory.			
	#include <stdo< th=""><th></th></stdo<>				
	char *env_list	<pre>[] = { "SOURCE=MYDATA",     "TARGET=OUTPUT",     "lines=65",     NULL     };</pre>			
		og", og", "ARG1", "ARG2", NULL, list );			
	The preceding invok	tes "myprog" as if			
	myprog AR	G1 ARG2			
	had been entered as	a command to DOS. The program will be found if one of			
	myprog. myprog.com myprog.exe				

is found in the current working directory. The DOS environment for the invoked program will consist of the three environment variables SOURCE, TARGET and lines.

```
#include <stddef.h>
#include <process.h>
char *arg_list[] = { "myprog", "ARG1", "ARG2", NULL };
execv( "myprog", arg_list );
The preceding invokes "myprog" as if
    myprog ARG1 ARG2
```

had been entered as a command to DOS. The program will be found if one of

```
myprog.
myprog.com
myprog.exe
```

is found in the current working directory.

**Classification:** POSIX 1003.1 with extensions

### **Systems:**

```
execl - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execle - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execlp - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execlpe - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execv - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execve - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execvp - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
execvpe - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execl - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execle - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execlp - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execlpe - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execv - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execve - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execvp - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_execvpe - DOS/16, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_{\text{wexecl}} - DOS/16, Win32, OS/2 1.x(all), OS/2-32
_{\text{wexecle}} - DOS/16, Win32, OS/2 1.x(all), OS/2-32
_{\text{wexeclp}} - \text{DOS}/16, Win32, OS/2 1.x(all), OS/2-32
_wexeclpe - DOS/16, Win32, OS/2 1.x(all), OS/2-32
_{\text{wexecv}} - \text{DOS}/16, Win32, OS/2 1.x(all), OS/2-32
_wexecve - DOS/16, Win32, OS/2 1.x(all), OS/2-32
_wexecvp - DOS/16, Win32, OS/2 1.x(all), OS/2-32
_wexecvpe - DOS/16, Win32, OS/2 1.x(all), OS/2-32
```

	exec Functions

```
Synopsis: #include <stdlib.h>
    void _Exit( int status );
    void _exit( int status );
```

**Description:** The \_Exit function causes normal program termination to occur.

- 1. The functions registered by the atexit or \_onexit functions are not called.
- 2. Any unopened files are not closed and any buffered output is not flushed to the associated files or devices.
- 3. Any files created by tmpfile are not removed.
- 4. The return *status* is made available to the parent process. Only the low order byte of *status* is available on DOS systems. The *status* value is typically set to 0 to indicate successful termination and set to some other value to indicate an error.

The \_exit is functionaly equivalent to \_Exit.

**Returns:** The \_Exit function does not return to its caller.

See Also: abort, atexit, \_bgetcmd, exec..., exit, \_exit, getcmd, getenv, main, putenv, spawn..., system, \_wsystem

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>

void main( int argc, char *argv[] )
{
    FILE *fp;

    if( argc <= 1 ) {
        fprintf( stderr, "Missing argument\n" );
        exit( EXIT_FAILURE );
    }

    fp = fopen( argv[1], "r" );
    if( fp == NULL ) {
        fprintf( stderr, "Unable to open '%s'\n", argv[1] );
        _Exit( EXIT_FAILURE );
    }
    fclose( fp );
    _Exit( EXIT_SUCCESS );
}</pre>
```

Classification: ISO C99

\_exit is POSIX 1003.1

Systems: \_Exit - All, Linux, RDOS, Netware \_exit - All, Linux, RDOS, Netware

		_Exit, _exit

Synopsis: #include <stdlib.h>
 void exit( int status );

**Description:** The exit function causes normal program termination to occur.

First, all functions registered by the atexit function are called in the reverse order of their registration. Next, all open files are flushed and closed, and all files created by the tmpfile function are removed. Finally, the return *status* is made available to the parent process. Only the low order byte of *status* is available on DOS systems. The *status* value is typically set to 0 to indicate successful termination and set to some other value to indicate an error.

**Returns:** The exit function does not return to its caller.

See Also: abort, atexit, \_Exit, \_exit

Example: #include <stdio.h>
#include <stdlib.h>

void main( int argc, char \*argv[] )
{
 FILE \*fp;

 if( argc <= 1 ) {
 fprintf( stderr, "Missing argument\n" );
 exit( EXIT\_FAILURE );
}

 fp = fopen( argv[1], "r" );
 if( fp == NULL ) {
 fprintf( stderr, "Unable to open '%s'\n", argv[1] );
 exit( EXIT\_FAILURE );
 }
 fclose( fp );
 exit( EXIT\_SUCCESS );
}</pre>

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <math.h>

double exp(double x);

**Description:** The exp function computes the exponential function of x. A range error occurs if the magnitude of x is

too large.

**Returns:** The exp function returns the exponential value. When the argument is outside the permissible range,

> the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to ERANGE, and print a "RANGE error" diagnostic message using the stderr

stream.

See Also: log, matherr

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
   printf( \$f\n, exp(.5));
```

produces the following:

1.648721

**Classification:** ISO C

Math **Systems:** 

```
Synopsis: #include <math.h>
double exp2( double x );
```

**Description:** The exp2 function computes 2.0 raised to the value x. calculation.

**Returns:** The function returns two to the power x.

See Also: exp, pow

Example: #include <stdio.h>
 #include <math.h>

 void main()
 {
 printf( "%f\n", exp2( 2.0 ) );
 }

produces the following:

4.000000

Classification: ISO C99

Systems: Math

**Synopsis:** #include <math.h> double expm1( double x);

**Description:** The expm1 function computes the value of the exponential of x minus 1. This routine provides far

better accuracy for cases where the exponential of the argument x is significantly less than 1.0.

**Returns:** The function returns a the exponential of x minus 1 without loss of accuracy due to subtractive

cancelation.

See Also: exp

**Example:** #include <stdio.h> #include <math.h>

> void main() { printf( "%f\n", expm1( -1.0E-3 ) );

produces the following:

-0.000995

Classification: ISO C99

**Systems:** Math

## **Synopsis:**

```
#include <malloc.h>
void *_expand( void *mem_blk, size_t size );
void __based(void) *_bexpand( __segment seg,
                             void __based(void) *mem_blk,
                             size_t size );
void __far *_fexpand(void __far *mem_blk,size_t size);
void __near *_nexpand(void __near *mem_blk,size_t size);
```

### **Description:**

The \_expand functions change the size of the previously allocated block pointed to by mem blk by attempting to expand or contract the memory block without moving its location in the heap. The argument size specifies the new desired size for the memory block. The contents of the memory block are unchanged up to the shorter of the new and old sizes.

Each function expands the memory from a particular heap, as listed below:

Function Heap Expanded Depends on data model of the program expand \_bexpand Based heap specified by seg value \_fexpand Far heap (outside the default data segment) \_nexpand Near heap (inside the default data segment)

In a small data memory model, the \_expand function is equivalent to the \_nexpand function; in a large data memory model, the \_expand function is equivalent to the \_fexpand function.

## **Returns:**

The \_expand functions return the value mem\_blk if it was successful in changing the size of the block. The return value is NULL (\_NULLOFF for \_bexpand) if the memory block could not be expanded to the desired size. It will be expanded as much as possible in this case.

The appropriate \_msize function can be used to determine the new size of the expanded block.

#### See Also:

calloc Functions, free Functions, halloc, hfree, malloc Functions, \_msize Functions, realloc Functions, sbrk

# **Example:**

```
#include <stdio.h>
#include <malloc.h>
void main()
  {
    char *buf;
    char __far *buf2;
```

```
buf = (char *) malloc(80);
               printf( "Size of buffer is %u\n", _msize(buf) );
               if( _expand( buf, 100 ) == NULL ) {
                   printf( "Unable to expand buffer\n" );
               printf( "New size of buffer is %u\n", _msize(buf) );
               buf2 = (char _far *) _fmalloc(2000);
               printf( "Size of far buffer is %u\n", _fmsize(buf2) );
               if( _{\text{fexpand}}( buf2, 8000 ) == NULL ) {
                   printf( "Unable to expand far buffer\n" );
               printf( "New size of far buffer is %u\n",
                        _fmsize(buf2) );
             }
           produces the following:
           Size of buffer is 80
           Unable to expand buffer
           New size of buffer is 80
           Size of far buffer is 2000
           New size of far buffer is 8000
Classification: WATCOM
Systems:
          _expand - All, Linux, RDOS
          _bexpand - DOS/16, Windows, OS/2 1.x(all)
          _fexpand - DOS/16, Windows, OS/2 1.x(all)
           _nexpand - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
           OS/2-32, Linux, RDOS
```

**Systems:** 

Math

```
Synopsis:
             #include <math.h>
             double fabs ( double x );
Description:
             The fabs function computes the absolute value of the argument x.
Returns:
             The fabs function returns the absolute value of x.
See Also:
             abs, labs, imaxabs
Example:
             #include <stdio.h>
             #include <math.h>
             void main()
                  printf( "%f %f\n", fabs(.5), fabs(-.5) );
             produces the following:
             0.500000 0.500000
Classification: ISO C
```

**Synopsis:** #include <stdio.h> int fclose(FILE \*fp);

**Description:** The fclose function closes the file fp. If there was any unwritten buffered data for the file, it is

written out before the file is closed. Any unread buffered data is discarded. If the associated buffer was

automatically allocated, it is deallocated.

**Returns:** The fclose function returns zero if the file was successfully closed, or non-zero if any errors were

detected. When an error has occurred, errno contains a value indicating the type of error that has

been detected.

See Also: fcloseall, fdopen, fopen, freopen, \_fsopen

**Example:** #include <stdio.h>

```
void main()
   FILE *fp;
    fp = fopen("stdio.h", "r");
    if( fp != NULL ) {
        fclose( fp );
```

Classification: ISO C

Synopsis: #include <stdio.h>
 int fcloseall( void );

**Description:** The fcloseall function closes all open stream files, except stdin, stdout, stderr, stdaux,

and  ${\tt stdprn}$ . This includes streams created (and not yet closed) by  ${\tt fdopen}$ ,  ${\tt fopen}$  and  ${\tt freopen}$ .

The stdaux and stdprn files are not available for some Windows platforms.

**Returns:** The fcloseall function returns the number of streams that were closed if no errors were

encountered. When an error occurs, EOF is returned.

See Also: fclose, fdopen, fopen, freopen, \_fsopen

Example: #include <stdio.h>

**Classification:** WATCOM

**Synopsis:** 

```
#include <stdlib.h>
char *fcvt( double value,
            int ndigits,
            int *dec,
            int *sign );
char *_fcvt( double value,
             int ndigits,
             int *dec,
             int *sign );
wchar_t *_wfcvt( double value,
                  int ndigits,
                  int *dec.
                  int *sign );
```

# **Description:**

The fort function converts the floating-point number value into a character string. The parameter ndigits specifies the number of digits desired after the decimal point. The converted number will be rounded to this position.

The character string will contain only digits and is terminated by a null character. The integer pointed to by dec will be filled in with a value indicating the position of the decimal point relative to the start of the string of digits. A zero or negative value indicates that the decimal point lies to the left of the first digit. The integer pointed to by sign will contain 0 if the number is positive, and non-zero if the number is negative.

The \_fcvt function is identical to fcvt. Use \_fcvt for ANSI naming conventions.

The \_wfcvt function is a wide character version of fcvt except that it produces a wide character string.

**Returns:** 

The fevt function returns a pointer to a static buffer containing the converted string of digits. Note: ecvt and fcvt both use the same static buffer.

See Also:

ecvt, gcvt, printf

#include <stdio.h>

**Example:** 

```
#include <stdlib.h>
void main()
  {
     char *str;
    int dec, sign;
     str = fcvt(-123.456789, 5, &dec, &sign);
    printf( "str=%s, dec=%d, sign=%d\n", str,dec,sign );
  }
```

produces the following:

```
str=12345679, dec=3, sign=-1
```

**Classification:** WATCOM

\_fcvt conforms to ANSI naming conventions

**Systems:** fcvt - Math \_fcvt - Math \_wfcvt - Math

```
Synopsis:
           #include <math.h>
           double fdim( double x, double y);
```

**Description:** The fdim function computes the positive difference of x and y.

```
fmax(x - y, 0.0);
```

**Returns:** The routine will either return x - y or 0.0, whichever is greater.

See Also: fmax, fmin

**Example:** #include <stdio.h> #include <math.h> void main() { printf( "% $f\n$ ", fdim( 3.0, 2.0 ) );

produces the following:

1.000000

Classification: ISO C99

**Systems:** Math

```
Synopsis: #include <stdio.h>
    FILE *fdopen( int handle, const char *mode );
    FILE *_fdopen( int handle, const char *mode );
    FILE *_wfdopen( int handle, const wchar_t *mode );
```

**Description:** 

The fdopen function associates a stream with the file handle handle which represents an opened file or device. The handle was returned by one of creat, dup, dup2, open, or \_sopen. The open mode mode must match the mode with which the file or device was originally opened.

The argument *mode* is described in the description of the fopen function.

The \_fdopen function is identical to fdopen. Use \_fdopen for ANSI naming conventions.

The \_wfdopen function is identical to fdopen except that it accepts a wide character string for the second argument.

**Returns:** 

The fdopen function returns a pointer to the object controlling the stream. This pointer must be passed as a parameter to subsequent functions for performing operations on the file. If the open operation fails, fdopen returns a NULL pointer. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: creat, \_dos\_open, dup, dup2, fopen, freopen, \_fsopen, \_grow\_handles, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen

**Example:** 

```
#include <stdio.h>
#include <fcntl.h>
#include <io.h>
void main()
  {
    int handle;
    FILE *fp;
    handle = open( "file", O_RDONLY | O_TEXT );
    if (handle !=-1) {
      fp = fdopen( handle, "r" );
      if( fp != NULL ) {
        /*
            process the stream
        */
        fclose(fp);
      } else {
        close( handle );
  }
```

Classification: POSIX 1003.1

\_fdopen conforms to ANSI naming conventions

Systems: fdopen - All, Linux, RDOS, Netware
\_fdopen - All, Linux, RDOS, Netware
\_wfdopen - All, Linux

	fdopen,	_fdopen, _wfdopen

Synopsis: #include <fenv.h>

int feclearexcept( int excepts );

**Description:** The feclear except function attempts to clear the floating-point exceptions specified by the *excepts* 

argument.

For valid exception values see fegetexceptflag.

**Returns:** The feclear except function returns zero if the *excepts* argument is zero or if all the specified

exceptions were successfully cleared. Otherwise, it returns a nonzero value.

See Also: fegetexceptflag, feraiseexcept, fesetexceptflag, fetestexcept

Example: #include <fenv.h>

```
void main( void )
{
    feclearexcept( FE_OVERFLOW|FE_UNDERFLOW );
}
```

Classification: ISO C99

```
Synopsis:
             #include <fenv.h>
             void fedisableexcept( int excepts );
             void __fedisableexcept( int excepts );
            The fedisable except function disables the floating point exceptions specified by the excepts
Description:
             argument.
             For valid exception values see fegetexceptflag.
Returns:
             No value is returned.
See Also:
             feenableexcept
Example:
             #include <fenv.h>
             void main( void )
```

**Classification:** WATCOM

**Systems:** fedisableexcept - All, Linux, RDOS, Netware \_\_fedisableexcept - All, Linux, RDOS, Netware

fedisableexcept( FE\_DIVBYZERO );

Library Functions and Macros 281

```
Synopsis:
            #include <fenv.h>
            void feenableexcept( int excepts );
            void __feenableexcept( int excepts );
Description:
            The feenableexcept function enables the floating point exceptions specified by the excepts
            argument.
            For valid exception values see fegetexceptflag.
            No value is returned.
Returns:
See Also:
            fedisableexcept
Example:
            #include <fenv.h>
            void main( void )
                 feenableexcept(FE_DIVBYZERO);
Classification: WATCOM
Systems:
            feenableexcept - All, Linux, RDOS, Netware
            __feenableexcept - All, Linux, RDOS, Netware
```

**Synopsis:** #include <fenv.h> int fegetenv( fenv\_t \*envp );

**Description:** The fegetenv function attempts to store the current floating-point environment in the object pointed

to by envp argument.

**Returns:** The fegetenv function returns zero if the environment was successfully stored. Otherwise, it returns

a nonzero value.

See Also: feholdexcept, fesetenv, feupdateenv

**Example:** #include <stdio.h>

#include <fenv.h> void main( void ) fenv\_t env; fegetenv( &env );

Classification: ISO C99

Synopsis: #include <fenv.h>
 int fegetexceptflag( fexcept\_t \*flagp, int excepts );

**Description:** The fegetexceptflag function attempts to store a representation of the floating-point exceptions

specified by the *excepts* argument into the fexcept\_t object pointed by the *flagp* argument.

Valid exception bit values are

**FE\_INVALID** At least one of the arguments is a value for which the function is not defined.

**FE\_DENORMAL** The result is not normalized.

**FE\_DIVBYZERO** Division by zero.

**FE\_OVERFLOW** The result is too large in magnitude to be represented as the return type.

**FE\_UNDERFLOW** The result is too small in magnitude to be represented as the return type.

**FE\_INEXACT** The result is not exact.

**FE\_ALL\_EXCEPT** Is the logical OR of all exceptions.

**Returns:** The fegetexceptflag function returns zero if the representation was successfully stored.

Otherwise, it returns a nonzero value.

See Also: feclear except, feraise except, feset except flag, fet est except

Example: #include <fenv.h>

```
void main( void )
{
    fexcept_t flags;
    fegetexceptflag( &flags, FE_DIVBYZERO );
}
```

Classification: ISO C99

**Synopsis:** #include <fenv.h> int fegetround( void );

**Description:** The fegetround function returns a value that indicates the rounding direction mode, as specified in

the current floating point environment.

**Returns:** The feget round function returns the value of the rounding direction macro representing the current

rounding direction or a negative value if there is no such rounding direction macro or the current

rounding direction is not determinable.

For valid rounding modes see fesetround.

See Also: fesetround

**Example:** #include <stdio.h> #include <fenv.h>

```
void main( void )
    int mode;
   mode = fegetround();
    if ( mode == FE_TONEAREST )
        printf( "Nearest\n" );
    else if ( mode == FE_DOWNWARD )
        printf( "Down\n" );
    else if ( mode == FE_TOWARDZERO )
        printf( "To Zero\n" );
    else if ( mode == FE_UPWARD )
        printf( "Up\n" );
```

Classification: ISO C99

All, Linux, RDOS, Netware **Systems:** 

Synopsis: #include <fenv.h>
 int feholdexcept( fenv\_t \*envp );

**Description:** The feholdexcept function saves the current floating-point environment in the object pointed to by

envp argument, clears the floating-point status flags, and then installs a non-stop (continue on

floating-point exceptions) mode, if available, for all floating-point exceptions.

Returns: The feholdexcept function returns zero if and only if non-stop floating-point exception handling

was successfully installed.

See Also: fegetenv, fesetenv, feupdateenv

Example: #include <fenv.h>

void main( void )
{
 fenv\_t env;
 feholdexcept( &env );

Classification: ISO C99

**Synopsis:** #include <stdio.h> int feof(FILE \*fp);

**Description:** 

The feof function tests the end-of-file indicator for the stream pointed to by fp. Because this indicator is set when an input operation attempts to read past the end of the file the feof function will detect the end of the file only after an attempt is made to read beyond the end of the file. Thus, if a file contains 10 lines, the feof will not detect end of file after the tenth line is read; it will detect end of file once the program attempts to read more data.

**Returns:** The feof function returns non-zero if the end-of-file indicator is set for *fp*.

See Also: clearerr, ferror, fopen, freopen, perror, read, strerror

**Example:** #include <stdio.h>

```
void process_record( char *buf )
    printf( "%s\n", buf );
void main()
  {
    FILE *fp;
    char buffer[100];
    fp = fopen( "file", "r" );
    fgets( buffer, sizeof( buffer ), fp );
    while( ! feof( fp ) ) {
      process_record( buffer );
      fgets( buffer, sizeof( buffer ), fp );
    fclose( fp );
```

Classification: ISO C

All, Linux, RDOS, Netware **Systems:** 

Synopsis: #include <fenv.h>

int feraiseexcept( int excepts );

**Description:** The feraiseexcept function attempts to raise the floating-point exceptions specified by the *excepts* 

argument.

For valid exception values see fegetexceptflag.

**Returns:** The feraiseexcept function returns zero if the *excepts* argument is zero or if all the specified

exceptions were successfully raised. Otherwise, it returns a nonzero value.

See Also: feclearexcept, fegetexceptflag, fetestexcept

Example: #include <fenv.h>

```
void main( void )
{
    feraiseexcept( FE_DIVBYZERO );
}
```

Classification: ISO C99

```
Synopsis:
           #include <stdio.h>
           int ferror( FILE *fp );
```

**Description:** The ferror function tests the error indicator for the stream pointed to by *fp*.

**Returns:** The ferror function returns non-zero if the error indicator is set for fp.

See Also: clearerr, feof, perror, strerror

```
Example:
           #include <stdio.h>
           void main()
               FILE *fp;
               int c;
               fp = fopen( "file", "r" );
               if( fp != NULL ) {
                 c = fgetc(fp);
                 if( ferror( fp ) ) {
                   printf( "Error reading file\n" );
               fclose( fp );
```

Classification: ISO C

All, Linux, RDOS, Netware **Systems:** 

Synopsis: #include <fenv.h>

int fesetenv( const fenv\_t \*envp );

**Description:** The feseteny function attempts to establish the floating-point environment to environment

represented by the object pointed by *envp* argument. The *envp* argument shall point to an object set by a call to fegetenv or feholdexcept, or equal the FE\_DFL\_ENV macro. Note that fesetenv merely installs the state of the floating-point status flags represented through its argument, and does not

raise these floating-point exceptions.

Returns: The fesetenv function returns zero if the environment was successfully established. Otherwise, it

returns a nonzero value.

See Also: fegetenv, feholdexcept, feupdateenv

Example: #include <fenv.h>

```
void main( void )
{
    fenv_t env;
    fegetenv( &env );
    fesetenv( FE_DFL_ENV );
    fesetenv( &env );
}
```

Classification: ISO C99

**Synopsis:** #include <fenv.h>

int fesetexceptflag( const fexcept\_t \*flagp, int excepts );

**Description:** 

The fesetexceptflag function attempts to set the exceptions indicated by excepts argument with the states stored in the object pointed by flagp argument. The value pointed by the flagp argument shall have been set by a previous call to fegetexceptflag whose second argument represented at least those floating-point exceptions represented by the excepts argument. This function does not raise floating-point exceptions, but only sets the state of the flags.

For valid exception values see fegetexceptflag.

**Returns:** 

The fesetexceptflag function returns zero if the excepts argument is zero or if all the specified flags were successfully set to the appropriate state. Otherwise, it returns a nonzero value.

See Also:

feclearexcept, fegetexceptflag, feraiseexcept, fetestexcept

**Example:** 

```
#include <fenv.h>
void main( void )
    fexcept_t flags;
    fgetexceptflag( &flags, FE_DENORMAL | FE_INVALID );
    fsetexceptflag( &flags, FE_INVALID );
```

Classification: ISO C99

Synopsis: #include <fenv.h>

int fesetround (int mode);

**Description:** The feset round function sets the rounding direction mode, specified by *mode*, for the current

floating point environment.

The rounding direction mode can be one of the following values:

FE\_TONEAREST Round to nearest integer, halfway rounding away from zero

**FE\_DOWNWARD** Round downward to the next lowest integer

**FE\_TOWARDZERO** Round to the nearest integer in the direction of zero

FE\_UPWARD Round upward to the next highest integer

**Returns:** The feset round function returns a zero value if and only if the requested rounding direction was

established.

See Also: fegetround, nearbyint, rint

Example: #include <stdio.h>
#include <math.h>

```
void main()
{
   fesetround(FE_DOWNWARD)
   printf( "%f\n", rint( 1.5 ) );
   fesetround(FE_UPWARD)
   printf( "%f\n", rint( 1.5 ) );
}
```

produces the following:

1.00000 2.00000

Classification: ISO C99

**Synopsis:** #include <fenv.h> int fetestexcept( int excepts );

**Description:** The fetestexcept function tests which of the specified floating-point exceptions flags are currently

set. The *excepts* argument specifies the floating-point exceptions to be queried.

For valid exception values see fegetexceptflag.

**Returns:** The fetestexcept function returns the value of the bitwise OR of the floating-point exception

macros corresponding to the currently set floating-point exceptions included in the excepts argument.

See Also: feclearexcept, fegetexceptflag, feraiseexcept, fesetexceptflag

**Example:** #include <stdio.h>

```
#include <fenv.h>
void main( void )
    int excepts;
    feclearexcept(FE_DIVBYZERO);
    ...code that may cause a divide by zero exception
    excepts = fetestexcept( FE_DIVBYZERO );
    if ( excepts & FE_DIVBYZERO)
        printf( "Divide by zero occurred\n" );
```

Classification: ISO C99

All, Linux, RDOS, Netware **Systems:** 

Synopsis: #include <fenv.h>

int feupdateenv( const fenv\_t \*envp );

**Description:** The feupdateenv function attempts to save the currently raised floating-point exceptions in its

automatic storage, installs the floating-point environment represented by the object pointed to by *envp* argument, and then raises the saved floating-point exceptions. The argument *envp* shall point to an object set by a call to feholdexcept or fegeteny, or equal a floating-point environment macro.

Returns: The feupdateenv function returns zero if all the actions were successfully carried out. Otherwise, it

returns a nonzero value.

See Also: fegetenv, feholdexcept, fesetenv

Example: #include <fenv.h>

```
void main( void )
{
    fenv_t env;
    fegetenv( &env );
    fesetenv( FE_DFL_ENV );
    feupdateenv( &env );
}
```

Classification: ISO C99

**Synopsis:** #include <stdio.h> int fflush(FILE \*fp);

**Description:** If the file fp is open for output or update, the fflush function causes any unwritten data to be written to

the file. If the file fp is open for input or update, the fflush function undoes the effect of any

preceding ungetc operation on the stream. If the value of fp is NULL, then all files that are open will

be flushed.

**Returns:** The fflush function returns EOF if a write error occurs and zero otherwise. When an error has

occurred, errno contains a value indicating the type of error that has been detected.

See Also: fgetc, fgets, \_flushall, fopen, getc, gets, setbuf, setvbuf, ungetc

**Example:** #include <stdio.h> #include <conio.h>

```
void main()
  {
    printf( "Press any key to continue..." );
    fflush ( stdout );
    getch();
```

Classification: ISO C

```
Synopsis:
              #include <strings.h>
              int ffs( int i );
Description:
             The ffs finds the first bit set, beginning with the least significant bit, in i. Bits are numbered starting
              at one (the least significant bit).
Returns:
             The ffs function returns the index of the first bit set. If i is 0, ffs returns zero.
See Also:
              _lrotl, _lrotr, _rotl, _rotr
Example:
              #include <stdio.h>
              #include <strings.h>
              int main( void )
                   printf( ^{\circ}d\n^{\circ}, ffs( 0 ) );
                   printf( %d\n'', ffs( 16 ) );
                   printf( \d^n, ffs( 127 ) );
                   printf( "%d\n", ffs( -16 ) );
                   return(0);
              produces the following:
              0
              5
              1
              5
Classification: POSIX 1003.1
Systems:
              All, Linux, RDOS, Netware
```

**Synopsis:** 

```
#include <stdio.h>
int fgetc(FILE *fp);
#include <stdio.h>
#include <wchar.h>
wint_t fgetwc( FILE *fp );
```

#include <stdio.h>

**Description:** 

The fgetc function gets the next character from the file designated by fp. The character is signed.

The fgetwc function is identical to fgetc except that it gets the next multibyte character (if present) from the input stream pointed to by fp and converts it to a wide character.

**Returns:** 

The fgetc function returns the next character from the input stream pointed to by fp. If the stream is at end-of-file, the end-of-file indicator is set and fgetc returns EOF. If a read error occurs, the error indicator is set and fgetc returns EOF.

The fgetwc function returns the next wide character from the input stream pointed to by fp. If the stream is at end-of-file, the end-of-file indicator is set and fgetwc returns WEOF. If a read error occurs, the error indicator is set and fgetwo returns WEOF. If an encoding error occurs, errno is set to EILSEQ and fgetwc returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fgetchar, fgets, fopen, getc, getchar, gets, ungetc

**Example:** 

```
void main()
   FILE *fp;
    int c;
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
      while ( (c = fgetc(fp)) != EOF)
        fputc( c, stdout );
      fclose(fp);
    }
  }
```

Classification: ISO C

**Systems:** 

```
fgetc - All, Linux, RDOS, Netware
fgetwc - All, Linux
```

## **Synopsis:**

```
#include <stdio.h>
int fgetchar( void );
int _fgetchar( void );
wint_t _fgetwchar( void );
```

**Description:** 

The fgetchar function is equivalent to fgetc with the argument stdin.

The \_fgetchar function is identical to fgetchar. Use \_fgetchar for ANSI naming conventions.

The \_fgetwchar function is identical to fgetchar except that it gets the next multibyte character (if present) from the input stream pointed to by stdin and converts it to a wide character.

**Returns:** 

The fgetchar function returns the next character from the input stream pointed to by stdin. If the stream is at end-of-file, the end-of-file indicator is set and fgetchar returns EOF. If a read error occurs, the error indicator is set and fgetchar returns EOF.

The \_fgetwchar function returns the next wide character from the input stream pointed to by stdin. If the stream is at end-of-file, the end-of-file indicator is set and \_fgetwchar returns WEOF. If a read error occurs, the error indicator is set and \_fgetwchar returns WEOF. If an encoding error occurs, error is set to EILSEQ and \_fgetwchar returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fgetc, fgets, fopen, getc, getchar, gets, ungetc

#include <stdio.h>

**Example:** 

```
void main()
{
   FILE *fp;
   int c;

   fp = freopen( "file", "r", stdin );
   if( fp != NULL ) {
     while( (c = fgetchar()) != EOF )
        fputchar(c);
     fclose( fp );
   }
}
```

**Classification:** WATCOM

\_fgetchar conforms to ANSI naming conventions

**Systems:** 

```
fgetchar - All, Linux, RDOS, Netware
_fgetchar - All, Linux, RDOS, Netware
_fgetwchar - All, Linux
```

fgetchar, _fgetchar, _fgetwchar

Synopsis: #include <stdio.h>
 int fgetpos( FILE \*fp, fpos\_t \*pos );

**Description:** The fgetpos function stores the current position of the file fp in the object pointed to by pos. The

value stored is usable by the fsetpos function for repositioning the file to its position at the time of

the call to the fgetpos function.

**Returns:** The fgetpos function returns zero if successful, otherwise, the fgetpos function returns a non-zero

value. When an error has occurred, errno contains a value indicating the type of error that has been

detected.

See Also: fopen, fseek, fsetpos, ftell

Example: #include <stdio.h>

Classification: ISO C

**Synopsis:** 

```
#include <stdio.h>
char *fgets( char *buf, int n, FILE *fp );
#include <stdio.h>
#include <wchar.h>
wchar_t *fgetws( wchar_t *buf, int n, FILE *fp );
```

**Description:** 

The fgets function gets a string of characters from the file designated by fp and stores them in the array pointed to by buf. The fgets function stops reading characters when end-of-file is reached, or when a newline character is read, or when n-1 characters have been read, whichever comes first. The new-line character is not discarded. A null character is placed immediately after the last character read into the array.

The fgetws function is identical to fgets except that it gets a string of multibyte characters (if present) from the input stream pointed to by fp, converts them to wide characters, and stores them in the wide character array pointed to by buf. In this case, n specifies the number of wide characters, less one, to be read.

A common programming error is to assume the presence of a new-line character in every string that is read into the array. A new-line character will not be present when more than n-1 characters occur before the new-line. Also, a new-line character may not appear as the last character in a file, just before end-of-file.

The gets function is similar to fgets except that it operates with stdin, it has no size argument, and it replaces a newline character with the null character.

**Returns:** 

The fgets function returns buf if successful. NULL is returned if end-of-file is encountered, or a read error occurs. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fgetc, fgetchar, fopen, getc, getchar, gets, ungetc

**Example:** 

```
void main()
  {
    FILE *fp;
    char buffer[80];
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
      while (fgets (buffer, 80, fp ) != NULL )
        fputs (buffer, stdout);
      fclose( fp );
  }
```

**Classification:** ISO C

**Systems:** 

```
fgets - All, Linux, RDOS, Netware
fgetws - All, Linux
```

#include <stdio.h>

fgets, fgetws			

```
Synopsis:
           #include <math.h>
           extern int _fieeetomsbin( float *src, float *dest );
```

**Description:** The \_fieeetomsbin function loads the float pointed to by src in IEEE format and converts it to Microsoft binary format, storing the result into the float pointed to by dest.

> For \_fieeetomsbin IEEE Nan's and Infinities will cause overflow. IEEE denormals will be converted if within range. Otherwise, they will be converted to 0 in the Microsoft binary format.

The range of Microsoft binary format floats is 2.938736e-39 to 1.701412e+38. The range of Microsoft binary format doubles is 2.938735877056e-39 to 1.701411834605e+38.

Microsoft Binary Format was used by early versions of Microsoft QuickBASIC before coprocessors became standard.

**Returns:** The \_fieeetomsbin function returns 0 if the conversion was successful. Otherwise, it returns 1 if conversion would cause an overflow.

See Also: \_dieeetomsbin, \_dmsbintoieee, \_fmsbintoieee

**Example:** #include <stdio.h> #include <math.h> void main()

```
{
  float fieee, fmsb;
  double dieee, dmsb;
  fieee = 0.5;
 dieee = -2.0;
  /* Convert IEEE format to Microsoft binary format */
 _fieeetomsbin( &fieee, &fmsb );
 _dieeetomsbin( &dieee, &dmsb );
  /* Convert Microsoft binary format back to IEEE format */
 _fmsbintoieee( &fmsb, &fieee );
 _dmsbintoieee( &dmsb, &dieee );
  /* Display results */
 printf( "fieee = %f, dieee = %f\n", fieee, dieee );
```

produces the following:

```
fieee = 0.500000, dieee = -2.000000
```

**Classification:** WATCOM

**Systems:** All, Linux, Netware

_fieeetomsbin			

```
Synopsis:
             #include <io.h>
             long _filelength( int handle );
             __int64 _filelengthi64( int handle );
             ** deprecated **
             long filelength( int handle );
Description:
             The _filelength function returns, as a 32-bit long integer, the number of bytes in the opened file
             indicated by the file handle handle.
             The _filelengthi64 function returns, as a 64-bit integer, the number of bytes in the opened file indicated
             by the file handle handle.
             The filelength function is deprecated, use _filelength instead.
Returns:
             If an error occurs in _filelength (-1L) is returned.
             If an error occurs in _filelengthi64, (-1I64) is returned.
             When an error has occurred, errno contains a value indicating the type of error that has been detected.
             Otherwise, the number of bytes written to the file is returned.
See Also:
             fstat, lseek, _tell
Example:
             #include <sys/types.h>
             #include <fcntl.h>
             #include <stdio.h>
             #include <io.h>
             void main( void )
                  int handle;
                  /* open a file for input
                  handle = open( "file", O_RDONLY | O_TEXT );
                  if (handle !=-1) {
                       printf( "Size of file is %ld bytes\n",
                               _filelength( handle ) );
                       close( handle );
                  }
             }
             produces the following:
             Size of file is 461 bytes
Classification: WATCOM
```

\_filelength - All, Linux, RDOS, Netware

filelength - All, Linux, RDOS, Netware

\_filelengthi64 - All, Linux

**Systems:** 

_filelength, _filelen	ngthi64, filelength		

**Synopsis:** #include <stdio.h>

#define FILENAME\_MAX 123

**Description:** The FILENAME\_MAX macro is the size of an array of char big enough to hold a string naming any file

that the implementation expects to open; If there is no practical file name length limit,

FILENAME\_MAX is the recommended size of such an array. As file name string contents must meet

other system-specific constraints, some strings of length FILENAME\_MAX may not work.

FILENAME\_MAX typically sizes an array to hold a file name.

**Returns:** The FILENAME\_MAX macro returns a positive integer value.

**Example:** #include <stdio.h> #include <string.h>

> int main( int argc, char \*argv[] ) if( argc ) { char fname[FILENAME\_MAX]; strcpy( fname, argv[0] ); puts( fname ); return(0);

Classification: ISO C

**Systems: MACRO**  Synopsis: #include <stdio.h>
 int fileno(FILE \*stream);

**Description:** 

The fileno function returns the number of the file handle for the file designated by *stream*. This number can be used in POSIX input/output calls anywhere the value returned by open can be used. The following symbolic values in <io.h> define the file handles that are associated with the C language *stdin*, *stdout*, *stderr*, *stdaux*, and *stdprn* files when the application is started. The *stdaux* and *stdprn* files are not available for Win32.

Value	Meaning
STDIN_FILENO	Standard input file number, stdin (0)
STDOUT_FILENO	Standard output file number, stdout (1)
STDERR_FILENO	Standard error file number, stderr (2)
STDAUX_FILENO	Standard auxiliary file number, <i>stdaux</i> (3)
STDPRN_FILENO	Standard printer file number, stdprn (4)

**Returns:** 

The fileno function returns the number of the file handle for the file designated by *stream*. If an error occurs, a value of -1 is returned and error is set to indicate the error.

See Also: open

```
Example: #include <stdio.h>
```

```
void main()
{
   FILE *stream;

   stream = fopen( "file", "r" );
   printf( "File number is %d\n", fileno( stream ) );
   fclose( stream );
}
```

produces the following:

File number is 7

Classification: POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <io.h>

int \_findclose( intptr\_t handle );

**Description:** The \_findclose function closes the directory of filenames established by a call to the \_findfirst

function. The *handle* argument was returned by the \_findfirst function.

**Returns:** If successful, \_findclose returns 0; otherwise, \_findclose and returns -1 and sets errno to one

of the following values:

**Constant** Meaning

**ENOENT** No matching files

See Also: \_dos\_find..., \_findfirst, \_findnext, closedir, opendir, readdir

**Example:** #include <stdio.h> #include <io.h>

```
void main()
  {
    struct _finddata_t fileinfo;
    intptr_t
                        handle;
    int
                        rc;
    /* Display name and size of "*.c" files */
   handle = _findfirst( "*.c", &fileinfo );
    rc = handle;
    while ( rc !=-1 ) {
      printf( "%14s %10ld\n", fileinfo.name,
                               fileinfo.size );
      rc = _findnext( handle, &fileinfo );
     _findclose( handle );
```

**Classification:** DOS

**Systems:** DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

## **Synopsis:**

# **Description:**

The \_findfirst function returns information on the first file whose name matches the *filespec* argument. The *filespec* argument may contain wildcard characters ('?' and '\*'). The information is returned in a \_finddata\_t structure pointed to by *fileinfo*.

The \_wfindfirsti64 function returns information on the first file whose name matches the *filespec* argument. It differs from the \_findfirst function in that it returns a 64-bit file size. The *filespec* argument may contain wildcard characters ('?' and '\*'). The information is returned in a \_finddatai64\_t structure pointed to by *fileinfo*.

The \_wfindfirst function is a wide character version of \_findfirst that operates with wide character strings.

The wide character function is similar to the \_wfindfirsti64 function but operates on wide character strings. It differs from the \_wfindfirst function in that it returns a 64-bit file size.

```
struct _wfinddatai64_t {
    unsigned
                attrib;
                                  /* -1 for FAT file systems */
    time_t
                time_create;
    time_t
                time_access;
                                  /* -1 for FAT file systems */
    time_t
                time_write;
                                  /* 64-bit size info
                                                              */
    ___int64
                size;
    wchar_t
                name[_MAX_PATH];
};
```

**Returns:** 

If successful, \_findfirst returns a unique search handle identifying the file or group of files matching the filespec specification, which can be used in a subsequent call to \_findnext or to \_findclose. Otherwise, \_findfirst returns -1 and sets errno to one of the following values:

Constant Meaning

#include <stdio.h>

**ENOENT** No matching files

**EINVAL** Invalid filename specification

See Also: \_dos\_find..., \_findclose, \_findnext, closedir, opendir, readdir

**Example:** 

```
#include <io.h>
void main()
  {
    struct _finddata_t fileinfo;
                        handle;
    intptr_t
    int
                        rc;
    /* Display name and size of "*.c" files */
    handle = _findfirst( "*.c", &fileinfo );
    rc = handle;
    while ( rc !=-1 ) {
     printf( "%14s %10ld\n", fileinfo.name,
                               fileinfo.size );
      rc = _findnext( handle, &fileinfo );
    _findclose( handle );
```

**Classification:** DOS

**Systems:** 

```
_findfirst - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
RDOS
_findfirsti64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
_wfindfirst - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
_wfindfirsti64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

_findfirst, _findfirsti64	4, _wfindfirst, _wfindfirsti64	

## **Synopsis:**

```
#include <io.h>
int _findnext( intptr_t handle, struct _finddata_t *fileinfo );
int _findnexti64( intptr_t handle, struct _finddatai64_t *fileinfo );
int _wfindnext( intptr_t handle, struct _wfinddata_t *fileinfo );
int _wfindnexti64( intptr_t handle, struct _wfinddatai64_t *fileinfo
```

# **Description:**

The \_findnext function returns information on the next file whose name matches the *filespec* argument that was specified in a call to the \_findfirst function. The handle argument was returned by the \_findfirst function. The information is returned in a \_finddata\_t structure pointed to by fileinfo.

```
struct _finddata_t {
     unsigned attrib;
     time_t time_create; /* -1 for FAT file systems */
time_t time_access; /* -1 for FAT file systems */
time_t time_write;
_fsize_t size;
     char name[_MAX_PATH];
};
```

The \_wfindnexti64 function returns information on the next file whose name matches the *filespec* argument that was specified in a call to the \_findfirsti64 function. It differs from the \_findnext function in that it returns a 64-bit file size. The handle argument was returned by the \_findfirsti64 function. The information is returned in a \_finddatai64\_t structure pointed to by fileinfo.

```
struct _finddatai64_t {
      unsigned attrib;
      time_t time_create;  /* -1 for FAT file systems */
time_t time_access;  /* -1 for FAT file systems */
      time_t time_access;

time_t time_write;

__int64 size;

char name[_MAX_PATH];
                                                     /* 64-bit size info
                                                                                                */
};
```

The \_wfindnext function is a wide character version of \_findnext that operates with wide character strings.

```
struct _wfinddata_t {
     unsigned attrib;
     time_t time_create;    /* -1 for FAT file systems */
time_t time_access;    /* -1 for FAT file systems */
time_t time_write;
     _fsize_t size;
     wchar_t
                   name[_MAX_PATH];
};
```

The wide character function is similar to the \_wfindnexti64 function but operates on wide character strings. It differs from the \_wfindnext function in that it returns a 64-bit file size.

```
struct _wfinddatai64_t {
   unsigned
               attrib;
                              /* -1 for FAT file systems */
   time_t
               time_create;
   time_t
               time_access;
                               /* -1 for FAT file systems */
   time_t
               time_write;
                                 /* 64-bit size info
                                                            */
    ___int64
               size;
   wchar_t
               name[_MAX_PATH];
};
```

If successful, \_findnext returns 0; otherwise, \_findnext and returns -1 and sets errno to one of

the following values:

**Returns:** 

Constant Meaning

**ENOENT** No matching files

See Also: \_dos\_find..., \_findclose, \_findfirst, closedir, opendir, readdir

Example: #include <stdio.h>
#include <io.h>

**Classification:** DOS

Systems: \_\_findnext - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS \_\_findnexti64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

\_\_wfindnext - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32 \_\_wfindnexti64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

```
Synopsis:
           #include <float.h>
           int _finite( double x );
```

**Description:** The \_finite function determines whether the double precision floating-point argument is a valid

number (i.e., not infinite and not a NAN).

**Returns:** The \_finite function returns 0 if the number is not valid and non-zero otherwise.

See Also: \_clear87, \_control87, \_controlfp, \_fpreset, printf, \_status87, isfinite,

fpclassify

**Example:** #include <stdio.h> #include <float.h>

```
void main()
 {
  printf( "%s\n", (_finite( 1.797693134862320e+308 ) )
     ? "Valid" : "Invalid" );
```

produces the following:

Valid Invalid

**Classification:** WATCOM

**Systems:** Math

# 

**Description:** The \_floodfill functions fill an area of the screen. The \_floodfill function uses the view coordinate system. The \_floodfill\_w function uses the window coordinate system.

The filling starts at the point (x, y) and continues in all directions: when a pixel is filled, the neighbouring pixels (horizontally and vertically) are then considered for filling. Filling is done using the current color and fill mask. No filling will occur if the point (x, y) lies outside the clipping region.

short stop\_color );

If the argument  $stop\_color$  is a valid pixel value, filling will occur in each direction until a pixel is encountered with a pixel value of  $stop\_color$ . The filled area will be the area around (x,y), bordered by  $stop\_color$ . No filling will occur if the point (x,y) has the pixel value  $stop\_color$ .

If  $stop\_color$  has the value (-1), filling occurs until a pixel is encountered with a pixel value different from the pixel value of the starting point (x, y). No filling will occur if the pixel value of the point (x, y) is the current color.

**Returns:** The \_floodfill functions return zero when no filling takes place; a non-zero value is returned to indicate that filling has occurred.

See Also: \_setcliprgn, \_setcolor, \_setfillmask, \_setplotaction

Example: #include <conio.h>
#include <graph.h>

```
main()
{
    _setvideomode( _VRES16COLOR );
    _setcolor( 1 );
    _ellipse( _GBORDER, 120, 90, 520, 390 );
    _setcolor( 2 );
    _floodfill( 320, 240, 1 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: \_floodfill - DOS \_floodfill\_w - DOS

		_ <b>f</b> I	oodfill Functions

```
Synopsis:
               #include <math.h>
               double floor( double x );
Description:
               The floor function computes the largest integer not greater than x.
Returns:
               The floor function computes the largest integer not greater than x, expressed as a double.
See Also:
               ceil, fmod
Example:
               #include <stdio.h>
                #include <math.h>
               void main()
                  {
                     printf( "%f\n", floor( -3.14 ) );
                     printf( "%f\n", floor( 3.14 ) );
printf( "%f\n", floor( 0. ) );
printf( "%f\n", floor( 3.14 ) );
printf( "%f\n", floor( 3. ) );
               produces the following:
               -4.000000
               -3.00000
               0.000000
               3.000000
               3.000000
Classification: ISO C
Systems:
               Math
```

```
Synopsis:
           #include <stdio.h>
           int _flushall( void );
           ** deprecated **
           int flushall( void );
```

**Description:** 

The \_flushall function clears all buffers associated with input streams and writes any buffers associated with output streams. A subsequent read operation on an input file causes new data to be read from the associated file or device.

Calling the \_flushall function is equivalent to calling the fflush for all open stream files. The flushall function is deprecated, use \_flushall instead.

**Returns:** 

The \_flushall function returns the number of open streams. When an output error occurs while writing to a file, the errno global variable will be set.

See Also: fopen, fflush

**Example:** 

```
#include <stdio.h>
void main()
   printf( "The number of open files is %d\n",
            _flushall() );
  }
```

produces the following:

The number of open files is 4

**Classification:** WATCOM

**Systems:** 

\_flushall - All, Linux, RDOS, Netware flushall - All, Linux, RDOS, Netware

```
Synopsis: \#include <math.h> double fma( double x, double y, double z);
```

**Description:** The fma function performs a fused multiply-add operation. The resultant value is the product of x and y summed with z.

**Returns:** The x\*y+z

produces the following:

7.00000

Classification: ISO C99

**Systems:** Math

```
Synopsis:
             #include <math.h>
             double fmax( double x, double y);
Description:
            The fmax function returns the larger of x and y.
Returns:
             The routine will return the larger of x or y.
See Also:
             fdim, fmin
Example:
             #include <stdio.h>
             #include <math.h>
             void main()
               {
                 printf( \$f\n, fmax( 3.0, 2.0 ));
             produces the following:
             3.000000
```

Classification: ISO C99

**Systems:** Math

```
Synopsis:
             #include <math.h>
             double fmin( double x, double y);
Description:
             The fmin function returns the smaller of x and y.
Returns:
             The routine will return the smaller of x or y.
See Also:
             fdim, fmax
Example:
             #include <stdio.h>
             #include <math.h>
             void main()
                {
                  printf( "%f\n", fmin( 3.0, 2.0 ) );
             produces the following:
             2.000000
Classification: ISO C99
Systems:
```

Math

**Synopsis:** #include <math.h>

double fmod( double x, double y);

**Description:** The fmod function computes the floating-point remainder of x/y, even if the quotient x/y is not

representable.

**Returns:** The fmod function returns the value x - (i \* y), for some integer i such that, if y is non-zero, the result

has the same sign as x and magnitude less than the magnitude of y. If the value of y is zero, then the

value returned is zero.

See Also: ceil, fabs, floor

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
```

printf( "% $f\n$ ", fmod( 4.5, 2.0)); printf( "%f\n", fmod( -4.5, 2.0 ) ); printf(  $\$f\n$ , fmod( 4.5, -2.0 )); printf( "% $f\n$ ", fmod( -4.5, -2.0 ) );

produces the following:

0.500000 -0.500000 0.500000 -0.500000

**Classification:** ISO C

**Systems:** Math Synopsis: #include <math.h>
 extern int \_fmsbintoieee( float \*src, float \*dest );

**Description:** The \_fmsbintoieee function loads the float pointed to by *src* in Microsoft binary format and

converts it to IEEE format, storing the result &into the float pointed to by dest.

The range of Microsoft binary format floats is 2.938736e-39 to 1.701412e+38. The range of Microsoft binary format doubles is 2.938735877056e-39 to 1.701411834605e+38.

Microsoft Binary Format was used by early versions of Microsoft QuickBASIC before coprocessors became standard

**Returns:** The \_fmsbintoieee function returns 0 if the conversion was successful. Otherwise, it returns 1 if

conversion would cause an overflow.

See Also: \_\_dieeetomsbin, \_\_dmsbintoieee, \_\_fieeetomsbin

Example: #include <stdio.h>
#include <math.h>

```
void main()
{
   float fieee, fmsb;
   double dieee, dmsb;

   fieee = 0.5;
   dieee = -2.0;

   /* Convert IEEE format to Microsoft binary format */
   _fieeetomsbin( &fieee, &fmsb );
   _dieeetomsbin( &dieee, &dmsb );

   /* Convert Microsoft binary format back to IEEE format */
   _fmsbintoieee( &fmsb, &fieee );
   _dmsbintoieee( &dmsb, &dieee );

   /* Display results */
   printf( "fieee = %f, dieee = %f\n", fieee, dieee );
}
```

produces the following:

fieee = 0.500000, dieee = -2.000000

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

		_fmsbintoieee

Synopsis: #include <fnmatch.h>

**Description:** 

The fnmatch function checks the string specified by the *s* argument to see if it matches the pattern specified by the *pattern* argument.

The *flag* argument is a bitwise inclusive OR of the bits described below. It modifies the interpretation of *pattern* and *s*.

Flag Meaning

**FNM\_PATHNAME** If set, a path separator in s is explicitly matched by a slash in *pattern*. It isn't matched by either the asterisk or question mark special characters, or by a bracket expression.

**FNM\_PERIOD** If set, a leading period in *s* matches a period in *pattern*, where the definition of "leading" depends on FNM\_PATHNAME:

- If FNM\_PATHNAME is set, a period is leading if it's the first character in s, or if it immediately follows a path separator.
- If FNM\_PATHNAME isn't set, a period is leading only if it's the first character in s.

FNM\_NOESCAPE If set, disables backslash escaping:

- If FNM\_NOESCAPE isn't set in *flags*, a backslash character (\) in *pattern* followed by any other character matches that second character in *s*. In particular, \\ matches a backslash in *s*.
- If FNM\_NOESCAPE is set, a backslash character is treated as an ordinary character.

**FNM\_IGNORECASE** If set, the matching is case-insensitive.

FNM\_CASEFOLD A synonym for FNM\_IGNORECASE.

**FNM\_LEADING\_DIR** If set, the final path separator and any following characters in s are ignored during matching.

A pattern-matching special character that is quoted is a pattern that matches the special character itself. When not quoted, such special characters have special meaning in the specification of patterns. The pattern-matching special characters and the contexts in which they have their special meaning are as follows:

- ? a ? is a pattern that matches any printable or nonprintable character except <newline>.
- \* the \* matches any string, including the null string.

[br\_exp] a pattern that matches a single character as per Regular Expression Bracket Expressions (1003.2 2.9.1.2) except that

- The exclamation point character (!) replaces the circumflex character (^) in its role as a nonmatching list in the regular expression notation.
- The backslash is used as an escape character within bracket expressions.

The ?, \* and [ characters aren't special when used inside a bracket expression.

The concatenation of patterns matching a single character is a valid pattern that matches the concatenation of the single characters matched by each of the concatenated patterns. For example, the pattern a [bc] matches the strings ab and ac.

The concatenation of one or more patterns matching a single character with one or more asterisks (\*) is a valid pattern. In such patterns, each asterisk matches a string of zero or more characters, up to the first character that matches the character following the asterisk in the pattern. For example, the pattern a\*d matches the strings ad, abd, and abcd, but not the string abc.

When asterisk is the first or last character in a pattern, it matches zero or more characters that precede or follow the characters matched by the remainded of the pattern. For example, the pattern a\*d\* matches the strings ad, abcd, abcdef, aaaad and adddd. The pattern \*a\*d matches the strings ad, abcd, efabcd, aaaad and adddd.

**Returns:** 

The fination returns zero when s matches the pattern specified by pattern. If there is no match, FNM\_NOMATCH is returned. If an error occurs, fnmatch returns another non-zero value.

**Example:** 

```
#include <stdio.h>
#include <fnmatch.h>
#include <stdlib.h>
#include <limits.h>
int main( int argc, char **argv )
    int
            buffer[PATH_MAX+1];
    char
    while( gets( buffer ) ) {
        for(i = 1; i < argc; i++) {
            if ( fnmatch ( argv[i], buffer, 0 ) == 0 ) {
                printf( "'%s' matches pattern '%s' \n",
                         buffer, argv[i] );
                break;
    return( EXIT_SUCCESS );
```

Classification: POSIX 1003.2

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <stdio.h>

Safer C: The Safer C Library extension provides the fopen\_s function which is a safer alternative to fopen.

**Description:** The fopen function opens the file whose name is the string pointed to by *filename*, and associates a stream with it. The argument *mode* points to a string beginning with one of the following sequences:

Mode	Meaning
''r''	open file for reading
''w''	create file for writing, or truncate to zero length
''a''	append: open file or create for writing at end-of-file
"r+"	open file for update (reading and/or writing)
''w+''	create file for update, or truncate to zero length
''a+''	append: open file or create for update, writing at end-of-file

In addition to the above characters, you can also include one of the following characters in *mode* to specify the translation mode for newline characters:

The letter "t" may be added to any of the above sequences in the second or later position to indicate that the file is (or must be) a text file. It also overrides the global translation mode flag if you link your program with BINMODE.OBJ. The global translation mode flag default is "text" unless you explicitly link your program with BINMODE.OBJ.

When neither "t" nor "b" is specified, the value of the global variable \_fmode establishes whether the file is to treated as a binary or a text file. Unless this value is changed by the program or you have linked your program with BINMODE.OBJ, the default will be text mode.

b The letter "b" may be added to any of the above sequences in the second or later position to indicate that the file is (or must be) a binary file (an ISO C requirement for portability to systems that make a distinction between text and binary files).

You can also include one of the following characters to enable or disable the "commit" flag for the associated file.

c The letter "c" may be added to any of the above sequences in the second or later position to indicate that any output is committed by the operating system whenever a flush (fflush or \_flushall) is done.

This option is not supported under Netware.

n The letter "n" may be added to any of the above sequences in the second or later position to indicate that the operating system need not commit any output whenever a

flush is done. It also overrides the global commit flag if you link your program with COMMODE.OBJ. The global commit flag default is "no-commit" unless you explicitly link your program with COMMODE.OBJ.

This option is not supported under Netware.

The "t", "c", and "n" mode options are extensions for fopen and \_fdopen and should not be used where ISO C portability is desired.

Opening a file with read mode (r as the first character in the *mode* argument) fails if the file does not exist or it cannot be read. Opening a file with append mode (a as the first character in the mode argument) causes all subsequent writes to the file to be forced to the current end-of-file, regardless of previous calls to the fseek function. When a file is opened with update mode (+ as the second or later character of the *mode* argument), both input and output may be performed on the associated stream.

When a stream is opened in update mode, both reading and writing may be performed. However, writing may not be followed by reading without an intervening call to the fflush function or to a file positioning function (fseek, fsetpos, rewind). Similarly, reading may not be followed by writing without an intervening call to a file positioning function, unless the read resulted in end-of-file.

The \_wfopen function is a wide character version of fopen that operates with wide character strings.

**Returns:** 

The fopen function returns a pointer to the object controlling the stream. This pointer must be passed as a parameter to subsequent functions for performing operations on the file. If the open operation fails, fopen returns NULL. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

\_dos\_open, fclose, fcloseall, fdopen, fopen\_s, freopen, freopen\_s, \_fsopen, \_grow\_handles, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen

**Example:** 

```
#include <stdio.h>
void main()
    FILE *fp;
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
      /* rest of code goes here */
      fclose( fp );
    }
}
```

**Classification:** ISO C ('t', 'c', 'n' are Open Watcom extensions)

**Systems:** fopen - All, Linux, RDOS, Netware \_wfopen - All, Linux

fopen, _wfopen				

### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
errno_t fopen_s( FILE * restrict * restrict streamptr,
                const char * restrict filename,
                const char * restrict mode);
errno_t _wfopen_s( FILE * restrict * restrict streamptr,
                   const wchar_t * restrict filename,
                   const wchar_t * restrict mode);
```

### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and fopen\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

None of *streamptr*, *filename*, or *mode* shall be a null pointer. If there is a runtime-constraint violation, fopen\_s does not attempt to open a file. Furthermore, if streamptr is not a null pointer, fopen\_s sets \*streamptr to the null pointer.

# **Description:**

The fopen\_s function opens the file whose name is the string pointed to by filename, and associates a stream with it. The *mode* string shall be as described for fopen, with the addition that modes starting with the character 'w' or 'a' may be preceded by the character 'u', see below:

Mode	Meaning
''uw''	truncate to zero length or create text file for writing, default permissions
''ua''	append; open or create text file for writing at end-of-file, default permissions
''uwb''	truncate to zero length or create binary file for writing, default permissions
''uab''	append; open or create binary file for writing at end-of-file, default permissions
"uw+"	truncate to zero length or create text file for update, default permissions
''ua+''	append; open or create text file for update, writing at end-of-file, default permissions

<sup>&</sup>quot;uw+b or uwb+" truncate to zero length or create binary file for update, default permissions

To the extent that the underlying system supports the concepts, files opened for writing shall be opened with exclusive (also known as non-shared) access. If the file is being created, and the first character of the mode string is not 'u', to the extent that the underlying system supports it, the file shall have a file permission that prevents other users on the system from accessing the file. If the file is being created and first character of the mode string is 'u', then by the time the file has been closed, it shall have the system default file access permissions. If the file was opened successfully, then the pointer to FILE pointed to by *streamptr* will be set to the pointer to the object controlling the opened file. Otherwise, the pointer to FILE pointed to by *streamptr* will be set to a null pointer.

In addition to the above characters, you can also include one of the following characters in mode to specify the translation mode for newline characters:

<sup>&</sup>quot;ua+b or uab+" append; open or create binary file for update, writing at end-of-file, default permissions

The letter "t" may be added to any of the above sequences in the second or later position to indicate that the file is (or must be) a text file. It also overrides the global translation mode flag if you link your program with BINMODE.OBJ. The global translation mode flag default is "text" unless you explicitly link your program with BINMODE.OBJ.

When neither "t" nor "b" is specified, the value of the global variable \_fmode establishes whether the file is to treated as a binary or a text file. Unless this value is changed by the program or you have linked your program with BINMODE.OBJ, the default will be text mode.

**b** The letter "b" may be added to any of the above sequences in the second or later position to indicate that the file is (or must be) a binary file (an ISO C requirement for portability to systems that make a distinction between text and binary files).

You can also include one of the following characters to enable or disable the "commit" flag for the associated file.

c The letter "c" may be added to any of the above sequences in the second or later position to indicate that any output is committed by the operating system whenever a flush (fflush or \_flushall) is done.

This option is not supported under Netware.

n The letter "n" may be added to any of the above sequences in the second or later position to indicate that the operating system need not commit any output whenever a flush is done. It also overrides the global commit flag if you link your program with COMMODE.OBJ. The global commit flag default is "no-commit" unless you explicitly link your program with COMMODE.OBJ.

This option is not supported under Netware.

The "t", "c", and "n" mode options are extensions for fopen\_s and should not be used where ISO C portability is desired.

Opening a file with read mode (r as the first character in the *mode* argument) fails if the file does not exist or it cannot be read. Opening a file with append mode (a as the first character in the *mode* argument) causes all subsequent writes to the file to be forced to the current end-of-file, regardless of previous calls to the fseek function. When a file is opened with update mode (+ as the second or later character of the *mode* argument), both input and output may be performed on the associated stream.

When a stream is opened in update mode, both reading and writing may be performed. However, writing may not be followed by reading without an intervening call to the fflush function or to a file positioning function (fseek, fsetpos, rewind). Similarly, reading may not be followed by writing without an intervening call to a file positioning function, unless the read resulted in end-of-file.

The \_wfopen\_s function is a wide character version of fopen\_s that operates with wide character strings.

**Returns:** The fopen\_s function returns zero if it opened the file. If it did not open the file or if there was a runtime-constraint violation, fopen\_s returns a non-zero value.

See Also: \_\_dos\_open, fclose, fcloseall, fdopen, fopen, freopen\_s, \_fsopen, \_\_grow\_handles, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen

```
#define __STDC_WANT_LIB_EXT1__ 1
Example:
           #include <stdio.h>
           void main()
               errno_t rc;
               FILE *fp;
               rc = fopen_s( &fp, "file", "r" );
               if( fp != NULL ) {
                /* rest of code goes here */
                 fclose( fp );
           }
Classification: TR 24731
           _wfopen_s is WATCOM
Systems:
           fopen_s - All, Linux, RDOS, Netware
           _wfopen_s - All, Linux
```

```
Synopsis:
            #include <i86.h>
            unsigned FP_OFF( void __far *far_ptr );
Description:
            The FP_OFF macro can be used to obtain the offset portion of the far pointer value given in far_ptr.
Returns:
            The macro returns an unsigned integer value which is the offset portion of the pointer value.
See Also:
            FP_SEG, MK_FP, segread
Example:
            #include <stdio.h>
            #include <i86.h>
            char ColourTable[256][3];
            void main()
              {
                union REGPACK r;
                int i;
                 /* read block of colour registers */
                r.h.ah = 0x10;
                r.h.al = 0x17;
            #if defined(___386_
                r.x.ebx = 0;
                r.x.ecx = 256;
                r.x.edx = FP_OFF( ColourTable );
                 r.w.ds = r.w.fs = r.w.gs = FP\_SEG( &r );
            #else
                r.w.bx = 0;
                r.w.cx = 256;
                r.w.dx = FP_OFF( ColourTable );
            #endif
                r.w.es = FP_SEG( ColourTable );
                intr( 0x10, &r );
                 for(i = 0; i < 256; i++) {
                   printf( "Colour index = %d "
                            "{ Red=%d, Green=%d, Blue=%d \n",
                            i,
                            ColourTable[i][0],
                            ColourTable[i][1],
                            ColourTable[i][2] );
Classification: Intel
```

334 Library Functions and Macros

**MACRO** 

**Systems:** 

		FP_OFF

```
Synopsis:
            #include <i86.h>
            unsigned FP_SEG( void __far *far_ptr );
Description:
            The FP_SEG macro can be used to obtain the segment portion of the far pointer value given in far_ptr.
Returns:
            The macro returns an unsigned integer value which is the segment portion of the pointer value.
See Also:
            FP_OFF, MK_FP, segread
Example:
            #include <stdio.h>
            #include <i86.h>
            char ColourTable[256][3];
            void main()
              {
                union REGPACK r;
                int i;
                 /* read block of colour registers */
                r.h.ah = 0x10;
                r.h.al = 0x17;
            #if defined(___386_
                r.x.ebx = 0;
                r.x.ecx = 256;
                r.x.edx = FP_OFF( ColourTable );
                 r.w.ds = r.w.fs = r.w.gs = FP\_SEG( &r );
            #else
                r.w.bx = 0;
                r.w.cx = 256;
                r.w.dx = FP_OFF( ColourTable );
            #endif
                r.w.es = FP_SEG( ColourTable );
                intr( 0x10, &r );
                 for(i = 0; i < 256; i++) {
                   printf( "Colour index = %d "
                            "{ Red=%d, Green=%d, Blue=%d \n",
                            i,
                            ColourTable[i][0],
                            ColourTable[i][1],
                            ColourTable[i][2] );
Classification: Intel
```

**MACRO** 

**Systems:** 

Synopsis: #include <math.h>
 int fpclassify( x );

**Description:** The fpclassify macro classifies its argument *x* as NaN, infinite, normal, subnormal, or zero. First,

an argument represented in a format wider than its semantic type is converted to its semantic type.

Then classification is based on the type of the argument.

The argument *x* must be an expression of real floating type.

The possible return values of fpclassify and their meanings are listed below.

 Constant
 Meaning

 FP\_INFINITE
 positive or negative infinity

 FP\_NAN
 NaN (not-a-number)

 FP\_NORMAL
 normal number (neither zero, subnormal, NaN, nor infinity)

 FP\_SUBNORMAL
 subnormal number

**FP\_ZERO** positive or negative zero

**Returns:** The fpclassify macro returns the value of the number classification macro appropriate to the value

of its argument x.

See Also: isfinite, isinf, isnan, isnormal, signbit

Example: #include <math.h>
#include <stdio.h>

produces the following:

infinity is not a normal number

Classification: ISO C

**Systems:** MACRO

		fpclassify

```
Synopsis: #include <float.h>
    void _fpreset( void );
```

**Description:** The \_fpreset function resets the floating-point unit to the default state that the math library requires

for correct function. After a floating-point exception, it may be necessary to call the \_fpreset

function before any further floating-point operations are attempted.

In multi-threaded environments, \_fpreset only affects the current thread.

**Returns:** No value is returned.

See Also: \_\_clear87, \_control87, \_controlfp, \_finite, \_status87

Example:

```
#include <stdio.h>
#include <float.h>
char *status[2] = { "No", " " };
void main( void )
    unsigned int fp_status;
    fp_status = _status87();
    printf( "80x87 status\n" );
    printf( "%s invalid operation\n",
            status[ (fp_status & SW_INVALID) == 0 ] );
    printf( "%s denormalized operand\n",
            status[ (fp_status & SW_DENORMAL) == 0 ] );
    printf( "%s divide by zero\n",
            status[ (fp_status & SW_ZERODIVIDE) == 0 ] );
    printf( "%s overflow\n",
            status[ (fp_status & SW_OVERFLOW) == 0 ] );
    printf( "%s underflow\n",
            status[ (fp_status & SW_UNDERFLOW) == 0 ] );
    printf( "%s inexact result\n",
            status[ (fp_status & SW_INEXACT) == 0 ] );
    _fpreset();
```

**Classification:** Intel

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <stdio.h> int fprintf(FILE \*fp, const char \*format, ...); #include <stdio.h> #include <wchar.h> int fwprintf(FILE \*fp, const wchar\_t \*format, ...);

Safer C: The Safer C Library extension provides the fprintf\_s function which is a safer alternative to fprintf.

The fprintf function writes output to the file pointed to by fp under control of the argument format. **Description:** The *format* string is described under the description of the printf function.

> The fwprintf function is a wide character version of fprintf. It accepts a wide character string argument for format and produces wide character output.

**Returns:** The fprintf function returns the number of characters written, or a negative value if an output error occurred. The fwprintf function returns the number of wide characters written, or a negative value if an output error occurred. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: \_bprintf, cprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

**Example:** #include <stdio.h> char \*weekday = { "Saturday" }; char \*month = { "April" }; void main( void ) fprintf( stdout, "%s, %s %d, %d\n", weekday, month, 18, 1987); } produces the following: Saturday, April 18, 1987

**Classification:** ISO C

fwprintf is ISO C95

**Systems:** fprintf - All, Linux, RDOS, Netware fwprintf - All, Linux

fprintf, fwprintf			

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
int fprintf_s( FILE * restrict stream,
        const char * restrict format, ...);
#include <wchar.h>
int fwprintf_s( FILE * restrict stream.
       const wchar_t * restrict format, ...);
```

# **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and fprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither stream nor format shall be a null pointer. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by format. Any argument to fprintf\_s corresponding to a %s specifier shall not be a null pointer.

If there is a runtime-constraint violation, the fprintf\_s function does not attempt to produce further output, and it is unspecified to what extent fprintf s produced output before discovering the runtime-constraint violation.

# **Description:**

The fprintf\_s function is equivalent to the fprintf function except for the explicit runtime-constraints listed above.

The fwprintf\_s function is a wide character version of fprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

# **Returns:**

The fprintf\_s function returns the number of characters written, or a negative value if an output error or runtime-constraint violation occurred.

The fwprintf\_s function returns the number of wide characters written, or a negative value if an output error or runtime-constraint violation occurred.

# See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, bwprintf, fwprintf, swprintf, vbwprintf, vfwprintf, vwprintf, vswprintf

# **Example:**

```
#define ___STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
char *weekday = { "Friday" };
char *month = { "August" };
void main( void )
    fprintf_s( stdout, "%s, %s %d, %d\n",
                weekday, month, 13, 2004);
}
produces the following:
```

Friday, August 13, 2004

Classification: TR 24731

# fprintf\_s, fwprintf\_s

fprintf\_s - All, Linux, RDOS, Netware
fwprintf\_s - All, Linux **Systems:** 

```
#include <stdio.h>
int fputc( int c, FILE *fp );
#include <stdio.h>
#include <wchar.h>
wint_t fputwc( wint_t c, FILE *fp );
```

**Description:** 

The fputc function writes the character specified by the argument c to the output stream designated by

The fputwc function is identical to fputc except that it converts the wide character specified by c to a multibyte character and writes it to the output stream.

**Returns:** 

The fputc function returns the character written or, if a write error occurs, the error indicator is set and fputc returns EOF.

The fputwc function returns the wide character written or, if a write error occurs, the error indicator is set and fputwc returns WEOF. If an encoding error occurs, errno is set to EILSEQ and fputwc returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fopen, fputchar, fputs, putc, putchar, puts, ferror

**Example:** 

```
void main()
    FILE *fp;
    int c;
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
      while( (c = fgetc( fp )) != EOF )
        fputc( c, stdout );
      fclose( fp );
```

#include <stdio.h>

**Classification:** ISO C

**Systems:** 

fputc - All, Linux, RDOS, Netware fputwc - All, Linux

```
#include <stdio.h>
int fputchar( int c );
int _fputchar( int c );
wint_t _fputwchar( wint_t c );
```

# **Description:**

The fputchar function writes the character specified by the argument c to the output stream stdout. This function is identical to the putchar function.

The function is equivalent to:

#include <stdio.h>

```
fputc( c, stdout );
```

The \_fputchar function is identical to fputchar. Use \_fputchar for ANSI naming conventions.

The  $\_$ fputwchar function is identical to fputchar except that it converts the wide character specified by c to a multibyte character and writes it to the output stream.

# **Returns:**

The fputchar function returns the character written or, if a write error occurs, the error indicator is set and fputchar returns EOF.

The \_fputwchar function returns the wide character written or, if a write error occurs, the error indicator is set and \_fputwchar returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

# See Also:

fopen, fputc, fputs, putc, putchar, puts, ferror

# **Example:**

```
void main()
{
   FILE *fp;
   int c;

   fp = fopen( "file", "r" );
   if( fp != NULL ) {
      c = fgetc( fp );
      while( c != EOF ) {
        _fputchar( c );
      c = fgetc( fp );
   }
   fclose( fp );
}
```

# **Classification:** WATCOM

\_fputchar conforms to ANSI naming conventions

# **Systems:**

```
fputchar - All, Linux, RDOS, Netware
_fputchar - All, Linux, RDOS, Netware
_fputwchar - All, Linux
```

fputchar, _fputchar, _fputwchar

Synopsis: #include <stdio.h>
 int fputs( const char \*buf, FILE \*fp );
 #include <stdio.h>
 #include <wchar.h>
 int fputws( const wchar\_t \*buf, FILE \*fp );

**Description:** The fputs function writes the character string pointed to by *buf* to the output stream designated by *fp*. The terminating null character is not written.

The fputws function is identical to fputs except that it converts the wide character string specified by *buf* to a multibyte character string and writes it to the output stream.

**Returns:** The fputs function returns EOF if an error occurs; otherwise, it returns a non-negative value (the number of characters written). The fputws function returns EOF if a write or encoding error occurs; otherwise, it returns a non-negative value (the number of characters written). When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: fopen, fputc, fputchar, putc, putchar, puts, ferror

void main()
{
 FILE \*fp;
 char buffer[80];

 fp = fopen( "file", "r" );
 if( fp != NULL ) {
 while( fgets( buffer, 80, fp ) != NULL )
 fputs( buffer, stdout );
 fclose( fp );
 }
}

**Classification:** ISO C

Systems: fputs - All, Linux, RDOS, Netware fputws - All, Linux

```
#include <stdio.h>
size_t fread( void *buf,
              size_t elsize,
              size_t nelem,
              FILE *fp );
```

**Description:** 

The fread function reads nelem elements of elsize bytes each from the file specified by fp into the buffer specified by buf.

**Returns:** 

The fread function returns the number of complete elements successfully read. This value may be less than the requested number of elements.

The feof and ferror functions can be used to determine whether the end of the file was encountered or if an input/output error has occurred. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fopen, feof, ferror

**Example:** 

The following example reads a simple student record containing binary data. The student record is described by the struct student\_data declaration.

```
#include <stdio.h>
struct student_data {
                    student_id;
    int
    unsigned char marks[10];
};
size_t read_data(FILE *fp, struct student_data *p )
    return( fread( p, sizeof(*p), 1, fp ) );
  }
void main()
   FILE *fp;
    struct student_data std;
    int i;
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
      while( read_data( fp, &std ) != 0 ) {
        printf( "id=%d ", std.student_id );
        for( i = 0; i < 10; i++)
          printf( "%3d ", std.marks[ i ] );
        printf( "\n" );
      fclose( fp );
```

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware

fread			

```
#include <stdlib.h> For ISO C compatibility (free only)
#include <malloc.h> Required for other function prototypes
void free( void *ptr );
void _bfree( __segment seg, void __based(void) *ptr );
void _ffree( void __far *ptr );
void __nfree( void __near *ptr );
```

# **Description:**

When the value of the argument ptr is NULL, the free function does nothing; otherwise, the free function deallocates the memory block located by the argument ptr which points to a memory block previously allocated through a call to the appropriate version of calloc, malloc or realloc. After the call, the freed block is available for allocation.

Each function deallocates memory from a particular heap, as listed below:

Function	Неар
free	Depends on data model of the program
_bfree	Based heap specified by seg value
_ffree	Far heap (outside the default data segment)
nfree	Near heap (inside the default data segment)

In a large data memory model, the free function is equivalent to the \_ffree function; in a small data memory model, the free function is equivalent to the \_nfree function.

**Returns:** The free functions return no value.

See Also: calloc Functions, \_expand Functions, halloc, hfree, malloc Functions, \_msize Functions, realloc Functions, sbrk

# **Example:**

```
#include <stdio.h>
#include <stdlib.h>
void main()
  {
    char *buffer;
   buffer = (char *)malloc( 80 );
    if( buffer == NULL ) {
      printf( "Unable to allocate memory\n" );
    } else {
      /* rest of code goes here */
      free( buffer ); /* deallocate buffer */
    }
  }
```

**Classification:** ISO C

```
Systems:
           free - All, Linux, RDOS, Netware
           _bfree - DOS/16, Windows, OS/2 1.x(all)
```

```
_ffree - DOS/16, Windows, OS/2 1.x(all) _nfree - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT), OS/2-32, Linux, RDOS
```

**Synopsis:** #include <malloc.h> unsigned int \_freect( size\_t size );

**Description:** 

The \_freect function returns the number of times that \_nmalloc (or malloc in small data models) can be called to allocate a item of size bytes. In the tiny, small and medium memory models, the default data segment is only extended as needed to satisfy requests for memory allocation. Therefore, you will need to call \_nheapgrow in these memory models before calling \_freect in order to get a meaningful result.

**Returns:** The \_freect function returns the number of calls as an unsigned integer.

See Also: calloc, \_heapgrow Functions, malloc Functions, \_memavl, \_memmax

**Example:** 

```
#include <stdio.h>
#include <malloc.h>
void main()
  {
    int i;
    printf( "Can allocate %u longs before _nheapgrow\n",
            _freect( sizeof(long) ) );
    _nheapgrow();
    printf( "Can allocate %u longs after _nheapgrow\n",
            _freect( sizeof(long) ) );
    for( i = 1; i < 1000; i++ ) {
      _nmalloc( sizeof(long) );
    printf( "After allocating 1000 longs:\n" );
    printf( "Can still allocate %u longs\n",
            _freect( sizeof(long) ) );
  }
```

produces the following:

Can allocate 0 longs before \_nheapgrow Can allocate 10447 longs after \_nheapgrow After allocating 1000 longs: Can still allocate 9447 longs

**Classification:** WATCOM

**Systems:** All, Linux, RDOS Safer C: The Safer C Library extension provides the freopen\_s function which is a safer alternative to freopen.

**Description:** The stream located by the fp pointer is closed. The freopen function opens the file whose name is the string pointed to by *filename*, and associates a stream with it. The stream information is placed in the structure located by the *fp* pointer.

The argument *mode* is described in the description of the fopen function.

The \_wfreopen function is a wide character version of freopen that operates with wide character strings.

**Returns:** The freopen function returns a pointer to the object controlling the stream. This pointer must be passed as a parameter to subsequent functions for performing operations on the file. If the open operation fails, freopen returns NULL. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: \_\_dos\_open, fclose, fcloseall, fdopen, fopen, fopen\_s, freopen\_s, \_fsopen, \_\_grow\_handles, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen

texample: #include <stdio.h>

void main()
{
 FILE \*fp;
 int c;

 fp = freopen( "file", "r", stdin );
 if( fp != NULL ) {
 while( (c = fgetchar()) != EOF )
 fputchar(c);
 fclose( fp );
 }
}

**Classification:** ISO C

Systems: freopen - All, Linux, RDOS, Netware
\_wfreopen - All, Linux

_wfreopen

```
#include <stdio.h>
#define __STDC_WANT_LIB_EXT1__ 1
errno_t freopen_s(FILE * restrict * restrict newstreamptr,
                    const char * filename,
                    const char * restrict mode,
                    FILE * restrict stream );
errno_t _wfreopen_s( FILE * restrict * restrict newstreamptr,
                     const wchar_t * restrict filename,
                     const wchar_t * restrict mode,
                     FILE * restrict stream );
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and freopen\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> None of *newstreamptr*, *mode*, and *stream* shall be a null pointer. If there is a runtime-constraint violation, freopen\_s neither attempts to close any file associated with stream nor attempts to open a file. Furthermore, if newstreamptr is not a null pointer, freopen\_s sets \*newstreamptr to the null pointer.

# **Description:**

The freopen\_s function opens the file whose name is the string pointed to by *filename* and associates the stream pointed to by *stream* with it. The *mode* argument has the same meaning as in the fopen\_s function (including the mode's effect on exclusive access and file permissions). If filename is a null pointer, the freopen\_s function attempts to change the mode of the stream to that specified by mode, as if the name of the file currently associated with the stream had been used. It is implementation-defined which changes of mode are permitted (if any), and under what circumstances. The freopen\_s function first attempts to close any file that is associated with *stream*. Failure to close the file is ignored. The error and end-of-file indicators for the stream are cleared. If the file was opened successfully, then the pointer to FILE pointed to by newstreamptr will be set to the value of stream. Otherwise, the pointer to FILE pointed to by newstreamptr will be set to a null pointer.

The \_wfreopen\_s function is a wide character version of freopen\_s that operates with wide character strings.

# **Returns:**

The freopen\_s function returns zero if it opened the file. If it did not open the file or there was a runtime-constraint violation, freopen\_s returns a non-zero value.

# See Also:

\_dos\_open, fclose, fcloseall, fdopen, fopen, fopen\_s, freopen, \_fsopen, \_grow\_handles, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen

# **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
void main()
    errno_t rc;
   FILE *fp;
    int
            c;
```

```
rc = freopen_s( &fp, "file", "r", stdin );
               if( rc == 0 ) {
                 while( (c = fgetc( fp )) != EOF )
                    fputchar(c);
                 fclose( fp );
               }
           }
Classification: TR 24731
           _wfreopen_s is WATCOM
Systems:
           freopen_s - All, Linux, RDOS, Netware
           _wfreopen_s - All, Linux
```

Synopsis: #include <math.h>

double frexp( double value, int \*exp );

**Description:** The frexp function breaks a floating-point number into a normalized fraction and an integral power of

2. It stores the integral power of 2 in the *int* object pointed to by *exp*.

**Returns:** The frexp function returns the value of x, such that x is a double with magnitude in the interval

[0.5,1) or zero, and value equals x times 2 raised to the power \*exp. If value is zero, then both parts of

the result are zero.

See Also: ldexp, modf

Example: #include <stdio.h>
#include <math.h>

```
void main()
{
  int expon;
  double value;

  value = frexp( 4.25, &expon );
  printf( "%f %d\n", value, expon );
  value = frexp( -4.25, &expon );
  printf( "%f %d\n", value, expon );
}
```

produces the following:

0.531250 3 -0.531250 3

Classification: ISO C

Systems: Math

**Synopsis:** #include <stdio.h>

int fscanf(FILE \*fp, const char \*format, ...); #include <stdio.h> #include <wchar.h>

int fwscanf(FILE \*fp, const wchar\_t \*format, ...);

Safer C: The Safer C Library extension provides the fscanf\_s function which is a safer alternative to

fscanf.

The fscanf function scans input from the file designated by fp under control of the argument format. **Description:** 

Following the format string is a list of addresses to receive values. The *format* string is described under

the description of the scanf function.

The fwscanf function is identical to fscanf except that it accepts a wide character string argument

for format.

**Returns:** The fscanf function returns EOF if an input failure occurred before any conversion. Otherwise, the

number of input arguments for which values were successfully scanned and stored is returned. When a

file input error occurs, the errno global variable may be set.

See Also: cscanf, scanf, sscanf, vcscanf, vfscanf, vscanf, vsscanf, fwscanf, wscanf,

swscanf, vfwscanf, vwscanf, vswscanf

**Example:** To scan a date in the form "Saturday April 18 1987":

```
#include <stdio.h>
void main( void )
    int day, year;
    char weekday[10], month[10];
    FILE *in_data;
    in_data = fopen( "file", "r" );
    if( in_data != NULL ) {
        fscanf( in_data, "%s %s %d %d",
                weekday, month, &day, &year );
        printf( "Weekday=%s Month=%s Day=%d Year=%d\n",
                weekday, month, day, year );
        fclose( in_data );
    }
}
```

Classification: ISO C90

fwscanf is ISO C95

**Systems:** fscanf - All, Linux, RDOS, Netware

fwscanf - All, Linux

fscanf, fwscanf			

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
int fscanf_s(FILE * restrict stream,
       const char * restrict format, ...);
#include <stdio.h>
#include <wchar.h>
int fwscanf_s(FILE * restrict stream,
      const wchar_t * restrict format, ...);
```

### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and fscanf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither stream nor format shall be a null pointer. Any argument indirected through in order to store converted input shall not be a null pointer.

If there is a runtime-constraint violation, the fscanf\_s function does not attempt to perform further input, and it is unspecified to what extent fscanf\_s performed input before discovering the runtime-constraint violation.

# **Description:**

The fscanf\_s function is equivalent to fscanf except that the c, s, and [ conversion specifiers apply to a pair of arguments (unless assignment suppression is indicated by a \*). The first of these arguments is the same as for fscanf. That argument is immediately followed in the argument list by the second argument, which has type size\_t and gives the number of elements in the array pointed to by the first argument of the pair. If the first argument points to a scalar object, it is considered to be an array of one element.

A matching failure occurs if the number of elements in a receiving object is insufficient to hold the converted input (including any trailing null character).

The fwscanf\_s function is identical to fscanf\_s except that it accepts a wide character string argument for format.

# **Returns:**

The fscanf\_s function returns EOF if an input failure occurred before any conversion or if there was a runtime-constraint violation. Otherwise, the fscanf s function returns the number of input items successfully assigned, which can be fewer than provided for, or even zero.

When a file input error occurs, the errno global variable may be set.

# See Also:

cscanf, fscanf, scanf, sscanf, vcscanf, vfscanf, vscanf, vsscanf, fwscanf, wscanf, swscanf, vfwscanf, vwscanf, vswscanf

# **Example:**

To scan a date in the form "Friday August 13 2004":

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
void main( void )
    int day, year;
    char weekday[10], month[10];
    FILE *in_data;
```

**Synopsis:** #include <stdio.h> int fseek (FILE \*fp, long int offset, int where );

# **Description:**

The fseek function changes the read/write position of the file specified by fp. This position defines the character that will be read or written on the next I/O operation on the file. The argument fp is a file pointer returned by fopen or freopen. The argument offset is the position to seek to relative to one of three positions specified by the argument where. Allowable values for where are:

#### Value Meaning

SEEK\_SET The new file position is computed relative to the start of the file. The value of offset must not be negative.

**SEEK\_CUR** The new file position is computed relative to the current file position. The value of *offset* may be positive, negative or zero.

**SEEK\_END** The new file position is computed relative to the end of the file.

The fseek function clears the end-of-file indicator and undoes any effects of the ungetc function on the same file.

The ftell function can be used to obtain the current position in the file before changing it. The position can be restored by using the value returned by ftell in a subsequent call to fseek with the where parameter set to SEEK\_SET.

**Returns:** 

The fseek function returns zero if successful, non-zero otherwise. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fgetpos, fopen, fsetpos, ftell

**Example:** 

The size of a file can be determined by the following example which saves and restores the current position of the file.

```
#include <stdio.h>
long int filesize(FILE *fp )
  {
    long int save_pos, size_of_file;
    save_pos = ftell( fp );
    fseek( fp, OL, SEEK_END );
    size_of_file = ftell( fp );
    fseek( fp, save_pos, SEEK_SET );
    return( size_of_file );
```

```
void main()
{
   FILE *fp;

   fp = fopen( "file", "r" );
   if( fp != NULL ) {
      printf( "File size=%ld\n", filesize( fp ) );
      fclose( fp );
   }
}
```

Classification: ISO C

Systems: All, Linux, RDOS, Netware

**Synopsis:** #include <stdio.h> int fsetpos(FILE \*fp, fpos\_t \*pos);

**Description:** The fsetpos function positions the file fp according to the value of the object pointed to by pos,

which shall be a value returned by an earlier call to the fgetpos function on the same file.

**Returns:** The fsetpos function returns zero if successful, otherwise, the fsetpos function returns a non-zero

value. When an error has occurred, errno contains a value indicating the type of error that has been

detected.

See Also: fgetpos, fopen, fseek, ftell

**Example:** #include <stdio.h>

```
void main()
  {
    FILE *fp;
    fpos_t position;
    auto char buffer[80];
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
      fgetpos( fp, &position ); /* get position
      fgets( buffer, 80, fp ); /* read record
                                                     */
      fsetpos( fp, &position ); /* set position
                                                     */
      fgets( buffer, 80, fp ); /* read same record */
      fclose(fp);
    }
  }
```

Classification: ISO C

All, Linux, RDOS, Netware **Systems:** 

**Description:** 

The \_fsopen function opens the file whose name is the string pointed to by *filename*, and associates a stream with it. The arguments *mode* and *share* control shared reading or writing. The argument *mode* points to a string beginning with one of the following sequences:

Mode	Meaning
''r''	open file for reading; use default file translation
''w''	create file for writing, or truncate to zero length; use default file translation
''a''	append: open text file or create for writing at end-of-file; use default file translation
''rb''	open binary file for reading
''rt''	open text file for reading
''wb''	create binary file for writing, or truncate to zero length
''wt''	create text file for writing, or truncate to zero length
''ab''	append; open binary file or create for writing at end-of-file
''at''	append; open text file or create for writing at end-of-file
''r+''	open file for update (reading and/or writing); use default file translation
''w+''	create file for update, or truncate to zero length; use default file translation
''a+''	append; open file or create for update, writing at end-of-file; use default file translation
"r+b", "rb+"	open binary file for update (reading and/or writing)
"r+t", "rt+"	open text file for update (reading and/or writing)
"w+b", "wb+	" create binary file for update, or truncate to zero length
"w+t", "wt+"	create text file for update, or truncate to zero length
''a+b'', ''ab+''	append; open binary file or create for update, writing at end-of-file
"a+t", "at+"	append; open text file or create for update, writing at end-of-file

When default file translation is specified, the value of the global variable \_fmode establishes whether the file is to treated as a binary or a text file. Unless this value is changed by the program, the default will be text mode.

Opening a file with read mode ('r' as the first character in the *mode* argument) fails if the file does not exist or it cannot be read. Opening a file with append mode ('a' as the first character in the mode argument) causes all subsequent writes to the file to be forced to the current end-of-file, regardless of previous calls to the fseek function. When a file is opened with update mode ('+' as the second or third character of the *mode* argument), both input and output may be performed on the associated stream.

When a stream is opened in update mode, both reading and writing may be performed. However, writing may not be followed by reading without an intervening call to the fflush function or to a file positioning function (fseek, fsetpos, rewind). Similarly, reading may not be followed by writing without an intervening call to a file positioning function, unless the read resulted in end-of-file.

The shared access for the file, share, is established by a combination of bits defined in the <share.h> header file. The following values may be set:

Value	Meaning
SH_COMPAT	Set compatibility mode.
SH_DENYRW	Prevent read or write access to the file.
SH_DENYWR	Prevent write access of the file.
SH_DENYRD	Prevent read access to the file.
SH_DENYNO	Permit both read and write access to the file.

You should consult the technical documentation for the DOS system that you are using for more detailed information about these sharing modes.

The \_wfsopen function is a wide character version of \_fsopen that operates with wide character strings.

**Returns:** 

The \_fsopen function returns a pointer to the object controlling the stream. This pointer must be passed as a parameter to subsequent functions for performing operations on the file. If the open operation fails, \_fsopen returns NULL. When an error has occurred, errno contains a value indicating the type of error that has been detected.

```
See Also:
            _dos_open, fclose, fcloseall, fdopen, fopen, freopen, _grow_handles, _hdopen,
            open, _open_osfhandle, _popen, _sopen
```

**Example:** 

```
#include <stdio.h>
#include <share.h>
void main()
  {
    FILE *fp;
      open a file and prevent others from writing to it
    fp = _fsopen( "report.dat", "w", SH_DENYWR );
    if ( fp != NULL ) {
      /* rest of code goes here */
      fclose(fp);
    }
  }
```

# \_fsopen, \_wfsopen

**Classification:** WATCOM

Systems: \_fsopen - All, Linux, RDOS, Netware

\_wfsopen - All, Linux

### **Synopsis:** #include <sys/types.h>

```
#include <sys/stat.h>
int fstat( int handle, struct stat *buf );
int _fstat( int handle, struct stat *buf );
int _fstati64( int handle, struct _stati64 *buf );
```

**Description:** 

The fstat functions obtain information about an open file whose file handle is handle. This information is placed in the structure located at the address indicated by buf.

The file <sys/stat.h> contains definitions for the structure stat.

The structure \_stati64 differs from stat in the following way:

Field	Type/Meaning	
st_dev	(dev_t) the disk drive the file resides on	
st_ino	(ino_t) this inode's number (not used for DOS)	
st_mode	(unsigned short) file mode	
st_nlink	(short) number of hard links	
st_uid	(unsigned long) user-id (always 'root' for DOS)	
st_gid	(short) group-id (always 'root' for DOS)	
st_rdev	(dev_t) this should be the device type but it is the same as st_dev for the time being	
st_size	(off_t) total file size	
st_atime	(time_t) this should be the file "last accessed" time if the file system supports it	
st_mtime	(time_t) the file "last modified" time	
st_ctime	(time_t) this should be the file "last status change" time if the file system supports it	
	The following fields are Netware only:	
st_btime	(time_t) the file "last archived" time	
st_attr	(unsigned long) the file's attributes	
st_archivedID	(unsigned long) the user/object ID that last archived file	
st_updatedID	(unsigned long) the user/object ID that last updated file	
st_inheritedRightsMask (unsigned short) the inherited rights mask		
st_originatingNameSpace (unsigned char) the originating name space		

st\_size (\_\_int64) total file size (as a 64-bit value)

At least the following macros are defined in the <sys/stat.h> header file.

Macro	Meaning
$S_{ISFIFO}(m)$	Test for FIFO.
S_ISCHR(m)	Test for character special file.
$S_{ISDIR}(m)$	Test for directory file.
S_ISBLK(m)	Test for block special file.
S_ISREG(m)	Test for regular file.

The value *m* supplied to the macros is the value of the st\_mode field of a stat structure. The macro evaluates to a non-zero value if the test is true and zero if the test is false.

The following bits are encoded within the st\_mode field of a stat structure.

Mask	Owner Permissions
S IRWXU	Read, write, search (if a directory), or execute (otherwise)
S_IRUSR	Read permission bit
S_IWUSR	Write permission bit
S_IXUSR	Search/execute permission bit
S_IREAD	== S_IRUSR (for Microsoft compatibility)
S_IWRITE	== S_IWUSR (for Microsoft compatibility)
S_IEXEC	== S_IXUSR (for Microsoft compatibility)

S\_IRWXU is the bitwise inclusive OR of S\_IRUSR, S\_IWUSR, and S\_IXUSR.

Mask	Group Permissions (same as owner's on DOS, OS/2 or Windows)
S_IRWXG	Read, write, search (if a directory), or execute (otherwise)
S_IRGRP	Read permission bit
S_IWGRP	Write permission bit
S_IXGRP	Search/execute permission bit

S\_IRWXG is the bitwise inclusive OR of S\_IRGRP, S\_IWGRP, and S\_IXGRP.

Mask	Other Permissions (same as owner's on DOS, OS/2 or Windows)
S_IRWXO	Read, write, search (if a directory), or execute (otherwise)
S_IROTH	Read permission bit
S_IWOTH	Write permission bit
S_IXOTH	Search/execute permission bit

S\_IRWXO is the bitwise inclusive OR of S\_IROTH, S\_IWOTH, and S\_IXOTH.

Mask	Meaning
S_ISUID	(Not supported by DOS, OS/2 or Windows) Set user ID on execution. The
	process's effective user ID shall be set to that of the owner of the file when the file
	is run as a program. On a regular file, this bit should be cleared on any write.
S_ISGID	(Not supported by DOS, OS/2 or Windows) Set group ID on execution. Set
	effective group ID on the process to the file's group when the file is run as a
	program. On a regular file, this bit should be cleared on any write.
	en e

The \_fstat function is identical to fstat. Use \_fstat for ANSI naming conventions.

The \_fstati64 function differ from fstat in the type of structure that they are asked to fill in. The differences in the structures are described above.

Returns:

All forms of the fstat function return zero when the information is successfully obtained. Otherwise, -1 is returned.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

#### **Constant** Meaning

**EBADF** The *handle* argument is not a valid file handle.

See Also: creat, dup, dup2, open, \_sopen, stat

# **Example:**

```
#include <stdio.h>
#include <sys/types.h>
#include <sys/stat.h>
#include <fcntl.h>
#include <io.h>
void main()
    int handle, rc;
    struct stat buf;
    handle = open( "file", O_RDONLY );
    if (handle !=-1) {
        rc = fstat( handle, &buf );
        if ( rc !=-1 )
            printf( "File size = %d\n", buf.st_size );
        close( handle );
    }
}
```

# Classification: POSIX 1003.1

\_fstat conforms to ANSI naming conventions

\_fstati64 is WATCOM

# **Systems:**

```
fstat - All, Linux, RDOS, Netware
_fstat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fstati64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

fstat, _fstati, _fstati64					

**Synopsis:** #include <io.h> int fsync( int fd );

**Description:** 

The fsync function writes to disk all the currently queued data for the open file specified by fd. All necessary file system information required to retrieve the data is also written to disk. The file access times are also updated.

The fsync function is used when you wish to ensure that both the file data and file system information required to recover the complete file have been written to the disk.

The fsync function does not return until the transfer is completed.

**Returns:** 

The fsync function returns zero if successful. Otherwise, it returns -1 and errno is set to indicate the error. If the fsync function fails, outstanding i/o operations are not guaranteed to have been completed.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning		
<b>EBADF</b>	The fd argument is not a valid file handle.		
EINVAL	Synchronized i/o is not supported for this file.		
EIO	A physical I/O error occurred (e.g., a bad block). The precise meaning is device dependent.		
ENOSYS	The fsync function is not supported.		

See Also: fstat, open, stat, write

**Example:** 

```
Write a file and make sure it is on disk.
 */
#include <fcntl.h>
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <io.h>
char buf[512];
void main()
    int handle;
    int i;
    handle = creat( "file", S_IWRITE | S_IREAD );
    if ( handle == -1 ) {
      perror( "Error creating file" );
      exit( EXIT_FAILURE );
    }
```

```
for( i = 0; i < 255; ++i ) {
    memset( buf, i, sizeof( buf ) );
    if( write( handle, buf, sizeof(buf) ) != sizeof(buf) ) {
        perror( "Error writing file" );
        exit( EXIT_FAILURE );
    }
}

if( fsync( handle ) == -1 ) {
    perror( "Error sync'ing file" );
    exit( EXIT_FAILURE );
}

close( handle );
    exit( EXIT_SUCCESS );
}</pre>
```

Classification: POSIX 1003.4

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <stdio.h> long int ftell(FILE \*fp);

**Description:** The ftell function returns the current read/write position of the file specified by fp. This position defines the character that will be read or written by the next I/O operation on the file. The value returned by ftell can be used in a subsequent call to fseek to set the file to the same position.

**Returns:** The ftell function returns the current read/write position of the file specified by fp. When an error is detected, -1L is returned. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: fgetpos, fopen, fsetpos, fseek

**Example:** #include <stdio.h> long int filesize(FILE \*fp ) long int save\_pos, size\_of\_file; save\_pos = ftell( fp ); fseek( fp, OL, SEEK\_END ); size\_of\_file = ftell( fp ); fseek( fp, save\_pos, SEEK\_SET ); return( size\_of\_file ); } void main() FILE \*fp; fp = fopen( "file", "r" ); if( fp != NULL ) { printf( "File size=%ld\n", filesize( fp ) ); fclose( fp );

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

} }

```
Synopsis:
            #include <sys/timeb.h>
            int ftime( struct timeb *timeptr );
            struct timeb {
                                              /* time in seconds since Jan 1, 1970 UTC
                                  time;
                 time_t
                 unsigned short millitm;
                                              /* milliseconds
                                  timezone; /* difference in minutes from UTC
                 short
                                  dstflag; /* nonzero if in daylight savings time
                 short
            };
Description:
            The ftime function gets the current time and stores it in the structure pointed to by timeptr.
Returns:
            The ftime function fills in the fields of the structure pointed to by timeptr. The ftime function
            returns -1 if not successful, and no useful value otherwise.
See Also:
            asctime Functions, asctime_s, clock, ctime Functions, ctime_s, difftime, gmtime,
            gmtime_s, localtime, localtime_s, mktime, strftime, time, tzset
Example:
            #include <stdio.h>
            #include <time.h>
            #include <sys/timeb.h>
            void main()
                 struct timeb timebuf;
                         *tod;
                 char
                 ftime ( &timebuf );
                 tod = ctime( &timebuf.time );
                 printf( "The time is %.19s.%hu %s",
                     tod, timebuf.millitm, &tod[20]);
               }
            produces the following:
            The time is Tue Dec 25 15:58:42.870 1990
Classification: WATCOM
Systems:
            All, Linux, RDOS
```

```
#include <stdlib.h>
char *_fullpath( char *buffer,
                 const char *path,
                 size_t size );
wchar_t *_wfullpath( wchar_t *buffer ,
                     const wchar_t *path,
                     size_t size );
```

## **Description:**

The \_fullpath function returns the full pathname of the file specification in path in the specified buffer buffer of length size.

The maximum size that might be required for buffer is \_MAX\_PATH. If the buffer provided is too small, NULL is returned and errno is set.

If buffer is NULL then a buffer of size \_MAX\_PATH is allocated using malloc. This buffer may be freed using the free function.

If path is NULL or points to a null string ("") then the current working directory is returned in buffer.

The \_wfullpath function is a wide character version of \_fullpath that operates with wide character strings.

## **Returns:**

The \_fullpath function returns a pointer to the full path specification if no error occurred. Otherwise, NULL is returned.

#### **Errors:**

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning
ENOENT	The current working directory could not be obtained.
<b>ENOMEM</b>	The buffer could not be allocated.
<b>ERANGE</b>	The buffer passed was too small.

#### See Also:

\_makepath, \_splitpath

# **Example:**

```
#include <stdio.h>
#include <stdlib.h>
void main( int argc, char *argv[] )
  {
    int i;
    char buff[ PATH_MAX ];
    for(i = 1; i < argc; ++i) {
     puts( argv[i] );
      if( _fullpath( buff, argv[i], PATH_MAX ) ) {
        puts( buff );
      } else {
        puts( "FAIL!" );
    }
  }
```

# \_fullpath, \_wfullpath

**Classification:** WATCOM

Systems: \_fullpath - All, Linux, RDOS, Netware

\_wfullpath - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

**Synopsis:** #include <stdio.h> #include <wchar.h> int fwide(FILE \*fp, int mode);

**Description:** The fwide function determines the orientation of the stream pointed to by fp. If mode is greater than zero, the function first attempts to make the stream wide oriented. If mode is less than zero, the function first attempts to make the stream byte oriented. Otherwise, mode is zero and the fwide

function does not alter the orientation of the stream.

**Returns:** The fwide function returns a value greater than zero if, after the call, the stream has wide orientation, a value less than zero if the stream has byte orientation, or zero if the stream has no orientation.

See Also: fopen, freopen

**Example:** #include <stdio.h> #include <wchar.h>

```
void main( void )
    FILE
            *fp;
    int
            mode;
    fp = fopen( "file", "r" );
    if( fp != NULL ) {
        mode = fwide(fp, -33);
        printf( "orientation: %s\n",
            mode > 0 ? "wide" :
            mode < 0 ? "byte" : "none" );</pre>
```

produces the following:

orientation: byte

Classification: ISO C95

**Systems:** All, Linux, RDOS

**Description:** The fwrite function writes *nelem* elements of *elsize* bytes each to the file specified by *fp*.

**Returns:** The fwrite function returns the number of complete elements successfully written. This value will be less than the requested number of elements only if a write error occurs. When an error has occurred,

errno contains a value indicating the type of error that has been detected.

See Also: ferror, fopen

Example: #include <stdio.h>

```
struct student_data {
                  student_id;
   int
   unsigned char marks[10];
};
void main()
  {
   FILE *fp;
   struct student_data std;
   int i;
    fp = fopen( "file", "w" );
    if( fp != NULL ) {
      std.student_id = 1001;
      for( i = 0; i < 10; i++)
        std.marks[i] = (unsigned char) (85 + i);
      /* write student record with marks */
      i = fwrite( &std, sizeof(std), 1, fp );
      printf( "%d record written\n", i );
      fclose( fp );
  }
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

```
#include <stdlib.h>
char *gcvt( double value,
            int ndigits,
            char *buffer );
char *_gcvt( double value,
            int ndigits,
            char *buffer );
wchar_t *_wgcvt( double value,
                 int ndigits,
                 wchar_t *buffer );
```

# **Description:**

The govt function converts the floating-point number value into a character string and stores the result in buffer. The parameter ndigits specifies the number of significant digits desired. The converted number will be rounded to this position.

If the exponent of the number is less than -4 or is greater than or equal to the number of significant digits wanted, then the number is converted into E-format, otherwise the number is formatted using F-format.

The \_gcvt function is identical to gcvt. Use \_gcvt for ANSI naming conventions.

The \_wgcvt function is a wide character version of gcvt except that it produces a wide character string.

**Returns:** The govt function returns a pointer to the string of digits.

See Also: ecvt, fcvt, printf

# **Example:**

```
#include <stdio.h>
#include <stdlib.h>
void main()
  {
   char buffer[80];
   printf( "%s\n", gcvt( -123.456789, 5, buffer ) );
   printf( "%s\n", gcvt( 123.456789E+12, 5, buffer ) );
```

produces the following:

```
-123.46
1.2346E+014
```

# **Classification: WATCOM**

\_gcvt conforms to ANSI naming conventions

# **Systems:**

```
gcvt - Math
_gcvt - Math
_wgcvt - Math
```

gcvt, _gcvt, _wgcvt			

**Synopsis:** #include <graph.h> short \_FAR \_getactivepage( void );

**Description:** The \_getactivepage function returns the number of the currently selected active graphics page.

> Only some combinations of video modes and hardware allow multiple pages of graphics to exist. When multiple pages are supported, the active page may differ from the visual page. The graphics information in the visual page determines what is displayed upon the screen. Animation may be accomplished by alternating the visual page. A graphics page can be constructed without affecting the screen by setting the active page to be different than the visual page.

The number of available video pages can be determined by using the \_getvideoconfig function. The default video page is 0.

**Returns:** The \_qetactivepage function returns the number of the currently selected active graphics page.

See Also: \_setactivepage, \_setvisualpage, \_getvisualpage, \_getvideoconfig

**Example:** #include <conio.h> #include <graph.h>

main() int old\_apage; int old\_vpage; \_setvideomode( \_HRES16COLOR ); old\_apage = \_getactivepage(); old\_vpage = \_getvisualpage(); /\* draw an ellipse on page 0 \*/ \_setactivepage(0); \_setvisualpage(0); \_ellipse( \_GFILLINTERIOR, 100, 50, 540, 150 ); /\* draw a rectangle on page 1 \*/ \_setactivepage(1); \_rectangle( \_GFILLINTERIOR, 100, 50, 540, 150 ); getch(); /\* display page 1 \*/ \_setvisualpage(1); getch(); \_setactivepage( old\_apage ); \_setvisualpage( old\_vpage ); \_setvideomode( \_DEFAULTMODE ); }

Classification: PC Graphics

**Systems:** DOS

_getactivepage			

```
Synopsis:
           #include <graph.h>
           short _FAR _getarcinfo( struct xycoord _FAR *start_pt,
                                    struct xycoord _FAR *end_pt,
                                    struct xycoord _FAR *inside_pt );
```

**Description:** The \_getarcinfo function returns information about the arc most recently drawn by the \_arc or

\_pie functions. The arguments *start\_pt* and *end\_pt* are set to contain the endpoints of the arc. The argument inside\_pt will contain the coordinates of a point within the pie. The points are all specified in

the view coordinate system.

The endpoints of the arc can be used to connect other lines to the arc. The interior point can be used to fill the pie.

**Returns:** The \_getarcinfo function returns a non-zero value when successful. If the previous arc or pie was not successfully drawn, zero is returned.

See Also: \_arc,\_pie

```
Example:
           #include <conio.h>
           #include <graph.h>
```

```
main()
{
    struct xycoord start_pt, end_pt, inside_pt;
   _setvideomode( _VRES16COLOR );
   _arc( 120, 90, 520, 390, 520, 90, 120, 390 );
   _getarcinfo( &start_pt, &end_pt, &inside_pt );
   _moveto( start_pt.xcoord, start_pt.ycoord );
   _lineto( end_pt.xcoord, end_pt.ycoord );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

Systems: DOS

**Synopsis:** #include <graph.h> long \_FAR \_getbkcolor( void );

**Description:** The \_getbkcolor function returns the current background color. In text modes, the background

color controls the area behind each individual character. In graphics modes, the background refers to

the entire screen. The default background color is 0.

**Returns:** The \_getbkcolor function returns the current background color.

See Also: \_setbkcolor, \_remappalette

**Example:** #include <conio.h>

```
#include <graph.h>
long colors[ 16 ] = {
   _BLACK, _BLUE, _GREEN, _CYAN,
   _RED, _MAGENTA, _BROWN, _WHITE,
   _GRAY, _LIGHTBLUE, _LIGHTGREEN, _LIGHTCYAN,
   _LIGHTRED, _LIGHTMAGENTA, _YELLOW, _BRIGHTWHITE
};
main()
    long old_bk;
    int bk;
    _setvideomode( _VRES16COLOR );
    old_bk = _getbkcolor();
    for ( bk = 0; bk < 16; ++bk ) {
        _setbkcolor( colors[ bk ] );
        getch();
    _setbkcolor( old_bk );
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

**Systems:** DOS

```
#include <stdio.h>
int getc( FILE *fp );
#include <stdio.h>
#include <wchar.h>
wint_t getwc( FILE *fp );
```

**Description:** 

The getc function gets the next character from the file designated by fp. The character is returned as an int value. The getc function is equivalent to fgetc, except that it may be implemented as a macro.

The getwc function is identical to getc except that it gets the next multibyte character (if present) from the input stream pointed to by fp and converts it to a wide character.

**Returns:** 

The getc function returns the next character from the input stream pointed to by fp. If the stream is at end-of-file, the end-of-file indicator is set and getc returns EOF. If a read error occurs, the error indicator is set and getc returns EOF.

The getwc function returns the next wide character from the input stream pointed to by fp. If the stream is at end-of-file, the end-of-file indicator is set and getwc returns WEOF. If a read error occurs, the error indicator is set and getwc returns WEOF. If an encoding error occurs, errno is set to EILSEQ and getwc returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: fgetc, fgetchar, fgets, fopen, getchar, gets, ungetc

#include <stdio.h>

**Example:** 

```
void main()
{
   FILE *fp;
   int c;

   fp = fopen( "file", "r" );
   if( fp != NULL ) {
     while( (c = getc( fp )) != EOF )
        putchar(c);
     fclose( fp );
   }
}
```

**Classification:** ISO C

**Systems:** 

```
getc - All, Linux, RDOS, Netware
getwc - All, Linux
```

		getc, getwc

Synopsis: #include <conio.h>
int getch( void );

**Description:** The getch function obtains the next available keystroke from the console. Nothing is echoed on the

screen (the function getche will echo the keystroke, if possible). When no keystroke is available, the

function waits until a key is depressed.

The kbhit function can be used to determine if a keystroke is available.

**Returns:** A value of EOF is returned when an error is detected; otherwise the getch function returns the value

of the keystroke (or character).

When the keystroke represents an extended function key (for example, a function key, a cursor-movement key or the ALT key with a letter or a digit), zero is returned and the next call to

getch returns a value for the extended function.

See Also: getche, kbhit, putch, ungetch

Example: #include <stdio.h>

#include <conio.h>

void main()
{
 int c;

 printf( "Press any key\n" );
 c = getch();
 printf( "You pressed %c(%d)\n", c, c );
}

Classification: WATCOM

**Systems:** All, Linux, RDOS, Netware

390 Library Functions and Macros

```
#include <stdio.h>
int getchar( void );
#include <wchar.h>
wint_t getwchar( void );
```

**Description:** 

The getchar function is equivalent to getc with the argument stdin.

The getwchar function is similar to getchar except that it is equivalent to getwc with the argument stdin.

**Returns:** 

The getchar function returns the next character from the input stream pointed to by stdin. If the stream is at end-of-file, the end-of-file indicator is set and getchar returns EOF. If a read error occurs, the error indicator is set and getchar returns EOF.

The getwchar function returns the next wide character from the input stream pointed to by stdin. If the stream is at end-of-file, the end-of-file indicator is set and getwchar returns WEOF. If a read error occurs, the error indicator is set and getwchar returns WEOF. If an encoding error occurs, errno is set to EILSEQ and getwchar returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fgetc, fgetchar, fgets, fopen, getc, gets, ungetc

**Example:** 

```
#include <stdio.h>
void main()
  {
   FILE *fp;
    int c;
    fp = freopen( "file", "r", stdin );
    while( (c = getchar()) != EOF )
      putchar(c);
    fclose(fp);
```

**Classification:** ISO C

**Systems:** 

```
getchar - All, Linux, RDOS, Netware
getwchar - All, Linux
```

See Also:

Synopsis: #include <conio.h>
 int getche( void );

**Description:** The getche function obtains the next available keystroke from the console. The function will wait

until a keystroke is available. That character is echoed on the screen at the position of the cursor (use

getch when it is not desired to echo the keystroke).

The kbhit function can be used to determine if a keystroke is available.

**Returns:** A value of EOF is returned when an error is detected; otherwise, the getche function returns the value

of the keystroke (or character).

When the keystroke represents an extended function key (for example, a function key, a cursor-movement key or the ALT key with a letter or a digit), zero is returned and the next call to getche returns a value for the extended function.

getch, kbhit, putch, ungetch

Example: #include <stdio.h>
#include <conio.h>

void main()
{
 int c;
 printf( "Bross any koy\n" );

printf( "Press any key\n" );
c = getche();
printf( "You pressed %c(%d)\n", c, c );

Classification: WATCOM

**Systems:** All, Linux, RDOS, Netware

392 Library Functions and Macros

```
Synopsis:
           #include <graph.h>
           void _FAR _getcliprgn( short _FAR *x1, short _FAR *y1,
                                   short _FAR *x2, short _FAR *y2 );
```

**Description:** The \_getcliprgn function returns the location of the current clipping region. A clipping region is defined with the \_setcliprgn or \_setviewport functions. By default, the clipping region is the

entire screen.

The current clipping region is a rectangular area of the screen to which graphics output is restricted. The top left corner of the clipping region is placed in the arguments (x1, y1). The bottom right corner of the clipping region is placed in (x2, y2).

**Returns:** The \_getcliprgn function returns the location of the current clipping region.

See Also: \_setcliprqn, \_setviewport

```
Example:
           #include <conio.h>
           #include <graph.h>
           main()
               short x1, y1, x2, y2;
               _setvideomode( _VRES16COLOR );
               _getcliprgn( &x1, &y1, &x2, &y2 );
               _setcliprgn( 130, 100, 510, 380 );
               _ellipse( _GBORDER, 120, 90, 520, 390 );
               getch();
               _setcliprgn( x1, y1, x2, y2 );
               _setvideomode( _DEFAULTMODE );
           }
```

Classification: PC Graphics

DOS **Systems:** 

Synopsis: #include process.h>
char \*getcmd( char \*cmd\_line );

**Description:** The getemd function causes the command line information, with the program name removed, to be

copied to *cmd\_line*. The information is terminated with a null character. This provides a method of

obtaining the original parameters to a program unchanged (with the white space intact).

This information can also be obtained by examining the vector of program parameters passed to the

main function in the program.

**Returns:** The address of the target *cmd\_line* is returned.

See Also: abort, atexit, \_bgetcmd, exec..., exit, \_Exit, \_exit, getenv, main, putenv,

spawn..., system, \_wsystem

**Example:** Suppose a program were invoked with the command line

```
myprog arg-1 ( my stuff ) here
```

where that program contains

produces the following:

```
arg-1 ( my stuff ) here
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <graph.h> short \_FAR \_getcolor( void );

**Description:** The \_getcolor function returns the pixel value for the current color. This is the color used for

displaying graphics output. The default color value is one less than the maximum number of colors in

the current video mode.

**Returns:** The \_getcolor function returns the pixel value for the current color.

See Also: \_setcolor

**Example:** #include <conio.h> #include <graph.h> main() int col, old\_col; \_setvideomode( \_VRES16COLOR ); old\_col = \_getcolor(); for( col = 0; col < 16; ++col ) { \_setcolor( col ); \_rectangle( \_GFILLINTERIOR, 100, 100, 540, 380 ); getch(); \_setcolor( old\_col ); \_setvideomode( \_DEFAULTMODE );

Classification: PC Graphics

}

**Systems:** DOS

```
Synopsis:
             #include <graph.h>
             struct xycoord _FAR _getcurrentposition( void );
             struct _wxycoord _FAR _getcurrentposition_w( void );
Description:
             The _getcurrentposition functions return the current output position for graphics. The
             _getcurrentposition function returns the point in view coordinates. The
             _getcurrentposition_w function returns the point in window coordinates.
             The current position defaults to the origin, (0,0), when a new video mode is selected. It is changed
             by successful calls to the _arc, _moveto and _lineto functions as well as the _setviewport
             function.
             Note that the output position for graphics output differs from that for text output. The output position
             for text output can be set by use of the _settextposition function.
Returns:
             The _getcurrentposition functions return the current output position for graphics.
See Also:
             _moveto, _settextposition
Example:
             #include <conio.h>
             #include <graph.h>
             main()
             {
                  struct xycoord old_pos;
                  _setvideomode( _VRES16COLOR );
                  old_pos = _getcurrentposition();
                  _moveto( 100, 100 );
                  _lineto( 540, 100 );
                  _lineto( 320, 380 );
```

\_moveto( old\_pos.xcoord, old\_pos.ycoord );

Classification: PC Graphics

Systems: \_getcurrentposition - DOS

qetch();

\_getcurrentposition\_w - DOS

\_lineto( 100, 100 );

\_setvideomode( \_DEFAULTMODE );

```
#include <direct.h>
char *getcwd( char *buffer, size_t maxlen );
wchar_t *_wgetcwd( wchar_t *buffer, size_t maxlen );
```

## **Description:**

The get cwd function returns the name of the current working directory. The buffer address is either NULL or is the location at which a string containing the name of the current working directory is placed. In the latter case, the value of maxlen is the length in characters (including the terminating null character) which can be be used to store this name. An error occurs if the length of the path (including the terminating null character) exceeds maxlen.

The maximum size that might be required for *buffer* is PATH\_MAX + 1 bytes.

Extension: When buffer has a value of NULL, a string is allocated using malloc to contain the name of the current working directory. This string may be freed using the free function.

The \_wgetcwd function is a wide character version of getcwd that operates with wide character strings. The *maxlen* is the length in wide characters (wchar\_t).

# **Returns:**

The get cwd function returns the address of the string containing the name of the current working directory, unless an error occurs, in which case NULL is returned.

## **Errors:**

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning
EINVAL	The argument <i>maxlen</i> is negative.
ENOMEM	Not enough memory to allocate a buffer.
ERANGE	The buffer is too small (specified by <i>maxlen</i> ) to contain the name of the current working directory.

See Also:

chdir, chmod, \_getdcwd, mkdir, rmdir

# **Example:**

```
#include <stdio.h>
#include <stdlib.h>
#include <direct.h>
void main()
  {
    char *cwd;
    cwd = getcwd( NULL, 0 );
    if ( cwd != NULL ) {
      printf( "My working directory is %s\n", cwd );
      free ( cwd );
    }
  }
```

produces the following:

My working directory is C:\PROJECT\C

Classification: POSIX 1003.1 with extensions

Systems: getcwd - All, Linux, RDOS, Netware

 $\_$ wgetcwd - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

```
#include <direct.h>
char *_getdcwd( int drive, char *buffer, size_t maxlen );
wchar_t *_wgetdcwd( int drive, wchar_t *buffer, size_t maxlen );
```

# **Description:**

The \_getdcwd function gets the full path of the current working directory on the specified drive. The drive argument specifies the drive (0 = default drive, 1 = A, 2 = B, etc.). The buffer address is either NULL or is the location at which a string containing the name of the current working directory is placed. In the latter case, the value of *maxlen* is the length in characters (including the terminating null character) which can be be used to store this name. An error occurs if the length of the path (including the terminating null character) exceeds maxlen.

The maximum size that might be required for *buffer* is PATH\_MAX + 1 bytes.

When buffer has a value of NULL, a string is allocated using malloc to contain the name of the current working directory. This string may be freed using the free function.

The \_wgetdcwd function is a wide character version of \_getdcwd that operates with wide character strings. The *maxlen* is the length in wide characters (wchar\_t).

## **Returns:**

The \_getdcwd function returns the address of the string containing the name of the current working directory on the specified drive, unless an error occurs, in which case NULL is returned.

# **Errors:**

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning
ENODEV	The drive cannot be accessed.
ENOMEM	Not enough memory to allocate a buffer.
ERANGE	The buffer is too small (specified by <i>size</i> ) to contain the name of the current working directory.

See Also:

chdir, chmod, getcwd, mkdir, rmdir

# **Example:**

```
#include <stdio.h>
#include <stdlib.h>
#include <direct.h>
void main()
  {
    char *cwd;
    cwd = \_getdcwd(3, NULL, 0);
    if( cwd != NULL ) {
      printf( "The current directory on drive C is %s\n",
      free ( cwd );
    }
  }
```

produces the following:

The current directory on drive C is C:\PROJECT\C

**Classification:** WATCOM

\_getdcwd - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS \_wgetdcwd - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32 **Systems:** 

**Synopsis:** #include <stdio.h> ssize\_t getdelim( char \*\*line, size\_t \*n, int delim, FILE \*fp );

**Description:** The getdelim function reads in text from a stream fp up to and including a delimiter delim and returns the resulting text in a buffer pointed to by line when complete. The buffer pointed to by line should be of the size pointed to by n initially.

> The buffer pointed to by *line* can initially be null and *n* should reflect the size of *line* and be set to null. When getdelim is invoked, it will check if the buffer pointed to by *line* is allocated and large enough. If not, it will first call realloc to resize the buffer appropriately and adjust the value pointed to by nto reflect the new size of *line* after reallocation. If allocation fails, errno will be set to ENOMEM.

**Returns:** The function returns the number of characters read into the buffer or -1 on either error or if no further data is available.

**Example:** The following program would print out each line in a text file "test.txt".

```
#include <stdio.h>
int main( void )
    char *line = NULL;
    size_t n = 0;
   FILE *fp;
    fp = fopen("test.txt", "r");
    while (getdelim (&line, &n, ' \n', fp) >= 0) {
        printf("> %s", line);
    fclose(fp);
    return(0);
```

Classification: POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

```
Synopsis:
            #include <direct.h>
            unsigned _getdiskfree( unsigned drive,
                                        struct diskfree_t *diskspace );
            struct diskfree_t {
                 unsigned short total_clusters;
                 unsigned short avail_clusters;
                 unsigned short sectors_per_cluster;
                 unsigned short bytes_per_sector;
            };
Description:
            The _getdiskfree function uses system call 0x36 to obtain useful information on the disk drive
            specified by drive. Specify 0 for the default drive, 1 for drive A, 2 for drive B, etc. The information
            about the drive is returned in the structure diskfree_t pointed to by diskspace.
Returns:
            The _getdiskfree function returns zero if successful. Otherwise, it returns a non-zero value and
            sets errno to EINVAL indicating an invalid drive was specified.
See Also:
            _dos_getdiskfree, _dos_getdrive, _dos_setdrive, _getdrive
Example:
            #include <stdio.h>
            #include <direct.h>
            void main()
              {
                 struct diskfree_t disk_data;
                 /* get information about drive 3 (the C drive) */
                 if( _getdiskfree( 3, &disk_data ) == 0 ) {
                   printf( "total clusters: %u\n",
                                        disk_data.total_clusters );
                   printf( "available clusters: %u\n",
                                        disk_data.avail_clusters );
                   printf( "sectors/cluster: %u\n",
                                        disk_data.sectors_per_cluster );
                   printf( "bytes per sector: u\n",
                                        disk_data.bytes_per_sector );
                 } else {
                   printf( "Invalid drive specified\n" );
              }
            produces the following:
            total clusters: 16335
            available clusters: 510
            sectors/cluster: 4
            bytes per sector: 512
Classification: DOS
```

DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

402 Library Functions and Macros

**Systems:** 

		_getdiskfree

Synopsis: #include <direct.h>
 int \_getdrive( void );

 $\textbf{Description:} \quad \text{The $\_$getdrive function returns the current (default) drive number.}$ 

**Returns:** A value of 1 is drive A, 2 is drive B, 3 is drive C, etc.

See Also: \_\_dos\_getdiskfree, \_dos\_getdrive, \_dos\_setdrive, \_getdiskfree

The current drive is C

Classification: DOS

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

```
Synopsis:
           #include <unistd.h>
           gid_t getegid( void );
```

**Description:** The getegid function returns the efective group ID for the current process.

**Returns:** The efective group ID for the current process.

See Also: getgid, getuid, geteuid

```
Example:
            * Print the effective group ID of the process.
           #include <stdio.h>
           #include <unistd.h>
           int main( void )
                printf( "My effective group ID is %d\n", getegid() );
                return(0);
```

Classification: POSIX 1003.1

}

**Systems:** Linux **Safer C:** The Safer C Library extension provides the getenv\_s function which is a safer alternative to getenv.

**Description:** The getenv function searches the environment list for an entry matching the string pointed to by *name*. The matching is case-insensitive; all lowercase letters are treated as if they were in upper case.

Entries can be added to the environment list with the DOS set command or with the puterv or setenv functions. All entries in the environment list can be displayed by using the DOS set command with no arguments.

To assign a string to a variable and place it in the environment list:

```
C>SET INCLUDE=C:\WATCOM\H
```

To see what variables are in the environment list, and their current assignments:

```
C>SET
COMSPEC=C:\COMMAND.COM
PATH=C:\;C:\WATCOM
INCLUDE=C:\WATCOM\H
```

The \_wgetenv function is a wide character version of getenv that operates with wide character strings.

**Returns:** 

The getenv function returns a pointer to the string assigned to the environment variable if found, and NULL if no match was found. Note: the value returned should be duplicated if you intend to modify the contents of the string.

See Also:

exec..., \_wexec..., clearenv, getenv\_s, putenv, \_searchenv, setenv, unsetenv, \_wgetenv, \_wputenv, \_wsearchenv, \_wsetenv, \_wunsetenv, spawn..., system, \_wsystem

**Example:** 

**Classification:** ISO C

```
Systems: getenv - All, Linux, RDOS, Netware _wgetenv - All, Linux
```

		getenv, _wgetenv

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and getenv\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

name shall not be a null pointer. *maxsize* shall neither be equal to zero nor be greater than RSIZE\_MAX. If *maxsize* is not equal to zero, then *value* shall not be a null pointer.

If there is a runtime-constraint violation, the integer pointed to by *len* (if *len* is not null) is set to zero, and the environment list is not searched.

## **Description:**

The getenv\_s function searches the environment list for an entry matching the string pointed to by *name*.

If that entry is found, getenv\_s performs the following actions. If *len* is not a null pointer, the length of the string associated with the matched entry is stored in the integer pointed to by *len*. If the length of the associated string is less than *maxsize*, then the associated string is copied to the array pointed to by *value*.

If that entry is not found, getenv\_s performs the following actions. If *len* is not a null pointer, zero is stored in the integer pointed to by *len*. If *maxsize* is greater than zero, then *value[0]* is set to the null character.

The matching is case-insensitive; all lowercase letters are treated as if they were in upper case.

Entries can be added to the environment list with the DOS set command or with the puterv or setenv functions. All entries in the environment list can be displayed by using the DOS set command with no arguments.

To assign a string to a variable and place it in the environment list:

```
C>SET INCLUDE=C:\WATCOM\H
```

To see what variables are in the environment list, and their current assignments:

```
C>SET
COMSPEC=C:\COMMAND.COM
PATH=C:\;C:\WATCOM
INCLUDE=C:\WATCOM\H
```

# **Returns:**

The getenv\_s function returns zero if the environment string specified by *name* was found and successfully stored in the buffer pointed to by *value*. Otherwise, a non-zero value is returned.

# See Also:

```
exec..., _wexec..., clearenv, getenv, putenv, _searchenv, setenv, unsetenv,
_wgetenv, _wputenv, _wsearchenv, _wsetenv, _wunsetenv, spawn...,
system, _wsystem
```

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdlib.h>
Example:
              #include <stdio.h>
              void main( void )
                   char
                            buffer[128];
                   size_t len;
                   if( getenv_s( &len, buffer, sizeof( buffer ), "INCLUDE" ) == 0 )
    printf( "INCLUDE=%s\n", buffer );
```

**Classification:** TR 24731

**Systems:** All, Linux, RDOS, Netware **Systems:** 

Linux

```
Synopsis:
             #include <unistd.h>
             uid_t geteuid( void );
             The \ensuremath{\mbox{\tt geteuid}} function returns the efective user ID for the calling process.
Description:
Returns:
             The efective user ID for the calling process
See Also:
             getuid, getgid, getegid
Example:
              * Print the effective user ID of the process.
             #include <stdio.h>
             #include <unistd.h>
             int main( void )
                  printf( "My effective user ID is %d\n", geteuid() );
                  return(0);
Classification: POSIX 1003.1
```

**Synopsis:** #include <graph.h> unsigned char \_FAR \* \_FAR \_getfillmask( unsigned char \_FAR \*mask );

**Description:** The \_getfillmask function copies the current fill mask into the area located by the argument mask. The fill mask is used by the \_ellipse, \_floodfill, \_pie, \_polygon and \_rectangle

functions that fill an area of the screen.

The fill mask is an eight-byte array which is interpreted as a square pattern (8 by 8) of 64 bits. Each bit in the mask corresponds to a pixel. When a region is filled, each point in the region is mapped onto the fill mask. When a bit from the mask is one, the pixel value of the corresponding point is set using the current plotting action with the current color; when the bit is zero, the pixel value of that point is not affected.

When the fill mask is not set, a fill operation will set all points in the fill region to have a pixel value of the current color.

**Returns:** If no fill mask has been set, NULL is returned; otherwise, the \_getfillmask function returns mask.

See Also: \_floodfill, \_setfillmask, \_setplotaction

**Example:** #include <conio.h> #include <graph.h>

```
char old_mask[ 8 ];
char new_mask[ 8 ] = { 0x81, 0x42, 0x24, 0x18,
                       0x18, 0x24, 0x42, 0x81 };
main()
    _setvideomode( _VRES16COLOR );
   _getfillmask( old_mask );
   _setfillmask( new_mask );
   _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
   _setfillmask( old_mask );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

DOS **Systems:** 

Synopsis: #include <graph.h>

short \_FAR \_getfontinfo( struct \_fontinfo \_FAR \*info );

**Description:** 

The \_getfontinfo function returns information about the currently selected font. Fonts are selected with the \_setfont function. The font information is returned in the \_fontinfo structure indicated by the argument *info*. The structure contains the following fields:

*type* 1 for a vector font, 0 for a bit-mapped font

ascent distance from top of character to baseline in pixels

*pixwidth* character width in pixels (0 for a proportional font)

*pixheight* character height in pixels

avgwidth average character width in pixels

filename name of the file containing the current font

facename name of the current font

**Returns:** The \_getfontinfo function returns zero if the font information is returned successfully; otherwise a

negative value is returned.

See Also: \_registerfonts, \_unregisterfonts, \_setfont, \_outgtext, \_getgtextextent,

\_setgtextvector, \_getgtextvector

Example: #include <conio.h>
#include <graph.h>

Classification: PC Graphics

Systems: DOS

			_getfontinfo		

```
Synopsis:
            #include <unistd.h>
            gid_t getgid( void );
Description:
            The getgid function returns the group ID for the current process.
Returns:
            The group ID for the current process.
See Also:
            getuid, geteuid, getegid
Example:
              * Print the group ID of the process.
            #include <stdio.h>
            #include <unistd.h>
            int main( void )
                  printf( "I belong to group ID %d\n", getgid() );
                  return(0);
               }
Classification: POSIX 1003.1
```

**Synopsis:** #include <graph.h>

short \_FAR \_getgtextextent( char \_FAR \*text );

**Description:** The \_qetqtextextent function returns the length in pixels of the argument text as it would be

displayed in the current font by the function \_outgtext. Note that the text is not displayed on the

screen, only its length is determined.

**Returns:** The \_getgtextextent function returns the length in pixels of a string.

See Also: \_registerfonts, \_unregisterfonts, \_setfont, \_getfontinfo, \_outgtext,

\_setgtextvector, \_getgtextvector

**Example:** #include <conio.h>

```
#include <graph.h>
main()
    int width;
    struct _fontinfo info;
    _setvideomode( _VRES16COLOR );
    _getfontinfo( &info );
    _moveto( 100, 100 );
    _outgtext( "WATCOM Graphics" );
    width = _getgtextextent( "WATCOM Graphics" );
    _rectangle( _GBORDER, 100, 100,
                100 + width, 100 + info.pixheight);
    getch();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

**Systems:** DOS **Description:** 

Synopsis: #include <graph.h>
struct xycoord \_FAR \_getgtextvector( void );

The \_getgtextvector function returns the current value of the text orientation vector. This is the

direction used when text is displayed by the \_outgtext function.

**Returns:** The \_getgtextvector function returns, as an xycoord structure, the current value of the text

orientation vector.

See Also: \_registerfonts, \_unregisterfonts, \_setfont, \_getfontinfo, \_outgtext,

\_getgtextextent, \_setgtextvector

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    struct xycoord old_vec;

    _setvideomode( _VRES16COLOR );
    old_vec = _getgtextvector();
    _setgtextvector( 0, -1 );
    _moveto( 100, 100 );
    _outgtext( "WATCOM Graphics" );
    _setgtextvector( old_vec.xcoord, old_vec.ycoord );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: DOS

**Synopsis:** #include <netdb.h>

```
struct hostent *gethostbyaddr( const void *addr,
                                socklen_t len,
                                int type );
```

**Description:** 

The gethostbyaddr function searches the system's network host database for a host matching the addr argument. The address should be specified in network byte order. The len argument specifies the length in bytes of the addr argument, and type specifies the address type. Accepted types, such as AF\_INET or AF\_INET6, are expected. The routine will query only the local network hosts database.

The structure returned is defined as:

```
struct hostent {
   char
           *h_name;
                         /* host official name
                                                              */
           **h_aliases; /* host alternate names, up to 16,
   char
                             terminated by a NULL pointer
           h_length; /* address length in bytes
   int.
           **h_addr_list; /* array of pointers to network
   char
                              addresses in network byte order,
                              terminated by a NULL pointer
};
```

The pointer returned by gethostbyaddr points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If a matching host is found, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

If the host is found, the h\_name member will be the defintive name of the host, and h\_aliases will contain a NULL-terminated list of aliases. The addresses are contained in the h\_addr\_list member as a NULL-terminated list, and this structure entry will never be NULL.

If no matching host is found or an error occurs, the return value will be NULL.

See Also: gethostent, gethostbyname

Classification: POSIX 1003.1

Synopsis: #include <netdb.h>

struct hostent \*gethostbyname( const char \*name );

**Description:** 

The gethostbyname function determines the address or addresses of a host specified by the *name* argument. The routine will query the local database initially. If not found, the routine will perform a DNS query, returning all "A" records for the given host name.

The structure returned is defined as:

In the current Open Watcom implementation, this routine will only ever return IPv4 addresses, and all addresses will be of AF\_INET address type.

The pointer returned by gethostbyname points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If a matching host is found, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

If the host is found, the h\_name member will be a copy of the *name* argument. The addresses are contained in the h\_addr\_list member as a NULL-terminated list, and this structure entry will never be NULL.

If no matching host is found or an error occurs, the return value will be NULL.

See Also: ge

gethostent, gethostbyaddr

**Example:** 

The following program will attempt to determine the address of a hostname passed as an argument.

```
#include <stdio.h>
#include <netdb.h>
#include <arpa/inet.h>
int main(int argc, char *argv[])
    int i;
    struct hostent *he;
    struct in_addr **addr_list;
    if (argc != 2) {
        fprintf(stderr,"usage: %s <hostname>\n", argv[0]);
        return 1;
    if ((he = gethostbyname(argv[1])) == NULL) { // get the host inf
        printf("Failed to find %s\n", argv[1]);
       return 2;
   printf("IP addresses for %s:\n", argv[1]);
    addr_list = (struct in_addr **)he->h_addr_list;
    for(i = 0; addr_list[i] != NULL; i++) {
       printf(" %s\n", inet_ntoa(*addr_list[i]));
    return 0;
```

Classification: POSIX 1003.1

Synopsis: #include <netdb.h>

struct hostent \*gethostent( void );

**Description:** 

The gethostent function reads, parses, and returns entries from the network host database at /etc/hosts. The first call will return the first entry, and subsequent calls return subsequent entries. A null pointer is returned if either an error is encountered or no further entries exist.

If a call to sethostent was not first made, the gethostent function will open the database if necessary initially. By default, this will always return the first entry in the database.

The structure returned is defined as:

In the current Open Watcom implementation, this routine will only ever return IPv4 addresses, and all addresses will be of AF\_INET address type.

The pointer returned by gethostent points to a static location, and the user should free neither the pointer itself nor any of its consituent structure members.

This function is not thread-safe. Other calls to functions accessing the hostname database may affect the return value from this function.

**Returns:** A parsed host database entry, or NULL if no further entries exist or an error occurred.

See Also: sethostent, endhostent

**Example:** The following program will print out each user and their user ID in the system's password database

```
#include <stdio.h>
#include <netdb.h>
#include <arpa/inet.h>
int main(int argc, char *argv[])
  struct hostent *e;
    sethostent(1);
    e = gethostent();
    while(e != NULL) {
        char *ia = e->h_addr_list[0];
        printf("%s - %d.%d.%d.%d\n",
               e->h_name,
               ia[0],ia[1],ia[2],ia[3]
        );
        e = gethostent();
    }
    endhostent();
    return 0;
```

Classification: POSIX 1003.1

**Description:** 

The \_getimage functions store a copy of an area of the screen into the buffer indicated by the *image* argument. The \_getimage function uses the view coordinate system. The \_getimage\_w and \_getimage\_wxy functions use the window coordinate system.

The screen image is the rectangular area defined by the points (x1,y1) and (x2,y2). The buffer *image* must be large enough to contain the image (the size of the image can be determined by using the \_imagesize function). The image may be displayed upon the screen at some later time by using the \_putimage functions.

**Returns:** The \_getimage functions do not return a value.

See Also: \_imagesize, \_putimage

**Example:** 

```
#include <conio.h>
#include <graph.h>
#include <malloc.h>
main()
    char *buf;
    int y;
    _setvideomode( _VRES16COLOR );
    _ellipse( _GFILLINTERIOR, 100, 100, 200, 200 );
    buf = (char*) malloc(
                  _imagesize( 100, 100, 201, 201 ) );
    if( buf != NULL ) {
        _getimage( 100, 100, 201, 201, buf );
        _putimage( 260, 200, buf, _GPSET );
        _putimage( 420, 100, buf, _GPSET );
        for (y = 100; y < 300;) {
            _putimage( 420, y, buf, _GXOR );
            y += 20;
            _putimage( 420, y, buf, _GXOR );
        free ( buf );
    getch();
    _setvideomode( _DEFAULTMODE );
```

**Classification:** PC Graphics

**Systems:** \_getimage - DOS

\_getimage\_w - DOS \_getimage\_wxy - DOS

Synopsis: #include <stdio.h>
 ssize\_t getline( char \*\*line, size\_t \*n, FILE \*fp );

**Description:** The getline function reads a single line of text from a stream fp and returns the resulting text,

including any new line characters, in a buffer pointed to by *line* when complete. The buffer pointed to

by line should be of the size pointed to by n initially.

The buffer pointed to by *line* can initially be null and *n* should reflect the size of *line* and be set to 0. When getline is invoked, it will check if the buffer pointed to by *line* is allocated and large enough. If not, it will first call realloc to resize the buffer appropriately and adjust the value pointed to by *n* to reflect the new size of *line* after reallocation. If allocation fails, errno will be set to ENOMEM.

**Returns:** The function returns the number of characters read into the buffer or -1 on either error or if no further

data is available.

**Example:** The following program would print out each line in a text file "test.txt"

```
#include <stdio.h>
int main( void )
{
    char *line = NULL;
    size_t n = 0;
    FILE *fp;

    fp = fopen("test.txt", "r");
    while(getline(&line, &n, fp) >= 0) {
        printf("> %s", line);
    }
    fclose(fp);
    return( 0 );
}
```

Classification: POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <graph.h> unsigned short \_FAR \_getlinestyle( void );

**Description:** The \_getlinestyle function returns the current line-style mask.

> The line-style mask determines the style by which lines and arcs are drawn. The mask is treated as an array of 16 bits. As a line is drawn, a pixel at a time, the bits in this array are cyclically tested. When a bit in the array is 1, the pixel value for the current point is set using the current color according to the current plotting action; otherwise, the pixel value for the point is left unchanged. A solid line would result from a value of 0xFFFF and a dashed line would result from a value of 0xF0F0

The default line style mask is 0xFFFF

**Returns:** The \_getlinestyle function returns the current line-style mask.

See Also: \_lineto, \_pie, \_rectangle, \_polygon, \_setlinestyle

**Example:** #include <conio.h> #include <graph.h>

getch();

#define DASHED 0xf0f0 main() unsigned old\_style; \_setvideomode( \_VRES16COLOR ); old\_style = \_getlinestyle(); \_setlinestyle( DASHED ); \_rectangle( \_GBORDER, 100, 100, 540, 380 ); \_setlinestyle( old\_style );

\_setvideomode( \_DEFAULTMODE );

Classification: PC Graphics

**Systems:** DOS Synopsis: #include <mbctype.h>
 int \_getmbcp( void );

**Description:** The \_getmbcp function returns the current multibyte code page number.

**Returns:** The \_getmbcp function returns the current multibyte code page. A return value of zero indicates that

a single-byte character code page is in use.

See Also: \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha,

\_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint,

\_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc,

\_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

Example: #include <stdio.h>

```
#include <mbctype.h>

void main()
{
    printf( "%d\n", _setmbcp( 932 ) );
    printf( "%d\n", _getmbcp() );
}
```

produces the following:

0 932

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

**Synopsis:** #include <netdb.h>

struct netent \*getnetbyaddr( in\_addr\_t net, int type );

**Description:** 

The getnetbyaddr function searches the network database for a network with a matching address type, specified by type as AF\_INET, AF\_INET6, etc., and address matching the net argument. The function returns information about said network if a match is found. The routine will query the local database only.

The structure returned is defined as:

```
struct netent {
                         /* official network name */
   char
             *n_name;
           **n_aliases;
                         /* alias list
   char
                                              */
   int n_addrtype;
                         /* address type
   uint32_t n_net;
                          /* network number
};
```

The pointer returned by getnetbyaddr points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If a matching host is found, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The alias names of said network are contained in the n\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no matching host is found or an error occurs, the return value will be NULL.

See Also: getnetent, getnetbyname

Classification: POSIX 1003.1

Synopsis: #include <netdb.h>

struct netent \*getnetbyname( const char \*name );

**Description:** 

The getnetbyname function searches the network database for a network *name* and returns information about said network if a match is found. The routine will query the local database only.

The structure returned is defined as:

The pointer returned by getnetbyname points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If a matching host is found, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The addresses are contained in the  $n_{aliases}$  member as a NULL-terminated list, and this structure entry will never be NULL.

If no matching host is found or an error occurs, the return value will be NULL.

**See Also:** getnetent, getnetbyaddr

Classification: POSIX 1003.1

**Synopsis:** #include <netdb.h>

struct netent \*getnetent( void );

### **Description:**

The getnetent function retrieves the next entry in the network database. If not proceeded by an appropriate call to setnetent, the function will always return the first network in the database. The routine will query the local database only.

The structure returned is defined as:

```
struct netent {
      char *n_name; /* official network name */
char **n_aliases; /* alias list */
int n_addrtype; /* address type */
uint 32 t n_net: /* notwork number */
      uint32_t n_net;
                                                       /* network number
};
```

The pointer returned by getnetent points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

### **Returns:**

If the database contains more entries, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The alias names of said network are contained in the n\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no additional network is found or an error occurs, the return value will be NULL.

See Also:

setnetent, endnetent, getnetbyname, getnetbyaddr

Classification: POSIX 1003.1

## **Synopsis:**

# **Description:**

The getopt function is a command-line parser that can be used by applications that follow Utility Syntax Guidelines 3, 4, 5, 6, 7, 9 and 10 in the Base Definitions volume of IEEE Std 1003.1-2001, Section 12.2, Utility Syntax Guidelines.

The parameters *argc* and *argv* are the argument count and argument array as passed to main. The argument *optstring* is a string of recognised option characters; if a character is followed by a colon, the option takes an argument. All option characters allowed by Utility Syntax Guideline 3 are allowed in *optstring*.

The global variable optind is the index of the next element of the argv[] vector to be processed. It is initialised to 1 by the system, and getopt updates it when it finishes with each element of argv[]. When an element of argv[] contains multiple option characters, getopt uses a static variable to determine which options have already been processed.

The getopt function returns the next option character (if one is found) from *argv* that matches a character in *optstring*, if there is one that matches. If the option takes an argument, getopt sets the variable optarg to point to the option-argument as follows:

If the option was the last character in the string pointed to by an element of argv, then optarg contains the next element of argv, and optind is incremented by 2. If the resulting value of optind is not less than argc, this indicates a missing option-argument, and getopt returns an error indication.

Otherwise, optarg points to the string following the option character in that element of *argv*, and optind is incremented by 1.

If, when getopt is called:

- argv[optind] is a null pointer
- \*argv[optind] is not the character '-'
- argv[optind] points to the string "-"

getopt returns -1 without changing optind. If *argv[optind]* points to the string "--", getopt returns -1 after incrementing optind.

If getopt encounters an option character that is not contained in *optstring*, it returns the question-mark (?) character. If it detects a missing option-argument, it returns the colon character (:) if the first character of *optstring* was a colon, or a question-mark character (?) otherwise. In either case, getopt will set the global variable optopt to the option character that caused the error. If the application has not set the global variable opterr to 0 and the first character of *optstring* is not a colon, getopt also prints a diagnostic message to stderr.

The getopt function is not re-entrant and hence not thread-safe.

**Returns:** The getopt function returns the next option character specified on the command line.

> A colon (:) is returned if getopt detects a missing argument and the first character of optstring was a colon (:).

> A question mark (?) is returned if getopt encounters an option character not in optstring or detects a missing argument and the first character of *optstring* was not a colon (:).

Otherwise, getopt returns -1 when all command line options are parsed.

See Also: abort, atexit, \_bgetcmd, exec..., exit, \_Exit, \_exit, getcmd, getenv, main, putenv, spawn..., system, \_wsystem

**Example:** 

```
#include <stdio.h>
#include <unistd.h>
int main( int argc, char **argv )
    int
            c;
    char
            *ifile;
    char
            *ofile;
    while ( (c = getopt ( argc, argv, ":abf:o:" )) !=-1 ) {
        switch(c) {
        case 'a':
            printf( "option a is set\n" );
            break;
        case 'b':
            printf( "option b is set\n" );
            break;
        case 'f':
            ifile = optarg;
            printf( "input filename is '%s'\n", ifile );
            break;
        case 'o':
            ofile = optarg;
            printf( "output filename is '%s'\n", ofile );
            break;
        case ':':
            printf( "-%c without filename\n", optopt );
            break;
        case '?':
            printf( "usage: %s -ab -f <filename> -o <filename>\n", ar
gv[0]);
            break;
        }
    }
    return(0);
}
produces the following:
option a is set
input filename is 'in'
output filename is 'out'
```

when the program is executed with the command

cprogram name> -afin -o out

Classification: POSIX 1003.1

Systems: All, Linux

**Synopsis:** #include <io.h> long \_get\_osfhandle( int posixhandle );

**Description:** The \_get\_osfhandle function returns the operating system's internal file handle that corresponds to the POSIX-level file handle specified by posixhandle.

> The value returned by \_get\_osfhandle can be used as an argument to the \_open\_osfhandle function which can be used to connect a second POSIX-level handle to an open file.

The example below demonstrates the use of these two functions. Note that the example shows how the dup2 function can be used to obtain almost identical functionality.

When the POSIX-level file handles associated with one OS file handle are closed, the first one closes successfully but the others return an error (since the first call close the file and released the OS file handle). So it is important to call close at the right time, i.e., after all I/O operations are completed to the file.

**Returns:** If successful, \_qet\_osfhandle returns an operating system file handle corresponding to posixhandle. Otherwise, it returns -1 and sets errno to EBADF, indicating an invalid file handle.

See Also: close, dup2, fdopen, \_hdopen, open, \_open\_osfhandle, \_os\_handle

**Example:** #include <stdio.h> #include <stdlib.h> #include <io.h> #include <fcntl.h>

> void main() long os\_handle; int fh1, fh2, rc; fh1 = open( "file", O\_WRONLY | O\_CREAT | O\_TRUNC | O\_BINARY, S\_IRUSR | S\_IWUSR | S\_IRGRP | S\_IWGRP ); if(fh1 == -1) { printf( "Could not open output file\n" ); exit( EXIT\_FAILURE );

printf( "First POSIX handle %d\n", fh1 );

```
#if defined(USE_DUP2)
   fh2 = 6;
   if ( dup2 ( fh1, fh2 ) == -1 ) fh2 = -1;
#else
   os_handle = _get_osfhandle( fh1 );
   printf( "OS Handle %ld\n", os_handle );
    fh2 = _open_osfhandle( os_handle, O_WRONLY |
                                      O_BINARY );
#endif
    if(fh2 == -1) {
       printf( "Could not open with second handle\n" );
       exit( EXIT_FAILURE );
   printf( "Second POSIX handle %d\n", fh2 );
   rc = write(fh2, "trash\x0d\x0a", 7);
   printf( "Write file using second handle %d\n", rc );
   rc = close(fh2);
   printf( "Closing second handle %d\n", rc );
   rc = close(fh1);
   printf( "Closing first handle %d\n", rc );
```

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, Netware

```
Synopsis:
           #include <unistd.h>
           gid_t getpgrp( void );
```

**Description:** The getpgrp function returns the process group ID for the current process.

**Returns:** The process group ID for the current process.

See Also: getuid, geteuid, getegid

```
Example:
            * Print the process group ID of the process.
           #include <stdio.h>
           #include <unistd.h>
           int main( void )
                printf( "I belong to group ID %d\n", getpgrp() );
                return(0);
```

Classification: POSIX 1003.1

}

Synopsis: #include <graph.h>
 struct xycoord \_FAR \_getphyscoord( short x, short y );

**Description:** The \_getphyscoord function returns the physical coordinates of the position with view coordinates

(x,y) . View coordinates are defined by the  $\_$ setvieworg and  $\_$ setviewport functions.

**Returns:** The \_getphyscoord function returns the physical coordinates, as an xycoord structure, of the

given point.

See Also: \_getviewcoord, \_setvieworg, \_setviewport

Example: #include <conio.h>
#include <graph.h>

#include <stdlib.h>
main()
{

Classification: PC Graphics

Systems: DOS

```
Synopsis:
            #include <unistd.h>
            pid_t getpid( void );
            pid_t _getpid( void );
Description:
            The getpid function returns the process ID for the current process.
Returns:
            The process ID for the current process.
See Also:
            getppid, gettid
Example:
             * print out the ID of this process
            #include <stdio.h>
            #include <unistd.h>
            int main( void )
                 printf( "I'm process %d\n", getpid() );
                 return(0);
Classification: POSIX 1003.1
Systems:
            getpid - All, Linux, RDOS
            _getpid - All, Linux, RDOS
```

```
Synopsis:
            #include <graph.h>
            short _FAR _getpixel( short x, short y );
            short _FAR _getpixel_w( double x, double y );
Description:
            The \_getpixel functions return the pixel value for the point with coordinates (x,y). The
            _getpixel function uses the view coordinate system. The _getpixel_w function uses the window
            coordinate system.
Returns:
            The _getpixel functions return the pixel value for the given point when the point lies within the
            clipping region; otherwise, (-1) is returned.
See Also:
            _setpixel
Example:
            #include <conio.h>
            #include <graph.h>
            #include <stdlib.h>
            main()
                 int x, y;
                 unsigned i;
                 _setvideomode( _VRES16COLOR );
                 _rectangle( _GBORDER, 100, 100, 540, 380 );
                 for( i = 0; i \le 60000; ++i ) {
                      x = 101 + rand() % 439;
                      y = 101 + rand() % 279;
                      \_setcolor(\_getpixel(x, y) + 1);
                      _setpixel(x, y);
                 getch();
                 _setvideomode( _DEFAULTMODE );
Classification: PC Graphics
            _getpixel - DOS
Systems:
            _getpixel_w - DOS
```

**Synopsis:** #include <graph.h> short \_FAR \_getplotaction( void );

**Description:** The \_getplotaction function returns the current plotting action.

> The drawing functions cause pixels to be set with a pixel value. By default, the value to be set is obtained by replacing the original pixel value with the supplied pixel value. Alternatively, the replaced value may be computed as a function of the original and the supplied pixel values.

The plotting action can have one of the following values:

\_GPSET replace the original screen pixel value with the supplied pixel value

\_GAND replace the original screen pixel value with the bitwise and of the original

pixel value and the supplied pixel value

\_GOR replace the original screen pixel value with the bitwise or of the original pixel

value and the supplied pixel value

GXOR replace the original screen pixel value with the bitwise exclusive-or of the

> original pixel value and the supplied pixel value. Performing this operation twice will restore the original screen contents, providing an efficient method

to produce animated effects.

**Returns:** The \_getplotaction function returns the current plotting action.

See Also: \_setplotaction

Example: #include <conio.h> #include <qraph.h>

```
main()
    int old_act;
    _setvideomode( _VRES16COLOR );
    old_act = _getplotaction();
   _setplotaction( _GPSET );
   _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
    _setplotaction( _GXOR );
    _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
    getch();
    _setplotaction( old_act );
    _setvideomode( _DEFAULTMODE );
```

**Classification:** PC Graphics

**Systems:** DOS

_getplotaction			

```
Synopsis:
           #include <unistd.h>
           pid_t getppid(void);
```

**Description:** The getppid function allows the calling process to find out its parent ID.

**Returns:** The process parent's process ID.

See Also: getpid

**Example:** 

```
* Print the parent's process ID.
#include <stdio.h>
#include <unistd.h>
int main( void )
   printf( "My parent is %d\n", getppid() );
   return(0);
```

Classification: POSIX 1003.1

# getprotobyname

Synopsis: #include <netdb.h>

struct netent \*getprotobyname( const char \*name );

**Description:** 

The getprotobyname function searches the protocol database for a protocol matching the specified *name*, considering both the official name and aliases. The routine will query the local database only.

The structure returned is defined as:

The pointer returned by getprotobyname points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the protocol database may affect the return value from this function.

**Returns:** 

If a matching protocol database entry is found, the return value will point to a struct protoent as defined above.

The alias names of said protocol are contained in the p\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no protocol is found or an error occurs, the return value will be NULL.

See Also: getprotoent, setprotoent, endprotoent, getprotobynumber

Classification: POSIX 1003.1

**Synopsis:** #include <netdb.h>

struct netent \*getprotobynumber( int protocol );

**Description:** 

The getprotobynumber function searches the protocol database for a protocol matching the specified by the *protocol* argument. The routine will query the local database only.

The structure returned is defined as:

```
char *p_name; /* official protocol name */
char **p_aliases; /* alias list */
int p_proto; /* protocol ***
struct protoent {
};
```

The pointer returned by getprotobynumber points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the protocol database may affect the return value from this function.

**Returns:** 

See Also:

If a matching protocol database entry is found, the return value will point to a struct protoent as defined above.

The alias names of said protocol are contained in the p\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no protocol is found or an error occurs, the return value will be NULL.

getprotoent, setprotoent, endprotoent, getprotobyname

Classification: POSIX 1003.1

Synopsis: #include <netdb.h>

struct netent \*getprotoent( void );

**Description:** 

The getprotoent function retrieves the next entry in the protocol database. If not proceeded by an appropriate call to setprotoent, the function will always return the first protocol in the database. The routine will query the local database only.

The structure returned is defined as:

The pointer returned by getprotoent points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the protocol database may affect the return value from this function.

**Returns:** 

If the database contains more entries, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The alias names of said protocol are contained in the p\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no protocol is found or an error occurs, the return value will be NULL.

See Also: setprotoent, endprotoent, getprotobyname, getprotobynumber

Classification: POSIX 1003.1

**Synopsis:** #include <pwd.h> struct passwd \*getpwent( void );

## **Description:**

The getpwent function reads, parses, and returns entries from the password database at /etc/passwd. The first call will return the first entry, and subsequent calls return subsequent entries. A null pointer is returned if either an error is encountered or no further entries exist.

The structure returned is defined as:

```
struct passwd {
  char *pw_name;
  char
  uid_t pw_uid;
                   /* user ID number
                                   */
                   /* group ID number
  gid_t pw_gid;
                   /* real name
                                   */
  char
        *pw_gecos;
                   /* home directory
        *pw_dir;
  char
        *pw_shell; /* initial program
  char
};
```

On most modern Linux implementations, the resulting password will simply be 'x' as passwords are not normally stored in the password database itself.

The pointer returned by getpwent points to a static location, and the user should free neither the pointer itself nor any of its consituent structure members.

This function is not thread-safe. Other calls to functions accessing the password database may affect the return value from this function.

Returns: A parsed password database entry, or NULL if no further entries exist or an error occurred.

See Also: setpwent, endpwent, getpwnam, getpwuid

**Example:** The following program will print out each user and their user ID in the system's password database

```
#include <stdio.h>
#include <pwd.h>
void main()
  {
    struct passwd *pw;
    setpwent();
    while((pw = getpwent()) != NULL) {
        printf("User id %d is %s\n", (int)pw->pw_uid, pw->pw_name);
    endpwent();
  }
```

Classification: POSIX 1003.1

getpwent			

**Synopsis:** #include <pwd.h> struct passwd \*getpwnam( const char \*name );

**Description:** 

The getpwnam function locates and returns a parsed password database entry for the user with the specified username. If a matching entry is not found or an error occurs, a null pointer will be returned.

The structure returned is defined as:

```
struct passwd {
                        /* user's login name */
   char *pw_name;
          *pw_passwd;
                        /* user's password
   char
   uid_t pw_uid;
                        /* user ID number
                        /* group ID number
   gid_t pw_gid;
          *pw_gecos;
   char
                       /* real name
                                           */
   char
                       /* home directory
                                           */
          *pw_dir;
                       /* initial program
   char
          *pw_shell;
};
```

On most modern Linux implementations, the resulting password will simply be 'x' as passwords are not normally stored in the password database itself.

The pointer returned by getpwnam points to a static location, and the user should free neither the pointer itself nor any of its consituent structure members.

This function is not thread-safe. Other calls to functions accessing the password database may affect the return value from this function.

**Returns:** A matching parsed password database entry, or NULL if no match is found.

See Also: setpwent, endpwent, getpwuid, getpwent

**Example:** The following program will locate and print out the user ID corresponding to a user name 'root.'

```
#include <stdio.h>
#include <pwd.h>
void main()
 {
    struct passwd *pw;
    pw = getpwnam( "root" );
    if(pw) {
        printf("The user id for root is %d\n", (int)pw->pw_uid);
    } else {
        printf("User 'root' was not found.\n");
  }
```

Classification: POSIX 1003.1

**Systems:** Linux

getpwnam			

**Synopsis:** #include <pwd.h> struct passwd \*getpwuid( uit\_t uid );

**Description:** 

The getpwuid function locates and returns a parsed password database entry for the user with the specified user ID. If a matching entry is not found or an error occurs, a null pointer will be returned.

The structure returned is defined as:

```
struct passwd {
                        /* user's login name */
   char *pw_name;
          *pw_passwd;
                         /* user's password
   char
   uid_t pw_uid;
                         /* user ID number
                         /* group ID number
   gid_t pw_gid;
          *pw_gecos; /* real name
*pw_dir; /* home direct
   char
                                              */
   char
                         /* home directory
                                              */
           *pw_dir;
          *pw_shell;
                         /* initial program
   char
};
```

On most modern Linux implementations, the resulting password will simply be 'x' as passwords are not normally stored in the password database itself.

The pointer returned by getpwuid points to a static location, and the user should free neither the pointer itself nor any of its consituent structure members.

This function is not thread-safe. Other calls to functions accessing the password database may affect the return value from this function.

**Returns:** A matching parsed password database entry, or NULL if no match is found.

See Also: setpwent, endpwent, getpwnam, getpwent

**Example:** The following program will locate and print out the user name corresponding to a user ID of 1000.

```
#include <stdio.h>
#include <pwd.h>
void main()
 {
    struct passwd *pw;
   pw = getpwuid((uid_t)1000);
   if(pw)
        printf("The corresponding username is '%s'\n", pw->pw_name);
    else
        printf("User id 1000 was not found.\n");
  }
```

Classification: POSIX 1003.1

**Systems:** Linux

getpwuid			

**Synopsis:** 

```
#include <stdio.h>
char *gets( char *buf );
#include <stdio.h>
wchar_t *_getws( wchar_t *buf );
```

**Description:** 

The gets function gets a string of characters from the file designated by stdin and stores them in the array pointed to by buf until end-of-file is encountered or a new-line character is read. Any new-line character is discarded, and a null character is placed immediately after the last character read into the

The \_getws function is a wide character version of gets that operates with wide character strings. The \_getws function gets a string of multibyte characters (if present) from the input stream pointed to by stdin, converts them to wide characters, and stores them in the wide character array pointed to by buf until end-of-file is encountered or a wide character new-line character is read.

It is recommended that fgets be used instead of gets because data beyond the array buf will be destroyed if a new-line character is not read from the input stream stdin before the end of the array buf is reached.

A common programming error is to assume the presence of a new-line character in every string that is read into the array. A new-line character may not appear as the last character in a file, just before end-of-file.

**Returns:** 

The gets function returns buf if successful. NULL is returned if end-of-file is encountered, or if a read error occurs. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fgetc, fgetchar, fgets, fopen, getc, getchar, ungetc

**Example:** 

```
void main()
  {
    char buffer[80];
    while( gets( buffer ) != NULL )
      puts( buffer );
```

#include <stdio.h>

**Classification:** ISO C

**Systems:** 

```
gets - All, Linux, RDOS, Netware
_getws - All, Linux
```

**Synopsis:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
char *gets_s( char *s, rsize_t n );
```

**Constraints:** 

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and gets\_s will set s[0] to be the null character, and characters are read and discarded from stdin until a new-line character is read, or end-of-file or a read error occurs.

s shall not be a null pointer. n shall neither be equal to zero nor be greater than RSIZE\_MAX. A new-line character, end-of-file, or read error shall occur within reading n-1 characters from stdin.

**Description:** 

The gets\_s function gets a string of characters from the file designated by stdin and stores them in the array pointed to by s until end-of-file is encountered or a new-line character is read. Size of the array s is specified by the argument n, this information is used to protect buffer from overflow. If buffer s is about to be overflown, runtime-constraint is activated. Any new-line character is discarded, and a null character is placed immediately after the last character read into the array.

**Returns:** 

The gets\_s function returns s if successful. NULL is returned if there was a runtime-constraint violation, or if end-of-file is encountered and no caracters have been read into the array, or if a read error occurs.

See Also: fgetc, fgetchar, fgets, fopen, getc, getchar, gets, ungetc

**Example:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>

int main()
{
    char buffer[80];

    while( gets_s( buffer, sizeof( buffer ) ) != NULL )
        puts( buffer );
}
```

Classification: TR 24731

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** 

```
#include <netdb.h>
struct servent *getservbyname( const char *name, const char *protocol
);
```

**Description:** 

The getservbyname function searches the service database for a service with matching *name* and protocol, returning a pointer the a struct servent if found. The function will search for matching aliases as well. If protocol is NULL, the first encountered service matching the specified name will be returned regardless of protocol. The routine will query the local database only.

The structure returned is defined as:

```
struct servent {
        char *s_name; /* official service name */
char **s_aliases; /* alias list */
int s_port; /* port number */
char *s_proto; /* protocol to use */
};
```

The pointer returned by getservbyname points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If a match is found, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The alias names of said network are contained in the s\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no additional network is found or an error occurs, the return value will be NULL.

See Also:

getservent, setservent, endservent, getservbyport

Classification: POSIX 1003.1

**Systems:** 

Linux

Synopsis: #include <netdb.h>

struct servent \*getservbyname( int port, const char \*protocol );

**Description:** 

The getservbyport function searches the service database for a service listening on *port* using *protocol*, returning a pointer the a struct servent if found. If *protocol* is NULL, the first encountered service matching the specified port number will be returned regardless of protocol. The routine will query the local database only.

The structure returned is defined as:

The pointer returned by getservbyport points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If a match is found, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The alias names of said network are contained in the s\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no additional network is found or an error occurs, the return value will be NULL.

See Also: getservent, setservent, endservent, getservbyname

Classification: POSIX 1003.1

Systems: Linux

**Synopsis:** #include <netdb.h>

struct servent \*getservent( void );

**Description:** 

The getservent function retrieves the next entry in the service database. If not proceeded by an appropriate call to setservent, the function will always return the first service in the database. The routine will query the local database only.

The structure returned is defined as:

```
struct servent {
      char *s_name; /* official service name */
char **s_aliases; /* alias list */
int s_port; /* port number */
char *s_proto; /* protocol to use */
                                                  /* protocol to use
};
```

The pointer returned by getservent points to a private location, and the user should free neither the pointer itself nor any of its constituent structure members. Subsequent calls to this function may result in the values changing.

This function is not thread-safe. Other calls to this function or to other functions accessing the hostname database may affect the return value from this function.

**Returns:** 

If the database contains more entries, the return value will be non-NULL. The returned pointer should not be freed by the calling routine.

The alias names of said network are contained in the s\_aliases member as a NULL-terminated list, and this structure entry will never be NULL.

If no additional network is found or an error occurs, the return value will be NULL.

See Also: setservent, endservent, getservbyname, getservbyport

Classification: POSIX 1003.1

**Systems:** Linux Synopsis: #include <graph.h>

short \_FAR \_gettextcolor( void );

**Description:** The \_gettextcolor function returns the pixel value of the current text color. This is the color used

for displaying text with the  $\_\mathtt{outtext}$  and  $\_\mathtt{outmem}$  functions. The default text color value is set to

7 whenever a new video mode is selected.

**Returns:** The \_gettextcolor function returns the pixel value of the current text color.

See Also: \_settextcolor, \_setcolor, \_outtext, \_outmem

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    int old_col;
    long old_bk;

    _setvideomode( _TEXTC80 );
    old_col = _gettextcolor();
    old_bk = _getbkcolor();
    _settextcolor( 7 );
    _setbkcolor( _BLUE );
    _outtext( " WATCOM \nGraphics" );
    _settextcolor( old_col );
    _setbkcolor( old_bk );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

**Classification:** PC Graphics

Systems: DOS

**Synopsis:** #include <graph.h> short \_FAR \_gettextcursor( void );

**Description:** The \_gettextcursor function returns the current cursor attribute, or shape. The cursor shape is set

with the \_settextcursor function. See the \_settextcursor function for a description of the

value returned by the \_gettextcursor function.

**Returns:** The \_gettextcursor function returns the current cursor shape when successful; otherwise, (-1) is

returned.

See Also: \_settextcursor, \_displaycursor

**Example:** #include <conio.h>

```
#include <graph.h>
main()
    int old_shape;
    old_shape = _gettextcursor();
    _settextcursor( 0x0007 );
    _outtext( "\nBlock cursor" );
    getch();
    _settextcursor( 0x0407 );
    _outtext( "\nHalf height cursor" );
    getch();
    \_settextcursor( 0x2000 );
    _outtext( "\nNo cursor" );
    getch();
    _settextcursor( old_shape );
}
```

Classification: PC Graphics

**Systems:** DOS

**Description:** The \_gettextextent function simulates the effect of using the \_grtext function to display the text string *text* at the position (x,y), using the current text settings. The concatenation point is returned in the argument *concat*. The text extent parallelogram is returned in the array *extent*.

The concatenation point is the position to use to output text after the given string. The text extent parallelogram outlines the area where the text string would be displayed. The four points are returned in counter-clockwise order, starting at the upper-left corner.

**Returns:** The \_gettextextent function does not return a value.

**See Also:** \_grtext, \_gettextsettings

Example: #include <conio.h>
#include <graph.h>

```
main()
{
    struct xycoord concat;
    struct xycoord extent[ 4 ];

    _setvideomode( _VRES16COLOR );
    _grtext( 100, 100, "hot" );
    _gettextextent( 100, 100, "hot", &concat, extent );
    _polygon( _GBORDER, 4, extent );
    _grtext( concat.xcoord, concat.ycoord, "dog" );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

DOS **Systems:** 

Synopsis: #include <graph.h>

struct rccoord \_FAR \_gettextposition( void );

**Description:** The \_gettextposition function returns the current output position for text. This position is in

terms of characters, not pixels.

The current position defaults to the top left corner of the screen, (1,1), when a new video mode is selected. It is changed by successful calls to the \_outtext, \_outmem, \_settextposition and

\_settextwindow functions.

Note that the output position for graphics output differs from that for text output. The output position for graphics output can be set by use of the \_moveto function.

**Returns:** The \_gettextposition function returns, as an rccoord structure, the current output position for

text.

See Also: \_outtext, \_outmem, \_settextposition, \_settextwindow, \_moveto

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    struct rccoord old_pos;

    _setvideomode( _TEXTC80 );
    old_pos = _gettextposition();
    _settextposition( 10, 40 );
    _outtext( "WATCOM Graphics" );
    _settextposition( old_pos.row, old_pos.col );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

**Classification:** PC Graphics

Systems: DOS

```
Synopsis:
                 #include <graph.h>
                 struct textsettings _FAR * _FAR _gettextsettings
    ( struct textsettings _FAR *settings );
```

is displayed by the \_grtext function. The information is stored in the textsettings structure

indicated by the argument settings. The structure contains the following fields (all are short fields):

The \_gettextsettings function returns information about the current text settings used when text

basevectorx x-component of the current base vector

basevectory y-component of the current base vector

path current text path

height current text height (in pixels)

width current text width (in pixels)

spacing current text spacing (in pixels)

horizalign horizontal component of the current text alignment

vertalign vertical component of the current text alignment

**Returns:** The \_gettextsettings function returns information about the current graphics text settings.

See Also: \_grtext, \_setcharsize, \_setcharspacing, \_settextalign, \_settextpath,

\_settextorient

**Example:** #include <conio.h> #include <graph.h>

```
main()
    struct textsettings ts;
    _setvideomode( _VRES16COLOR );
   _gettextsettings( &ts );
   _grtext( 100, 100, "WATCOM" );
   _setcharsize( 2 * ts.height, 2 * ts.width );
   _grtext( 100, 300, "Graphics" );
   _setcharsize( ts.height, ts.width );
    getch();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

}

**Systems:** DOS

**Description:** 

_gettextsettings			

```
Synopsis:
           #include <graph.h>
           void _FAR _gettextwindow(
                            short _FAR *row1, short _FAR *col1,
                            short _FAR *row2, short _FAR *col2 );
```

**Description:** The \_gettextwindow function returns the location of the current text window. A text window is defined with the \_settextwindow function. By default, the text window is the entire screen.

> The current text window is a rectangular area of the screen. Text display is restricted to be within this window. The top left corner of the text window is placed in the arguments (row1, col1). The bottom right corner of the text window is placed in (row2, col2).

**Returns:** The \_gettextwindow function returns the location of the current text window.

See Also: \_settextwindow, \_outtext, \_outmem, \_settextposition, \_scrolltextwindow

**Example:** #include <conio.h> #include <graph.h> #include <stdio.h> main() int i; short r1, c1, r2, c2; char buf[ 80 ]; \_setvideomode( \_TEXTC80 ); \_gettextwindow( &r1, &c1, &r2, &c2 ); \_settextwindow( 5, 20, 20, 40 ); for( $i = 1; i \le 20; ++i$ ) { sprintf( buf, "Line %d\n", i ); \_outtext( buf ); } getch(); \_settextwindow( r1, c1, r2, c2 );

\_setvideomode( \_DEFAULTMODE );

Classification: PC Graphics

}

**Systems:** DOS

## gettid

Synopsis: #include cess.h>

int gettid(void);

**Description:** The gettid function returns the thread id for the current thread on Linux systems. It provides a

wrapper around the appropriate kernel system call.

**Returns:** The gettid function returns the thread id for the current thread.

See Also: getpid

**Classification:** WATCOM

**Systems:** Linux

```
Synopsis:
             #include <unistd.h>
             uid_t getuid( void );
Description:
             The getuid function returns the user ID for the calling process.
Returns:
             The user ID for the calling process
See Also:
             geteuid, getgid, getegid
Example:
              \mbox{\scriptsize \star} Print the user ID of this process.
             #include <stdio.h>
             #include <unistd.h>
             int main( void )
                  printf( "My userid is %d\n", getuid() );
                  return(0);
```

Classification: POSIX 1003.1

**Systems:** Linux **Synopsis:** #include <graph.h>

**Description:** 

The \_getvideoconfig function returns information about the current video mode and the hardware configuration. The information is returned in the videoconfig structure indicated by the argument

config. The structure contains the following fields (all are short fields):

number of pixels in x-axis numxpixels

numypixels number of pixels in y-axis

number of text columns numtextcols

numtextrows number of text rows

number of actual colors numcolors

bitsperpixel number of bits in a pixel value

numvideopages number of video pages

current video mode mode

adapter adapter type

monitor monitor type

number of kilobytes (1024 characters) of video memory memory

The adapter field will contain one of the following values:

\_NODISPLAY no display adapter attached

\_UNKNOWN unknown adapter/monitor type

MDPAMonochrome Display/Printer Adapter

\_CGA Color Graphics Adapter

\_HERCULES Hercules Monochrome Adapter

\_MCGA Multi-Color Graphics Array

\_EGA Enhanced Graphics Adapter

 $_{\mathbf{VGA}}$ Video Graphics Array

\_SVGA SuperVGA Adapter The monitor field will contain one of the following values:

 $\_MONO$ regular monochrome

\_COLOR regular color

\_ENHANCED enhanced color

\_ANALOGMONO analog monochrome

\_ANALOGCOLOR analog color

The amount of memory reported by \_getvideoconfig will not always be correct for SuperVGA adapters. Since it is not always possible to determine the amount of memory, \_getvideoconfig will always report 256K, the minimum amount.

**Returns:** The \_getvideoconfig function returns information about the current video mode and the hardware

configuration.

See Also: \_setvideomode, \_setvideomoderows

```
Example:
           #include <conio.h>
           #include <graph.h>
           #include <stdio.h>
           #include <stdlib.h>
           main()
           {
                int mode;
               struct videoconfig vc;
               char buf[ 80 ];
               _getvideoconfig( &vc );
/* select "best" video mode */
                switch( vc.adapter ) {
               case \_VGA:
               case _SVGA :
                   mode = _VRES16COLOR;
                   break;
               case _MCGA :
                   mode = _MRES256COLOR;
                   break;
               case _EGA :
                    if( vc.monitor == _MONO ) {
                        mode = _ERESNOCOLOR;
                    } else {
                        mode = _ERESCOLOR;
                    }
                    break;
                case _CGA :
                   mode = \_MRES4COLOR;
                   break;
                case _HERCULES :
                    mode = _HERCMONO;
                    break;
                default :
                    puts( "No graphics adapter" );
                    exit(1);
                if( _setvideomode( mode ) ) {
                    _getvideoconfig( &vc );
                    sprintf(buf, "%d x %d x %d\n", vc.numxpixels,
                                      vc.numypixels, vc.numcolors );
                    _outtext( buf );
                    getch();
                    _setvideomode( _DEFAULTMODE );
           }
```

Classification: PC Graphics

Systems: DOS

_getvideoconfig		

```
Synopsis:
            #include <graph.h>
            struct xycoord _FAR _getviewcoord( short x, short y );
            struct xycoord _FAR _getviewcoord_w( double x, double y );
            struct xycoord _FAR _getviewcoord_wxy(
                                    struct _wxycoord _FAR *p );
Description:
            The _getviewcoord functions translate a point from one coordinate system to viewport coordinates.
            The \_getviewcoord function translates the point (x, y) from physical coordinates. The
            _getviewcoord_w and _getviewcoord_wxy functions translate the point from the window
            coordinate system.
            Viewport coordinates are defined by the _setvieworg and _setviewport functions. Window
            coordinates are defined by the _setwindow function.
            Note: In previous versions of the software, the _getviewcoord function was called
            _getlogcoord.
Returns:
            The _getviewcoord functions return the viewport coordinates, as an xycoord structure, of the
            given point.
See Also:
            _getphyscoord, _setvieworg, _setviewport, _setwindow
Example:
            #include <conio.h>
            #include <graph.h>
            #include <stdlib.h>
            main()
                 struct xycoord pos1, pos2;
                 _setvideomode( _VRES16COLOR );
                 _setvieworg( rand() % 640, rand() % 480 );
                 pos1 = _getviewcoord( 0, 0 );
                 pos2 = \_getviewcoord(639, 479);
                 _rectangle( _GBORDER, posl.xcoord, posl.ycoord,
                                           pos2.xcoord, pos2.ycoord);
                 qetch();
                 _setvideomode( _DEFAULTMODE );
            }
Classification: PC Graphics
Systems:
            _getviewcoord - DOS
            _getviewcoord_w - DOS
```

\_getviewcoord\_wxy - DOS

_getviewcoord Functions

Synopsis: #include <graph.h>
short \_FAR \_getvisualpage( void );

**Description:** The \_getvisualpage function returns the number of the currently selected visual graphics page.

Only some combinations of video modes and hardware allow multiple pages of graphics to exist. When multiple pages are supported, the active page may differ from the visual page. The graphics information in the visual page determines what is displayed upon the screen. Animation may be accomplished by alternating the visual page. A graphics page can be constructed without affecting the screen by setting the active page to be different than the visual page.

The number of available video pages can be determined by using the  $\_getvideoconfig$  function. The default video page is 0.

**Returns:** The \_getvisualpage function returns the number of the currently selected visual graphics page.

See Also: \_\_setvisualpage, \_setactivepage, \_getactivepage, \_getvideoconfig

Example: #include <conio.h>
#include <graph.h>

```
main()
    int old_apage;
    int old_vpage;
    _setvideomode( _HRES16COLOR );
    old_apage = _getactivepage();
    old_vpage = _getvisualpage();
    /* draw an ellipse on page 0 */
    _setactivepage(0);
    _setvisualpage( 0 );
    _ellipse( _GFILLINTERIOR, 100, 50, 540, 150 );
    /* draw a rectangle on page 1 */
    _setactivepage(1);
    _rectangle( _GFILLINTERIOR, 100, 50, 540, 150 );
    getch();
    /* display page 1 */
    _setvisualpage(1);
    getch();
    _setactivepage( old_apage );
    _setvisualpage( old_vpage );
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: DOS

		_getvisualpage

Synopsis: #include <stdio.h>
 int \_getw( int binint, FILE \*fp );

**Description:** The \_getw function reads a binary value of type *int* from the current position of the stream *fp* and

increments the associated file pointer to point to the next unread character in the input stream. \_getw

does not assume any special alignment of items in the stream.

\_getw is provided primarily for compatibility with previous libraries. Portability problems may occur with \_getw because the size of an *int* and the ordering of bytes within an *int* differ across systems.

**Returns:** The \_getw function returns the integer value read or, if a read error or end-of-file occurs, the error

indicator is set and  $\_$ getw returns EOF. Since EOF is a legitimate value to read from fp, use ferror

to verify that an error has occurred.

See Also: ferror, fgetc, fgetchar, fgets, fopen, getc, getchar, gets, \_putw, ungetc

Example: #include <stdio.h>

```
void main()
{
   FILE *fp;
   int c;

   fp = fopen( "file", "r" );
   if( fp != NULL ) {
     while( (c = _getw( fp )) != EOF )
        _putw( c, stdout );
     fclose( fp );
   }
}
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <graph.h> struct \_wxycoord \_FAR \_getwindowcoord( short x, short y );

**Description:** The \_getwindowcoord function returns the window coordinates of the position with view

coordinates (x, y). Window coordinates are defined by the \_setwindow function.

**Returns:** The \_getwindowcoord function returns the window coordinates, as a \_wxycoord structure, of the

given point.

See Also: \_setwindow, \_getviewcoord

**Example:** #include <conio.h>

```
#include <graph.h>
main()
    struct xycoord centre;
    struct _wxycoord pos1, pos2;
    /* draw a box 50 pixels square */
    /* in the middle of the screen */
    _setvideomode( _MAXRESMODE );
    centre = _getviewcoord_w( 0.5, 0.5 );
    pos1 = _getwindowcoord( centre.xcoord - 25,
                            centre.ycoord - 25 );
    pos2 = _getwindowcoord( centre.xcoord + 25,
                            centre.ycoord + 25 );
    _rectangle_wxy( _GBORDER, &pos1, &pos2 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

**Systems:** DOS

```
Synopsis:
              #include <time.h>
              struct tm * gmtime( const time_t *timer );
              struct tm *_gmtime( const time_t *timer,
                                       struct tm *tmbuf );
              struct tm {
                int tm_sec; /* seconds after the minute -- [0,61] */
                int tm_min; /* minutes after the hour -- [0,59] */
                int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
int tm_year; /* years since 1900 */
                int tm_wday; /* days since Sunday
                                                                        -- [0,6] */
                int tm_wday; /* days since Sunday -- [0,6] */
int tm_yday; /* days since January 1 -- [0,365]*/
                 int tm_isdst; /* Daylight Savings Time flag
Safer C:
              The Safer C Library extension provides the gmtime_s function which is a safer alternative to
              gmtime.
Description:
              The gmt ime functions convert the calendar time pointed to by timer into a broken-down time,
              expressed as Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time, or GMT).
              The function _gmtime places the converted time in the tm structure pointed to by tmbuf, and the
              gmtime function places the converted time in a static structure that is re-used each time gmtime is
              called.
              The time set on the computer with the DOS time command and the DOS date command reflects the
              local time. The environment variable TZ is used to establish the time zone to which this local time
              applies. See the section The TZ Environment Variable for a discussion of how to set the time zone.
Returns:
              The gmt ime functions return a pointer to a structure containing the broken-down time.
See Also:
              asctime Functions, asctime_s, clock, ctime Functions, ctime_s, difftime, gmtime_s,
              localtime, localtime_s, mktime, strftime, time, tzset
Example:
              #include <stdio.h>
              #include <time.h>
              void main()
                   time_t time_of_day;
                   auto char buf[26];
                   auto struct tm tmbuf;
                   time_of_day = time( NULL );
                   _gmtime( &time_of_day, &tmbuf );
                   printf( "It is now: %.24s GMT\n",
                              _asctime( &tmbuf, buf ) );
              }
              produces the following:
```

It is now: Fri Dec 25 15:58:27 1987 GMT

Classification: ISO C

**Systems:** gmtime - All, Linux, RDOS, Netware

\_gmtime - All, Linux, RDOS

```
Synopsis:
              #define __STDC_WANT_LIB_EXT1__ 1
              #include <time.h>
              struct tm * qmtime_s( const time_t * restrict timer,
                                           struct tm * restrict result );
              struct tm {
                 int tm_sec; /* seconds after the minute -- [0,61] */
                 int tm_min; /* minutes after the hour -- [0,59] */
                 int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
int tm_year; /* years since 1900 */
                 int tm_year; /* years since 1900 */
int tm_wday; /* days since Sunday -- [0,6] */
int tm_yday; /* days since January 1 -- [0,365]*/
                 int tm_isdst; /* Daylight Savings Time flag
Constraints:
              If any of the following runtime-constraints is violated, the currently active runtime-constraint handler
              will be invoked and gmtime_s will return a non-zero value to indicate an error, or the
              runtime-constraint handler aborts the program.
              Neither timer nor result shall be a null pointer. If there is a runtime-constraint violation, there is no
              attempt to convert the time.
Description:
              The gmtime_s function converts the calendar time pointed to by timer into a broken-down time,
              expressed as UTC. The broken-down time is stored in the structure pointed to by result.
Returns:
              The gmtime_s function returns result, or a null pointer if the specified time cannot be converted to
              UTC or there is a runtime-constraint violation.
See Also:
              asctime Functions, asctime_s, clock, ctime Functions, ctime_s, difftime, qmtime,
              localtime, localtime_s, mktime, strftime, time, tzset
Example:
              #define __STDC_WANT_LIB_EXT1__ 1
              #include <stdio.h>
              #include <time.h>
              void main()
                    time_t time_of_day;
                    auto char buf[26];
                    auto struct tm tmbuf;
                    time_of_day = time( NULL );
                    gmtime_s( &time_of_day, &tmbuf );
                    asctime_s( buf, sizeof( buf ), &tmbuf );
                    printf( "It is now: %.24s GMT\n", buf );
              produces the following:
              It is now: Thu Jan 31 15:12:27 2006 GMT
```

Classification: TR 24731

**Systems:** DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware **Synopsis:** #include <stdio.h> int \_grow\_handles( int new\_count );

## **Description:**

The \_grow\_handles function increases the number of POSIX level files that are allowed to be open at one time. The parameter new\_count is the new requested number of files that are allowed to be opened. The return value is the number that is allowed to be opened after the call. This may be less than, equal to, or greater than the number requested. If the number is less than, an error has occurred and the errno variable should be consulted for the reason. If the number returned is greater than or equal to the number requested, the call was successful.

Note that even if \_grow\_handles returns successfully, you still might not be able to open the requested number of files due to some system limit (e.g. FILES= in the CONFIG.SYS file under DOS) or because some file handles are already in use (stdin, stdout, stderr, etc.).

The number of file handles that the run-time system can open by default is described by \_NFILES in <stdio.h> but this can be changed by the application developer. To change the number of file handles available during execution, follow the steps outlined below.

- Let n represent the number of files to be opened concurrently. Ensure that the stdin, stdout, and stderr files are included in the count. Also include stdaux and stdprn files in the count for some versions of DOS. The *stdaux* and *stdprn* files are not available for Win32.
- For DOS-based systems, change the CONFIG.SYS file to include "FILES=n" where "n" is the number of file handles required by the application plus an additional 5 handles for the standard files. The number of standard files that are opened by DOS varies from 3 to 5 depending on the version of DOS that you are using.

If you are running a network such as Novell's NetWare, this will also affect the number of available file handles. In this case, you may have to increase the number specified in the "FILES=n" statement.

Add a call to \_grow\_handles in your application similar to that shown in the example below.

## **Returns:**

The \_grow\_handles function returns the maximum number of file handles which the run-time system can accommodate. This number can exceed an operating system limit such as that imposed by the "FILES=" statement under DOS. This limit will be the determining factor in how many files can be open concurrently.

**Errors:** When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also: \_dos\_open, fdopen, fileno, fopen, freopen, \_fsopen, \_hdopen, open, \_open\_osfhandle, \_popen, \_sopen, tmpfile

**Example:** 

```
FILE *fp[ 50 ];
void main()
    int hndl_count;
    int i;
```

#include <stdio.h>

```
hndl_count = _NFILES;
if( hndl_count < 50 ) {</pre>
    hndl_count = _grow_handles( 50 );
for( i = 0; i < hndl_count; i++ ) {</pre>
  fp[ i ] = tmpfile();
  if( fp[ i ] == NULL ) break;
  printf( "File %d successfully opened\n", i );
printf( "%d files were successfully opened\n", i );
```

**Classification:** WATCOM

**Systems:** All, Linux **Description:** The \_grstatus function returns the status of the most recently called graphics library function. The

function can be called after any graphics function to determine if any errors or warnings occurred. The function returns 0 if the previous function was successful. Values less than 0 indicate an error occurred;

values greater than 0 indicate a warning condition.

The following values can be returned:

```
Constant
                       Value Explanation
                         0
_GROK
                            no error
                        -1 graphics error
_GRERROR
_GRMODENOTSUPPORTED
                        -2 video mode not supported
                        -3 function n/a in this mode
GRNOTINPROPERMODE
_GRINVALIDPARAMETER -4 invalid parameter(s)
_GRINSUFFICIENTMEMORY -5
_GRFONTFILENOTFOUND -6
_GRINVALIDFONTFILE -7
                              out of memory
                              can't open font file
                              font file has invalid format
_GRNOOUTPUT
                         1
                              nothing was done
_GRCLIPPED
                              output clipped
```

**Returns:** The \_grstatus function returns the status of the most recently called graphics library function.

```
Example: #include <conio.h>
```

```
#include <graph.h>
#include <stdlib.h>

main()
{
    int x, y;

    _setvideomode( _VRES16COLOR );
    while( _grstatus() == _GROK ) {
        x = rand() % 700;
        y = rand() % 500;
        _setpixel( x, y );
    }
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: DOS

_grstatus

### **Synopsis:**

```
#include <graph.h>
short _FAR _grtext( short x, short y,
                    char _FAR *text );
short _FAR _grtext_w( double x, double y,
                      char _FAR *text );
```

## **Description:**

The \_grtext functions display a character string. The \_grtext function uses the view coordinate system. The \_grtext\_w function uses the window coordinate system.

The character string *text* is displayed at the point (x, y). The string must be terminated by a null character ('\0'). The text is displayed in the current color using the current text settings.

The graphics library can display text in three different ways.

- The \_outtext and \_outmem functions can be used in any video mode. However, this variety of text can be displayed in only one size.
- The \_grtext function displays text as a sequence of line segments, and can be drawn in different sizes, with different orientations and alignments.
- The \_outgtext function displays text in the currently selected font. Both bit-mapped and vector fonts are supported; the size and type of text depends on the fonts that are available.

#### **Returns:**

The \_grtext functions return a non-zero value when the text was successfully drawn; otherwise, zero is returned.

#### See Also:

\_outtext, \_outmem, \_outgtext, \_setcharsize, \_settextalign, \_settextpath, \_settextorient, \_setcharspacing

## **Example:**

```
#include <conio.h>
#include <graph.h>
main()
    _setvideomode( _VRES16COLOR );
    _grtext( 200, 100, " WATCOM" );
    _grtext( 200, 200, "Graphics" );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:

WATCOM

Graphics

Classification: PC Graphics

\_grtext - DOS \_grtext\_w - DOS **Systems:** 

Synopsis: #include <malloc.h>
 void \_\_huge \*halloc( long int numb, size\_t size );

**Description:** The halloc function allocates space for an array of *numb* objects of *size* bytes each and initializes

each object to 0. When the size of the array is greater than 64K bytes, then the size of an array element

must be a power of 2 since an object could straddle a segment boundary.

**Returns:** The halloc function returns a far pointer (of type void huge \*) to the start of the allocated

memory. The NULL value is returned if there is insufficient memory available. The NULL value is also returned if the size of the array is greater than 64K bytes and the size of an array element is not a power

of 2.

See Also: calloc Functions, \_expand Functions, free Functions, hfree, malloc Functions, \_msize

Functions, realloc Functions, sbrk

Example: #include <stdio.h>
#include <malloc.h>

**Classification:** WATCOM

**Systems:** DOS/16, Windows, OS/2 1.x(all)

```
Synopsis:
            #include <dos.h>
```

```
void _harderr( int (__far *handler)() );
void _hardresume( int action );
void _hardretn( int error );
```

## **Description:**

The \_harderr routine installs a critical error handler (for INT 0x24) to handle hardware errors. This critical error handler will call the user-defined function specified by handler when a critical error occurs (for example, attempting to open a file on a floppy disk when the drive door is open). The parameters to this function are as follows:

```
int handler (unsigned deverror,
             unsigned errcode,
             unsigned __far *devhdr );
```

The low-order byte of *errcode* can be one of the following values:

Value	Meaning
0x00	Attempt to write to a write-protected disk
0x01	Unknown unit
0x02	Drive not ready
0x03	Unknown command
0x04	CRC error in data
0x05	Bad drive-request structure length
0x06	Seek error
0x07	Unknown media type
0x08	Sector not found
0x09	Printer out of paper
$\theta x \theta A$	Write fault
$\theta x \theta B$	Read fault
0x0C	General failure

The devhdr argument points to a device header control-block that contains information about the device on which the error occurred. Your error handler may inspect the information in this control-block but must not change it.

If the error occurred on a disk device, bit 15 of the deverror argument will be 0 and the deverror argument will indicate the following:

Bit	Meaning	
bit 15	0 indicates	disk error
bit 14	not used	
bit 13	0 indicates	"Ignore" response not allowed
bit 12		"Retry" response not allowed
bit 11		"Fail" response not allowed
bit 9,10	location of error	
	Value	Meaning
	00	MS-DOS
	01	File Allocation Table (FAT)

10 Directory11 Data area

bit 8 0 indicates read error, 1 indicates write error

The low-order byte of *deverror* indicates the drive where the error occurred; (0 = drive A, 1 = drive B, etc.).

The handler is very restricted in the type of system calls that it can perform. System calls 0x01 through 0x0C, and 0x59 are the only system calls allowed to be issued by the handler. Therefore, many of the standard C run-time functions such as stream I/O and low-level I/O cannot be used by the handler. Console I/O is allowed (e.g., cprintf, cputs).

The handler must indicate what action to take by returning one of the following values or calling \_hardresume with one of the following values:

Value	Meaning
_HARDERR_IGNORE	Ignore the error
_HARDERR_RETRY	Retry the operation
_HARDERR_ABORT	Abort the program issuing INT 0x23
_HARDERR_FAIL	Fail the system call that is in progress (DOS 3.0 or higher)

Alternatively, the handler can return directly to the application program rather than returning to DOS by using the \_hardretn function. The application program resumes at the point just after the failing I/O function request. The \_hardretn function should be called only from within a user-defined hardware error-handler function.

The *error* argument of \_hardretn should be a DOS error code. See *The MS-DOS Encyclopedia* or *Programmer's PC Sourcebook, 2nd Edition,* for more detailed information on DOS error codes that may be returned by a given DOS function call.

If the failing I/O function request is an INT 0x21 function greater than or equal to function 0x38, \_hardretn will return to the application with the carry flag set and the AX register set to the \_hardretn error argument. If the failing INT 0x21 function request is less than function 0x38 abd the function can return an error, the AL register will be set to 0xFF on return to the application. If the failing INT 0x21 function does not have a way of returning an error condition (which is true of certain INT 0x21 functions below 0x38), the error argument of \_hardretn is not used, and no error code is returned to the application.

**Returns:** These functions do not return a value. The \_hardresume and \_hardretn functions do not return to the caller.

See Also: \_\_chain\_intr, \_dos\_getvect, \_dos\_setvect

**Example:** 

```
#include <stdio.h>
           #include <conio.h>
           #include <dos.h>
           #if defined(__DOS__) && defined(__386__)
               #define FAR ___far
           #else
               #if defined(__386__)
                   #define FAR
               #else
                   #define FAR ___far
               #endif
           #endif
           int FAR critical_error_handler( unsigned deverr,
                                             unsigned errcode,
                                             unsigned FAR *devhdr )
             {
               cprintf( "Critical error: " );
               cprintf( "deverr=%4.4X errcode=%d\r\n",
                         deverr, errcode );
               cprintf( "devhdr = %Fp\r\n", devhdr );
               return ( _HARDERR_IGNORE );
             }
           main()
               FILE *fp;
               _harderr( critical_error_handler );
               fp = fopen( "a:tmp.tmp", "r" );
               printf( "fp = p\n", fp );
           produces the following:
           Critical error: deverr=1A00 errcode=2
           devhdr = 0070:01b6
           fp = 0000
Classification: DOS
           _harderr - DOS
           _hardresume - DOS
           _hardretn - DOS/16
```

**Systems:** 

```
Synopsis: #include <io.h>
    int _hdopen( int os_handle, int mode );
```

**Description:** The \_hdopen function takes a previously opened operating system file handle specified by os\_handle

and opened with access and sharing specified by *mode*, and creates a POSIX-style file handle.

**Returns:** The \_hdopen function returns the new POSIX-style file handle if successful. Otherwise, it returns -1.

See Also: close, \_dos\_open, fdopen, fopen, freopen, \_fsopen, \_grow\_handles, open,

\_open\_osfhandle, \_os\_handle, \_popen, \_sopen

```
Example:
           #include <stdio.h>
           #include <dos.h>
           #include <fcntl.h>
           #include <io.h>
           #include <windows.h>
           void main()
             {
               HANDLE os_handle;
               DWORD desired_access, share_mode;
               int handle;
               os_handle = CreateFileA( "file", GENERIC_WRITE,
                                      O, NULL, CREATE_ALWAYS,
                                      FILE_ATTRIBUTE_NORMAL, NULL );
               if( os_handle == INVALID_HANDLE_VALUE ) {
                   printf( "Unable to open file\n" );
               } else {
                   handle = _hdopen( os_handle, O_RDONLY );
                   if (handle !=-1) {
                       write( handle, "hello\n", 6 );
                       close( handle );
                   } else {
                       CloseHandle( os_handle );
               }
```

**Classification:** WATCOM

**Systems:** All, Linux, Netware

### **Synopsis:**

```
#include <malloc.h>
int _heapchk( void );
int _bheapchk( __segment seg );
int _fheapchk( void );
int _nheapchk( void );
```

## **Description:**

The \_heapchk functions along with \_heapset and \_heapwalk are provided for debugging heap related problems in programs.

The \_heapchk functions perform a consistency check on the unallocated memory space or "heap". The consistency check determines whether all the heap entries are valid. Each function checks a particular heap, as listed below:

Function	Heap Checked
_heapchk	Depends on data model of the program
_bheapchk	Based heap specified by seg value; _NULLSEG specifies all based heaps
_fheapchk	Far heap (outside the default data segment)
_nheapchk	Near heap (inside the default data segment)

In a small data memory model, the \_heapchk function is equivalent to the \_nheapchk function; in a large data memory model, the \_heapchk function is equivalent to the \_fheapchk function.

## **Returns:**

Constant

All four functions return one of the following manifest constants which are defined in <malloc.h>.

```
The heap appears to be consistent.
            _HEAPOK
            _HEAPEMPTY
                             The heap is empty.
            _HEAPBADBEGIN The heap has been damaged.
            _HEAPBADNODE The heap contains a bad node, or is damaged.
See Also:
            _heapenable, _heapgrow, _heapmin, _heapset, _heapshrink, _heapwalk
Example:
            #include <stdio.h>
            #include <malloc.h>
            void main()
                 char *buffer;
```

Meaning

```
buffer = (char *)malloc( 80 );
               malloc( 1024 );
               free( buffer );
               switch( _heapchk() ) {
               case _HEAPOK:
                 printf( "OK - heap is good\n" );
                 break;
               case _HEAPEMPTY:
                 printf( "OK - heap is empty\n" );
               case _HEAPBADBEGIN:
                 printf( "ERROR - heap is damaged\n" );
                 break;
               case _HEAPBADNODE:
                 printf( "ERROR - bad node in heap\n" );
                 break;
             }
Classification: WATCOM
Systems:
           _heapchk - All, Linux, RDOS
           _bheapchk - DOS/16, Windows, OS/2 1.x(all)
           _fheapchk - DOS/16, Windows, OS/2 1.x(all)
           _nheapchk - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
           OS/2-32, Linux, RDOS
```

**Synopsis:** #include <malloc.h> int \_heapenable( int enabled );

**Description:** 

The \_heapenable function is used to control attempts by the heap allocation manager to request more memory from the operating system's memory pool. If enabled is 0 then all further allocations which would normally go to the operating system for more memory will instead fail and return NULL. If enabled is 1 then requests for more memory from the operating system's memory pool are re-enabled.

This function can be used to impose a limit on the amount of system memory that is allocated by an application. For example, if an application wishes to allocate no more than 200K bytes of memory, it could allocate 200K and immediately free it. It can then call \_heapenable to disable any further requests from the system memory pool. After this, the application can allocate memory from the 200K pool that it has already obtained.

**Returns:** The return value is the previous state of the system allocation flag.

See Also: \_heapchk, \_heapgrow, \_heapmin, \_heapset, \_heapshrink, \_heapwalk

**Example:** 

```
#include <stdio.h>
#include <malloc.h>
void main()
  {
   char *p;
   p = malloc(200*1024);
   if( p != NULL ) free( p );
   _heapenable(0);
      allocate memory from a pool that
      has been capped at 200K
  }
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS

```
Synopsis: #include <malloc.h>
     void _heapgrow( void );
     void _nheapgrow( void );
     void _fheapgrow( void );
```

**Description:** 

The \_nheapgrow function attempts to grow the near heap to the maximum size of 64K. You will want to do this in the small data models if you are using both malloc and \_fmalloc or halloc. Once a call to \_fmalloc or halloc has been made, you may not be able to allocate any memory with malloc unless space has been reserved for the near heap using either malloc, sbrk or \_nheapgrow.

The \_fheapgrow function doesn't do anything to the heap because the far heap will be extended automatically when needed. If the current far heap cannot be extended, then another far heap will be started.

In a small data memory model, the \_heapgrow function is equivalent to the \_nheapgrow function; in a large data memory model, the \_heapgrow function is equivalent to the \_fheapgrow function.

**Returns:** These functions do not return a value.

#include <stdio.h>

See Also: \_heapchk, \_heapenable, \_heapmin, \_heapset, \_heapshrink, \_heapwalk

```
Example:
```

```
#include <malloc.h>

void main()
{
    char *p, *fmt_string;
    fmt_string = "Amount of memory available is %u\n";
    printf( fmt_string, _memavl() );
    _nheapgrow();
    printf( fmt_string, _memavl() );
    p = (char *) malloc( 2000 );
    printf( fmt_string, _memavl() );
}
```

produces the following:

```
Amount of memory available is 0
Amount of memory available is 62732
Amount of memory available is 60730
```

**Classification:** WATCOM

```
Systems:
```

```
_heapgrow - All, Linux, RDOS
_fheapgrow - DOS/16, Windows, OS/2 1.x(all)
_nheapgrow - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

_heapgrow Functions

## Synopsis:

```
#include <malloc.h>
int _heapmin( void );
int _bheapmin( __segment seg );
int _fheapmin( void );
int _nheapmin( void );
```

## **Description:**

The \_heapmin functions attempt to shrink the specified heap to its smallest possible size by returning all free entries at the end of the heap back to the system. This can be used to free up as much memory as possible before using the system function or one of the spawn... functions.

The various \_heapmin functions shrink the following heaps:

Function	Heap Minimized
_heapmin	Depends on data model of the program
_bheapmin	Based heap specified by seg value; _NULLSEG specifies all based heaps
_fheapmin	Far heap (outside the default data segment)
_nheapmin	Near heap (inside the default data segment)

In a small data memory model, the \_heapmin function is equivalent to the \_nheapmin function; in a large data memory model, the \_heapmin function is equivalent to the \_fheapmin function.

Any function from \_heapmin group is identical to the appropriate function from \_heapshrink group.

**Returns:** These functions return zero if successful, and non-zero if some error occurred.

See Also: \_heapchk, \_heapenable, \_heapgrow, \_heapset, \_heapshrink, \_heapwalk

### **Example:**

```
#include <stdlib.h>
#include <malloc.h>

void main()
{
    _heapmin();
    system( "chdir c:\\watcomc" );
}
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

### **Classification:** WATCOM

## **Systems:**

```
_heapmin - All, Linux, RDOS
_bheapmin - DOS/16, Windows, OS/2 1.x(all)
_fheapmin - DOS/16, Windows, OS/2 1.x(all)
_nheapmin - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

_heapmin Functions

## Synopsis: #include <malloc.h>

```
int _heapset( unsigned int fill_char );
int _bheapset( __segment seg, unsigned int fill_char );
int _fheapset( unsigned int fill_char );
int _nheapset( unsigned int fill_char );
```

## **Description:**

The \_heapset functions along with \_heapchk and \_heapwalk are provided for debugging heap related problems in programs.

The \_heapset functions perform a consistency check on the unallocated memory space or "heap" just as \_heapchk does, and sets the heap's free entries with the *fill\_char* value.

Each function checks and sets a particular heap, as listed below:

Heap Filled
Depends on data model of the program
Based heap specified by seg value; _NULLSEG specifies all based heaps
Far heap (outside the default data segment)
Near heap (inside the default data segment)

In a small data memory model, the \_heapset function is equivalent to the \_nheapset function; in a large data memory model, the \_heapset function is equivalent to the \_fheapset function.

# **Returns:**

See Also:

The \_heapset functions return one of the following manifest constants which are defined in <malloc.h>.

\_heapchk, \_heapenable, \_heapgrow, \_heapmin, \_heapshrink, \_heapwalk

```
Constant Meaning
```

**\_HEAPOK** The heap appears to be consistent.

**\_HEAPEMPTY** The heap is empty.

\_HEAPBADBEGIN The heap has been damaged.

**\_HEAPBADNODE** The heap contains a bad node, or is damaged.

```
Example: #include <stdio.h> #include <malloc.h>
```

```
void main()
    {
      int heap_status;
      char *buffer;
```

```
buffer = (char *) malloc(80);
               malloc( 1024 );
               free( buffer );
               heap\_status = \_heapset( 0xff );
               switch( heap_status ) {
               case _HEAPOK:
                 printf( "OK - heap is good\n" );
                 break;
               case _HEAPEMPTY:
                 printf( "OK - heap is empty\n" );
                 break;
               case _HEAPBADBEGIN:
                 printf( "ERROR - heap is damaged\n" );
               case _HEAPBADNODE:
                 printf( "ERROR - bad node in heap\n" );
                 break;
               }
             }
Classification: WATCOM
          _heapset - All, Linux, RDOS
          _bheapset - DOS/16, Windows, OS/2 1.x(all)
          _fheapset - DOS/16, Windows, OS/2 1.x(all)
           _nheapset - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
```

**Systems:** 

OS/2-32, Linux, RDOS

## Synopsis: #include <malloc.h>

```
int _heapshrink( void );
int _bheapshrink( __segment seg );
int _fheapshrink( void );
int _nheapshrink( void );
```

### **Description:**

The \_heapshrink functions attempt to shrink the heap to its smallest possible size by returning all free entries at the end of the heap back to the system. This can be used to free up as much memory as possible before using the system function or one of the spawn... functions.

The various \_heapshrink functions shrink the following heaps:

Function	Heap Shrinked
_heapshrink	Depends on data model of the program
_bheapshrink	Based heap specified by seg value; _NULLSEG specifies all based heaps
_fheapshrink	Far heap (outside the default data segment)
_nheapshrink	Near heap (inside the default data segment)

In a small data memory model, the \_heapshrink function is equivalent to the \_nheapshrink function; in a large data memory model, the \_heapshrink function is equivalent to the \_fheapshrink function.

Any function from \_heapshrink group is identical to the appropriate function from \_heapmin group.

**Returns:** These functions return zero if successful, and non-zero if some error occurred.

See Also: \_heapchk, \_heapenable, \_heapgrow, \_heapmin, \_heapset, \_heapwalk

### Example:

```
#include <stdlib.h>
#include <malloc.h>

void main()
{
    _heapshrink();
    system( "chdir c:\\watcomc" );
}
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

### **Classification:** WATCOM

```
Systems: _heapshrink - All, Linux, RDOS
```

```
_bheapshrink - DOS/16, Windows, OS/2 1.x(all)
_fheapshrink - DOS/16, Windows, OS/2 1.x(all)
_nheapshrink - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

_heapshrink Functions

### **Synopsis:**

## **Description:**

The \_heapwalk functions along with \_heapchk and \_heapset are provided for debugging heap related problems in programs.

The \_heapwalk functions walk through the heap, one entry per call, updating the \_heapinfo structure with information on the next heap entry. The structure is defined in <malloc.h>. You must initialize the \_pentry field with NULL to start the walk through the heap.

Each function walks a particular heap, as listed below:

\*\*\* \*\* \*

Function	Heap Walked
_heapwalk	Depends on data model of the program
_bheapwalk	Based heap specified by $seg$ value; _NULLSEG specifies all based heaps
_fheapwalk	Far heap (outside the default data segment)
_nheapwalk	Near heap (inside the default data segment)

In a small data memory model, the \_heapwalk function is equivalent to the \_nheapwalk function; in a large data memory model, the \_heapwalk function is equivalent to the \_fheapwalk function.

### **Returns:**

These functions return one of the following manifest constants which are defined in <malloc.h>.

Constant	Meaning			
_HEAPOK	The heap is $OK$ so far, and the $\_$ heapinfo structure contains information about the next entry in the heap.			
_HEAPEMPTY	The heap is empty.			
_HEAPBADPTR	The _pentry field of the <i>entry</i> structure does not contain a valid pointer into the heap.			
_HEAPBADBEGIN The header information for the heap was not found or has been damaged.				
_HEAPBADNODE	The heap contains a bad node, or is damaged.			

The end of the heap was reached successfully.

\_HEAPEND

```
See Also:
           _heapchk, _heapenable, _heapgrow, _heapmin, _heapset, _heapshrink
Example:
           #include <stdio.h>
           #include <malloc.h>
           heap_dump()
             {
               struct _heapinfo h_info;
               int heap_status;
               h_info._pentry = NULL;
               for(;;) {
                 heap_status = _heapwalk( &h_info );
                 if( heap_status != _HEAPOK ) break;
                 printf( " %s block at %Fp of size %4.4X\n",
                    (h_info._useflag == _USEDENTRY ? "USED" : "FREE"),
                   h_info._pentry, h_info._size );
               switch( heap_status ) {
               case _HEAPEND:
                 printf( "OK - end of heap\n" );
                 break;
               case _HEAPEMPTY:
                 printf( "OK - heap is empty\n" );
                 break;
               case _HEAPBADBEGIN:
                 printf( "ERROR - heap is damaged\n" );
               case _HEAPBADPTR:
                 printf( "ERROR - bad pointer to heap\n" );
                 break;
               case _HEAPBADNODE:
                 printf( "ERROR - bad node in heap\n" );
             }
           void main()
             {
               char *p;
                             p = (char *) malloc(80);
               heap_dump();
                              free(p);
               heap_dump();
               heap_dump();
             }
           produces the following:
           On 16-bit 80x86 systems, the following output is produced:
           OK - heap is empty
             USED block at 23f8:0ab6 of size 0202
             USED block at 23f8:0cb8 of size 0052
             FREE block at 23f8:0d0a of size 1DA2
           OK - end of heap
             USED block at 23f8:0ab6 of size 0202
             FREE block at 23f8:0cb8 of size 1DF4
           OK - end of heap
```

# On 32-bit 80386/486 systems, the following output is produced:

```
OK - heap is empty
USED block at 0014:00002a7c of size 0204
USED block at 0014:00002c80 of size 0054
FREE block at 0014:00002cd4 of size 1D98
OK - end of heap
USED block at 0014:00002a7c of size 0204
FREE block at 0014:00002c80 of size 1DEC
OK - end of heap
```

## **Classification:** WATCOM

```
Systems: _heapwalk - All, Linux, RDOS
_bheapwalk - DOS/16, Windows, OS/2 1.x(all)
_fheapwalk - DOS/16, Windows, OS/2 1.x(all)
_nheapwalk - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

**Synopsis:** #include <malloc.h> void hfree( void \_\_huge \*ptr );

**Description:** The hfree function deallocates a memory block previously allocated by the halloc function. The

argument ptr points to a memory block to be deallocated. After the call, the freed block is available for

allocation.

**Returns:** The hfree function returns no value.

See Also: calloc Functions, \_expand Functions, free Functions, halloc, malloc Functions, \_msize

Functions, realloc Functions, sbrk

**Example:** #include <stdio.h>

```
#include <malloc.h>
void main()
    long int __huge *big_buffer;
   big_buffer = (long int __huge *)
                  halloc( 1024L, sizeof(long) );
    if( big_buffer == NULL ) {
      printf( "Unable to allocate memory\n" );
    } else {
      /* rest of code goes here */
      hfree( big_buffer ); /* deallocate */
  }
```

**Classification: WATCOM** 

**Systems:** DOS/16, Windows, OS/2 1.x(all) Synopsis: #include <math.h>

double hypot ( double x, double y );

**Description:** 

The hypot function computes the length of the hypotenuse of a right triangle whose sides are x and y adjacent to that right angle. The calculation is equivalent to

```
sqrt(x*x + y*y)
```

The computation may cause an overflow, in which case the matherr function will be invoked.

**Returns:** 

The value of the hypotenuse is returned. When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Example:** 

```
#include <stdio.h>
#include <math.h>

void main()
{
    printf( "%f\n", hypot( 3.0, 4.0 ) );
}
```

produces the following:

5.000000

**Classification: WATCOM** 

**Systems:** Math

```
#define __STDC_WANT_LIB_EXT1__ 1
Synopsis:
            #include <stdlib.h>
            void ignore_handler_s(
                     const char * restrict msg,
                     void * restrict ptr,
                     errno_t error );
Description:
            A pointer to the ignore_handler_s function may be passed as an argument to the
            set_constraint_handler_s function. The ignore_handler_s function simply returns to
            its caller.
Returns:
            The ignore_handler_s function does not returns no value.
See Also:
            abort_handler_s, set_constraint_handler_s
Example:
            #define ___STDC_WANT_LIB_EXT1__ 1
            #include <stdlib.h>
            #include <stdio.h>
            void main( void )
                constraint_handler_t old_handler;
                old_handler =
                     set_constraint_handler_s( ignore_handler_s );
                if( getenv_s( NULL, NULL, 0, NULL ) ) {
                     printf( "getenv_s failed\n" );
                set_constraint_handler_s( old_handler );
            }
            produces the following:
            getenv_s failed
Classification: TR 24731
Systems:
            All, Linux, RDOS, Netware
```

Synopsis: #include <math.h>

int ilogb( double x );

**Description:** The ilogb function returns the exponent portion of the argument x as an int.

**Returns:** If successful, the return value is the exponent of x. When the argument is zero, the function returns

FP\_ILOGBO. When the argument is not-a-number, or NAN, the function returns FP\_ILOGBNAN. For

positive or negative infinity, the function returns INT\_MAX.

See Also: logb

Example: #include <stdio.h>
#include <math.h>

void main()
 {
 printf( "%d\n", ilogb( 1024.0 ) );
}

produces the following:

10

Classification: ISO C99

**Systems:** Math

```
Synopsis:
            #include <graph.h>
            long _FAR _imagesize( short x1, short y1,
                                     short x2, short y2);
            long _FAR _imagesize_w( double x1, double y1,
                                        double x2, double y2);
            long _FAR _imagesize_wxy( struct _wxycoord _FAR *p1,
                                          struct _wxycoord _FAR *p2 );
Description:
            The _imagesize functions compute the number of bytes required to store a screen image. The
            _imagesize function uses the view coordinate system. The _imagesize_w and
            _imagesize_wxy functions use the window coordinate system.
            The screen image is the rectangular area defined by the points (x1, y1) and (x2, y2). The storage
            area used by the _getimage functions must be at least this large (in bytes).
Returns:
            The _imagesize functions return the size of a screen image.
See Also:
            _getimage, _putimage
Example:
            #include <conio.h>
            #include <graph.h>
            #include <malloc.h>
            main()
                char *buf;
                int y;
                _setvideomode( _VRES16COLOR );
                _ellipse( _GFILLINTERIOR, 100, 100, 200, 200 );
                buf = (char*) malloc(
                                 _imagesize( 100, 100, 201, 201 ) );
                 if( buf != NULL ) {
                     _getimage( 100, 100, 201, 201, buf );
                     _putimage( 260, 200, buf, _GPSET );
                     _putimage( 420, 100, buf, _GPSET );
                     for (y = 100; y < 300;) {
                          _putimage( 420, y, buf, _GXOR );
                          y += 20;
                          _putimage( 420, y, buf, _GXOR );
                     free( buf );
                getch();
                _setvideomode( _DEFAULTMODE );
Classification: PC Graphics
Systems:
            _imagesize - DOS
            _imagesize_w - DOS
            _imagesize_wxy - DOS
```

_imagesize Functions		

```
Synopsis:
            #include <inttypes.h>
             intmax_t imaxabs( intmax_t j );
Description:
            The imaxabs function returns the absolute value of its maximum-size integer argument j.
Returns:
            The imaxabs function returns the absolute value of its argument.
See Also:
            labs, llabs, abs, fabs
Example:
            #include <stdio.h>
             #include <inttypes.h>
            void main( void )
                            х, у;
                 intmax_t
                 x = -5000000000000;
                 y = imaxabs(x);
                 printf( "imaxabs(%jd) = %jd\n", x, y );
            }
            produces the following:
            imaxabs(-500000000000) = 500000000000
Classification: ISO C99
```

All, Linux, RDOS, Netware

**Systems:** 

```
Synopsis:
            #include <stdlib.h>
            imaxdiv_t imaxdiv( intmax_t numer, intmax_t denom );
            typedef struct {
                intmax_t quot; /* quotient */
                             rem; /* remainder */
                 intmax_t
            } imaxdiv_t;
Description:
            The imaxdiv function calculates the quotient and remainder of the division of the numerator numer by
            the denominator denom.
Returns:
            The imaxdiv function returns a structure of type imaxdiv_t that contains the fields quot and rem,
            which are both of type intmax_t.
See Also:
            div, ldiv, lldiv
Example:
            #include <stdio.h>
            #include <inttypes.h>
            void print_time( intmax_t ticks )
                 imaxdiv_t sec_ticks;
                 imaxdiv_t min_sec;
                 sec_ticks = imaxdiv( ticks, 1000000 );
                min_sec = imaxdiv(sec_ticks.quot, 60);
                printf( "It took %jd minutes and %jd seconds\n",
                         min_sec.quot, min_sec.rem );
            }
            void main( void )
                print_time( 9876543210 );
            produces the following:
            It took 164 minutes and 36 seconds
Classification: ISO C99
Systems:
            All, Linux, RDOS, Netware
```

**Synopsis:** #include <conio.h>

unsigned int inp( int port );

**Description:** The inp function reads one byte from the 80x86 hardware port whose number is given by port.

> A hardware port is used to communicate with a device. One or two bytes can be read and/or written from each port, depending upon the hardware. Consult the technical documentation for your computer

to determine the port numbers for a device and the expected usage of each port for a device.

**Returns:** The value returned is the byte that was read.

See Also: inpd, inpw, outp, outpd, outpw

**Example:** #include <conio.h>

```
void main()
    /* turn off speaker */
    outp( 0x61, inp( 0x61 ) & 0xFC );
```

Classification: Intel

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <conio.h>

unsigned long inpd( int port );

**Description:** The inpd function reads a double-word (four bytes) from the 80x86 hardware port whose number is

given by port.

A hardware port is used to communicate with a device. One or two bytes can be read and/or written from each port, depending upon the hardware. Consult the technical documentation for your computer

to determine the port numbers for a device and the expected usage of each port for a device.

**Returns:** The value returned is the double-word that was read.

See Also: inp, inpw, outp, outpd, outpw

Example: #include <conio.h> #define DEVICE 34

void main()
{
 unsigned long transmitted;

 transmitted = inpd( DEVICE );
}

Classification: Intel

**Systems:** DOS/32, Win386, Win32, OS/2-32, Linux, RDOS, Netware

**Synopsis:** #include <conio.h> unsigned int inpw( int port );

**Description:** The inpw function reads a word (two bytes) from the 80x86 hardware port whose number is given by

port.

A hardware port is used to communicate with a device. One or two bytes can be read and/or written from each port, depending upon the hardware. Consult the technical documentation for your computer to determine the port numbers for a device and the expected usage of each port for a device.

**Returns:** The value returned is the word that was read.

See Also: inp, inpd, outp, outpd, outpw

**Example:** #include <conio.h> #define DEVICE 34

> void main() unsigned int transmitted; transmitted = inpw( DEVICE ); }

Classification: Intel

**Systems:** All, Linux, RDOS, Netware **Description:** 

The int386 function causes the computer's central processor (CPU) to be interrupted with an interrupt whose number is given by *inter\_no*. This function is present in the 386 C libraries and may be executed on 80386/486 systems. Before the interrupt, the CPU registers are loaded from the structure located by *in\_regs*. Following the interrupt, the structure located by *out\_regs* is filled with the contents of the CPU registers. These structures may be located at the same location in memory.

You should consult the technical documentation for the computer that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The int 386 function returns the value of the CPU EAX register after the interrupt.

See Also: bdos, int386x, int86, int86x, intdos, intdosx, intr, intrf, segread

**Example:** 

**Classification:** Intel

**Systems:** DOS/32, Linux, RDOS, Netware

**Synopsis:** 

```
#include <i86.h>
int int386x( int inter_no,
             const union REGS *in_regs,
             union REGS *out_regs,
             struct SREGS *seg_regs );
```

**Description:** 

The int 386x function causes the computer's central processor (CPU) to be interrupted with an interrupt whose number is given by inter\_no. This function is present in the 32-bit C libraries and may be executed on Intel 386 compatible systems. Before the interrupt, the CPU registers are loaded from the structure located by in\_regs and the DS, ES, FS and GS segment registers are loaded from the structure located by seg\_regs. All of the segment registers must contain valid values. Failure to do so will cause a segment violation when running in protect mode. If you don't care about a particular segment register, then it can be set to 0 which will not cause a segment violation. The function segread can be used to initialize seg\_regs to their current values.

Following the interrupt, the structure located by *out\_regs* is filled with the contents of the CPU registers. The *in regs* and *out regs* structures may be located at the same location in memory. The original values of the DS, ES, FS and GS registers are restored. The structure seg\_regs is updated with the values of the segment registers following the interrupt.

You should consult the technical documentation for the computer that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The int386x function returns the value of the CPU EAX register after the interrupt.

See Also: bdos, int386, int86, int86x, intdos, intdosx, intr, intrf, segread

**Example:** 

```
#include <stdio.h>
#include <i86.h>
/* get current mouse interrupt handler address */
void main()
 {
   union REGS r;
    struct SREGS s;
    s.ds = s.es = s.fs = s.gs = FP\_SEG( &s );
#if defined(__PHARLAP__)
   r.w.ax = 0x2503; /* get real-mode vector */
                        /* interrupt vector 0x33 */
    r.h.cl = 0x33;
    int386( 0x21, &r, &r );
   printf( "mouse handler real-mode address="
            "%lx\n", r.x.ebx );
   r.w.ax = 0x2502;
                       /* get protected-mode vector */
                        /* interrupt vector 0x33 */
   r.h.cl = 0x33;
    int386x( 0x21, &r, &r, &s);
   printf( "mouse handler protected-mode address="
            "%x:%lx\n", s.es, r.x.ebx);
```

Classification: Intel

**Systems:** DOS/32, Linux, RDOS, Netware

**Synopsis:** #include <i86.h> int int86( int inter\_no, const union REGS \*in\_regs, union REGS \*out\_regs );

**Description:** The int86 function causes the computer's central processor (CPU) to be interrupted with an interrupt

whose number is given by *inter\_no*. Before the interrupt, the CPU registers are loaded from the structure located by in\_regs. Following the interrupt, the structure located by out\_regs is filled with the contents of the CPU registers. These structures may be located at the same location in memory.

You should consult the technical documentation for the computer that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The int86 function returns the value of the CPU AX register after the interrupt.

See Also: bdos, int386, int386x, int86x, intdos, intdosx, intr, intrf, segread

**Example:** 

```
* This example clears the screen on DOS
#include <i86.h>
void main()
  {
    union REGS regs;
    regs.w.cx = 0;
    regs.w.dx = 0x1850;
    regs.h.bh = 7;
    regs.w.ax = 0x0600;
#if defined(__386__) && defined(__DOS__)
    int386( 0x10, &regs, &regs );
#else
    int86( 0x10, &regs, &regs );
#endif
  }
```

Classification: Intel

DOS/16, Windows, Win386, DOS/PM **Systems:** 

**Synopsis:** 

**Description:** 

The int86x function causes the computer's central processor (CPU) to be interrupted with an interrupt whose number is given by <code>inter\_no</code>. Before the interrupt, the CPU registers are loaded from the structure located by <code>in\_regs</code> and the DS and ES segment registers are loaded from the structure located by <code>seg\_regs</code>. All of the segment registers must contain valid values. Failure to do so will cause a segment violation when running in protect mode. If you don't care about a particular segment register, then it can be set to 0 which will not cause a segment violation. The function <code>segread</code> can be used to initialize <code>seg\_regs</code> to their current values.

Following the interrupt, the structure located by *out\_regs* is filled with the contents of the CPU registers. The *in\_regs* and *out\_regs* structures may be located at the same location in memory. The original values of the DS and ES registers are restored. The structure *seg\_regs* is updated with the values of the segment registers following the interrupt.

You should consult the technical documentation for the computer that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The function returns the value of the CPU AX register after the interrupt.

See Also: bdos, int386, int386x, int86, intdos, intdosx, intr, intrf, segread

**Example:** 

Classification: Intel

**Systems:** DOS/16, Windows, Win386, DOS/PM

int86x

**Description:** 

The intdos function causes the computer's central processor (CPU) to be interrupted with an interrupt number hexadecimal 21 (0x21), which is a request to invoke a specific DOS function. Before the interrupt, the CPU registers are loaded from the structure located by *in\_regs*. The AH register contains a number indicating the function requested. Following the interrupt, the structure located by *out\_regs* is filled with the contents of the CPU registers. These structures may be located at the same location in memory.

You should consult the technical documentation for the DOS operating system that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** 

The function returns the value of the AX (EAX in 386 library) register after the interrupt has completed. The CARRY flag (when set, an error has occurred) is copied into the structure located by *out\_regs*. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also: bdos, int386, int386x, int86, int86x, intdosx, intr, intrf, segread

Example: #include <dos.h>

#define DISPLAY\_OUTPUT 2 void main() { union REGS in\_regs, out\_regs; rc; in\_regs.h.ah = DISPLAY\_OUTPUT;  $in_regs.h.al = 0;$  $in\_regs.w.dx = 'I';$ rc = intdos( &in\_regs, &out\_regs );  $in\_regs.w.dx = 'N';$ rc = intdos( &in\_regs, &out\_regs ); in\_regs.w.dx = 'T'; rc = intdos( &in\_regs, &out\_regs );  $in\_regs.w.dx = 'D';$ rc = intdos( &in\_regs, &out\_regs );  $in\_regs.w.dx = 'O';$ rc = intdos( &in\_regs, &out\_regs );  $in\_regs.w.dx = 'S';$ rc = intdos( &in\_regs, &out\_regs ); }

**Classification:** DOS

**Systems:** DOS, Windows, Win386, DOS/PM

			intdos

**Synopsis:** 

**Description:** 

The intdosx function causes the computer's central processor (CPU) to be interrupted with an interrupt number hexadecimal 21 (0x21), which is a request to invoke a specific DOS function. Before the interrupt, the CPU registers are loaded from the structure located by  $in\_regs$  and the segment registers DS and ES are loaded from the structure located by  $seg\_regs$ . The AH register contains a number indicating the function requested. All of the segment registers must contain valid values. Failure to do so will cause a segment violation when running in protect mode. If you don't care about a particular segment register, then it can be set to 0 which will not cause a segment violation. The function segread can be used to initialize  $seg\_regs$  to their current values.

Following the interrupt, the structure located by *out\_regs* is filled with the contents of the CPU registers. The *in\_regs* and *out\_regs* structures may be located at the same location in memory. The original values for the DS and ES registers are restored. The structure *seg\_regs* is updated with the values of the segment registers following the interrupt.

You should consult the technical documentation for the DOS operating system that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** 

The intdosx function returns the value of the AX (EAX in 32-bit library) register after the interrupt has completed. The CARRY flag (when set, an error has occurred) is copied into the structure located by *out\_regs*. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

bdos, int386, int386x, int86, int86x, intdos, intr, intrf, segread

**Example:** 

```
#include <stdio.h>
#include <dos.h>
/* get current mouse interrupt handler address */
void main()
  {
    union REGS r;
    struct SREGS s;
#if defined(__386__)
    s.ds = s.es = s.fs = s.gs = FP\_SEG( &s );
#endif
    r.h.ah = 0x35; /* get vector */
    r.h.al = 0x33; /* vector 0x33 */
    intdosx( &r, &r, &s );
#if defined(__386__)
    printf( "mouse handler address=%4.4x:%lx\n",
            s.es, r.x.ebx);
#else
   printf( "mouse handler address=%4.4x:%4.4x\n",
            s.es, r.x.bx );
#endif
  }
```

**Classification:** DOS

DOS, Windows, Win386, DOS/PM **Systems:** 

Synopsis: #include <i86.h>
 void intr( int inter\_no, union REGPACK \*regs );

**Description:** 

The intr functions cause the computer's central processor (CPU) to be interrupted with an interrupt whose number is given by *inter\_no*. Before the interrupt, the CPU registers are loaded from the structure located by *regs*. Low 8-bit of the CPU flags are set to 0.

All of the segment registers must contain valid values. Failure to do so will cause a segment violation when running in protect mode. If you don't care about a particular segment register, then it can be set to 0 which will not cause a segment violation. Following the interrupt, the structure located by *regs* is filled with the contents of the CPU registers.

intr function is similar to the int86x function, except that only one structure is used for the register values and that the BP (EBP in 386 library) register is included in the set of registers that are passed and saved.

You should consult the technical documentation for the computer that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The intr function do not return a value.

See Also: bdos, int386, int386x, int86, int86x, intdos, intdosx, intrf, segread

**Example:** 

produces the following:

Break Key vector is eef:13c

Classification: Intel

**Systems:** DOS, Windows, Win386, Linux, RDOS, DOS/PM, Netware

intr

Synopsis: #include <i86.h>
 void intrf( int inter\_no, union REGPACK \*regs );

**Description:** 

The intrf functions cause the computer's central processor (CPU) to be interrupted with an interrupt whose number is given by *inter\_no*. Before the interrupt, the CPU registers are loaded from the structure located by *regs*. Low 8-bit of the CPU flags is set to the flags member of the structure *regs*.

All of the segment registers must contain valid values. Failure to do so will cause a segment violation when running in protect mode. If you don't care about a particular segment register, then it can be set to 0 which will not cause a segment violation. Following the interrupt, the structure located by *regs* is filled with the contents of the CPU registers.

intrf function is similar to the int86x function. Exception is that only one structure is used for the register values and that the BP (EBP in 386 library) register is included in the set of registers that are passed and saved and the CPU flags are set to flags member of the structure *regs* 

You should consult the technical documentation for the computer that you are using to determine the expected register contents before and after the interrupt in question.

**Returns:** The intrf function do not return a value.

See Also: bdos, int386, int386x, int86, int86x, intdos, intdosx, intr, segread

**Example:** 

produces the following:

Break Key vector is eef:13c

Classification: Intel

**Systems:** DOS, Windows, Win386, Linux, RDOS, DOS/PM, Netware

intri

```
Synopsis: #include <ctype.h>
    int isalnum( int c );
    #include <wctype.h>
    int iswalnum( wint_t c );
```

**Description:** The isalnum function tests if the argument *c* is an alphanumeric character ('a' to 'z', 'A' to 'Z', or '0' to '9'). An alphanumeric character is any character for which isalpha or isdigit is true.

The iswalnum function is a wide character version of isalnum that operates with wide character argument.

**Returns:** The isalnum function returns zero if the argument is neither an alphabetic character (A-Z or a-z) nor a digit (0-9). Otherwise, a non-zero value is returned. The iswalnum function returns a non-zero value

if either iswalpha or iswdigit is true for c.

See Also: isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct,

iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans,

towctrans

Example: #include <stdio.h>

```
#include <ctype.h>
void main()
{
    if( isalnum( getchar() ) ) {
        printf( "is alpha-numeric\n" );
    }
}
```

Classification: ISO C

iswalnum is ISO C95

Systems: isalnum - All, Linux, RDOS, Netware

iswalnum - All, Linux, RDOS, Netware

**Synopsis:** 

```
#include <ctype.h>
int isalpha( int c );
#include <wctype.h>
int iswalpha( wint_t c );
```

**Description:** 

The isalpha function tests if the argument c is an alphabetic character ('a' to 'z' and 'A' to 'Z'). An alphabetic character is any character for which isupper or islower is true.

The iswalpha function is a wide character version of isalpha that operates with wide character argument.

**Returns:** 

The isalpha function returns zero if the argument is not an alphabetic character (A-Z or a-z); otherwise, a non-zero value is returned. The iswalpha function returns a non-zero value only for wide characters for which iswupper or iswlower is true, or any wide character that is one of an implementation-defined set for which none of iswcntrl, iswdigit, iswpunct, or iswspace is true.

See Also:

isalnum, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
void main()
    if( isalpha( getchar() ) ) {
        printf( "is alphabetic\n" );
```

**Classification:** ISO C

iswalpha is ISO C95

**Systems:** 

isalpha - All, Linux, RDOS, Netware iswalpha - All, Linux, RDOS, Netware

```
Synopsis:
             #include <ctype.h>
             int isascii( int c );
             int __isascii( int c );
             #include <wctype.h>
             int iswascii( wint_t c );
Description:
            The isascii function tests for a character in the range from 0 to 127.
            The __isascii function is identical to isascii. Use __isascii for ANSI naming conventions.
            The iswascii function is a wide character version of isascii that operates with wide character
             argument.
Returns:
            The isascii function returns a non-zero value when the character is in the range 0 to 127; otherwise,
             zero is returned. The iswascii function returns a non-zero value when c is a wide character
             representation of an ASCII character.
See Also:
             isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint,
             ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum,
             iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint,
             iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype,
             wctrans, towctrans
Example:
             #include <stdio.h>
             #include <ctype.h>
             char chars[] = {
                 'A',
                  0x80,
                  'Z'
             };
             #define SIZE sizeof( chars ) / sizeof( char )
             void main()
             {
                 int
                      i;
                 for( i = 0; i < SIZE; i++ ) {
                      printf( "Char %c is %san ASCII character\n",
                                chars[i],
                                ( isascii( chars[i] ) ) ? "" : "not " );
             produces the following:
             Char A is an ASCII character
             Char is not an ASCII character
            Char Z is an ASCII character
Classification: WATCOM
             __isascii conforms to ANSI naming conventions
```

**Systems:** 

isascii - All, Linux, RDOS, Netware
\_\_isascii - All, Linux, RDOS, Netware
iswascii - All, Linux, RDOS, Netware

Synopsis: #include <io.h>

int isatty( int handle );
int \_isatty( int handle );

**Description:** 

The isatty function tests if the opened file or device referenced by the file handle handle is a character device (for example, a console, printer or port).

The \_isatty function is identical to isatty. Use \_isatty for ANSI naming conventions.

**Returns:** 

The isatty function returns zero if the device or file is not a character device; otherwise, a non-zero value is returned. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: open

Example:

Classification: POSIX 1003.1

\_isatty conforms to ANSI naming conventions

**Systems:** 

```
isatty - All, Linux, RDOS, Netware
_isatty - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

#### **Synopsis:**

```
#include <ctype.h>
int isblank( int c );
#include <wctype.h>
int iswblank( wint_t c );
```

**Description:** 

The isblank function tests for the following blank characters:

Constant	Character		
, ,	space		
'\t'	horizontal tab		

The iswblank function is a wide character version of isblank that operates with wide character argument.

#### **Returns:**

The isblank function returns a non-zero character when the argument is one of the indicated blank characters. The iswblank function returns a non-zero value when the argument is a wide character that corresponds to a standard blank character or is one of an implementation-defined set of wide characters for which iswalnum is false. Otherwise, zero is returned.

#### See Also:

isalnum, isalpha, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

#### **Example:**

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'A',
    0x09,
    , ,
    0x7d
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
      printf( "Char %c is %sa blank character\n",
            chars[i],
            ( isblank( chars[i] ) ) ? "" : "not " );
}
```

produces the following:

```
Char A is not a blank character
Char is a blank character
Char is a blank character
Char } is not a blank character
```

Classification: ISO C99

Systems: isblank - All, Linux, RDOS, Netware

iswblank - All, Linux, RDOS, Netware

```
Synopsis:
           #include <ctype.h>
           int iscntrl( int c );
           #include <wchar.h>
           int iswcntrl( wint_t c );
```

**Description:** The iscntrl function tests for any control character. A control character is any character whose value is from 0 through 31.

> The iswentrl function is a wide character version of isentrl that operates with wide character argument.

**Returns:** The iscntrl function returns a non-zero value when the argument is a control character. The iswentrl function returns a non-zero value when the argument is a control wide character. Otherwise, zero is returned.

See Also: isalnum, isalpha, isblank, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** #include <stdio.h> #include <ctype.h>

char chars[] = {

```
'Α',
    0x09,
    'Z'
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
{
    int
    for( i = 0; i < SIZE; i++ ) {
        printf( "Char %c is %sa Control character\n",
                chars[i],
                 ( iscntrl( chars[i] ) ) ? "" : "not " );
```

produces the following:

}

}

Char A is not a Control character Char is a Control character Char Z is not a Control character

Classification: ISO C

iswentrl is ISO C95

**Systems:** iscntrl - All, Linux, RDOS, Netware iswcntrl - All, Linux, RDOS, Netware

iscntrl, iswcntrl			

```
Synopsis:
             #include <ctype.h>
             int iscsym( int c );
             int __iscsym( int c );
             #include <wctype.h>
             int __iswcsym( wint_t c );
Description:
            The iscsym function tests for a letter, underscore or digit.
            The __iscsym function is identical to iscsym. Use __iscsym for ANSI naming conventions.
             The ___iswcsym function is a wide character version of iscsym that operates with wide character
             argument.
Returns:
             A non-zero value is returned when the character is a letter, underscore or digit; otherwise, zero is
             returned. The \__{iswcsym} function returns a non-zero value when c is a wide character representation
             of a letter, underscore or digit character.
See Also:
             isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint,
             ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum,
             iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint,
             iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype,
             wctrans, towctrans
Example:
             #include <stdio.h>
             #include <ctype.h>
             char chars[] = {
                 'A',
                 0x80,
                 '_',
                 , 9',
                 ' + '
             };
             #define SIZE sizeof( chars ) / sizeof( char )
             void main()
             {
                 int
                        i;
                 for( i = 0; i < SIZE; i++ ) {
                      printf( "Char %c is %sa C symbol character\n",
                                chars[i],
                                ( __iscsym( chars[i] ) ) ? "" : "not " );
             produces the following:
             Char A is a C symbol character
             Char is not a C symbol character
             Char _ is a C symbol character
             Char 9 is a C symbol character
             Char + is not a C symbol character
```

## iscsym, \_\_iscsym, \_\_iswcsym

Classification: WATCOM
\_\_iscsym conforms to ANSI naming conventions

Systems: iscsym - All, Linux, RDOS, Netware
\_\_iscsym - All, Linux, RDOS, Netware
\_\_iswcsym - All, Linux, RDOS, Netware

```
Synopsis:
             #include <ctype.h>
             int iscsymf( int c );
             int __iscsymf( int c );
             #include <wctype.h>
             int __iswcsymf( wint_t c );
Description:
            The iscsymf function tests for a letter or underscore.
            The __iscsymf function is identical to iscsymf. Use __iscsymf for ANSI naming conventions.
             The __iswcsymf function is a wide character version of iscsymf that operates with wide character
             argument.
Returns:
             A non-zero value is returned when the character is a letter or underscore; otherwise, zero is returned.
            The ___iswcsymf function returns a non-zero value when c is a wide character representation of a
             letter or underscore character.
See Also:
             isalpha, isalnum, iscntrl, isdigit, isgraph, islower, isprint, ispunct,
             isspace, isupper, isxdigit, tolower, toupper
Example:
             #include <stdio.h>
             #include <ctype.h>
             char chars[] = {
                  'A',
                 0x80,
                 '_',
                 '9',
                  ' +'
             };
             #define SIZE sizeof( chars ) / sizeof( char )
             void main()
             {
                 int
                        i;
                 for( i = 0; i < SIZE; i++ ) {
                      printf( "Char %c is %sa csymf character\n",
                                chars[i],
                                ( __iscsymf( chars[i] ) ) ? "" : "not " );
                  }
            produces the following:
             Char A is a csymf character
            Char is not a csymf character
             Char _ is a csymf character
             Char 9 is not a csymf character
             Char + is not a csymf character
```

**Classification:** WATCOM

\_\_iscsymf conforms to ANSI naming conventions

# iscsymf, \_\_iscsymf, \_\_iswcsymf

Systems:	iscsymf - All, Linux, RDOS, Netware	
	iscsymf - All, Linux, RDOS, Netware	
	iswcsymf - All, Linux, RDOS, Netware	

```
Synopsis:
             #include <ctype.h>
             int isdigit( int c );
             #include <wctype.h>
             int iswdigit( wint_t c );
Description:
            The isdigit function tests for any decimal-digit character '0' through '9'.
            The iswdigit function is a wide character version of isdigit that operates with wide character
             argument.
Returns:
             The isdigit function returns a non-zero value when the argument is a decimal-digit character. The
             iswdigit function returns a non-zero value when the argument is a wide character corresponding to a
             decimal-digit character. Otherwise, zero is returned.
See Also:
             isalnum, isalpha, isblank, iscntrl, isgraph, islower, isprint, ispunct,
             isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha,
             iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct,
             iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans,
             towctrans
Example:
             #include <stdio.h>
             #include <ctype.h>
             char chars[] = {
                 'A',
                 '5',
                 151
             };
             #define SIZE sizeof( chars ) / sizeof( char )
             void main()
                 int
                        i;
                 for( i = 0; i < SIZE; i++ ) {
                      printf( "Char %c is %sa digit character\n",
                                chars[i],
                                ( isdigit( chars[i] ) ) ? "" : "not " );
             produces the following:
             Char A is not a digit character
             Char 5 is a digit character
             Char $ is not a digit character
```

### Classification: ISO C

iswdigit is ISO C95

**Systems:** isdigit - All, Linux, RDOS, Netware iswdigit - All, Linux, RDOS, Netware

isdigit, iswdigit			

**Synopsis:** #include <math.h> int isfinite( x );

**Description:** The isfinite macro determines whether its argument x has a finite value (zero, subnormal, or

normal, and not infinite or NaN). First, an argument represented in a format wider than its semantic type is converted to its semantic type. Then determination is based on the type of the argument.

The argument *x* must be an expression of real floating type.

**Returns:** The isfinite macro returns a nonzero value if and only if its argument has a finite value.

See Also: fpclassify, isinf, isnan, isnormal, signbit, \_finite

**Example:** #include <math.h>

#include <stdio.h> void main( void ) printf( "zero %s a finite number\n", isfinite( 0.0 ) ? "is" : "is not" );

produces the following:

zero is a finite number

**Classification:** ISO C

**Systems: MACRO** 

```
Synopsis:
             #include <ctype.h>
             int isgraph (int c);
             #include <wctype.h>
             int iswgraph( wint_t c );
Description:
             The isgraph function tests for any printable character except space (''). The isprint function is
             similar, except that the space character is also included in the character set being tested.
             The iswgraph function is a wide character version of isgraph that operates with wide character
             argument.
Returns:
             The isgraph function returns non-zero when the argument is a printable character (except a space).
             The iswgraph function returns a non-zero value when the argument is a printable wide character
             (except a wide character space). Otherwise, zero is returned.
See Also:
             isalnum, isalpha, isblank, iscntrl, isdigit, islower, isprint, ispunct,
             isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha,
             iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct,
             iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans,
             towctrans
Example:
             #include <stdio.h>
             #include <ctype.h>
             char chars[] = {
                  'Α',
                  0x09,
                  , ,
                  0x7d
             };
             #define SIZE sizeof( chars ) / sizeof( char )
             void main()
             {
                  int
                         i;
                  for( i = 0; i < SIZE; i++ ) {
                       printf( "Char %c is %sa printable character\n",
                                 chars[i],
                                 ( isgraph( chars[i] ) ) ? "" : "not " );
                  }
             produces the following:
```

Classification: ISO C

iswgraph is ISO C95

Char A is a printable character

Char is not a printable character Char } is a printable character

is not a printable character

**Systems:** isgraph - All, Linux, RDOS, Netware
iswgraph - All, Linux, RDOS, Netware

Synopsis: #include <math.h>
 int isinf(x);

**Description:** The isinf macro determines whether its argument value is an infinity (positive or negative). First, an

argument represented in a format wider than its semantic type is converted to its semantic type. Then

determination is based on the type of the argument.

The argument x must be an expression of real floating type.

**Returns:** The isinf macro returns a nonzero value if and only if its argument has an infinite value.

See Also: fpclassify, isfinite, isnan, isnormal, signbit

Example: #include <math.h>
#include <stdio.h>

produces the following:

zero is not an infinite number

**Classification:** ISO C

**Systems:** MACRO

```
Synopsis:
           #include <ctype.h>
           int isleadbyte (int ch);
```

**Description:** The isleadbyte function tests if the argument ch is a valid first byte of a multibyte character in the current code page.

> For example, in code page 932, a valid lead byte is any byte in the range 0x81 through 0x9F or 0xE0 through 0xFC.

**Returns:** The isleadbyte function returns a non-zero value when the argument is a valid lead byte. Otherwise, zero is returned.

See Also: isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** #include <stdio.h> #include <ctype.h> #include <mbctype.h> const unsigned char chars[] = {

′.′, 11, 'A', 0x81,0x40, /\* double-byte space \*/ 0x82,0x60, /\* double-byte A \*/ 0x82,0xA6, /\* double-byte Hiragana \*/ 0x83,0x42, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ 0xA1, /\* single-byte Katakana alphabetic \*/ 0xA6, /\* single-byte Katakana alphabetic \*/ 0xE0,0xA1, /\* double-byte Kanji \*/ 0x00}; #define SIZE sizeof( chars ) / sizeof( char ) void main() { int i; \_setmbcp( 932 ); for( i = 0; i < SIZE; i++ ) { printf( "%2.2x is %sa valid lead byte\n", chars[i], ( isleadbyte( chars[i] ) ) ? "" : "not " ); }

produces the following:

```
20 is not a valid lead byte
2e is not a valid lead byte
31 is not a valid lead byte
41 is not a valid lead byte
81 is a valid lead byte
40 is not a valid lead byte
82 is a valid lead byte
60 is not a valid lead byte
82 is a valid lead byte
a6 is not a valid lead byte
83 is a valid lead byte
42 is not a valid lead byte
al is not a valid lead byte
a6 is not a valid lead byte
df is not a valid lead byte
e0 is a valid lead byte
al is not a valid lead byte
00 is not a valid lead byte
```

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

```
Synopsis:
           #include <ctype.h>
           int islower( int c );
           #include <wctype.h>
```

int iswlower( wint\_t c );

**Description:** The islower function tests for any lowercase letter 'a' through 'z'.

> The iswlower function is a wide character version of islower that operates with wide character argument.

**Returns:** 

The islower function returns a non-zero value when argument is a lowercase letter. The iswlower function returns a non-zero value when the argument is a wide character that corresponds to a lowercase letter, or if it is one of an implementation-defined set of wide characters for which none of iswcntrl, iswdigit, iswpunct, or iswspace is true. Otherwise, zero is returned.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'Α',
    ′a′,
    'z',
    'Z'
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
{
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "Char %c is %sa lowercase character\n",
                 chars[i],
                 ( islower( chars[i] ) ) ? "" : "not " );
    }
}
produces the following:
Char A is not a lowercase character
```

Classification: ISO C

iswlower is ISO C95

Char a is a lowercase character Char z is a lowercase character Char Z is not a lowercase character **Systems:** 

islower - All, Linux, RDOS, Netware iswlower - All, Linux, RDOS, Netware

```
Synopsis:
            #include <mbctype.h>
            int _ismbbalnum( unsigned int ch );
Description:
            The _ismbbalnum function tests if the argument ch satisfies the condition that one of isalnum or
            _ismbbkalnum is true.
            Note: The argument ch must represent a single-byte value (i.e., 0 \le ch \le 255). Incorrect results
            occur if the argument is a double-byte character.
Returns:
            The _ismbbalnum function returns a non-zero value if the argument satisfies the condition; otherwise
            a zero value is returned.
            _getmbcp, _mbbtombc, _mbcjistojms, _mbcjmstojis, _mbctombb, _ismbbalpha,
See Also:
            _ismbbgraph, _ismbbkalnum, _ismbbkalpha, _ismbbkana, _ismbbkprint,
            _ismbbkpunct, _ismbblead, _ismbbprint, _ismbbpunct, _ismbbtrail, _mbbtombc,
            _mbcjistojms, _mbcjmstojis, _mbctombb, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            unsigned int chars[] = {
                 , ,
                 '1',
                 'A',
                 0x8140, /* double-byte space */
                 0x8260, /* double-byte A */
                 0x82A6, /* double-byte Hiragana */
                 0x8342, /* double-byte Katakana */
                 0xA1, /* single-byte Katakana punctuation */
                 0xA6,
                        /* single-byte Katakana alphabetic */
                        /* single-byte Katakana alphabetic */
                 0xDF,
                 0xE0A1 /* double-byte Kanji */
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                 int
                       i;
                 _setmbcp( 932 );
                 for( i = 0; i < SIZE; i++ ) {
                   printf( "%#6.4x is %sa single-byte alphanumeric\n"
                            " or Katakana non-punctuation character\n",
                          chars[i],
                          ( _ismbbalnum( chars[i] ) ) ? "" : "not " );
              }
```

produces the following:

0x0020 is not a single-byte alphanumeric or Katakana non-punctuation character 0x002e is not a single-byte alphanumeric or Katakana non-punctuation character 0x0031 is a single-byte alphanumeric or Katakana non-punctuation character 0x0041 is a single-byte alphanumeric or Katakana non-punctuation character 0x8140 is not a single-byte alphanumeric or Katakana non-punctuation character 0x8260 is not a single-byte alphanumeric or Katakana non-punctuation character 0x82a6 is a single-byte alphanumeric or Katakana non-punctuation character 0x8342 is a single-byte alphanumeric or Katakana non-punctuation character 0x00a1 is not a single-byte alphanumeric or Katakana non-punctuation character 0x00a6 is a single-byte alphanumeric or Katakana non-punctuation character 0x00df is a single-byte alphanumeric or Katakana non-punctuation character 0xe0a1 is not a single-byte alphanumeric or Katakana non-punctuation character

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

```
Synopsis:
           #include <mbctype.h>
           int _ismbbalpha( unsigned int ch );
```

**Description:** The \_ismbbalpha function tests if the argument *ch* satisfies the condition that one of isalpha or \_ismbbkalpha is true.

> For example, in code page 932, \_ismbbalpha tests if the argument ch is a single-byte alphabetic character ("a" to "z" or "A" to "Z") or single-byte Katakana non-punctuation character.

> *Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character.

**Returns:** The \_ismbbalpha function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = {

> 11', 'A',

```
0x8140, /* double-byte space */
    0x8260, /* double-byte A */
    0x82A6, /* double-byte Hiragana */
    0x8342, /* double-byte Katakana */
          /* single-byte Katakana punctuation */
          /* single-byte Katakana alphabetic */
           /* single-byte Katakana alphabetic */
    0xE0A1 /* double-byte Kanji */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
   _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte alphabetic\n"
              " or Katakana alphabetic character\n",
            chars[i],
            ( _ismbbalpha( chars[i] ) ) ? "" : "not " );
  }
```

produces the following:

0x0020 is not a single-byte alphabetic or Katakana alphabetic character 0x002e is not a single-byte alphabetic or Katakana alphabetic character 0x0031 is not a single-byte alphabetic or Katakana alphabetic character 0x0041 is a single-byte alphabetic or Katakana alphabetic character 0x8140 is not a single-byte alphabetic or Katakana alphabetic character 0x8260 is not a single-byte alphabetic or Katakana alphabetic character 0x82a6 is a single-byte alphabetic or Katakana alphabetic character 0x8342 is a single-byte alphabetic or Katakana alphabetic character 0x00a1 is not a single-byte alphabetic or Katakana alphabetic character 0x00a6 is a single-byte alphabetic or Katakana alphabetic character 0x00df is a single-byte alphabetic or Katakana alphabetic character 0xe0a1 is not a single-byte alphabetic or Katakana alphabetic character

**Classification:** WATCOM

```
Synopsis:
           #include <mbctype.h>
           int _ismbbgraph( unsigned int ch );
```

**Description:** The \_ismbbgraph function tests if the argument ch satisfies the condition that one of isgraph or \_ismbbkprint is true.

> For example, in code page 932, \_ismbbgraph tests if the argument ch is a single-byte printable character excluding space (" ") or single-byte Katakana character.

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbgraph function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = {

```
11',
    'A',
    0x8140, /* double-byte space */
    0x8260, /* double-byte A */
    0x82A6, /* double-byte Hiragana */
    0x8342, /* double-byte Katakana */
          /* single-byte Katakana punctuation */
          /* single-byte Katakana alphabetic */
    0xA6,
           /* single-byte Katakana alphabetic */
    0xE0A1 /* double-byte Kanji */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
   _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte printable "
              "non-space character\n",
            chars[i],
            ( _ismbbgraph( chars[i] ) ) ? "" : "not " );
  }
```

produces the following:

```
0x0020 is not a single-byte printable non-space character 0x002e is a single-byte printable non-space character 0x0031 is a single-byte printable non-space character 0x0041 is a single-byte printable non-space character 0x8140 is a single-byte printable non-space character 0x8260 is a single-byte printable non-space character 0x82a6 is a single-byte printable non-space character 0x8342 is a single-byte printable non-space character 0x00a1 is a single-byte printable non-space character 0x00a6 is a single-byte printable non-space character 0x00df is a single-byte printable non-space character 0x00df is a single-byte printable non-space character 0xe0a1 is a single-byte printable non-space character
```

**Synopsis:** #include <mbctype.h> int \_ismbbkalnum( unsigned int ch );

**Description:** The \_ismbbkalnum function tests if the argument *ch* is a non-ASCII text symbol other than punctuation.

> For example, in code page 932, \_ismbbkalnum tests for a single-byte Katakana character (excluding the Katakana punctuation characters). Note that there are no Katakana digit characters. A single-byte Katakana non-punctuation character is any character for which the following expression is true:

```
0xA6 \le ch \le 0xDF
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbkalnum function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { , , '.', 11', 'A', 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ 0xA1, /\* single-byte Katakana alphabetic \*/ 0xA6, 0xDF, /\* single-byte Katakana alphabetic \*/ 0xE0A1 /\* double-byte Kanji \*/ } **;** #define SIZE sizeof( chars ) / sizeof( unsigned int )

```
void main()
  {
          i;
    int
    _setmbcp( 932 );
    for ( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte "
              "Katakana non-punctuation character\n",
            chars[i],
            ( _ismbbkalnum( chars[i] ) ) ? "" : "not " );
  }
```

```
0x0020 is not a single-byte Katakana non-punctuation character 0x002e is not a single-byte Katakana non-punctuation character 0x0031 is not a single-byte Katakana non-punctuation character 0x0041 is not a single-byte Katakana non-punctuation character 0x8140 is not a single-byte Katakana non-punctuation character 0x8260 is not a single-byte Katakana non-punctuation character 0x82a6 is a single-byte Katakana non-punctuation character 0x8342 is not a single-byte Katakana non-punctuation character 0x00a1 is not a single-byte Katakana non-punctuation character 0x00a6 is a single-byte Katakana non-punctuation character 0x00df is a single-byte Katakana non-punctuation character 0x00df is not a single-byte Katakana non-punctuation character 0x00a1 is not a single-byte Katakana non-punctuation character
```

**Classification:** WATCOM

```
Synopsis:
           #include <mbctype.h>
           int _ismbbkana( unsigned int ch );
```

**Description:** The \_ismbbkana function tests if the argument ch is a single-byte Katakana character. A single-byte Katakana character is any character for which the following expression is true:

```
0xA1 \le ch \le 0xDF
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbkana function returns non-zero if the argument is a single-byte Katakana character; otherwise, a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { ĩ,, ′.′, '1', 'A', 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ 0xA1, /\* single-byte Katakana alphabetic \*/ 0xA6, /\* single-byte Katakana alphabetic \*/ 0xDF, 0xE0A1 /\* double-byte Kanji \*/ }; #define SIZE sizeof( chars ) / sizeof( unsigned int ) void main() { int i;

produces the following:

}

\_setmbcp( 932 );

for( i = 0; i < SIZE; i++ ) {

chars[i],

printf( "%#6.4x is %sa single-byte " "Katakana character\n",

( \_ismbbkana( chars[i] ) ) ? "" : "not " );

```
0x0020 is not a single-byte Katakana character 0x002e is not a single-byte Katakana character 0x0031 is not a single-byte Katakana character 0x0041 is not a single-byte Katakana character 0x8140 is not a single-byte Katakana character 0x8260 is not a single-byte Katakana character 0x82a6 is a single-byte Katakana character 0x8342 is not a single-byte Katakana character 0x00a1 is a single-byte Katakana character 0x00a6 is a single-byte Katakana character 0x00df is a single-byte Katakana character 0x00df is a single-byte Katakana character 0x00a1 is a single-byte Katakana character
```

**Synopsis:** #include <mbctype.h> int \_ismbbkalpha( unsigned int ch );

**Description:** The \_ismbbkalpha function tests if the argument ch is a non-ASCII text symbol other than digits or punctuation.

> For example, in code page 932, \_ismbbkalpha tests for a single-byte Katakana character (excluding the Katakana punctuation characters). Note that there are no Katakana digit characters. A single-byte Katakana non-punctuation character is any character for which the following expression is true:

```
0xA6 \le ch \le 0xDF
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbkalpha function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { , , '.', 11', 'A', 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ 0xA1, /\* single-byte Katakana alphabetic \*/ 0xA6, 0xDF, /\* single-byte Katakana alphabetic \*/ 0xE0A1 /\* double-byte Kanji \*/ } **;** #define SIZE sizeof( chars ) / sizeof( unsigned int )

```
void main()
  {
          i;
    int
    _setmbcp( 932 );
    for ( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte "
               "Katakana alphabetic character\n",
            chars[i],
            ( _ismbbkalpha( chars[i] ) ) ? "" : "not " );
  }
```

```
0x0020 is not a single-byte Katakana alphabetic character 0x002e is not a single-byte Katakana alphabetic character 0x0031 is not a single-byte Katakana alphabetic character 0x0041 is not a single-byte Katakana alphabetic character 0x8140 is not a single-byte Katakana alphabetic character 0x8260 is not a single-byte Katakana alphabetic character 0x82a6 is a single-byte Katakana alphabetic character 0x8342 is not a single-byte Katakana alphabetic character 0x00a1 is not a single-byte Katakana alphabetic character 0x00a6 is a single-byte Katakana alphabetic character 0x00df is a single-byte Katakana alphabetic character 0x00df is not a single-byte Katakana alphabetic character 0x00df is not a single-byte Katakana alphabetic character
```

**Classification:** WATCOM

**Synopsis:** #include <mbctype.h> int \_ismbbkprint( unsigned int ch );

**Description:** The \_ismbbkprint function tests if the argument ch is a non-ASCII text or non-ASCII punctuation symbol.

> For example, in code page 932, \_ismbbkprint tests if the argument ch is a single-byte Katakana character. A single-byte Katakana character is any character for which the following expression is true:

```
0xA1 \le ch \le 0xDF
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbkprint function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { '1', 'A', 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ /\* single-byte Katakana alphabetic \*/ 0xA6, /\* single-byte Katakana alphabetic \*/

0xE0A1 /\* double-byte Kanji \*/ }; #define SIZE sizeof( chars ) / sizeof( unsigned int ) void main() { int i; \_setmbcp( 932 ); for( i = 0; i < SIZE; i++ ) { printf( "%#6.4x is %sa single-byte " "Katakana printable character\n", chars[i], ( \_ismbbkprint( chars[i] ) ) ? "" : "not " ); }

```
0x0020 is not a single-byte Katakana printable character 0x002e is not a single-byte Katakana printable character 0x0031 is not a single-byte Katakana printable character 0x0041 is not a single-byte Katakana printable character 0x8140 is not a single-byte Katakana printable character 0x8260 is not a single-byte Katakana printable character 0x82a6 is a single-byte Katakana printable character 0x8342 is not a single-byte Katakana printable character 0x00a1 is a single-byte Katakana printable character 0x00a6 is a single-byte Katakana printable character 0x00df is a single-byte Katakana printable character 0x00df is a single-byte Katakana printable character 0x00df is a single-byte Katakana printable character
```

**Classification:** WATCOM

**Synopsis:** #include <mbctype.h> int \_ismbbkpunct( unsigned int ch );

**Description:** The \_i smbbkpunct function tests if the argument *ch* is a non-ASCII punctuation character.

> For example, in code page 932, \_ismbbkpunct tests if the argument ch is a single-byte Katakana punctuation character. A single-byte Katakana punctuation character is any character for which the following expression is true:

```
0xA1 \le ch \le 0xA5
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbkpunct function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { 11', 'A', 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ /\* single-byte Katakana alphabetic \*/ 0xA6, /\* single-byte Katakana alphabetic \*/ 0xDF, 0xE0A1 /\* double-byte Kanji \*/

```
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte "
              "Katakana punctuation character\n",
            chars[i],
            ( _ismbbkpunct( chars[i] ) ) ? "" : "not " );
  }
```

```
0x0020 is not a single-byte Katakana punctuation character 0x002e is not a single-byte Katakana punctuation character 0x0031 is not a single-byte Katakana punctuation character 0x0041 is not a single-byte Katakana punctuation character 0x8140 is not a single-byte Katakana punctuation character 0x8260 is not a single-byte Katakana punctuation character 0x82a6 is not a single-byte Katakana punctuation character 0x8342 is not a single-byte Katakana punctuation character 0x00a1 is a single-byte Katakana punctuation character 0x00a6 is not a single-byte Katakana punctuation character 0x00df is not a single-byte Katakana punctuation character 0x00df is a single-byte Katakana punctuation character 0x00a1 is a single-byte Katakana punctuation character
```

**Classification:** WATCOM

```
Synopsis:
           #include <mbctype.h>
           int _ismbblead( unsigned int ch );
```

**Description:** The \_ismbblead function tests if the argument *ch* is a valid first byte of a multibyte character.

For example, in code page 932, valid ranges are 0x81 through 0x9F and 0xE0 through 0xFC.

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character.

**Returns:** \_ismbblead returns a non-zero value if the argument is valid as the first byte of a multibyte character; otherwise zero is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint,\_ismbbkpunct,\_ismbbprint,\_ismbbpunct,\_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { í,, ′.′,

11',

'A', 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ /\* single-byte Katakana punctuation \*/ 0xA1, 0xA6, /\* single-byte Katakana alphabetic \*/ /\* single-byte Katakana alphabetic \*/ 0xDF, 0xE0A1 /\* double-byte Kanji \*/ } **;** #define SIZE sizeof( chars ) / sizeof( unsigned int ) void main() {

```
int
        i;
 _setmbcp( 932 );
 for( i = 0; i < SIZE; i++ ) {
   printf( \%#6.4x does %shave a valid first byte\n",
          chars[i],
          ( _ismbblead( chars[i]>>8 ) ) ? "" : "not " );
}
```

produces the following:

```
0x0020 does not have a valid first byte 0x002e does not have a valid first byte 0x0031 does not have a valid first byte 0x0041 does not have a valid first byte 0x8140 does have a valid first byte 0x8260 does have a valid first byte 0x82a6 does have a valid first byte 0x8342 does have a valid first byte 0x00a1 does not have a valid first byte 0x00a6 does not have a valid first byte 0x00df does not have a valid first byte 0x00df does not have a valid first byte 0x00df does have a valid first byte 0xe0a1 does have a valid first byte
```

```
Synopsis:
           #include <mbctype.h>
           int _ismbbprint( unsigned int ch );
```

**Description:** The \_ismbbprint function tests if the argument ch is a single-byte printable character including space (" ").

> For example, in code page 932, \_ismbbprint tests if the argument ch is a single-byte printable character including space (" ") or a single-byte Katakana character. These are any characters for which the following expression is true:

```
isprint(ch) | _ismbbkprint(ch)
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbprint function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint,\_ismbbkpunct,\_ismbblead,\_ismbbpunct,\_ismbbtrail,\_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

```
Example:
           #include <stdio.h>
           #include <mbctype.h>
           unsigned int chars[] = {
               0x0D,
               ′.′,
               11',
               'A',
               0x8140, /* double-byte space */
               0x8260, /* double-byte A */
               0x82A6, /* double-byte Hiragana */
               0x8342, /* double-byte Katakana */
                       /* single-byte Katakana punctuation */
               0xA1,
                       /* single-byte Katakana alphabetic */
               0xA6,
               0xDF,
                       /* single-byte Katakana alphabetic */
               0xE0A1 /* double-byte Kanji */
           } ;
           #define SIZE sizeof( chars ) / sizeof( unsigned int )
```

```
void main()
  {
          i;
    int
    _setmbcp( 932 );
    for ( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte "
               "printable character\n",
            chars[i],
            ( _ismbbprint( chars[i] ) ) ? "" : "not " );
  }
```

```
0x000d is not a single-byte printable character 0x002e is a single-byte printable character 0x0031 is a single-byte printable character 0x0041 is a single-byte printable character 0x8140 is a single-byte printable character 0x8260 is a single-byte printable character 0x82a6 is a single-byte printable character 0x8342 is a single-byte printable character 0x00a1 is a single-byte printable character 0x00a6 is a single-byte printable character 0x00df is a single-byte printable character 0x00df is a single-byte printable character 0x00df is a single-byte printable character
```

**Classification:** WATCOM

```
Synopsis:
           #include <mbctype.h>
           int _ismbbpunct( unsigned int ch );
```

**Description:** The \_i smbbpunct function tests if the argument *ch* is a single-byte punctuation character.

> For example, in code page 932,  $\_ismbbpunct$  tests if the argument ch is a single-byte punctuation character or a single-byte Katakana punctuation character. These are any characters for which the following expression is true:

```
ispunct(ch) | _ismbbkpunct(ch)
```

*Note:* The argument ch must represent a single-byte value (i.e.,  $0 \le ch \le 255$ ). Incorrect results occur if the argument is a double-byte character. This is shown by the example below.

**Returns:** The \_ismbbpunct function returns a non-zero value if the argument satisfies the condition; otherwise a zero value is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint,\_ismbbkpunct,\_ismbblead,\_ismbbprint,\_ismbbtrail,\_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = {

```
11',
    'A',
    0x8140, /* double-byte space */
    0x8260, /* double-byte A */
    0x82A6, /* double-byte Hiragana */
    0x8342, /* double-byte Katakana */
          /* single-byte Katakana punctuation */
           /* single-byte Katakana alphabetic */
    0xA6,
           /* single-byte Katakana alphabetic */
    0xDF,
    0xE0A1 /* double-byte Kanji */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
   _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa single-byte "
              "punctuation character\n",
            chars[i],
            ( _ismbbpunct( chars[i] ) ) ? "" : "not " );
  }
```

```
0x0020 is not a single-byte punctuation character 0x002e is a single-byte punctuation character 0x0031 is not a single-byte punctuation character 0x0041 is not a single-byte punctuation character 0x8140 is a single-byte punctuation character 0x8260 is a single-byte punctuation character 0x82a6 is not a single-byte punctuation character 0x8342 is not a single-byte punctuation character 0x00a1 is a single-byte punctuation character 0x00a6 is not a single-byte punctuation character 0x00df is not a single-byte punctuation character 0x00df is a single-byte punctuation character 0xe0a1 is a single-byte punctuation character
```

**Classification:** WATCOM

```
Synopsis:
           #include <mbstring.h>
           int _ismbbtrail( unsigned int ch );
```

**Description:** The \_ismbbtrail function tests if ch is a valid second byte of a multibyte character.

For example, in code page 932, valid ranges are 0x40 through 0x7E and 0x80 through 0xFC.

*Note:* Only the least significant (trailing) byte of the argument ch is tested. If the argument is a double-byte character, the leading byte is ignored and may be invalid. This is shown by the example below.

**Returns:** \_ismbbtrail returns a non-zero value if the argument is valid as the second byte of a multibyte character; otherwise zero is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h> unsigned int chars[] = { · ', 11, 'A',

> 0x8140, /\* double-byte space \*/ 0x8260, /\* double-byte A \*/ 0x82A6, /\* double-byte Hiragana \*/ 0x8342, /\* double-byte Katakana \*/ 0xA1, /\* single-byte Katakana punctuation \*/ 0xA6. /\* single-byte Katakana alphabetic \*/ /\* single-byte Katakana alphabetic \*/ 0xDF, 0xE0A1 /\* double-byte Kanji \*/ };

#define SIZE sizeof( chars ) / sizeof( unsigned int ) void main() { int i; \_setmbcp( 932 ); for( i = 0; i < SIZE; i++ ) { printf( "%#6.4x does %shave a valid second byte\n",

( \_ismbbtrail(chars[i]&0xff) ) ? "" : "not " );

produces the following:

}

chars[i],

```
0x0020 does not have a valid second byte 0x002e does not have a valid second byte 0x0031 does not have a valid second byte 0x0041 does have a valid second byte 0x8140 does have a valid second byte 0x8260 does have a valid second byte 0x82a6 does have a valid second byte 0x8342 does have a valid second byte 0x00a1 does have a valid second byte 0x00a6 does have a valid second byte 0x00df does have a valid second byte
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcalnum( unsigned int ch );
Description:
            The _ismbcalnum function tests if the multibyte character argument ch is an alphanumeric character.
            For example, in code page 932, 'A' through 'Z', 'a' through 'z', or '0' through '9' and its
            corresponding double-byte versions are alphanumeric (among others). An alphanumeric character is
            any character for which _ismbcalpha or _ismbcdigit is true.
Returns:
            The _ismbcalnum function returns zero if the argument is not an alphanumeric character; otherwise,
            a non-zero value is returned.
See Also:
            _getmbcp, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbcgraph, _ismbchira,
            _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal, _ismbclower,
            _ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                 ′.′,
                 '1',
                 'A',
                 0x8143, /* double-byte , */
                 0x8254, /* double-byte 5 */
                 0x8260, /* double-byte A */
                 0x8279, /* double-byte Z */
                 0x8281, /* double-byte a */
                 0x829A, /* double-byte z */
                 0x829F, /* double-byte Hiragana */
                 0x8340, /* double-byte Katakana */
                 0x837F, /* illegal double-byte character */
                 0x889E, /* double-byte L0 character */
                 0x889F, /* double-byte L1 character */
                 0x989F, /* double-byte L2 character */
                         /* single-byte Katakana */
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                 int
                       i;
                 _setmbcp( 932 );
                 for( i = 0; i < SIZE; i++ ) {
                   printf( "%#6.4x is %sa valid "
                          "multibyte alphanumeric character\n",
                          chars[i],
                          ( _ismbcalnum( chars[i] ) ) ? "" : "not " );
              }
            produces the following:
```

```
0x002e is not a valid multibyte alphanumeric character
0x0031 is a valid multibyte alphanumeric character
0x0041 is a valid multibyte alphanumeric character
0x8143 is not a valid multibyte alphanumeric character
0x8254 is a valid multibyte alphanumeric character
0x8260 is a valid multibyte alphanumeric character
0x8279 is a valid multibyte alphanumeric character
0x8281 is a valid multibyte alphanumeric character
0x829a is a valid multibyte alphanumeric character
0x829f is a valid multibyte alphanumeric character
0x8340 is a valid multibyte alphanumeric character
0x837f is not a valid multibyte alphanumeric character
0x889e is not a valid multibyte alphanumeric character
0x889f is a valid multibyte alphanumeric character
0x989f is a valid multibyte alphanumeric character
0x00a6 is a valid multibyte alphanumeric character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcalpha( unsigned int ch );
Description:
            The _ismbcalpha function tests if the multibyte character argument ch is an alphabetic character.
            For example, in code page 932, 'A' through 'Z' or 'a' through 'z' and its corresponding double-byte
            versions and the Katakana letters (0xA6 through 0xDF) are alphabetic.
Returns:
            The _ismbcalpha function returns zero if the argument is not an alphabetic character; otherwise, a
            non-zero value is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbccntrl, _ismbcdigit, _ismbcgraph, _ismbchira,
            _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal, _ismbclower,
            _ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                 ′.′,
                11,
                'A',
                 0x8143, /* double-byte , */
                 0x8254, /* double-byte 5 */
                 0x8260, /* double-byte A */
                 0x8279, /* double-byte Z */
                 0x8281, /* double-byte a */
                 0x829A, /* double-byte z */
                 0x829F, /* double-byte Hiragana */
                 0x8340, /* double-byte Katakana */
                 0x837F, /* illegal double-byte character */
                 0x889E, /* double-byte L0 character */
                 0x889F, /* double-byte L1 character */
                 0x989F, /* double-byte L2 character */
                         /* single-byte Katakana */
                 0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                       i;
                int
                _setmbcp( 932 );
                for( i = 0; i < SIZE; i++ ) {
                   printf( "%#6.4x is %sa valid "
                          "multibyte alphabetic character\n",
                          chars[i],
                          ( _ismbcalpha( chars[i] ) ) ? "" : "not " );
```

```
0x002e is not a valid multibyte alphabetic character
0x0031 is not a valid multibyte alphabetic character
0x0041 is a valid multibyte alphabetic character
0x8143 is not a valid multibyte alphabetic character
0x8254 is not a valid multibyte alphabetic character
0x8260 is a valid multibyte alphabetic character
0x8279 is a valid multibyte alphabetic character
0x8281 is a valid multibyte alphabetic character
0x829a is a valid multibyte alphabetic character
0x829f is a valid multibyte alphabetic character
0x8340 is a valid multibyte alphabetic character
0x837f is not a valid multibyte alphabetic character
0x889e is not a valid multibyte alphabetic character
0x889f is a valid multibyte alphabetic character
0x989f is a valid multibyte alphabetic character
0x00a6 is a valid multibyte alphabetic character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbccntrl( unsigned int ch );
Description:
            The _ismbccntrl function tests for any multibyte control character.
Returns:
            The _ismbcontrl function returns a non-zero value when the argument is a member of this set of
            characters; otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbcdigit, _ismbcgraph, _ismbchira,
            _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal, _ismbclower,
            _ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                0x0D,
                ' . ' ,
                11',
                'A',
                0x8140, /* double-byte space */
                0x8143, /* double-byte , */
                0x8254, /* double-byte 5 */
                0x8260, /* double-byte A */
                0x8279, /* double-byte Z */
                0x8281, /* double-byte a */
                0x829A, /* double-byte z */
                0x989F, /* double-byte L2 character */
                0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                int
                       i;
                _setmbcp( 932 );
                for( i = 0; i < SIZE; i++ ) {
                  printf( "%#6.4x is %sa valid "
                          "multibyte control character\n",
                         chars[i],
                          ( _ismbccntrl( chars[i] ) ) ? "" : "not " );
              }
            produces the following:
```

```
0x000d is a valid multibyte control character 0x002e is not a valid multibyte control character 0x0020 is not a valid multibyte control character 0x0031 is not a valid multibyte control character 0x0041 is not a valid multibyte control character 0x8140 is a valid multibyte control character 0x8143 is a valid multibyte control character 0x8254 is not a valid multibyte control character 0x8260 is not a valid multibyte control character 0x8279 is not a valid multibyte control character 0x8281 is not a valid multibyte control character 0x829a is not a valid multibyte control character 0x989f is not a valid multibyte control character 0x00a6 is not a valid multibyte control character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcdigit( unsigned int ch );
Description:
           The _ismbcdigit function tests for any multibyte decimal-digit character '0' through '9'. In code
            page 932, this includes the corresponding double-byte versions of these characters.
Returns:
            The _ismbcdigit function returns a non-zero value when the argument is a decimal-digit character.
            Otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcgraph, _ismbchira,
            _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal, _ismbclower,
            _ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                ′.′,
                '1',
                'A',
                0x8143, /* double-byte , */
                0x8183, /* double-byte < */
                0x8254, /* double-byte 5 */
                0x8277, /* double-byte X */
                0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                int
                       i;
                _setmbcp( 932 );
                for( i = 0; i < SIZE; i++ ) {
                  printf( "%#6.4x is %sa valid "
                          "multibyte digit character\n",
                         chars[i],
                          ( _ismbcdigit( chars[i] ) ) ? "" : "not " );
              }
            produces the following:
            0x002e is not a valid multibyte digit character
            0x0031 is a valid multibyte digit character
            0x0041 is not a valid multibyte digit character
            0x8143 is not a valid multibyte digit character
            0x8183 is not a valid multibyte digit character
            0x8254 is a valid multibyte digit character
            0x8277 is not a valid multibyte digit character
            0x00a6 is not a valid multibyte digit character
```

# \_ismbcdigit

**Classification:** WATCOM

```
Synopsis:
            #include <mbstring.h>
            int _ismbcgraph( unsigned int ch );
Description:
            The _ismbcgraph function tests for any printable multibyte character except space (''). The
            _ismbcprint function is similar, except that the space character is also included in the character set
            being tested.
Returns:
            The _ismbcgraph function returns a non-zero value when the argument is a member of this set of
            characters; otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbchira,
            _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal, _ismbclower,
            _ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                 ', .',
                 11,
                 'A',
                 0x8140, /* double-byte space */
                 0x8143, /* double-byte , */
                 0x8254, /* double-byte 5 */
                 0x8260, /* double-byte A */
                 0x8279, /* double-byte Z */
                 0x8281, /* double-byte a */
                 0x829A, /* double-byte z */
                 0x989F, /* double-byte L2 character */
                 0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                 int
                       i;
                 _setmbcp( 932 );
                 for ( i = 0; i < SIZE; i++ ) {
                   printf( "%#6.4x is %sa valid "
                          "multibyte graph character\n",
                          chars[i],
                          ( _ismbcgraph( chars[i] ) ) ? "" : "not " );
            produces the following:
```

```
0x002e is a valid multibyte graph character 0x0020 is not a valid multibyte graph character 0x0031 is a valid multibyte graph character 0x0041 is a valid multibyte graph character 0x8140 is not a valid multibyte graph character 0x8143 is a valid multibyte graph character 0x8254 is a valid multibyte graph character 0x8260 is a valid multibyte graph character 0x8279 is a valid multibyte graph character 0x8281 is a valid multibyte graph character 0x829a is a valid multibyte graph character 0x989f is a valid multibyte graph character 0x9006 is a valid multibyte graph character
```

```
Synopsis:
           #include <mbstring.h>
           int _ismbchira( unsigned int ch );
```

**Description:** The \_ismbchira function tests for a double-byte Hiragana character. A double-byte Hiragana character is any character for which the following expression is true:

```
0x829F \le ch \le 0x82F1
```

Note: The Japanese double-byte character set includes Kanji, Hiragana, and Katakana characters - both alphabetic and numeric. Kanji is the ideogram character set of the Japanese character set. Hiragana and Katakana are two types of phonetic character sets of the Japanese character set. The Hiragana code set includes 83 characters and the Katakana code set includes 86 characters.

**Returns:** The \_ismbchira function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclegal, \_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol, \_ismbcupper, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h>

```
#include <mbctype.h>
#include <mbstring.h>
unsigned int chars[] = {
    'A',
    0x8140, /* double-byte space */
    0x8143, /* double-byte , */
    0x8260, /* double-byte A */
    0x829F, /* double-byte Hiragana */
    0x8340, /* double-byte Katakana */
    0x837F, /* illegal double-byte character */
    0x989F, /* double-byte L2 character */
           /* single-byte Katakana */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa valid "
            "Hiragana character\n",
            chars[i],
            ( _ismbchira( chars[i] ) ) ? "" : "not " );
  }
```

produces the following:

```
0 \times 0041 is not a valid Hiragana character 0 \times 8140 is not a valid Hiragana character 0 \times 8143 is not a valid Hiragana character 0 \times 8260 is not a valid Hiragana character 0 \times 829f is a valid Hiragana character 0 \times 8340 is not a valid Hiragana character 0 \times 837f is not a valid Hiragana character 0 \times 837f is not a valid Hiragana character 0 \times 989f is not a valid Hiragana character 0 \times 0006 is not a valid Hiragana character
```

**Synopsis:** #include <mbstring.h> int \_ismbckata( unsigned int ch );

**Description:** The \_ismbckata function tests for a double-byte Katakana character. A double-byte Katakana character is any character for which the following expression is true:

```
0x8340 \le ch \le 0x8396 && ch != 0x837F
```

Note: The Japanese double-byte character set includes Kanji, Hiragana, and Katakana characters - both alphabetic and numeric. Kanji is the ideogram character set of the Japanese character set. Hiragana and Katakana are two types of phonetic character sets of the Japanese character set. The Hiragana code set includes 83 characters and the Katakana code set includes 86 characters.

**Returns:** The \_ismbckata function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclegal, \_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol, \_ismbcupper, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** #include <stdio.h> #include <mbctype.h>

```
#include <mbstring.h>
unsigned int chars[] = {
    'A',
    0x8140, /* double-byte space */
    0x8143, /* double-byte , */
    0x8260, /* double-byte A */
    0x829F, /* double-byte Hiragana */
    0x8340, /* double-byte Katakana */
    0x837F, /* illegal double-byte character */
    0x989F, /* double-byte L2 character */
           /* single-byte Katakana */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa valid "
            "Katakana character\n",
            chars[i],
            ( _ismbckata( chars[i] ) ) ? "" : "not " );
  }
```

produces the following:

```
0x0041 is not a valid Katakana character 0x8140 is not a valid Katakana character 0x8143 is not a valid Katakana character 0x8260 is not a valid Katakana character 0x829f is not a valid Katakana character 0x8340 is a valid Katakana character 0x837f is not a valid Katakana character 0x989f is not a valid Katakana character 0x00a6 is not a valid Katakana character
```

```
Synopsis:
           #include <mbstring.h>
           int _ismbcl0( unsigned int ch );
```

### **Description:**

The \_ismbcl0 function tests if the argument ch is in the set of double-byte characters that include Hiragana, Katakana, punctuation symbols, graphical symbols, Roman and Cyrillic alphabets, etc. Double-byte Kanji characters are not in this set. These are any characters for which the following expression is true:

```
0x8140 \le ch \le 0x889E \&\& ch != 0x837F
```

The \_ismbcl0 function tests if the argument is a valid double-byte character (i.e., it checks that the lower byte is not in the ranges 0x00 - 0x3F, 0x7F, or 0xFD - 0xFF).

Note: The Japanese double-byte character set includes Kanji, Hiragana, and Katakana characters - both alphabetic and numeric. Kanji is the ideogram character set of the Japanese character set. Hiragana and Katakana are two types of phonetic character sets of the Japanese character set. The Hiragana code set includes 83 characters and the Katakana code set includes 86 characters.

**Returns:** 

The \_ismbc10 function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also:

```
_getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbcgraph,
_ismbchira, _ismbckata, _ismbcl1, _ismbcl2, _ismbclegal, _ismbclower,
_ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
_ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
```

### **Example:**

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
unsigned int chars[] = {
    'A',
    0x8140, /* double-byte space */
    0x8143, /* double-byte , */
    0x8260, /* double-byte A */
    0x829F, /* double-byte Hiragana */
    0x8340, /* double-byte Katakana */
    0x837F, /* illegal double-byte character */
    0x889E, /* double-byte L0 character */
    0x889F, /* double-byte L1 character */
    0x989F, /* double-byte L2 character */
           /* single-byte Katakana */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
    int
          i;
```

```
_setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa valid "
            "JIS LO character\n",
            chars[i],
            ( _ismbcl0( chars[i] ) ) ? "" : "not " );
  }
produces the following:
0x0041 is not a valid JIS LO character
0x8140 is a valid JIS LO character
0x8143 is a valid JIS LO character
0x8260 is a valid JIS LO character
0x829f is a valid JIS LO character
0x8340 is a valid JIS LO character
0x837f is not a valid JIS LO character
0x889e is a valid JIS LO character
0x889f is not a valid JIS LO character
0x989f is not a valid JIS LO character
0x00a6 is not a valid JIS LO character
```

**Synopsis:** #include <mbstring.h> int \_ismbcl1( unsigned int ch );

## **Description:**

The \_ismbcl1 function tests if the argument ch is a JIS (Japan Industrial Standard) level 1 double-byte character code. These are any valid double-byte characters for which the following expression is true:

```
0x889F \le ch \le 0x9872
```

The \_ismbcll function tests if the argument is a valid double-byte character (i.e., it checks that the lower byte is not in the ranges 0x00 - 0x3F, 0x7F, or 0xFD - 0xFF).

Note: JIS establishes two levels of the Kanji double-byte character set. One is called double-byte Kanji code set level 1 and the other is called double-byte Kanji code set level 2. Usually Japanese personal computers have font ROM/RAM support for both levels.

Valid double-byte characters are those in which the first byte falls in the range 0x81 - 0x9F or 0xE0 -0xFC and whose second byte falls in the range 0x40 - 0x7E or 0x80 - 0xFC.

## **Returns:**

The \_ismbcl1 function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

## See Also:

\_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl2, \_ismbclegal, \_ismbclower, \_ismbcprint,\_ismbcpunct,\_ismbcspace,\_ismbcsymbol,\_ismbcupper, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

## **Example:**

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
unsigned int chars[] = {
    'A',
    0x8140, /* double-byte space */
    0x8143, /* double-byte , */
    0x8260, /* double-byte A */
    0x829F, /* double-byte Hiragana */
    0x8340, /* double-byte Katakana */
    0x837F, /* illegal double-byte character */
    0x889E, /* double-byte L0 character */
    0x889F, /* double-byte L1 character */
    0x989F, /* double-byte L2 character */
            /* single-byte Katakana */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
```

```
_setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa valid "
            "JIS L1 character\n",
            chars[i],
            ( _ismbcl1( chars[i] ) ) ? "" : "not " );
  }
produces the following:
0x0041 is not a valid JIS L1 character
0x8140 is not a valid JIS L1 character
0x8143 is not a valid JIS L1 character
0x8260 is not a valid JIS L1 character
0x829f is not a valid JIS L1 character
0x8340 is not a valid JIS L1 character
0x837f is not a valid JIS L1 character
0x889e is not a valid JIS L1 character
0x889f is a valid JIS L1 character
0x989f is not a valid JIS L1 character
0x00a6 is not a valid JIS L1 character
```

**Synopsis:** #include <mbstring.h> int \_ismbcl2( unsigned int ch );

### **Description:**

The \_ismbc12 function tests if the argument ch is a JIS (Japan Industrial Standard) level 2 double-byte character code. These are any valid double-byte characters for which the following expression is true:

```
0x989F \le ch \le 0xEA9E
```

The \_ismbcl2 function tests if the argument is a valid double-byte character (i.e., it checks that the lower byte is not in the ranges 0x00 - 0x3F, 0x7F, or 0xFD - 0xFF).

Note: JIS establishes two levels of the Kanji double-byte character set. One is called double-byte Kanji code set level 1 and the other is called double-byte Kanji code set level 2. Usually Japanese personal computers have font ROM/RAM support for both levels.

Valid double-byte characters are those in which the first byte falls in the range 0x81 - 0x9F or 0xE0 -0xFC and whose second byte falls in the range 0x40 - 0x7E or 0x80 - 0xFC.

## **Returns:**

The \_ismbcl2 function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

## See Also:

\_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbclegal, \_ismbclower, \_ismbcprint,\_ismbcpunct,\_ismbcspace,\_ismbcsymbol,\_ismbcupper, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

## **Example:**

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
unsigned int chars[] = {
    'A',
    0x8140, /* double-byte space */
    0x8143, /* double-byte , */
    0x8260, /* double-byte A */
    0x829F, /* double-byte Hiragana */
    0x8340, /* double-byte Katakana */
    0x837F, /* illegal double-byte character */
    0x889E, /* double-byte L0 character */
    0x889F, /* double-byte L1 character */
    0x989F, /* double-byte L2 character */
    0xEA9E, /* double-byte L2 character */
           /* single-byte Katakana */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
          i;
    int
```

```
_setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( "%#6.4x is %sa valid "
            "JIS L2 character\n",
            chars[i],
            ( _ismbcl2( chars[i] ) ) ? "" : "not " );
    }
  }
produces the following:
0x0041 is not a valid JIS L2 character
0x8140 is not a valid JIS L2 character
0x8143 is not a valid JIS L2 character
0x8260 is not a valid JIS L2 character
0x829f is not a valid JIS L2 character
0x8340 is not a valid JIS L2 character
0x837f is not a valid JIS L2 character
0x889e is not a valid JIS L2 character
0x889f is not a valid JIS L2 character
0x989f is a valid JIS L2 character
Oxea9e is a valid JIS L2 character
0x00a6 is not a valid JIS L2 character
```

```
Synopsis:
           #include <mbstring.h>
           int _ismbclegal( unsigned int dbch );
```

**Description:** 

The \_ismbclegal function tests for a valid multibyte character. Multibyte characters include both single-byte and double-byte characters. For example, in code page 932, a legal double-byte character is one in which the first byte is within the ranges 0x81 - 0x9F or 0xE0 - 0xFC, while the second byte is within the ranges 0x40 - 0x7E or 0x80 - 0xFC. This is summarized in the following diagram.

```
[ 2nd byte ]
[ 1st byte ]
0x81 - 0x9F
                 0x40-0xFC
                  except 0x7F
     or
0xE0-0xFC
```

**Returns:** The \_ismbclegal function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol, \_ismbcupper,

\_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

0x8143, /\* double-byte , \*/

```
Example:
           #include <stdio.h>
           #include <mbctype.h>
           #include <mbstring.h>
           unsigned int chars[] = {
               ·Α',
               0x8131, /* illegal double-byte character */
               0x8140, /* double-byte space */
```

void main()

```
0x8260, /* double-byte A */
    0x829F, /* double-byte Hiragana */
    0x8340, /* double-byte Katakana */
    0x837F, /* illegal double-byte character */
    0x889E, /* double-byte L0 character */
    0x889F, /* double-byte L1 character */
    0x989F, /* double-byte L2 character */
    0xEA9E, /* double-byte L2 character */
          /* single-byte Katakana */
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
```

```
{
  int
        i;
  _setmbcp( 932 );
 for( i = 0; i < SIZE; i++ ) {
   printf( "%#6.4x is %sa legal "
          "double-byte character\n",
          chars[i],
          ( _ismbclegal( chars[i] ) ) ? "" : "not " );
 }
}
```

## produces the following:

```
0x0041 is not a legal double-byte character 0x8131 is not a legal double-byte character 0x8140 is a legal double-byte character 0x8143 is a legal double-byte character 0x8260 is a legal double-byte character 0x829f is a legal double-byte character 0x8340 is a legal double-byte character 0x837f is not a legal double-byte character 0x889e is a legal double-byte character 0x889f is a legal double-byte character 0x989f is a legal double-byte character 0xea9e is a legal double-byte character 0xea9e is a legal double-byte character 0x00a6 is not a legal double-byte character
```

**Classification:** WATCOM

```
Synopsis:
           #include <mbstring.h>
           int _ismbclower( unsigned int ch );
```

**Description:** The \_ismbclower function tests for a valid lowercase multibyte character. Multibyte characters include both single-byte and double-byte characters. For example, in code page 932, a lowercase double-byte character is one for which the following expression is true:

```
0x8281 \le c \le 0x829A
```

**Returns:** The \_ismbclower function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclegal, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol, \_ismbcupper, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

```
Example:
           #include <stdio.h>
           #include <mbctype.h>
           #include <mbstring.h>
           unsigned int chars[] = {
               11',
               'A',
               ′a′,
               0x8140, /* double-byte space */
               0x8143, /* double-byte , */
               0x8254, /* double-byte 5 */
               0x8260, /* double-byte A */
               0x8279, /* double-byte Z */
               0x8281, /* double-byte a */
               0x829A, /* double-byte z */
               0x989F, /* double-byte L2 character */
               0xA6
           };
           #define SIZE sizeof( chars ) / sizeof( unsigned int )
           void main()
             {
               int
                     i;
               _setmbcp( 932 );
               for( i = 0; i < SIZE; i++ ) {
                 printf( "%#6.4x is %sa valid "
                        "multibyte lowercase character\n",
                       chars[i],
                        ( _ismbclower( chars[i] ) ) ? "" : "not " );
```

produces the following:

```
0x0031 is not a valid multibyte lowercase character 0x0041 is not a valid multibyte lowercase character 0x0061 is a valid multibyte lowercase character 0x8140 is not a valid multibyte lowercase character 0x8143 is not a valid multibyte lowercase character 0x8254 is not a valid multibyte lowercase character 0x8260 is not a valid multibyte lowercase character 0x8279 is not a valid multibyte lowercase character 0x8281 is a valid multibyte lowercase character 0x829a is a valid multibyte lowercase character 0x989f is not a valid multibyte lowercase character 0x00a6 is not a valid multibyte lowercase character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcprint( unsigned int ch );
Description:
            The _ismbcprint function tests for any printable multibyte character including space (''). The
            _ismbcgraph function is similar, except that the space character is not included in the character set
            being tested.
Returns:
            The _ismbcprint function returns a non-zero value when the argument is a member of this set of
            characters; otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbcgraph,
            _ismbchira, _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal,
            _ismbclower, _ismbcpunct, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                 ', .',
                 11,
                 'A',
                 0x8140, /* double-byte space */
                 0x8143, /* double-byte , */
                 0x8254, /* double-byte 5 */
                 0x8260, /* double-byte A */
                 0x8279, /* double-byte Z */
                 0x8281, /* double-byte a */
                 0x829A, /* double-byte z */
                 0x989F, /* double-byte L2 character */
                 0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                 int
                       i;
                 _setmbcp( 932 );
                 for ( i = 0; i < SIZE; i++ ) {
                   printf( "%#6.4x is %sa valid "
                          "multibyte print character\n",
                          chars[i],
                          ( _ismbcprint( chars[i] ) ) ? "" : "not " );
            produces the following:
```

```
0x002e is a valid multibyte print character 0x0020 is a valid multibyte print character 0x0031 is a valid multibyte print character 0x0041 is a valid multibyte print character 0x8140 is a valid multibyte print character 0x8143 is a valid multibyte print character 0x8254 is a valid multibyte print character 0x8260 is a valid multibyte print character 0x8279 is a valid multibyte print character 0x8281 is a valid multibyte print character 0x829a is a valid multibyte print character 0x989f is a valid multibyte print character 0x00a6 is a valid multibyte print character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcpunct( unsigned int ch );
Description:
           The _ismbcpunct function tests for any multibyte punctuation character.
Returns:
            The _ismbcpunct function returns a non-zero value when the argument is a member of this set of
            characters; otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbcgraph,
            _ismbchira, _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal,
            _ismbclower, _ismbcprint, _ismbcspace, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                '.',
                , ,
                '1',
                'A',
                0x8140, /* double-byte space */
                0x8143, /* double-byte , */
                0x8254, /* double-byte 5 */
                0x8260, /* double-byte A */
                0x8279, /* double-byte Z */
                0x8281, /* double-byte a */
                0x829A, /* double-byte z */
                0x989F, /* double-byte L2 character */
                         /* single-byte Katakana punctuation */
                0xA6
                         /* single-byte Katakana alphabetic */
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                int
                       i;
                _setmbcp( 932 );
                for( i = 0; i < SIZE; i++ ) {
                  printf( "%#6.4x is %sa valid "
                         "multibyte punctuation character\n",
                         chars[i],
                         ( _ismbcpunct( chars[i] ) ) ? "" : "not " );
              }
            produces the following:
```

```
0 \times 002e is a valid multibyte punctuation character 0 \times 0020 is not a valid multibyte punctuation character 0 \times 0031 is not a valid multibyte punctuation character 0 \times 0041 is not a valid multibyte punctuation character 0 \times 8140 is not a valid multibyte punctuation character 0 \times 8143 is a valid multibyte punctuation character 0 \times 8254 is not a valid multibyte punctuation character 0 \times 8260 is not a valid multibyte punctuation character 0 \times 8279 is not a valid multibyte punctuation character 0 \times 8281 is not a valid multibyte punctuation character 0 \times 829a is not a valid multibyte punctuation character 0 \times 989f is not a valid multibyte punctuation character 0 \times 0046 is not a valid multibyte punctuation character 0 \times 0046 is not a valid multibyte punctuation character 0 \times 0046 is not a valid multibyte punctuation character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcspace( unsigned int ch );
Description:
            The _ismbcspace function tests for any multibyte space character. Multibyte characters include
            both single-byte and double-byte characters. For example, in code page 932, the double-byte space
            character is 0x8140.
Returns:
            The _ismbcspace function returns a non-zero value when the argument is a member of this set of
            characters; otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbcgraph,
            _ismbchira, _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal,
            _ismbclower, _ismbcprint, _ismbcpunct, _ismbcsymbol, _ismbcupper,
            _ismbcxdigit, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                 0x09,
                 '...',
                 11,
                 'A',
                 0x8140, /* double-byte space */
                 0x8143, /* double-byte , */
                 0x8254, /* double-byte 5 */
                 0x8260, /* double-byte A */
                 0x8279, /* double-byte Z */
                 0x8281, /* double-byte a */
                 0x829A, /* double-byte z */
                 0x989F, /* double-byte L2 character */
                 0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                 int
                       i;
                 _setmbcp( 932 );
                 for( i = 0; i < SIZE; i++ ) {
                   printf( "%#6.4x is %sa valid "
                          "multibyte space character\n",
                          chars[i],
                          ( _ismbcspace( chars[i] ) ) ? "" : "not " );
              }
```

produces the following:

```
0x0009 is a valid multibyte space character 0x002e is not a valid multibyte space character 0x0020 is a valid multibyte space character 0x0031 is not a valid multibyte space character 0x0041 is not a valid multibyte space character 0x8140 is a valid multibyte space character 0x8143 is not a valid multibyte space character 0x8254 is not a valid multibyte space character 0x8260 is not a valid multibyte space character 0x8279 is not a valid multibyte space character 0x8281 is not a valid multibyte space character 0x829a is not a valid multibyte space character 0x989f is not a valid multibyte space character 0x9006 is not a valid multibyte space character
```

```
Synopsis:
           #include <mbstring.h>
           int _ismbcsymbol( unsigned int ch );
```

**Description:** The \_ismbcsymbol function tests for a valid multibyte symbol character (punctuation and other special graphical symbols). For example, in code page 932, \_ismbcsymbol tests for a double-byte Kigou character and returns true if and only if

```
0x8141 \le ch \le 0x81AC && ch != 0x817F
```

**Returns:** The \_ismbcsymbol function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclegal, \_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcupper, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

```
Example:
           #include <stdio.h>
           #include <mbctype.h>
           #include <mbstring.h>
           unsigned int chars[] = {
               ,·,,
               '1',
               'A',
               0x8140, /* double-byte space */
               0x8143, /* double-byte , */
               0x8254, /* double-byte 5 */
               0x8260, /* double-byte A */
               0x8279, /* double-byte Z */
               0x8281, /* double-byte a */
               0x829A, /* double-byte z */
               0x989F, /* double-byte L2 character */
               0xA6
           };
           #define SIZE sizeof( chars ) / sizeof( unsigned int )
           void main()
             {
               int
                     i;
               _setmbcp( 932 );
               for( i = 0; i < SIZE; i++ ) {
                 printf( "%#6.4x is %sa valid "
                        "multibyte symbol character\n",
                        chars[i],
                        ( _ismbcsymbol( chars[i] ) ) ? "" : "not " );
```

produces the following:

}

```
0x002e is not a valid multibyte symbol character 0x0020 is not a valid multibyte symbol character 0x0031 is not a valid multibyte symbol character 0x0041 is not a valid multibyte symbol character 0x8140 is not a valid multibyte symbol character 0x8143 is a valid multibyte symbol character 0x8254 is not a valid multibyte symbol character 0x8260 is not a valid multibyte symbol character 0x8279 is not a valid multibyte symbol character 0x8281 is not a valid multibyte symbol character 0x829a is not a valid multibyte symbol character 0x989f is not a valid multibyte symbol character 0x9036 is not a valid multibyte symbol character 0x0036 is not a valid multibyte symbol character
```

```
Synopsis:
           #include <mbstring.h>
           int _ismbcupper( unsigned int ch );
```

**Description:** The \_ismbcupper function tests for a valid uppercase multibyte character. Multibyte characters include both single-byte and double-byte characters. For example, in code page 932, an uppercase double-byte character is one for which the following expression is true:

```
0x8260 \le c \le 0x8279
```

**Returns:** The \_ismbcupper function returns a non-zero value when the argument is a member of this set of characters; otherwise, zero is returned.

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph, \_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclegal, \_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol, \_ismbcxdigit, \_mbbtype, \_mbsbtype, \_setmbcp

```
Example:
           #include <stdio.h>
           #include <mbctype.h>
           #include <mbstring.h>
           unsigned int chars[] = {
               11',
               'A',
               ′a′,
               0x8140, /* double-byte space */
               0x8143, /* double-byte , */
               0x8254, /* double-byte 5 */
               0x8260, /* double-byte A */
               0x8279, /* double-byte Z */
               0x8281, /* double-byte a */
               0x829A, /* double-byte z */
               0x989F, /* double-byte L2 character */
               0xA6
           };
           #define SIZE sizeof( chars ) / sizeof( unsigned int )
           void main()
             {
               int
                     i;
               _setmbcp( 932 );
               for( i = 0; i < SIZE; i++ ) {
                 printf( "%#6.4x is %sa valid "
                        "multibyte uppercase character\n",
```

( \_ismbcupper( chars[i] ) ) ? "" : "not " );

produces the following:

chars[i],

```
0x0031 is not a valid multibyte uppercase character 0x0041 is a valid multibyte uppercase character 0x0061 is not a valid multibyte uppercase character 0x8140 is not a valid multibyte uppercase character 0x8143 is not a valid multibyte uppercase character 0x8254 is not a valid multibyte uppercase character 0x8260 is a valid multibyte uppercase character 0x8279 is a valid multibyte uppercase character 0x8281 is not a valid multibyte uppercase character 0x829a is not a valid multibyte uppercase character 0x989f is not a valid multibyte uppercase character 0x00a6 is not a valid multibyte uppercase character
```

```
Synopsis:
            #include <mbstring.h>
            int _ismbcxdigit( unsigned int ch );
Description:
           The _ismbcxdigit function tests for any multibyte hexadecimal-digit character '0' through '9' or
            'A' through 'F'. In code page 932, this includes the corresponding double-byte versions of these
            characters.
Returns:
            The _ismbcxdigit function returns a non-zero value when the argument is a hexadecimal-digit
            character. Otherwise, zero is returned.
See Also:
            _getmbcp, _ismbcalnum, _ismbcalpha, _ismbccntrl, _ismbcdigit, _ismbcgraph,
            _ismbchira, _ismbckata, _ismbcl0, _ismbcl1, _ismbcl2, _ismbclegal,
            _ismbclower, _ismbcprint, _ismbcpunct, _ismbcspace, _ismbcsymbol,
            _ismbcupper, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned int chars[] = {
                ·.',
                '1',
                'A',
                0x8143, /* double-byte "," */
                0x8183, /* double-byte "<" */
                0x8254, /* double-byte "5" */
                0x8265, /* double-byte "F" */
                0xA6
            };
            #define SIZE sizeof( chars ) / sizeof( unsigned int )
            void main()
              {
                int
                       i;
                _setmbcp( 932 );
                for( i = 0; i < SIZE; i++ ) {
                  printf( "%#6.4x is %sa valid "
                         "multibyte hexadecimal digit character\n",
                         chars[i],
                          ( _ismbcxdigit( chars[i] ) ) ? "" : "not " );
              }
            produces the following:
            0x002e is not a valid multibyte hexadecimal digit character
            0x0031 is a valid multibyte hexadecimal digit character
            0x0041 is a valid multibyte hexadecimal digit character
            0x8143 is not a valid multibyte hexadecimal digit character
            0x8183 is not a valid multibyte hexadecimal digit character
            0x8254 is a valid multibyte hexadecimal digit character
            0x8265 is a valid multibyte hexadecimal digit character
            0x00a6 is not a valid multibyte hexadecimal digit character
```

# \_ismbcxdigit

**Classification:** WATCOM

**Synopsis:** #include <math.h> int isnan(x);

**Description:** The isnan macro determines whether its argument x is a NaN. First, an argument represented in a

format wider than its semantic type is converted to its semantic type. Then determination is based on

the type of the argument.

The argument *x* must be an expression of real floating type.

**Returns:** The isnan macro returns a nonzero value if and only if its argument has a NaN value.

See Also: fpclassify, isfinite, isinf, isnormal, signbit

**Example:** #include <math.h> #include <stdio.h>

```
void main( void )
   printf( "NAN %s a NaN\n",
        isnan( NAN ) ? "is" : "is not" );
```

produces the following:

NAN is a NaN

Classification: ISO C

**Systems: MACRO**  Synopsis: #include <math.h>
 int isnormal(x);

**Description:** The isnormal macro determines whether its argument value is normal (neither zero, subnormal,

infinite, nor NaN). First, an argument represented in a format wider than its semantic type is converted

to its semantic type. Then determination is based on the type of the argument.

The argument *x* must be an expression of real floating type.

**Returns:** The isnormal macro returns a nonzero value if and only if its argument has a normal value.

See Also: fpclassify, isfinite, isinf, isnan, signbit

Example: #include <math.h>

produces the following:

zero is not a normal number

**Classification:** ISO C

**Systems:** MACRO

```
Synopsis:
           #include <ctype.h>
           int isprint( int c );
           #include <wctype.h>
           int iswprint( wint_t c );
```

The isprint function tests for any printable character including space (''). The isgraph function **Description:** is similar, except that the space character is excluded from the character set being tested.

> The iswprint function is a wide character version of isprint that operates with wide character argument.

**Returns:** The isprint function returns a non-zero value when the argument is a printable character. The

iswprint function returns a non-zero value when the argument is a printable wide character.

Otherwise, zero is returned.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'Α',
    0x09,
    , ,
    0x7d
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
{
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "Char %c is %sa printable character\n",
                 chars[i],
                 ( isprint( chars[i] ) ) ? "" : "not " );
    }
}
produces the following:
Char A is a printable character
```

is not a printable character

Char is a printable character Char } is a printable character

**Classification:** ISO C

iswprint is ISO C95

Char

# isprint, iswprint

isprint - All, Linux, RDOS, Netware iswprint - All, Linux, RDOS, Netware **Systems:** 

```
Synopsis:
           #include <ctype.h>
           int ispunct( int c );
           #include <wctype.h>
           int iswpunct( wint_t c );
```

**Description:** The ispunct function tests for any punctuation character such as a comma (,) or a period (.).

> The iswpunct function is a wide character version of ispunct that operates with wide character argument.

**Returns:** 

The ispunct function returns a non-zero value when the argument is a punctuation character. The iswpunct function returns a non-zero value when the argument is a printable wide character that is neither the space wide character nor a wide character for which iswalnum is true. Otherwise, zero is returned.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'A',
    '!',
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
{
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "Char %c is %sa punctuation character\n",
                 chars[i],
                 ( ispunct( chars[i] ) ) ? "" : "not " );
produces the following:
```

```
Char A is not a punctuation character
Char! is a punctuation character
Char . is a punctuation character
Char , is a punctuation character
Char : is a punctuation character
Char ; is a punctuation character
```

## ispunct, iswpunct

Classification: ISO C

iswpunct is ISO C95

**Systems:** 

ispunct - All, Linux, RDOS, Netware
iswpunct - All, Linux, RDOS, Netware

#### **Synopsis:** #include <ctype.h> int isspace( int c );

#include <wctype.h> int iswspace( wint\_t c );

**Description:** The isspace function tests for the following white-space characters:

Constant	Character		
,,	space		
'\f'	form feed		
'\n'	new-line or linefeed		
'\r'	carriage return		
'\t'	horizontal tab		
'\v'	vertical tab		

The iswspace function is a wide character version of isspace that operates with wide character argument.

## **Returns:**

The isspace function returns a non-zero character when the argument is one of the indicated white-space characters. The iswspace function returns a non-zero value when the argument is a wide character that corresponds to a standard white-space character or is one of an implementation-defined set of wide characters for which iswalnum is false. Otherwise, zero is returned.

## See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

## **Example:**

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'A',
    0x09,
    , ,
    0x7d
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
{
    int
        i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "Char %c is %sa space character\n",
                chars[i],
                 ( isspace( chars[i] ) ) ? "" : "not " );
    }
```

produces the following:

Char A is not a space character
Char is a space character
Char is a space character
Char } is not a space character

Classification: ISO C

iswspace is ISO C95

Systems: isspace - All, Linux, RDOS, Netware

iswspace - All, Linux, RDOS, Netware

```
Synopsis:
```

```
#include <ctype.h>
int isupper( int c );
#include <wctype.h>
int iswupper( wint_t c );
```

**Description:** 

The isupper function tests for any uppercase letter 'A' through 'Z'.

The iswupper function is a wide character version of isupper that operates with wide character argument.

**Returns:** 

The isupper function returns a non-zero value when the argument is an uppercase letter. The iswupper function returns a non-zero value when the argument is a wide character that corresponds to an uppercase letter, or if it is one of an implementation-defined set of wide characters for which none of iswcntrl, iswdigit, iswpunct, or iswspace is true. Otherwise, zero is returned.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'Α',
    ′a′,
    'z',
    'Z'
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
{
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "Char %c is %san uppercase character\n",
                 chars[i],
                 ( isupper( chars[i] ) ) ? "" : "not " );
    }
}
produces the following:
Char A is an uppercase character
Char a is not an uppercase character
```

**Classification:** ISO C

iswupper is ISO C95

Char z is not an uppercase character Char Z is an uppercase character

## isupper, iswupper

isupper - All, Linux, RDOS, Netware iswupper - All, Linux, RDOS, Netware **Systems:** 

**Synopsis:** #include <wctype.h>

int iswctype( wint\_t wc, wctype\_t desc );

**Description:** 

The iswetype function determines whether the wide character wc has the property described by desc. Valid values of *desc* are defined by the use of the wctype function.

The twelve expressions listed below have a truth-value equivalent to a call to the wide character testing function shown.

Expression	Equivalent
<pre>iswctype(wc, wctype("alnum"))</pre>	iswalnum(wc)
iswctype(wc, wctype(''alpha''))	iswalpha(wc)
iswctype(wc, wctype(''blank''))	iswblank(wc)
iswctype(wc, wctype("cntrl"))	iswcntrl(wc)
iswctype(wc, wctype(''digit''))	iswdigit(wc)
<pre>iswctype(wc, wctype("graph"))</pre>	iswgraph(wc)
iswctype(wc, wctype(''lower''))	iswlower(wc)
<pre>iswctype(wc, wctype("print"))</pre>	iswprint(wc)
<pre>iswctype(wc, wctype("punct"))</pre>	iswpunct(wc)
<pre>iswctype(wc, wctype("space"))</pre>	iswspace(wc)
<pre>iswctype(wc, wctype("upper"))</pre>	iswupper(wc)
iswctype(wc, wctype("xdigit"))	iswxdigit(wc)

**Returns:** 

The iswetype function returns non-zero (true) if and only if the value of the wide character wc has the property described by desc.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, wctype, wctrans, towctrans

**Example:** 

**Systems:** 

```
#include <stdio.h>
           #include <wctype.h>
           char *types[] = {
                "alnum",
                "alpha",
                "blank",
                "cntrl",
                "digit",
                "graph",
                "lower",
                "print",
                "punct",
                "space",
                "upper",
                "xdigit"
           };
           void main( void )
                int
                        i;
                wint_t wc = 'A';
                for( i = 0; i < 12; i++ )
                    if( iswctype( wc, wctype( types[i] ) ) )
                         printf( "%s\n", types[i] );
           }
           produces the following:
           alnum
           alpha
           graph
           print
           upper
           xdigit
Classification: ISO C95
```

All, Linux, RDOS

```
Synopsis:
           #include <ctype.h>
           int isxdigit( int c );
           #include <wchar.h>
           int iswxdigit( wint_t c );
```

The isxdigit function tests for any hexadecimal-digit character. These characters are the digits ('0' **Description:** through '9') and the letters ('a' through 'f') and ('A' through 'F').

> The iswxdigit function is a wide character version of isxdigit that operates with wide character argument.

**Returns:** 

The isxdigit function returns a non-zero value when the argument is a hexadecimal-digit character. The iswxdigit function returns a non-zero value when the argument is a wide character that corresponds to a hexadecimal-digit character. Otherwise, zero is returned.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
char chars[] = {
    'A',
    '5',
    '$'
};
 .exmp break
#define SIZE sizeof( chars ) / sizeof( char )
void main()
  {
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
      printf( "Char %c is %sa hexadecimal digit"
            " character\n", chars[i],
             ( isxdigit( chars[i] ) ) ? "" : "not " );
  }
```

produces the following:

```
Char A is a hexadecimal digit character
Char 5 is a hexadecimal digit character
Char $ is not a hexadecimal digit character
```

Classification: ISO C

iswxdigit is ISO C95

**Systems:** isxdigit - All, Linux, RDOS, Netware iswxdigit - All, Linux, RDOS, Netware

isxdigit, iswxdigit			

**Synopsis:** 

```
#include <stdlib.h>
char *itoa( int value, char *buffer, int radix );
char *_itoa( int value, char *buffer, int radix );
wchar_t *_itow( int value, wchar_t *buffer,
                int radix );
```

**Description:** 

The itoa function converts the binary integer value into the equivalent string in base radix notation storing the result in the character array pointed to by buffer. A null character is appended to the result. The size of buffer must be at least (8 \* sizeof(int) + 1) bytes when converting values in base 2. That makes the size 17 bytes on 16-bit machines, and 33 bytes on 32-bit machines. The value of radix must satisfy the condition:

```
2 <= radix <= 36
```

If radix is 10 and value is negative, then a minus sign is prepended to the result.

The \_itoa function is identical to itoa. Use \_itoa for ANSI naming conventions.

The \_itow function is a wide character version of itoa except that it produces a wide character string.

**Returns:** The itoa function returns the pointer to the result.

See Also:

atoi, atol, atoll, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull, strtoimax, strtoumax, ultoa, ulltoa, utoa

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
void main()
    char buffer[20];
    int base;
    for( base = 2; base <= 16; base = base + 2)
        printf( "%2d %s\n", base,
                itoa( 12765, buffer, base ) );
}
```

produces the following:

```
2 11000111011101
 4 3013131
 6 135033
8 30735
10 12765
12 7479
14 491b
16 31dd
```

**Classification:** WATCOM

itoa conforms to ANSI naming conventions

**Systems:** itoa - All, Linux, RDOS, Netware

```
_itoa - All, Linux, RDOS, Netware
_itow - All, Linux, RDOS
```

```
Synopsis:
           #include <conio.h>
           int kbhit( void );
           int _kbhit( void );
```

**Description:** The kbhit function tests whether or not a keystroke is currently available. When one is available, the function getch or getche may be used to obtain the keystroke in question.

> With a stand-alone program, the kbhit function may be called continuously until a keystroke is available.

The \_kbhit function is identical to kbhit. Use \_kbhit for ANSI naming conventions.

**Returns:** The kbhit function returns zero when no keystroke is available; otherwise, a non-zero value is returned.

See Also: getch, getche, putch, ungetch

```
Example:
            * This program loops until a key is pressed
            * or a count is exceeded.
           #include <stdio.h>
           #include <conio.h>
           void main( void )
               unsigned long i;
               printf( "Program looping. Press any key.\n" );
               for(i = 0; i < 10000; i++) {
                   if( kbhit() ) {
                       getch();
                       break;
               }
           }
```

### **Classification:** WATCOM

\_kbhit conforms to ANSI naming conventions

```
Systems:
           kbhit - All, Linux, RDOS, Netware
           _kbhit - All, RDOS, Netware
```

```
Synopsis:
             #include <stdlib.h>
             long int labs( long int j );
Description:
            The labs function returns the absolute value of its long-integer argument j.
Returns:
             The labs function returns the absolute value of its argument.
See Also:
             abs, llabs, imaxabs, fabs
Example:
             #include <stdio.h>
             #include <stdlib.h>
             void main( void )
                  long x, y;
                 x = -50000L;
                 y = labs(x);
                 printf( "labs(%ld) = %ld\n", x, y );
             }
             produces the following:
             labs(-50000) = 50000
Classification: ISO C90
```

**Systems:** All, Linux, RDOS, Netware **Synopsis:** #include <math.h> double ldexp( double x, int exp );

**Description:** The ldexp function multiplies a floating-point number by an integral power of 2. A range error may

occur.

**Returns:** The 1dexp function returns the value of x times 2 raised to the power exp.

See Also: frexp, modf

**Example:** #include <stdio.h> #include <math.h>

> void main() double value; value = 1dexp(4.7072345, 5);printf(  $\$f\n$ , value );

produces the following:

150.631504

Classification: ISO C

```
Synopsis:
            #include <stdlib.h>
            ldiv_t ldiv( long int numer, long int denom );
            typedef struct {
                                      /* quotient */
                 long int quot;
                                       /* remainder */
                 long int rem;
            } ldiv_t;
Description:
            The ldiv function calculates the quotient and remainder of the division of the numerator numer by the
            denominator denom.
Returns:
            The ldiv function returns a structure of type ldiv_t that contains the fields quot and rem, which
            are both of type long int.
See Also:
            div, lldiv, imaxdiv
Example:
            #include <stdio.h>
            #include <stdlib.h>
            void print_time( long int ticks )
                 ldiv_t sec_ticks;
                 ldiv_t min_sec;
                 sec_ticks = ldiv( ticks, 100L );
                 min_sec = ldiv( sec_ticks.quot, 60L );
                 printf( "It took %ld minutes and %ld seconds\n",
                          min_sec.quot, min_sec.rem );
            }
            void main( void )
                 print_time( 86712L );
            produces the following:
            It took 14 minutes and 27 seconds
Classification: ISO C90
Systems:
            All, Linux, RDOS, Netware
```

```
Synopsis:
           #include <search.h>
           void *lfind( const void *key, /* object to search for
                        const void *base,/* base of search data
                                                                   */
                        unsigned *num, /* number of elements
                                                                   */
                                        /* width of each element */
                        unsigned width,
                        int (*compare) ( const void *element1,
                                        const void *element2 ) );
```

**Description:** 

The 1find function performs a linear search for the value key in the array of num elements pointed to by base. Each element of the array is width bytes in size. The argument compare is a pointer to a user-supplied routine that will be called by Ifind to determine the relationship of an array element with the key. One of the arguments to the compare function will be an array element, and the other will be

The compare function should return 0 if element1 is identical to element2 and non-zero if the elements are not identical.

**Returns:** 

The 1find function returns a pointer to the array element in base that matches key if it is found, otherwise NULL is returned indicating that the key was not found.

See Also: bsearch, lsearch

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <search.h>
static const char *keywords[] = {
        "auto",
        "break",
        "case",
        "char",
        /* . */
        /* . */
        /* . */
        "while"
};
void main( int argc, const char *argv[] )
  {
    unsigned num = 5;
    extern int compare( const void *, const void *);
    if( argc <= 1 ) exit( EXIT_FAILURE );</pre>
    if( lfind( &argv[1], keywords, &num, sizeof(char **),
                     compare ) == NULL ) {
      printf( "'%s' is not a C keyword\n", argv[1] );
      exit( EXIT_FAILURE );
    } else {
      printf( "'%s' is a C keyword\n", argv[1] );
      exit( EXIT_SUCCESS );
  }
```

```
int compare( const void *op1, const void *op2 )
{
   const char **p1 = (const char **) op1;
   const char **p2 = (const char **) op2;
   return( strcmp( *p1, *p2 ) );
}
```

**Classification:** WATCOM

Systems: All, Linux, RDOS, Netware

**Synopsis:** #include <math.h>

double lgamma (double x);

**Description:** The 1 gamma function returns the natural logarithm of the absolute value of the Gamma function of x.

is called will be located in signgam. This function is not thread-safe if the user is interested in the sign

of Gamma, and lgamma\_r should be used instead in multithreaded applications.

**Returns:** If successful, the return value is the natural logarithm of the absolute value of the Gamma function

computed for x. returns NAN. For arguments of the values positive or negative infinity, the function

returns positive or negative infinity respectively.

See Also: lgamma\_r, tgamma

#include <stdio.h> **Example:** #include <math.h>

```
void main()
  {
   printf( \$f\n, lgamma( 2.0 ) );
   printf( "%d\n", signgam );
```

produces the following:

```
0.00000
```

Classification: ISO C99

**Synopsis:** #include <math.h>

double lgamma\_r( double x, int \*y );

**Description:** The lgamma\_r function returns the natural logarithm of the absolute value of the Gamma function of

x. in the location pointed to by y.

**Returns:** If successful, the return value is the natural logarithm of the absolute value of the Gamma function

computed for x. returns NAN. For arguments of the values positive or negative infinity, the function

returns positive or negative infinity respectively.

See Also: lgamma, tgamma

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
    int i;
    printf( "%f\n", lgamma_r( 2.0, &i ) );
    printf( "%d\n", i );
```

produces the following:

0.00000

**Classification:** WATCOM

**Synopsis:** #include <graph.h> short \_FAR \_lineto( short x, short y ); short \_FAR \_lineto\_w( double x, double y );

**Description:** The \_lineto functions draw straight lines. The \_lineto function uses the view coordinate system. The \_lineto\_w function uses the window coordinate system.

> The line is drawn from the current position to the point at the coordinates (x, y). The point (x, y)becomes the new current position. The line is drawn with the current plotting action using the current line style and the current color.

**Returns:** The \_lineto functions return a non-zero value when the line was successfully drawn; otherwise, zero is returned.

See Also: \_moveto, \_setcolor, \_setlinestyle, \_setplotaction

**Example:** #include <conio.h> #include <graph.h> main() \_setvideomode( \_VRES16COLOR ); \_moveto( 100, 100 ); \_lineto( 540, 100 ); \_lineto( 320, 380 ); \_lineto( 100, 100 ); getch(); \_setvideomode( \_DEFAULTMODE ); }

produces the following:



Classification: PC Graphics

\_lineto - DOS \_lineto\_w - DOS **Systems:** 

```
Synopsis:
             #include <stdlib.h>
             long long int llabs( long long int j );
Description:
            The llabs function returns the absolute value of its long long integer argument j.
Returns:
             The llabs function returns the absolute value of its argument.
See Also:
             labs, abs, imaxabs, fabs
Example:
             #include <stdio.h>
             #include <stdlib.h>
             void main( void )
                 long long x, y;
                 x = -50000000000;
                 y = llabs(x);
                 printf( "llabs(%lld) = %lld\n", x, y );
             }
             produces the following:
             11abs(-5000000000) = 5000000000
Classification: ISO C99
```

**Systems:** 

All, Linux, RDOS, Netware

Library Functions and Macros 639

```
Synopsis:
            #include <stdlib.h>
            lldiv_t lldiv( long long int numer,
                             long long int denom );
            typedef struct {
                 long long int quot; /* quotient */
                 long long int rem; /* remainder */
            } lldiv_t;
Description:
            The lldiv function calculates the quotient and remainder of the division of the numerator numer by the
            denominator denom.
Returns:
            The lldiv function returns a structure of type lldiv_t that contains the fields quot and rem,
            which are both of type long long int.
See Also:
            ldiv, div, imaxdiv
Example:
            #include <stdio.h>
            #include <stdlib.h>
            void print_time( long long int ticks )
                 lldiv_t sec_ticks;
                 lldiv_t min_sec;
                 sec_ticks = lldiv( ticks, 100 );
                min_sec = lldiv( sec_ticks.quot, 60 );
                 printf( "It took %lld minutes and %lld seconds\n",
                          min_sec.quot, min_sec.rem );
            }
            void main( void )
                 print_time( 73495132 );
            produces the following:
            It took 12249 minutes and 11 seconds
Classification: ISO C99
            All, Linux, RDOS, Netware
Systems:
```

**Synopsis:** #include <locale.h>

struct lconv \*localeconv( void );

**Description:** The localeconv function sets the components of an object of type struct lconv with values

appropriate for the formatting of numeric quantities according to the current locale. The components of

the struct lconv and their meanings are as follows:

Component Meaning

*char \*decimal\_point* The decimal-point character used to format non-monetary quantities.

char \*thousands\_sep The character used to separate groups of digits to the left of the decimal-point character in formatted non-monetary quantities.

char \*grouping A string whose elements indicate the size of each group of digits in formatted

non-monetary quantities.

char \*int curr symbol The international currency symbol applicable to the current locale. The first three characters contain the alphabetic international currency symbol in accordance with those specified in ISO 4217 Codes for the Representation of Currency and Funds. The fourth character (immediately preceding the null character) is the character used to separate the international currency symbol from

the monetary quantity.

*char \*currency\_symbol* The local currency symbol applicable to the current locale.

*char \*mon\_decimal\_point* The decimal-point character used to format monetary quantities.

char \*mon\_thousands\_sep The character used to separate groups of digits to the left of the decimal-point character in formatted monetary quantities.

char \*mon\_grouping A string whose elements indicate the size of each group of digits in formatted monetary quantities.

char \*positive\_sign The string used to indicate a nonnegative-valued monetary quantity.

*char \*negative\_sign* The string used to indicate a negative-valued monetary quantity.

char int\_frac\_digits The number of fractional digits (those to the right of the decimal-point) to be

displayed in an internationally formatted monetary quantity.

char frac\_digits The number of fractional digits (those to the right of the decimal-point) to be

displayed in a formatted monetary quantity.

charp cs precedes Set to 1 or 0 if the currency\_symbol respectively precedes or follows the

value for a nonnegative formatted monetary quantity.

char p\_sep\_by\_space Set to 1 or 0 if the currency\_symbol respectively is or is not separated by a

space from the value for a nonnegative formatted monetary quantity.

char n cs precedes Set to 1 or 0 if the currency\_symbol respectively precedes or follows the

value for a negative formatted monetary quantity.

*char n\_sep\_by\_space* Set to 1 or 0 if the currency\_symbol respectively is or is not separated by a space from the value for a negative formatted monetary quantity.

 ${\it char p\_sign\_posn}$  The position of the positive\_sign for a nonnegative formatted monetary

quantity.

*char n\_sign\_posn* The position of the positive\_sign for a negative formatted monetary

quantity.

The elements of grouping and mon\_grouping are interpreted according to the following:

Value	Meaning
CHAR_MAX	No further grouping is to be performed.
0	The previous element is to be repeatedly used for the remainder of the digits.
other	The value is the number of digits that comprise the current group. The next element is examined to determine the size of the next group of digits to the left of the current group.

The value of p\_sign\_posn and n\_sign\_posn is interpreted as follows:

Value	Meaning
0	Parentheses surround the quantity and currency_symbol.
1	The sign string precedes the quantity and currency_symbol.
2	The sign string follows the quantity and currency_symbol.
3	The sign string immediately precedes the quantity and currency_symbol.
4	The sign string immediately follows the quantity and currency_symbol.

**Returns:** The localeconv function returns a pointer to the filled-in object.

See Also: setlocale

Example: #include

```
printf( "*int_curr_symbol (%s)\n",
    lc->int_curr_symbol );
printf( "*currency_symbol (%s)\n",
    lc->currency_symbol );
printf( "*mon_decimal_point (%s)\n",
    lc->mon_decimal_point );
printf( "*mon_thousands_sep (%s)\n",
    lc->mon_thousands_sep );
printf( "*mon_grouping (%s)\n",
    lc->mon_grouping );
printf( "*grouping (%s)\n",
    lc->grouping );
printf( "*positive_sign (%s)\n",
    lc->positive_sign );
printf( "*negative_sign (%s)\n",
    lc->negative_sign );
printf( "int_frac_digits (%d)\n",
    lc->int_frac_digits );
printf( "frac_digits (%d)\n",
    lc->frac_digits );
printf( "p_cs_precedes (%d) \n",
    lc->p_cs_precedes );
printf( "p_sep_by_space (%d) \n",
    lc->p_sep_by_space );
printf( "n_cs_precedes (%d)\n",
    lc->n_cs_precedes );
printf( "n_sep_by_space (%d)\n",
    lc->n_sep_by_space );
printf( "p_sign_posn (%d) \n",
    lc->p_sign_posn );
printf( "n_sign_posn (%d)\n",
    lc->n_sign_posn );
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

localeconv			

### **Synopsis:**

```
#include <time.h>
struct tm * localtime( const time t *timer );
struct tm *_localtime( const time_t *timer,
                              struct tm *tmbuf );
struct tm {
  int tm_sec; /* seconds after the minute -- [0,61] */
  int tm_min; /* minutes after the hour -- [0,59] */
  int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
int tm_year; /* years since 1900 */
  int tm_wday; /* days since Sunday
                                                           -- [0,6] */
  int tm_wday; /* days since Sunday -- [0,6] */
int tm_yday; /* days since January 1 -- [0,365]*/
  int tm_isdst; /* Daylight Savings Time flag
```

The Safer C Library extension provides the localtime\_s function which is a safer alternative to Safer C: localtime.

#### **Description:**

The localtime functions convert the calendar time pointed to by timer into a structure of type tm, of time information, expressed as local time. Whenever localtime is called, the tzset function is also called.

The calendar time is usually obtained by using the time function. That time is Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time (GMT)).

The \_localtime function places the converted time in the tm structure pointed to by tmbuf, and the localtime function places the converted time in a static structure that is re-used each time localtime is called.

The time set on the computer with the DOS time command and the DOS date command reflects the local time. The environment variable TZ is used to establish the time zone to which this local time applies. See the section *The TZ Environment Variable* for a discussion of how to set the time zone.

**Returns:** The localtime functions return a pointer to a tm structure containing the time information.

See Also: asctime Functions, asctime\_s, clock, ctime Functions, ctime\_s, difftime, gmtime, gmtime\_s, localtime\_s, mktime, strftime, time, tzset

# **Example:**

```
#include <stdio.h>
#include <time.h>
void main()
    time_t time_of_day;
    auto char buf[26];
    auto struct tm tmbuf;
    time_of_day = time( NULL );
    _localtime( &time_of_day, &tmbuf );
    printf( "It is now: %s", _asctime( &tmbuf, buf ) );
}
```

# **localtime Functions**

## produces the following:

It is now: Sat Mar 21 15:58:27 1987

Classification: ISO C

Systems: localtime - All, Linux, RDOS, Netware

\_localtime - All, Linux, RDOS

```
#define __STDC_WANT_LIB_EXT1__ 1
Synopsis:
              #include <time.h>
              struct tm * localtime_s( const time_t * restrict timer,
                                                struct tm * restrict result);
              struct tm {
                 int tm_sec; /* seconds after the minute -- [0,61] */
                 int tm_min; /* minutes after the hour -- [0,59] */
                 int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
int tm_year; /* years since 1900 */
                 int tm_wday; /* days since Sunday
                                                                         -- [0,6] */
                 int tm_yday; /* days since Sunday -- [0,6] */
int tm_yday; /* days since January 1 -- [0,365]*/
                 int tm_isdst; /* Daylight Savings Time flag
              };
```

**Constraints:** 

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and localtime\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither timer nor result shall be a null pointer. If there is a runtime-constraint violation, there is no attempt to convert the time.

**Description:** The localtime\_s function converts the calendar time pointed to by timer into a broken-down time, expressed as local time. The broken-down time is stored in the structure pointed to by result.

**Returns:** The localtime\_s function returns result, or a null pointer if the specified time cannot be converted to local time or there is a runtime-constraint violation.

See Also: asctime Functions, asctime\_s, clock, ctime Functions, ctime\_s, difftime, gmtime, gmtime\_s, localtime, mktime, strftime, time, tzset

```
Example:
           #define __STDC_WANT_LIB_EXT1__ 1
           #include <stdio.h>
           #include <time.h>
           void main()
               time_t time_of_day;
               auto char buf[26];
               auto struct tm tmbuf;
               time_of_day = time( NULL );
               localtime_s( &time_of_day, &tmbuf );
               asctime_s( buf, sizeof( buf ), &tmbuf );
               printf( "It is now: %s", buf );
```

It is now: Mon Jan 30 15:28:33 2006

produces the following:

Classification: TR 24731

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware

```
Synopsis:
           #include <io.h>
           int lock (int handle,
                      unsigned long offset,
                      unsigned long nbytes );
```

**Description:** 

The lock function locks *nbytes* amount of data in the file designated by *handle* starting at byte *offset* in the file. This prevents other processes from reading or writing into the locked region until an unlock has been done for this locked region of the file.

Multiple regions of a file can be locked, but no overlapping regions are allowed. You cannot unlock multiple regions in the same call, even if the regions are contiguous. All locked regions of a file should be unlocked before closing a file or exiting the program.

With DOS, locking is supported by version 3.0 or later. Note that SHARE.COM or SHARE.EXE must be installed.

**Returns:** 

The lock function returns zero if successful, and -1 when an error occurs. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: locking, open, \_sopen, unlock

**Example:** 

```
#include <stdio.h>
#include <fcntl.h>
#include <io.h>
void main()
  {
    int handle;
    char buffer[20];
    handle = open( "file", O_RDWR | O_TEXT );
    if ( handle !=-1 ) {
      if( lock( handle, OL, 20L ) ) {
        printf( "Lock failed\n" );
        read( handle, buffer, 20 );
        /* update the buffer here */
        lseek( handle, OL, SEEK_SET );
        write( handle, buffer, 20 );
        unlock ( handle, OL, 20L );
      close( handle );
    }
  }
```

**Classification:** WATCOM

**Systems:** All, RDOS, Netware

lock			

**Synopsis:** #include <sys/locking.h>

> int locking (int handle, int mode, long nbyte); int \_locking( int handle, int mode, long nbyte );

**Description:** 

The locking function locks or unlocks *nbyte* bytes of the file specified by *handle*. Locking a region of a file prevents other processes from reading or writing the locked region until the region has been unlocked. The locking and unlocking takes place at the current file position. The argument mode specifies the action to be performed. The possible values for mode are:

Mode Meaning

\_LK\_LOCK, LK\_LOCK Locks the specified region. The function will retry to lock the region after 1 second intervals until successful or until 10 attempts have been made.

\_LK\_RLCK, LK\_RLCK Same action as \_LK\_LOCK.

**\_LK\_NBLCK**, **LK\_NBLCK** Non-blocking lock: makes only 1 attempt to lock the specified region.

\_LK\_NBRLCK, LK\_NBRLCK Same action as \_LK\_NBLCK.

**LK\_UNLCK**, **LK\_UNLCK** Unlocks the specified region. The region must have been previously locked.

Multiple regions of a file can be locked, but no overlapping regions are allowed. You cannot unlock multiple regions in the same call, even if the regions are contiguous. All locked regions of a file should be unlocked before closing a file or exiting the program.

With DOS, locking is supported by version 3.0 or later. Note that SHARE.COM or SHARE.EXE must be installed.

The \_locking function is identical to locking. Use \_locking for ANSI naming conventions.

**Returns:** 

The locking function returns zero if successful. Otherwise, it returns -1 and errno is set to indicate the error.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning			
EACCES	Indicates a locking violation (file already locked or unlocked).			
<b>EBADF</b>	Indicates an invalid file handle.			
EDEADLOCK	Indicates a locking violation. This error is returned when $mode$ is LK_LOCK or LK_RLCK and the file cannot be locked after 10 attempts.			
EINVAL	Indicates that an invalid argument was given to the function.			

See Also:

creat, \_dos\_creat, \_dos\_open, lock, open, \_sopen, unlock

```
Example:
           #include <stdio.h>
           #include <sys/locking.h>
           #include <share.h>
           #include <fcntl.h>
           #include <io.h>
           void main()
             {
               int handle;
               unsigned nbytes;
               unsigned long offset;
               auto char buffer[512];
               nbytes = 512;
               offset = 1024;
               handle = _sopen( "db.fil", O_RDWR, SH_DENYNO );
               if (handle !=-1) {
                 lseek( handle, offset, SEEK_SET );
                 locking( handle, LK_LOCK, nbytes );
                 read( handle, buffer, nbytes );
                 /* update data in the buffer */
                 lseek( handle, offset, SEEK_SET );
                 write( handle, buffer, nbytes );
                 lseek( handle, offset, SEEK_SET );
                 locking( handle, LK_UNLCK, nbytes );
                 close( handle );
             }
Classification: WATCOM
           _locking conforms to ANSI naming conventions
Systems:
           locking - All, Linux, RDOS
           _locking - All, Linux, RDOS
```

**Synopsis:** #include <math.h>

double log( double x );

**Description:** The log function computes the natural logarithm (base e) of x. A domain error occurs if the argument

is negative. A range error occurs if the argument is zero.

**Returns:** The log function returns the natural logarithm of the argument. When the argument is outside the

> permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: exp, log10, log2, pow, matherr

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
    printf( "%f\n", log(.5) );
```

produces the following:

-0.693147

Classification: ISO C

Synopsis: #include <math.h>

double log10 ( double x );

**Description:** The log10 function computes the logarithm (base 10) of x. A domain error occurs if the argument is

negative. A range error occurs if the argument is zero.

**Returns:** The log10 function returns the logarithm (base 10) of the argument. When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: exp, log, log2, pow, matherr

Example: #include <stdio.h>

```
#include <math.h>

void main()
    {
      printf( "%f\n", log10(.5) );
    }
```

produces the following:

-0.301030

Classification: ISO C

**Synopsis:** #include <math.h>

double log1p( double x );

**Description:** The log1p function computes the natural logarithm of one plus x. x this function provides far better

accuracy than using the log function directly.

**Returns:** If successful, the return value is the logarithm of one plus x. infinity. If the value of x is less than -1.0,

the function returns NAN.

See Also: log

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
    printf( "%f\n", log1p( 0.02 ) );
```

produces the following:

0.019803

Classification: ISO C99

Synopsis: #include <math.h>

double log2(double x);

**Description:** The log2 function computes the logarithm (base 2) of x. A domain error occurs if the argument is

negative. A range error occurs if the argument is zero.

**Returns:** The log2 function returns the logarithm (base 2) of the argument. When the argument is outside the

permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: exp, log, log10, pow, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", log2(.25) );
    }
```

produces the following:

-2.000000

**Classification:** WATCOM

```
Synopsis:
           #include <math.h>
           double logb( double x );
```

**Description:** The logb function returns the exponent portion of the argument x as a double.

**Returns:** If successful, the return value is the exponent of x. infinity.

See Also: ilogb

```
Example:
           #include <stdio.h>
           #include <math.h>
           void main()
             {
               printf( "%f\n", logb( 1024.0 ) );
```

produces the following:

10.0000

Classification: ISO C99

Synopsis: #include <setjmp.h>

void longjmp( jmp\_buf env, int return\_value );

**Description:** The longjmp function restores the environment saved by the most recent call to the setjmp function

with the corresponding jmp\_buf argument.

It is generally a bad idea to use longjmp to jump out of an interrupt function or a signal handler (unless the signal was generated by the raise function).

**Returns:** The longjmp function does not return to its caller. After the longjmp function restores the

environment, program execution continues as if the corresponding call to set jmp had just returned the

value specified by return\_value. If the value of return\_value is 0, the value returned is 1.

See Also: setjmp

Example: #include <stdio.h>
#include <setjmp.h>

```
jmp_buf env;

rtn()
    {
        printf( "about to longjmp\n" );
        longjmp( env, 14 );
    }

void main()
    {
        int ret_val = 293;

        if( 0 == ( ret_val = setjmp( env ) ) ) {
            printf( "after setjmp %d\n", ret_val );
            rtn();
            printf( "back from rtn %d\n", ret_val );
        } else {
```

printf( "back from longjmp %d\n", ret\_val );

produces the following:

after setjmp 0 about to longjmp back from longjmp 14

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware

}

		longjmp

```
Synopsis:
             #include <stdlib.h>
             unsigned long _lrotl( unsigned long value,
                                       unsigned int shift );
Description:
            The _lrot1 function rotates the unsigned long integer, determined by value, to the left by the number
             of bits specified in shift.
Returns:
            The rotated value is returned.
See Also:
             _lrotr, _rotl, _rotr
Example:
             #include <stdio.h>
             #include <stdlib.h>
             unsigned long mask = 0x12345678;
             void main()
               {
                 mask = lrotl(mask, 4);
                 printf( %081X\n, mask );
             produces the following:
             23456781
Classification: WATCOM
Systems:
             All, Linux, RDOS, Netware
```

```
Synopsis:
             #include <stdlib.h>
             unsigned long _lrotr( unsigned long value,
                                       unsigned int shift );
Description:
            The _lrotr function rotates the unsigned long integer, determined by value, to the right by the
             number of bits specified in shift.
Returns:
            The rotated value is returned.
See Also:
             _lrotl, _rotl, _rotr
Example:
             #include <stdio.h>
             #include <stdlib.h>
             unsigned long mask = 0x12345678;
             void main()
               {
                 mask = lrotr(mask, 4);
                 printf( %081X\n, mask );
             produces the following:
             81234567
Classification: WATCOM
Systems:
             All, Linux, RDOS, Netware
```

### **Synopsis:**

#### **Description:**

The lsearch function performs a linear search for the value *key* in the array of *num* elements pointed to by *base*. Each element of the array is *width* bytes in size. The argument *compare* is a pointer to a user-supplied routine that will be called by lsearch to determine the relationship of an array element with the *key*. One of the arguments to the *compare* function will be an array element, and the other will be *key*.

The *compare* function should return 0 if *element1* is identical to *element2* and non-zero if the elements are not identical.

### **Returns:**

If the *key* value is not found in the array, then it is added to the end of the array and the number of elements is incremented. The lsearch function returns a pointer to the array element in *base* that matches *key* if it is found, or the newly added key if it was not found.

See Also: bsearch, lfind

### **Example:**

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <search.h>
void main( int argc, const char *argv[] )
  {
    int i;
   unsigned num = 0;
   char **array = (char **) calloc( argc, sizeof(char **) );
   extern int compare ( const void *, const void * );
    for(i = 1; i < argc; ++i) {
      lsearch( &argv[i], array, &num, sizeof(char **),
                  compare );
    for(i = 0; i < num; ++i) {
     printf( "%s\n", array[i] );
int compare( const void *op1, const void *op2 )
  {
   const char **p1 = (const char **) op1;
    const char **p2 = (const char **) op2;
    return( strcmp( *p1, *p2 ) );
/* With input: one two one three four */
```

produces the following:

one two three four

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

### Synopsis: #include <stdio.h>

```
#include <io.h>
off_t lseek( int handle, off_t offset, int origin );
off_t _lseek( int handle, off_t offset, int origin );
__int64 _lseeki64( int handle, __int64 offset, int origin );
```

### **Description:**

The lseek function sets the current file position at the operating system level. The file is referenced using the file handle returned by a successful execution of one of the creat, dup, dup2, open or \_sopen functions. The value of *offset* is used as a relative offset from a file position determined by the value of the argument *origin*.

The new file position is determined in a manner dependent upon the value of *origin* which may have one of three possible values (defined in the <stdio.h> header file):

Origin	Definition
SEEK_SET	The new file position is computed relative to the start of the file. The value of <i>offset</i> must not be negative.
SEEK_CUR	The new file position is computed relative to the current file position. The value of <i>offset</i> may be positive, negative or zero.
SEEK_END	The new file position is computed relative to the end of the file.

An error will occur if the requested file position is before the start of the file.

The requested file position may be beyond the end of the file. On POSIX-conforming systems, if data is later written at this point, subsequent reads of data in the gap will return bytes whose value is equal to zero until data is actually written in the gap. On systems such DOS and OS/2 that are not POSIX-conforming, data that are read in the gap have arbitrary values.

Some versions of MS-DOS allow seeking to a negative offset, but it is not recommended since it is not supported by other platforms and may not be supported in future versions of MS-DOS.

The lseek function does not, in itself, extend the size of a file (see the \_chsize function).

The \_lseek function is identical to lseek. Use \_lseek for ANSI naming conventions.

The \_lseeki64 function is identical to lseek except that it accepts a 64-bit value for the *offset* argument.

The lseek function can be used to obtain the current file position (the \_tell function is implemented in terms of lseek). This value can then be used with the lseek function to reset the file position to that point in the file:

```
off_t file_posn;
int handle;
/* get current file position */
file_posn = lseek( handle, OL, SEEK_CUR );
  /* or */
file_posn = _tell( handle );
/* return to previous file position */
file_posn = lseek( handle, file_posn, SEEK_SET );
```

If all records in the file are the same size, the position of the n'th record can be calculated and read, as illustrated in the example included below. The function in this example assumes records are numbered starting with zero and that rec\_size contains the size of a record in the file (including the record-separator character). (including the carriage-return character in text files).

### **Returns:**

If successful, the current file position is returned in a system-dependent manner. A value of 0 indicates the start of the file.

If an error occurs in lseek (-1L) is returned.

If an error occurs in \_lseeki64, (-1I64) is returned.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

### **Errors:**

When an error has occurred, errno contains a value indicating the type of error that has been detected.

### Constant Meaning

**EBADF** The *handle* argument is not a valid file handle.

**EINVAL** The *origin* argument is not a proper value, or the resulting file offset would be invalid.

### See Also:

\_chsize, close, creat, dup, dup2, \_eof, exec..., fdopen, \_filelength, fileno, fstat, \_grow\_handles, isatty, open, read, \_setmode, \_sopen, stat, \_tell, write, umask

### **Example:**

```
#include <stdio.h>
#include <fcntl.h>
#include <io.h>
int read_record( int handle,
                 long rec_numb,
                 int rec_size,
                 char *buffer )
    if( lseek( handle, rec_numb * rec_size, SEEK_SET )
         == -1L ) {
        return (-1);
    return( read( handle, buffer, rec_size ) );
}
```

```
void main( void )
               int handle;
               int size_read;
               char buffer[80];
               /* open a file for input */
               handle = open( "file", O_RDONLY | O_TEXT );
               if (handle !=-1) {
                    /* read a piece of the text */
                    size_read = read_record( handle, 1, 80, buffer );
                    /* test for error */
                    if ( size\_read == -1 ) {
                        printf( "Error reading file\n" );
                    } else {
                        printf( %.80s\n, buffer );
                    /* close the file */
                    close( handle );
           }
Classification: POSIX 1003.1
           _lseek conforms to ANSI naming conventions
           _lseeki64 is WATCOM
Systems:
           lseek - All, Linux, RDOS, Netware
           _lseek - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
           _lseeki64 - All, Linux
```

**Synopsis:** 

```
#include <stdlib.h>
char *lltoa( long long int value,
             char *buffer,
             int radix );
char *_lltoa( long long int value,
              char *buffer,
              int radix );
wchar_t *_lltow( long long int value,
                 wchar_t *buffer,
                 int radix );
```

**Description:** 

The 11toa function converts the binary integer value into the equivalent string in base radix notation storing the result in the character array pointed to by buffer. A null character is appended to the result. The size of buffer must be at least 65 bytes when converting values in base 2. The value of radix must satisfy the condition:

```
2 <= radix <= 36
```

If radix is 10 and value is negative, then a minus sign is prepended to the result.

The \_lltoa function is identical to lltoa. Use \_lltoa for ANSI naming conventions.

The \_lltow function is a wide character version of lltoa except that it produces a wide character string.

**Returns:** The lltoa function returns a pointer to the result.

See Also: atoi, atol, atoll, itoa, ltoa, sscanf, strtol, strtoll, strtoul, strtoull,

strtoimax, strtoumax, ultoa, ulltoa, utoa

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
void print_value( long value )
    int base;
   char buffer[65];
    for( base = 2; base <= 16; base = base + 2)
        printf( %2d %s\n, base,
                lltoa( value, buffer, base ) );
}
void main()
   print_value( 1234098765LL );
```

produces the following:

```
2 1001001100011101101101001001101
 4 1021203231221031
 6 322243004113
 8 11143555115
10 1234098765
12 2a5369639
14 b9c8863b
```

### **Classification:** WATCOM

\_lltoa conforms to ANSI naming conventions

**Systems:** lltoa - All, Linux, RDOS, Netware

16 498eda4d

\_lltoa - All, Linux, RDOS, Netware \_lltow - All, Linux, RDOS

**Synopsis:** 

```
#include <stdlib.h>
char *ltoa( long int value,
            char *buffer,
            int radix );
char *_ltoa( long int value,
             char *buffer,
             int radix );
wchar_t *_ltow( long int value,
                wchar_t *buffer,
                int radix );
```

**Description:** 

The ltoa function converts the binary integer value into the equivalent string in base radix notation storing the result in the character array pointed to by buffer. A null character is appended to the result. The size of buffer must be at least 33 bytes when converting values in base 2. The value of radix must satisfy the condition:

```
2 <= radix <= 36
```

If radix is 10 and value is negative, then a minus sign is prepended to the result.

The \_ltoa function is identical to ltoa. Use \_ltoa for ANSI naming conventions.

The \_ltow function is a wide character version of ltoa except that it produces a wide character string.

**Returns:** The ltoa function returns a pointer to the result.

See Also: atoi, atol, atoll, itoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull, strtoimax, strtoumax, ultoa, ulltoa, utoa

**Example:** #include <stdio.h> #include <stdlib.h> void print\_value( long value )

```
int base;
    char buffer[33];
    for( base = 2; base <= 16; base = base + 2)
        printf( "%2d %s\n", base,
                ltoa( value, buffer, base ) );
}
void main()
    print_value( 12765L );
```

produces the following:

```
2 11000111011101
 4 3013131
 6 135033
 8 30735
10 12765
12 7479
14 491b
16 31dd
```

### **Classification:** WATCOM

\_ltoa conforms to ANSI naming conventions

### **Systems:** ltoa - All, Linux, RDOS, Netware

\_ltoa - All, Linux, RDOS, Netware \_ltow - All, Linux, RDOS

**Synopsis:** int main (void);

```
int main( int argc, char *argv[] );
int wmain( void );
int wmain( int argc, wchar_t *argv[] );
int PASCAL WinMain ( HINSTANCE hInstance,
                    HINSTANCE hPrevInstance,
                    LPSTR lpszCmdLine,
                    int nCmdShow );
int PASCAL wWinMain ( HINSTANCE hInstance,
                     HINSTANCE hPrevInstance,
                     wcharT *lpszCmdLine,
                     int nCmdShow );
```

### **Description:**

main is a user-supplied function where program execution begins. The command line to the program is broken into a sequence of tokens separated by blanks and are passed to main as an array of pointers to character strings in the parameter argv. The number of arguments found is passed in the parameter argc. The first element of argv will be a pointer to a character string containing the program name. The last element of the array pointed to by argy will be a NULL pointer (i.e. argy[argc] will be NULL). Arguments that contain blanks can be passed to main by enclosing them within double quote characters (which are removed from that element in the argy vector. A literal double quote character can be passed by preceding it with a backslash. A literal backslash followed by an enclosing double quote character can be passed as a pair of backslash characters and a double quote character.

### **Example:**

```
echo "he\"l\lo world\\"
passes the single argument he"No world
```

The command line arguments can also be obtained in its original format by using the getend function.

Alternatively, the main function can be declared to return void (i.e., no return value). In this case, you will not be able to return an exit code from main using a return statement but must use the exit function to do so.

The wmain function is a user-defined wide character version of main that operates with wide character strings. If this function is present in the application, then it will be called by the run-time system startup code (and the main function, if present, will not be called).

As with main the wmain function can be declared to return void and the same considerations will apply.

The WinMain function is called by the system as the initial entry point for a Windows-based application. The wWinMain function is a wide character version of WinMain.

Parameters	Meaning				
hInstance	Identifies the current instance of the application.				
hPrevInstance	Identifies the previous instance of the application. For an application written for Win32, this parameter is always NULL.				
lpszCmdLine	Points to a null-terminated string specifying the command line for the application.				
nCmdShow	Specifies how the window is to be shown. This parameter can be one of the following values:				

Value	Meaning				
SW_HIDE	Hides the window and activates another window.				
SW_MINIMIZE	Minimizes the specified window and activates the top-level window in the system's list.				
SW_RESTORE	Activates and displays a window. If the window is minimized or maximized, Windows restores it to its original size and position (same as SW_SHOWNORMAL).				
SW_SHOW	Activates a window and displays it in its current size and position.				
SW_SHOWMAXIMIZED Activates a window and displays it as a maximized window.					

SW\_SHOWMINIMIZED Activates a window and displays it as an icon.

**SW\_SHOWMINNOACTIVE** Displays a window as an icon. The active window remains active.

**SW\_SHOWNA** Displays a window in its current state. The active window remains active.

**SW\_SHOWNOACTIVATE** Displays a window in its most recent size and position. The active window remains active.

**SW\_SHOWNORMAL** Activates and displays a window. If the window is minimized or maximized, Windows restores it to its original size and position (same as SW\_RESTORE).

The WinMain function initializes an application, and then performs a message retrieval-and-dispatch loop that is the top-level control structure for the remainder of the application's execution. The loop terminates when a WM\_QUIT message is received. At that point, WinMain exits the application, returning the value passed in the WM\_QUIT message's wParam parameter. If WM\_QUIT was received as a result of calling PostQuitMessage, the value of wParam is the value of the PostQuitMessage function's nExitCode parameter.

# **Returns:** The main and wmain functions return an exit code to the calling program (usually the operating system).

If the WinMain function terminates before entering the message loop, it should return 0. Otherwise, it should terminate when it receives a WM\_QUIT message and return the exit value contained in that message's wParam parameter.

**See Also:** abort, atexit, \_bgetcmd, exec..., exit, \_Exit, \_exit, getcmd, getenv, putenv, spawn..., system, \_wsystem

**Example:** 

```
#include <stdio.h>
           int main( int argc, char *argv[] )
               int i;
               for(i = 0; i < argc; ++i) {
                   printf( "argv[%d] = %s\n", i, argv[i] );
               return(0);
           #ifdef _WIDE_
           int wmain( int wargc, wchar_t *wargv[] )
           {
               int i;
               for(i = 0; i < wargc; ++i) {
                   wprintf( L"wargv[%d] = %s\n", i, wargv[i] );
               return(0);
           #endif
           produces the following:
           argv[0] = C:\WATCOM\DEMO\MYPGM.EXE
           argv[1] = hhhhh
           argv[2] = another arg
           when the program mypgm is executed with the command
           mypgm hhhhh "another arg"
           A sample Windows main program is shown below.
           int PASCAL WinMain ( HINSTANCE this_inst, HINSTANCE prev_inst,
                                LPSTR cmdline, int cmdshow )
           {
               MSG
                            msq;
               if( !prev_inst ) {
                    if( !FirstInstance( this_inst ) ) return( 0 );
               if( !AnyInstance( this_inst, cmdshow ) ) return( 0 );
                 GetMessage returns FALSE when WM_QUIT is received
               while( GetMessage( &msg, NULL, NULL, NULL ) ) {
                   TranslateMessage( &msg );
                   DispatchMessage( &msg );
               return( msg.wParam );
           }
Classification: ISO C
           wmain is WATCOM
           WinMain is WATCOM
```

wWinMain is WATCOM

Library Functions and Macros 673

## main, wmain, WinMain, wWinMain

Systems: main - All, Netware

wmain - Win32, OS/2-32

WinMain - Windows, Win386, Win32

wWinMain - Win32

**Synopsis:** 

```
#include <stdlib.h>
void _makepath( char *path,
                const char *drive,
                const char *dir,
                const char *fname,
                const char *ext );
void _wmakepath( wchar_t *path,
                  const wchar_t *drive,
                  const wchar t *dir,
                  const wchar_t *fname,
                  const wchar_t *ext );
```

**Description:** 

The \_makepath function constructs a full pathname from the components consisting of a drive letter, directory path, file name and file name extension. The full pathname is placed in the buffer pointed to by the argument path.

The \_wmakepath function is a wide character version of \_makepath that operates with wide character strings.

The maximum size required for each buffer is specified by the manifest constants \_MAX\_PATH, \_MAX\_DRIVE, \_MAX\_DIR, \_MAX\_FNAME, and \_MAX\_EXT which are defined in <stdlib.h>.

drive

The drive argument points to a buffer containing the drive letter (A, B, C, etc.) followed by an optional colon. The \_makepath function will automatically insert a colon in the full pathname if it is missing. If drive is a NULL pointer or points to an empty string, no drive letter or colon will be placed in the full pathname.

dir

The dir argument points to a buffer containing just the pathname. Either forward slashes (/) or backslashes (\) may be used. The trailing slash is optional. The \_makepath function will automatically insert a trailing slash in the full pathname if it is missing. If dir is a NULL pointer or points to an empty string, no slash will be placed in the full pathname.

fname

The *fname* argument points to a buffer containing the base name of the file without any extension (suffix).

ext

The ext argument points to a buffer containing the filename extension or suffix. A leading period (.) is optional. The \_makepath routine will automatically insert a period in the full pathname if it is missing. If ext is a NULL pointer or points to an empty string, no period will be placed in the full pathname.

**Returns:** 

The \_makepath function returns no value.

See Also:

\_fullpath, \_splitpath

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
void main()
  {
    char full_path[ _MAX_PATH ];
    char drive[ _MAX_DRIVE ];
    char dir[ _MAX_DIR ];
    char fname[ _MAX_FNAME ];
    char ext[ _MAX_EXT ];
    _makepath(full_path,"c","watcomc\\h\\","stdio","h");
    printf( "Full path is: %s\n\n", full_path );
   _splitpath( full_path, drive, dir, fname, ext );
   printf( "Components after _splitpath\n" );
   printf( "drive: %s\n", drive );
   printf( "dir: %s\n", dir );
   printf( "fname: %s\n", fname );
   printf( "ext: %s\n", ext );
  }
produces the following:
Full path is: c:watcomc\h\stdio.h
Components after _splitpath
drive: c:
dir: watcomc\h\
fname: stdio
ext: .h
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

### **Classification:** WATCOM

```
Systems: _makepath - All, Linux, RDOS, Netware _wmakepath - All, Linux
```

### **Synopsis:**

```
#include <stdlib.h> For ISO C compatibility (malloc only)
#include <malloc.h> Required for other function prototypes
void *malloc( size_t size );
void __based(void) *_bmalloc( __segment seg, size_t size );
void __far *_fmalloc( size_t size );
void __near *_nmalloc( size_t size );
```

### **Description:**

The malloc functions allocate space for an object of size bytes. Nothing is allocated when the size argument has a value of zero.

Each function allocates memory from a particular heap, as listed below:

Function Heap malloc Depends on data model of the program bmalloc Based heap specified by seg value \_fmalloc Far heap (outside the default data segment) \_nmalloc Near heap (inside the default data segment)

In a small data memory model, the malloc function is equivalent to the \_nmalloc function; in a large data memory model, the malloc function is equivalent to the \_fmalloc function.

### **Returns:**

The malloc functions return a pointer to the start of the allocated memory. The malloc, \_fmalloc and \_nmalloc functions return NULL if there is insufficient memory available or if the requested size is zero. The \_bmalloc function returns \_NULLOFF if there is insufficient memory available or if the requested size is zero.

See Also:

calloc Functions, \_expand Functions, free Functions, halloc, hfree, \_msize Functions, realloc Functions, sbrk

### **Example:**

```
void main()
  {
    char *buffer;
    buffer = (char *)malloc(80);
    if( buffer != NULL ) {
        /* body of program */
        free( buffer );
    }
```

#include <stdlib.h>

### **Classification:** ISO C

### **Systems:**

```
malloc - All, Linux, RDOS, Netware
_bmalloc - DOS/16, Windows, OS/2 1.x(all)
_fmalloc - DOS/16, Windows, OS/2 1.x(all)
```

\_nmalloc - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT), OS/2-32, Linux, RDOS

**Synopsis:** #include <math.h>

int matherr( struct \_exception \*err\_info );

**Description:** 

The matherr function is invoked each time an error is detected by functions in the math library. The default matherr function supplied in the library returns zero which causes an error message to be displayed upon stderr and errno to be set with an appropriate error value. An alternative version of this function can be provided, instead of the library version, in order that the error handling for mathematical errors can be handled by an application.

A program may contain a user-written version of matherr to take any appropriate action when an error is detected. When zero is returned, an error message will be printed upon stderr and errno will be set as was the case with the default function. When a non-zero value is returned, no message is printed and errno is not changed. The value err\_info->retval is used as the return value for the function in which the error was detected.

The matherr function is passed a pointer to a structure of type struct \_exception which contains information about the error that has been detected:

```
struct _exception
                                                 */
               /* TYPE OF ERROR
{ int type;
 char *name;
               /* NAME OF FUNCTION
               /* FIRST ARGUMENT TO FUNCTION
 double arg1;
 double arg2; /* SECOND ARGUMENT TO FUNCTION
 double retval; /* DEFAULT RETURN VALUE
};
```

The type field will contain one of the following values:

Value	Meaning
DOMAIN	A domain error has occurred, such as sqrt (-1e0).
SING	A singularity will result, such as pow ( $0e0, -2$ ).
OVERFLOW	An overflow will result, such as pow (10e0, 100).
UNDERFLOW	An underflow will result, such as pow (10e0, -100).
TLOSS	Total loss of significance will result, such as exp (1000).
PLOSS	Partial loss of significance will result, such as sin (10e70).

The name field points to a string containing the name of the function which detected the error. The fields arg1 and arg2 (if required) give the values which caused the error. The field retval contains the value which will be returned by the function. This value may be changed by a user-supplied version of the matherr function.

**Returns:** 

The matherr function returns zero when an error message is to be printed and a non-zero value otherwise.

```
Example:
           #include <stdio.h>
           #include <stdlib.h>
           #include <string.h>
           #include <math.h>
           /* Demonstrate error routine in which negative */
           /* arguments to "sqrt" are treated as positive */
           void main()
              printf( "%e\n", sqrt( -5e0 ) );
              exit( 0 );
           int matherr( struct _exception *err )
               if( strcmp( err->name, "sqrt" ) == 0 ) {
                if( err->type == DOMAIN ) {
                  err->retval = sqrt( -(err->arg1) );
                  return(1);
                 } else
                  return(0);
               } else
                return(0);
```

**Classification:** WATCOM

**Systems:** Math

```
Synopsis:
           #include <stdlib.h>
           \#define max(a,b) (((a) > (b)) ? (a) : (b))
```

**Description:** The max macro will evaluate to be the greater of two values. It is implemented as follows.

```
#define max(a,b)
                 (((a) > (b)) ? (a) : (b))
```

**Returns:** The max macro will evaluate to the larger of the two values passed.

See Also: min

```
Example:
           #include <stdio.h>
           #include <stdlib.h>
           void main()
             {
               int a;
                * The following line will set the variable "a" to 10
                * since 10 is greater than 1.
               a = max(1, 10);
               printf( "The value is: %d\n", a );
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware **Synopsis:** #include <mbstring.h> unsigned int \_mbbtombc( unsigned int ch ); **Description:** The \_mbbt ombc function returns the double-byte character equivalent to the single-byte character ch. The single-byte character must be in the range 0x20 through 0x7E or 0xA1 through 0xDF. *Note:* This function was called hantozen in earlier versions. **Returns:** The \_mbbt ombc function returns ch if there is no equivalent double-byte character; otherwise \_mbbtombc returns a double-byte character. See Also: \_getmbcp, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp **Example:** #include <stdio.h> #include <mbctype.h> #include <mbstring.h> char alphabet[] = { "ABCDEFGHIJKLMNOPQRSTUVWXYZ" }; void main() { int i; unsigned short c;

produces the following:

\_setmbcp( 932 );

printf( "\n" );

ABCDEFGHIJKLMNOPQRSTUVWXYZ

for(i = 0;  $i < sizeof(alphabet) - 1; i++) {$ 

c = \_mbbtombc( alphabet[ i ] );
printf( "%c%c", c>>8, c );

**Classification: WATCOM** 

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

**Synopsis:** #include <mbstring.h>

> #include <mbctype.h> (for manifest constants) int \_mbbtype( unsigned char ch, int type );

**Description:** 

The \_mbbt ype function determines the type of a byte in a multibyte character. If the value of type is any value except 1, \_mbbtype tests for a valid single-byte or lead byte of a multibyte character. If the value of *type* is 1, \_mbbtype tests for a valid trail byte of a multibyte character.

*Note:* A similar function was called chkctype in earlier versions.

**Returns:** If the value of *type* is not 1, the \_mbbtype function returns one of the following values:

> \_MBC\_SINGLE the character is a valid single-byte character (e.g., 0x20 - 0x7E, 0xA1 - 0xDF

> > in code page 932)

\_MBC\_LEAD the character is valid lead byte character (e.g., 0x81 - 0x9F, 0xE0 - 0xFC in

code page 932)

\_MBC\_ILLEGAL the character is an illegal character (e.g., any value except 0x20 - 0x7E, 0xA1

- 0xDF, 0x81 - 0x9F, 0xE0 - 0xFC in code page 932)

If the value of *type* is 1, the \_mbbtype function returns one of the following values:

\_MBC\_TRAIL the character is a valid trailing byte character (e.g., 0x40 - 0x7E, 0x80 - 0xFC

in code page 932)

\_MBC\_ILLEGAL the character is an illegal character (e.g., any character except a valid trailing

byte character)

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph,

> \_ismbchira,\_ismbckata,\_ismbcl0,\_ismbcl1,\_ismbcl2,\_ismbclegal, \_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol,

\_ismbcupper, \_ismbcxdigit, \_mbsbtype, \_setmbcp

**Example:** 

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const char *types[4] = {
    "ILLEGAL",
    "SINGLE",
    "LEAD",
    "TRAIL"
} ;
const unsigned char chars[] = {
    ′.′,
    111,
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
               /* single-byte Katakana punctuation */
               /* single-byte Katakana alphabetic */
              /* single-byte Katakana alphabetic */
    0xDF,
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
#define SIZE sizeof( chars ) / sizeof( unsigned char )
void main()
 {
    int
            i, j, k;
    _setmbcp( 932 );
    k = 0;
    for( i = 0; i < SIZE; i++ ) {
      j = _mbbtype( chars[i], k );
      printf( "%s\n", types[ 1 + j ] );
      if(j == \_MBC\_LEAD)
        k = 1;
      else
        k = 0;
  }
```

produces the following:

SINGLE SINGLE SINGLE SINGLE LEAD TRAIL LEAD TRAIL LEAD TRAIL LEAD TRAIL SINGLE SINGLE SINGLE LEAD TRAIL ILLEGAL

**Classification:** WATCOM

DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS **Systems:** 

**Description:** The \_mbccmp function compares one multibyte character from s1 to one multibyte character from s2.

The \_fmbccmp function is a data model independent form of the \_mbccmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The \_mbccmp and \_fmbccmp functions return the following values.

```
Value Meaning
Meaning
multibyte character at s1 less than multibyte character at s2
multibyte character at s1 identical to multibyte character at s2
multibyte character at s1 greater than multibyte character at s2
```

See Also:

\_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs\_s, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** 

```
#include <mbctype.h>
#include <mbstring.h>
unsigned char mb1[2] = {
    0x81, 0x43
};
unsigned char mb2[2] = {
    0x81, 0x42
};
void main()
  {
    int
             i;
    _setmbcp( 932 );
    i = \underline{mbccmp(mb1, mb2)};
    if(i < 0)
        printf( "Less than \n" );
    else if ( i == 0 )
        printf( "Equal to\n" );
    else
        printf( "Greater than\n" );
  }
```

produces the following:

#include <stdio.h>

Greater than

Classification: ISO C

\_mbccmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS \_fmbccmp - DOS, Windows, OS/2 1.x(all) **Systems:** 

```
Synopsis:
            #include <mbstring.h>
            void _mbccpy( unsigned char *dest,
                            const unsigned char *ch );
            void _fmbccpy( unsigned char __far *dest,
                             const unsigned char __far *ch );
Description:
            The _mbccpy function copies one multibyte character from ch to dest.
            The _fmbccpy function is a data model independent form of the _mbccpy function that accepts far
            pointer arguments. It is most useful in mixed memory model applications.
Returns:
            The _mbccpy function does not return a value.
See Also:
            _mbccmp, _mbcicmp, _mbcjistojms, _mbcjmstojis, _mbclen, _mbctohira,
            _mbctokata, _mbctolower, _mbctombb, _mbctoupper, mblen, mbrlen, mbrtowc,
            mbsrtowcs, mbsrtowcs_s, mbstowcs, mbstowcs_s, mbtowc, mbsinit, btowc, wcrtomb,
            wcrtomb_s, wcsrtombs, wcsrtombs_s, wcstombs, wcstombs_s, wctob, wctomb,
            wctomb_s
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            unsigned char mb1[2] = {
                 0x00, 0x00
            };
            unsigned char mb2[4] = {
                 0x81, 0x42, 0x81, 0x41
            };
            void main()
              {
                 _setmbcp( 932 );
                printf( \%#6.4x\n", mb1[0] << 8 | mb1[1] );
                 _mbccpy( mb1, mb2 );
                printf( "%#6.4x\n", mb1[0] << 8 | mb1[1] );</pre>
              }
            produces the following:
              0000
            0x8142
Classification: WATCOM
            _mbccpy - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux,
Systems:
            _fmbccpy - DOS, Windows, OS/2 1.x(all)
```

		_mbccpy, _fmbccpy

### **Synopsis:**

### **Description:**

The function compares one multibyte character from s1 to one multibyte character from s2 using a case-insensitive comparison. Uppercase character from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_fmbcicmp function is a data model independent form of the \_mbcicmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

### **Returns:**

The function returns the following values.

#include <stdio.h>

Value	Meaning
< 0	multibyte character at $s1$ less than multibyte character at $s2$
0	multibyte character at $s1$ identical to multibyte character at $s2$
> 0	multibyte character at s1 greater than multibyte character at s2

### See Also:

\_mbccmp, \_mbccpy, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs\_s, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wcstomb, wctomb, wctomb\_s

### **Example:**

```
#include <mbctype.h>
#include <mbstring.h>
unsigned char mb1[2] = {
    0x41, 0x42
};
unsigned char mb2[2] = {
    0x61, 0x43
} ;
void main()
  {
            i;
    int
    _setmbcp( 932 );
    i = \underline{mbcicmp(mb1, mb2)};
    if(i < 0)
        printf( "Less than\n" );
    else if( i == 0 )
        printf( "Equal to\n" );
    else
        printf( "Greater than\n" );
  }
```

produces the following:

Equal to

**Classification:** WATCOM

\_mbcicmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS **Systems:** 

\_fmbcicmp - DOS, Windows, OS/2 1.x(all)

Synopsis: #include <mbstring.h>

unsigned int \_mbcjistojms( unsigned int ch );

**Description:** 

The \_mbcjistojms converts a JIS character set code to a shift-JIS character set code. If the argument is out of range, \_mbcjistojms returns 0. Valid JIS double-byte characters are those in which the first and second byte fall in the range 0x21 through 0x7E. This is summarized in the following diagram.

```
[ 1st byte ] [ 2nd byte ] 0x21-0x7E 0x21-0x7E
```

*Note:* The JIS character set code is a double-byte character set defined by JIS, the Japan Industrial Standard Institutes. Shift-JIS is another double-byte character set. It is defined by Microsoft for personal computers and is based on the JIS code. The first byte and the second byte of JIS codes can have values less than 0x80. Microsoft has designed shift-JIS code so that it can be mixed in strings with single-byte alphanumeric codes. Thus the double-byte shift-JIS codes are greater than or equal to 0x8140.

*Note:* This function was called jistojms in earlier versions.

**Returns:** The \_mbcjistojms function returns zero if the argument is not in the range; otherwise, the

corresponding shift-JIS code is returned.

See Also: \_getmbcp, \_mbbtombc, \_mbcjmstojis, \_mbctombb, \_ismbbalnum, \_ismbbalpha,

\_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint,

\_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc,

\_mbcjmstojis, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

Example: #include <stdio.h>

```
#include <mbctype.h>
#include <mbstring.h>

void main()
{
    unsigned short c;

    _setmbcp( 932 );
    c = _mbcjistojms( 0x2152 );
    printf( "%#6.4x\n", c );
}
```

produces the following:

0x8171

**Classification:** WATCOM

**Systems:** All, Linux, RDOS

		_mbcjistojms

Synopsis: #include <mbstring.h>

unsigned int \_mbcjmstojis( unsigned int ch );

**Description:** 

The \_mbcjmstojis converts a shift-JIS character set code to a JIS character set code. If the argument is out of range, \_mbcjmstojis returns 0. Valid shift-JIS double-byte characters are those in which the first byte falls in the range 0x81 through 0x9F or 0xE0 through 0xFC and whose second byte falls in the range 0x40 through 0x7E or 0x80 through 0xFC. This is summarized in the following diagram.

*Note:* The JIS character set code is a double-byte character set defined by JIS, the Japan Industrial Standard Institutes. Shift-JIS is another double-byte character set. It is defined by Microsoft for personal computers and is based on the JIS code. The first byte and the second byte of JIS codes can have values less than 0x80. Microsoft has designed shift-JIS code so that it can be mixed in strings with single-byte alphanumeric codes. Thus the double-byte shift-JIS codes are greater than or equal to 0x8140.

*Note:* This function was called jmstojis in earlier versions.

**Returns:** 

The \_mbcjmstojis function returns zero if the argument is not in the range; otherwise, the corresponding shift-JIS code is returned.

See Also:

\_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbctombb, \_ismbbalnum, \_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct, \_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbctombb, \_mbbtype, \_mbsbtype, \_setmbcp

**Example:** 

```
#include <stdio.h>
#include <mbctype.h>
#include <mbctring.h>

void main()
{
    unsigned short c;
    _setmbcp( 932 );
    c = _mbcjmstojis( 0x8171 );
    printf( "%#6.4x\n", c );
}
```

produces the following:

0x2152

**Classification:** WATCOM

**Systems:** All, Linux, RDOS

			_mbcjmstojis
-			

```
Synopsis: #include <mbstring.h>
     size_t _mbclen( const unsigned char *ch );
     size_t _fmbclen( const unsigned char __far *ch );
```

**Description:** The \_mbclen function determines the number of bytes comprising the multibyte character pointed to by *ch*.

The \_fmbclen function is a data model independent form of the \_mbclen function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** If *ch* is a NULL pointer, the \_mbclen function returns zero if multibyte character encodings do not have state-dependent encoding, and non-zero otherwise. If *ch* is not a NULL pointer, the \_mbclen

function returns:

# Value Meaning o if ch points to the null character 1 if ch points to a single-byte character 2 if ch points to a double-byte character -1 if ch does not point to a valid multibyte character

See Also: \_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbctohira, mbctokata, mbctolower, mbctombb, mbctoupper, mblen, mbrlen, mbrt

\_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbstowcs\_s, mbstowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb,

wctomb\_s

Example: #include <stdio.h>

```
#include <mbctype.h>
#include <mbstring.h>
unsigned char chars[] = {
   ' . ' ,
   11',
   'A',
   0x81,0x40, /* double-byte space */
   0x82,0x60, /* double-byte A */
   0x82,0xA6, /* double-byte Hiragana */
   0x83,0x42, /* double-byte Katakana */
             /* single-byte Katakana punctuation */
   0xA1,
             /* single-byte Katakana alphabetic */
   0xA6,
   0x00
           /* null character */
};
```

```
void main()
             {
                       i, j;
               int
               _setmbcp( 932 );
               for(i = 0; i < sizeof(chars); i += j) {
                   j = _mbclen( &chars[i] );
                   printf( "%d bytes in character\n", j );
             }
           produces the following:
           1 bytes in character
           1 bytes in character
           1 bytes in character
           1 bytes in character
           2 bytes in character
           2 bytes in character
           2 bytes in character
           2 bytes in character
           1 bytes in character
           1 bytes in character
           1 bytes in character
           2 bytes in character
           1 bytes in character
Classification: WATCOM
Systems:
           _mbclen - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux,
           _fmbclen - DOS, Windows, OS/2 1.x(all)
```

Synopsis: #include <mbstring.h>
 unsigned int \_mbctolower( unsigned int c );

**Description:** The \_mbctolower function converts an uppercase multibyte character to an equivalent lowercase multibyte character.

For example, in code page 932, this includes the single-byte uppercase letters A-Z and the double-byte uppercase characters such that:

```
0x8260 \le c \le 0x8279
```

*Note:* This function was called jtolower in earlier versions.

**Returns:** The \_mbctolower function returns the argument value if the argument is not a double-byte uppercase character; otherwise, the equivalent lowercase character is returned.

See Also: \_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs\_s, mbstowcs\_s, mbstowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** #include <stdio.h> #include <mbctype.h> #include <mbstring.h> unsigned int chars[] = { /\* single-byte A \*/ 'Α', /\* single-byte B \*/
/\* single-byte C \*/ ′B′, ′C′, /\* single-byte D \*/ 'D', /\* single-byte E \*/ Έ', /\* double-byte A \*/ 0x8260, /\* double-byte B \*/ 0x8261, 0x8262, /\* double-byte C \*/ /\* double-byte D \*/ 0x8263, 0x8264 /\* double-byte E \*/ };

#define SIZE sizeof( chars ) / sizeof( unsigned int )

void main()
{
 int i;
 unsigned int c;

 \_setmbcp( 932 );
 for( i = 0; i < SIZE; i++ ) {
 c = \_mbctolower( chars[ i ] );
 if( c > 0xff )
 printf( "%c%c", c>>8, c );
 else
 printf( "%c", c );
 }
 printf( "\n" );
}

produces the following:

abcde a b c d e

**Classification:** WATCOM

**Systems:** DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS **Synopsis:** #include <mbstring.h> unsigned int \_mbctoupper( unsigned int c );

**Description:** The \_mbctoupper function converts a lowercase multibyte character to an equivalent uppercase multibyte character.

> For example, in code page 932, this includes the single-byte lowercase letters a-z and the double-byte lowercase characters such that:

```
0x8281 \le c \le 0x829A
```

**Note:** This function was called jtoupper in earlier versions.

**Returns:** The \_mbctoupper function returns the argument value if the argument is not a double-byte lowercase character; otherwise, the equivalent uppercase character is returned.

See Also: \_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** #include <stdio.h> #include <mbctype.h> #include <mbstring.h> unsigned int chars[] = { /\* single-byte a \*/ 'a', 'b', /\* single-byte b \*/
/\* single-byte c \*/ 'c', /\* single-byte d \*/ 'd', /\* single-byte e \*/ 'e', /\* double-byte a \*/ 0x8281, /\* double-byte b \*/ 0x8282, 0x8283, /\* double-byte c \*/ /\* double-byte d \*/ 0x8284, /\* double-byte e \*/ 0x8285 }; #define SIZE sizeof( chars ) / sizeof( unsigned int ) void main()

```
c = _mbctoupper( chars[ i ] );
    if(c > 0xff)
      printf( "%c%c", c>>8, c );
    else
      printf( "%c", c );
 printf( "\n" );
}
```

for(i = 0; i < SIZE; i++) {

{

int

i; unsigned int c;

\_setmbcp( 932 );

produces the following:

ABCDE A B C D E

**Classification:** WATCOM

**Systems:** DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS Synopsis: #include <mbstring.h>
 unsigned int \_mbctohira( unsigned int ch );

**Description:** The \_mbctohira converts a double-byte Katakana character to a Hiragana character. A double-byte Katakana character is any character for which the following expression is true:

```
0x8340 \le ch \le 0x8396 && ch != 0x837F
```

Any Katakana character whose value is less than 0x8393 is converted to Hiragana (there are 3 extra Katakana characters that have no equivalent).

*Note:* The Japanese double-byte character set includes Kanji, Hiragana, and Katakana characters - both alphabetic and numeric. Kanji is the ideogram character set of the Japanese character set. Hiragana and Katakana are two types of phonetic character sets of the Japanese character set. The Hiragana code set includes 83 characters and the Katakana code set includes 86 characters.

*Note:* This function was called jtohira in earlier versions.

**Returns:** The \_mbctohira function returns the argument value if the argument is not a double-byte Katakana character; otherwise, the equivalent Hiragana character is returned.

See Also: \_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs\_s, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

Example: #include <stdio.h>

```
#include <mbctype.h>
#include <mbstring.h>
unsigned int chars[] = {
    0x8340,
    0x8364,
    0x8396
};
#define SIZE sizeof( chars ) / sizeof( unsigned int )
void main()
  {
    int
          i;
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      printf( \%#6.4x - \%#6.4x\n",
              chars[ i ],
              _mbctohira( chars[ i ] ) );
  }
```

produces the following:

0x8340 - 0x829f 0x8364 - 0x82c3 0x8396 - 0x8396

**Classification:** WATCOM

**Systems:** All, Linux, RDOS Synopsis: #include <mbstring.h>
 unsigned int \_mbctokata( unsigned int ch );

**Description:** The \_mbctokata converts a doub

The \_mbctokata converts a double-byte Hiragana character to a Katakana character. A double-byte Hiragana character is any character for which the following expression is true:

```
0x829F \le c \le 0x82F1
```

*Note:* The Japanese double-byte character set includes Kanji, Hiragana, and Katakana characters - both alphabetic and numeric. Kanji is the ideogram character set of the Japanese character set. Hiragana and Katakana are two types of phonetic character sets of the Japanese character set. The Hiragana code set includes 83 characters and the Katakana code set includes 86 characters.

Note: This function was called jtokata in earlier versions.

**Returns:** The \_mbctokata function returns the argument value if the argument is not a double-byte Hiragana character; otherwise, the equivalent Katakana character is returned.

See Also: \_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs\_s, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** #include <stdio.h> #include <mbctype.h> #include <mbstring.h> unsigned int chars[] = { 0x829F, 0x82B0, 0x82F1 }; #define SIZE sizeof( chars ) / sizeof( unsigned int ) void main() { int i; \_setmbcp( 932 ); for ( i = 0; i < SIZE; i++ ) { printf(  $\$\#6.4x - \$\#6.4x \n$ ",

chars[i],

\_mbctokata( chars[ i ] ) );

produces the following:

}

0x829f - 0x8340 0x82b0 - 0x8351 0x82f1 - 0x8393

**Classification:** WATCOM

m	h	^t	^	ka	ta
111	IJ	Gι	U	Νа	La

**Systems:** All, Linux, RDOS

```
Synopsis:
            #include <mbstring.h>
            unsigned int _mbctombb( unsigned int ch );
Description:
            The _mbct ombb function returns the single-byte character equivalent to the double-byte character ch.
            The single-byte character will be in the range 0x20 through 0x7E or 0xA1 through 0xDF.
            Note: This function was called zentohan in earlier versions.
Returns:
            The _mbctombb function returns ch if there is no equivalent single-byte character; otherwise
            _mbctombb returns a single-byte character.
See Also:
            _getmbcp, _mbbtombc, _mbcjistojms, _mbcjmstojis, _ismbbalnum, _ismbbalpha,
            _ismbbgraph, _ismbbkalnum, _ismbbkalpha, _ismbbkana, _ismbbkprint,
            _ismbbkpunct, _ismbblead, _ismbbprint, _ismbbpunct, _ismbbtrail, _mbbtombc,
            _mbcjistojms, _mbcjmstojis, _mbbtype, _mbsbtype, _setmbcp
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            #define ZEN(x) 130*256+(x-1+32)
            unsigned int alphabet[26] = {
                 ZEN('A'), ZEN('B'), ZEN('C'), ZEN('D'), ZEN('E'),
                 ZEN('F'), ZEN('G'), ZEN('H'), ZEN('I'), ZEN('J'),
                 ZEN('K'), ZEN('L'), ZEN('M'), ZEN('N'), ZEN('O'),
                 ZEN('P'), ZEN('Q'), ZEN('R'), ZEN('S'), ZEN('T'),
                 ZEN('U'), ZEN('V'), ZEN('W'), ZEN('X'), ZEN('Y'),
                 ZEN('Z')
            };
            #define SIZE sizeof( alphabet ) / sizeof( unsigned int )
            void main()
               {
                 int
                                    i;
                 unsigned int
                 _setmbcp( 932 );
                 for( i = 0; i < SIZE; i++ ) {
                   c = _mbctombb( alphabet[ i ] );
                   printf( "%c", c );
                 printf( "\n" );
               }
            produces the following:
            ABCDEFGHIJKLMNOPQRSTUVWXYZ
```

Classification: WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

		_mbctombb

```
Synopsis:
             #include <mbstring.h>
             unsigned char *_mbgetcode( unsigned char *mbstr,
                                              unsigned int *dbchp );
             unsigned char __far *_fmbgetcode( unsigned char __far *mbstr,
                                                      unsigned int __far *dbchp );
Description:
             The _mbgetcode function places the next single-byte or double-byte character from the start of the
             Kanji string specified by mbstr in the wide character pointed to by dbchp. If the second-half of a
             double-byte character is NULL, then the returned wide character is NULL.
             The _fmbgetcode function is a data model independent form of the _mbgetcode function. It
             accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model
             applications.
Returns:
             The _mbget code function returns a pointer to the next character to be obtained from the string. If
             mbstr points at a null character then mbstr is returned.
See Also:
             _mbsnccnt, _mbputchar
Example:
             #include <stdio.h>
             #include <mbctype.h>
             #include <mbstring.h>
             unsigned char set[] = {
                  "ab\x81\x41\x81\x42\cd\x81"
             };
             void main()
               {
                  unsigned int c;
                  unsigned char *str;
                  _setmbcp( 932 );
                  str = set;
                  for(; *str != '\0'; ) {
                      str = _mbgetcode( str, &c );
                      printf( "Character code 0x%2.2x\n", c );
               }
             produces the following:
             Character code 0x61
             Character code 0x62
             Character code 0x8141
             Character code 0x8142
             Character code 0x63
             Character code 0x64
             Character code 0x00
Classification: WATCOM
```

\_mbgetcode - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,

\_fmbgetcode - DOS, Windows, OS/2 1.x(all)

**Systems:** 

_mbgetcode, _fmbgetcode

## Synopsis: #include <stdlib.h>

or

#include <mbstring.h>
int mblen( const char \*s, size\_t n );
int \_fmblen( const char \_\_far \*s, size\_t n );

**Description:** 

The mblen function determines the number of bytes comprising the multibyte character pointed to by *s*. At most *n* bytes of the array pointed to by *s* will be examined.

The \_fmblen function is a data model independent form of the mblen function that accepts far pointer arguments. It is most useful in mixed memory model applications.

#### **Returns:**

If *s* is a NULL pointer, the mblen function returns zero if multibyte character encodings are not state dependent, and non-zero otherwise. If *s* is not a NULL pointer, the mblen function returns:

## Value Meaning

*o* if *s* points to the null character

*len* the number of bytes that comprise the multibyte character (if the next *n* or fewer bytes form a valid multibyte character)

-1 if the next *n* bytes do not form a valid multibyte character

#### See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs\_s, mbstowcs\_s, mbstowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

```
#include <stdio.h>
#include <mbstring.h>
const char chars[] = {
    ′.′,
    111,
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
               /* single-byte Katakana punctuation */
    0xA1,
               /* single-byte Katakana alphabetic */
    0xA6,
    0xDF,
               /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
void main()
  {
    int
                i, j, k;
    _setmbcp( 932 );
    printf( "Character encodings are %sstate dependent\n",
             ( mblen( NULL, MB_CUR_MAX ) ) ? "" : "not " );
    j = 1;
    for(i = 0; j > 0; i += j) {
      j = mblen( &chars[i], MB_CUR_MAX );
      printf( "%d bytes in character ", j );
      if(j == 0) {
        k = 0;
      } else if ( j == 1 ) {
        k = chars[i];
      } else if( j == 2 ) {
        k = chars[i] << 8 | chars[i+1];
      printf( "(\%#6.4x)\n", k );
    }
  }
produces the following:
Character encodings are not state dependent
1 bytes in character (0x0020)
1 bytes in character (0x002e)
1 bytes in character (0x0031)
1 bytes in character (0x0041)
2 bytes in character (0x8140)
2 bytes in character (0x8260)
2 bytes in character (0x82a6)
2 bytes in character (0x8342)
1 bytes in character (0x00a1)
1 bytes in character (0x00a6)
1 bytes in character (0x00df)
2 bytes in character (0xe0a1)
0 bytes in character ( 0000)
```

# mblen, \_fmblen

Classification: ISO C

Systems: mblen - All, Linux, RDOS, Netware

\_fmblen - DOS, Windows, OS/2 1.x(all)

```
Synopsis:
            #include <mbstring.h>
            unsigned char *_mbputchar( unsigned char *mbstr,
                                             unsigned int dbch );
            unsigned char __far *_fmbputchar( unsigned char __far *mbstr,
                                                     unsigned int dbch );
Description:
            The _mbput char function places the next single-byte or double-byte character specified by dbch at
            the start of the buffer specified by mbstr.
            The _fmbputchar function is a data model independent form of the _mbputchar function. It
            accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model
            applications.
Returns:
            The _mbputchar function returns a pointer to the next location in which to store a character.
See Also:
            _mbsnccnt, _mbgetcode
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            void main()
               {
                 unsigned int c;
                 unsigned char *str1;
                 unsigned char *str2;
                 unsigned char buf[30];
                 _setmbcp( 932 );
                 str1 = "ab\x82\x62\x82\x63\ef\x81\x66";
                 str2 = buf;
                 for(; *str1 != '\0'; ) {
                      str1 = _mbgetcode( str1, &c );
                      str2 = _mbputchar( str2, '<' );</pre>
                      str2 = \_mbputchar(str2, c);
                      str2 = _mbputchar( str2, '>' );
                 *str2 = '\0';
                 printf( "%s\n", buf );
            produces the following:
            <a><b>< C>< D><e><f>< G>
```

## **Classification:** WATCOM

```
Systems:
           _mbputchar - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
           _fmbputchar - DOS, Windows, OS/2 1.x(all)
```

_mbputchar, _	fmbputchar		

#### **Synopsis:**

```
#include <wchar.h>
size_t mbrlen( const char *s, size_t n, mbstate_t *ps );
size_t _fmbrlen( const char __far *s, size_t n, mbstate_t __far *ps )
```

#### **Description:**

The mbrlen function determines the number of bytes comprising the multibyte character pointed to by s. The mbrlen function is equivalent to the following call:

```
mbrtowc(NULL, s, n, ps != NULL ? ps : &internal)
```

where &internal is the address of the internal mbstate\_t object for the mbrlen function.

The \_fmbrlen function is a data model independent form of the mbrlen function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The restartable multibyte/wide character conversion functions differ from the corresponding internal-state multibyte character functions (mblen, mbtowc, and wctomb) in that they have an extra argument, ps, of type pointer to mbstate\_t that points to an object that can completely describe the current conversion state of the associated multibyte character sequence. If ps is a null pointer, each function uses its own internal mbstate\_t object instead. You are guaranteed that no other function in the library calls these functions with a null pointer for ps, thereby ensuring the stability of the state.

Also unlike their corresponding functions, the return value does not represent whether the encoding is state-dependent.

If the encoding is state-dependent, on entry each function takes the described conversion state (either internal or pointed to by ps) as current. The conversion state described by the pointed-to object is altered as needed to track the shift state of the associated multibyte character sequence. For encodings without state dependency, the pointer to the mbstate\_t argument is ignored.

## **Returns:**

The mbrlen function returns a value between 0 and n, inclusive, (size\_t) -2 or (size\_t) -1. The mbrlen function returns the first of the following that applies:

Value	Meaning
0	if the next $n$ or fewer bytes form the multibyte character that corresponds to the null wide character.
>0	if the next $n$ or fewer bytes form a valid multibyte character; the value returned is the number of bytes that constitute that multibyte character.
(size_t)-2	if the next $n$ bytes form an incomplete (but potentially valid) multibyte character, and all $n$ bytes have been processed; it is unspecified whether this can occur when the value of $n$ is less than that of the MB_CUR_MAX macro.
(size_t)-1	if an encoding error occurs (when the next $n$ or fewer bytes do not form a complete and valid multibyte character); the mbrlen function stores the value of the macro EILSEQ in errno and returns (size_t)-1; but the conversion state is unspecified.

#### See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

```
Example:
           #include <stdio.h>
           #include <wchar.h>
           #include <mbctype.h>
           #include <errno.h>
           const char chars[] = {
               ,, ,
               '.',
               111,
               'A',
               0x81,0x40, /* double-byte space */
               0x82,0x60, /* double-byte A */
               0x82,0xA6, /* double-byte Hiragana */
               0x83,0x42, /* double-byte Katakana */
               0xA1,
                          /* single-byte Katakana punctuation */
                          /* single-byte Katakana alphabetic */
               0xA6,
                         /* single-byte Katakana alphabetic */
               0xE0,0xA1, /* double-byte Kanji */
           } ;
           void main()
             {
                          i, j, k;
               int
               _setmbcp( 932 );
               j = 1;
               for(i = 0; j > 0; i += j) {
                 j = mbrlen( &chars[i], MB_CUR_MAX, NULL );
                 printf( "%d bytes in character ", j );
                 if( errno == EILSEQ ) {
                   printf( " - illegal multibyte character\n" );
                 } else {
                   if(j == 0) {
                     k = 0;
                   } else if ( j == 1 ) {
                     k = chars[i];
                   \} else if( j == 2 ) {
                     k = chars[i] << 8 | chars[i+1];
                   printf( "(%#6.4x)\n", k );
                 }
               }
             }
```

produces the following:

```
1 bytes in character (0x0020)
1 bytes in character (0x002e)
1 bytes in character (0x0031)
1 bytes in character (0x0041)
2 bytes in character (0x8140)
2 bytes in character (0x8260)
2 bytes in character (0x82a6)
2 bytes in character (0x8342)
1 bytes in character (0x00a1)
1 bytes in character (0x00a6)
1 bytes in character (0x00df)
2 bytes in character (0xe0a1)
0 bytes in character ( 0000)
```

### Classification: ISO C95

**Systems:** mbrlen - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux,

\_fmbrlen - DOS, Windows, OS/2 1.x(all)

#### **Synopsis:**

## **Description:**

If s is not a null pointer, the mbrtowc function determines the number of bytes that are contained in the multibyte character (plus any leading shift sequences) pointed to by s, produces the value of the corresponding wide character and then, if pwc is not a null pointer, stores that value in the object pointed to by pwc. If the corresponding wide character is the null wide character, the resulting state described will be the initial conversion state.

If s is a null pointer, the mbrtowc function is equivalent to call

```
mbrtowc(NULL, "", 1, ps)
```

In this case, the values of the parameters pwc and n are ignored. Function determines the number of bytes necessary to enter the initial shift state (zero if encodings are not state-dependent or if the initial conversion state is described).

The \_fmbrtowc function is a data model independent form of the mbrtowc function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The restartable multibyte/wide character conversion functions differ from the corresponding internal-state multibyte character functions ( mblen, mbtowc, and wctomb) in that they have an extra argument, ps, of type pointer to mbstate\_t that points to an object that can completely describe the current conversion state of the associated multibyte character sequence. If ps is a null pointer, each function uses its own internal mbstate\_t object instead. You are guaranteed that no other function in the library calls these functions with a null pointer for ps, thereby ensuring the stability of the state.

Also unlike their corresponding functions, the return value does not represent whether the encoding is state-dependent.

If the encoding is state-dependent, on entry each function takes the described conversion state (either internal or pointed to by ps) as current. The conversion state described by the pointed-to object is altered as needed to track the shift state of the associated multibyte character sequence. For encodings without state dependency, the pointer to the mbstate\_t argument is ignored.

#### **Returns:**

The mbrtowc function returns a value between 0 and n, inclusive, (size\_t) -2 or (size\_t) -1. The mbrtowc function returns the first of the following that applies:

Value	Meaning
0	if the next $n$ or fewer bytes form the multibyte character that corresponds to the null wide character.
>0	if the next $n$ or fewer bytes form a valid multibyte character; the value returned is the number of bytes that constitute that multibyte character.
(size_t)-2	if the next $n$ bytes form an incomplete (but potentially valid) multibyte character, and all $n$ bytes have been processed; it is unspecified whether this can occur when the value of $n$ is less than that of the MB_CUR_MAX macro.

(size t)-1if an encoding error occurs (when the next n or fewer bytes do not form a complete and valid multibyte character); the mbrtowc function stores the value of the macro EILSEQ in errno and returns (size\_t) -1; but the conversion state is unspecified.

See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

```
#include <stdio.h>
#include <wchar.h>
#include <mbctype.h>
#include <errno.h>
const char chars[] = {
   ′′,
   ′.′,
   '1',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
              /* single-byte Katakana punctuation */
    0xA1,
              /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
```

```
void main()
             {
               int
                           i, j, k;
               wchar_t
                           pwc;
               _setmbcp( 932 );
               i = mbrtowc( NULL, NULL, MB_CUR_MAX, NULL );
               printf( "Number of bytes to enter "
                        "initial shift state = %d\n", i );
               j = 1;
               for(i = 0; j > 0; i += j) {
                 j = mbrtowc( &pwc, &chars[i], MB_CUR_MAX, NULL );
                 printf( "%d bytes in character ", j );
                 if( errno == EILSEQ ) {
                   printf( " - illegal multibyte character\n" );
                 } else {
                   if(j == 0) {
                     k = 0;
                   } else if ( j == 1 ) {
                     k = chars[i];
                   \} else if( j == 2 ) {
                     k = chars[i] << 8 | chars[i+1];
                   printf( "(%#6.4x->%#6.4x)\n", k, pwc );
               }
             }
           produces the following:
           Number of bytes to enter initial shift state = 0
           1 bytes in character (0x0020->0x0020)
           1 bytes in character (0x002e->0x002e)
           1 bytes in character (0x0031->0x0031)
           1 bytes in character (0x0041->0x0041)
           2 bytes in character (0x8140 -> 0x3000)
           2 bytes in character (0x8260->0xff21)
           2 bytes in character (0x82a6->0x3048)
           2 bytes in character (0x8342->0x30a3)
           1 bytes in character (0x00a1->0xff61)
           1 bytes in character (0x00a6->0xff66)
           1 bytes in character (0x00df->0xff9f)
           2 bytes in character (0xe0a1->0x720d)
           0 bytes in character ( 0000-> 0000)
Classification: ISO C95
           mbrtowc - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux,
Systems:
           RDOS
           _fmbrtowc - DOS, Windows, OS/2 1.x(all)
```

	mbrtowc,	_fmbrtowc

Synopsis: #include <mbstring.h>

#include <mbctype.h> (for manifest constants)

int \_mbsbtype( const unsigned char \*mbstr, int count );

int \_fmbsbtype( const unsigned char \_\_far \*mbstr, int count );

**Description:** The \_mbsbtype function determines the type of a byte in a multibyte character string. The function

examines only the byte at offset count in mbstr, ignoring invalid characters before the specified byte.

Note: A similar function was called in earlier versions.

The \_fmbsbtype function is a data model independent form of the \_mbsbtype function that accepts

far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The \_mbsbtype function returns one of the following values:

**\_MBC\_SINGLE** the character is a valid single-byte character (e.g., 0x20 - 0x7E, 0xA1 - 0xDF

in code page 932)

\_MBC\_LEAD the character is a valid lead byte character (e.g., 0x81 - 0x9F, 0xE0 - 0xFC in

code page 932)

\_MBC\_TRAIL the character is a valid trailing byte character (e.g., 0x40 - 0x7E, 0x80 - 0xFC

in code page 932)

\_MBC\_ILLEGAL the character is an illegal character (e.g., any value except 0x20 - 0x7E, 0xA1

- 0xDF, 0x81 - 0x9F, 0xE0 - 0xFC in code page 932)

See Also: \_getmbcp, \_ismbcalnum, \_ismbcalpha, \_ismbccntrl, \_ismbcdigit, \_ismbcgraph,

\_ismbchira, \_ismbckata, \_ismbcl0, \_ismbcl1, \_ismbcl2, \_ismbclegal,

\_ismbclower, \_ismbcprint, \_ismbcpunct, \_ismbcspace, \_ismbcsymbol,

\_ismbcupper, \_ismbcxdigit, \_mbbtype, \_setmbcp

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const char *types[4] = {
    "ILLEGAL",
    "SINGLE",
    "LEAD",
    "TRAIL"
};
const unsigned char chars[] = {
    '.',
    111,
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
               /* single-byte Katakana punctuation */
    0xA1,
               /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xDF,
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
#define SIZE sizeof( chars ) / sizeof( unsigned char )
void main()
 {
    int
            i;
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ )
      printf( "%s\n", types[ 1+_mbsbtype( chars, i ) ] );
  }
produces the following:
SINGLE
SINGLE
SINGLE
SINGLE
LEAD
TRAIL
LEAD
TRAIL
LEAD
TRAIL
LEAD
TRAIL
SINGLE
SINGLE
SINGLE
LEAD
TRAIL
ILLEGAL
```

# \_mbsbtype, \_fmbsbtype

**Classification:** WATCOM

Systems: \_mbsbtype - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

\_fmbsbtype - DOS, Windows, OS/2 1.x(all)

### **Synopsis:**

```
#include <mbstring.h>
unsigned char *_mbsdec( const unsigned char *start,
                        const unsigned char *current );
unsigned char __far *_fmbsdec( const unsigned char __far *start,
                               const unsigned char __far *current );
#include <tchar.h>
char *_strdec( const char *start, const char *current );
wchar_t *_wcsdec( const wchar_t *start,
                  const wchar_t *current );
```

#### **Description:**

The \_mbsdec function returns a pointer to the previous multi-byte character in the multi-byte character string pointed to by *start* which must precede *current*. The current multi-byte character in the string is pointed to by current. You must ensure that current does not point into the middle of a multi-byte or wide character.

The \_fmbsdec function is a data model independent form of the \_mbsdec function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The header file <tchar.h> defines the generic-text macro \_tcsdec.

The \_tcsdec macro maps to \_mbsdec if \_MBCS has been defined, or to the \_wcsdec macro if \_UNICODE has been defined, otherwise it maps to \_strdec macro.

\_strdec and \_wcsdec are single-byte character string and wide character string versions of

The \_strdec and \_wcsdec macros are provided only for this mapping and should not be used otherwise.

**Returns:** 

These functions return a pointer to the previous character (multi-byte, wide, or single-byte).

See Also:

\_mbsinc, \_mbsninc

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char chars[] = {
    ′.′,
    11',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
              /* single-byte Katakana punctuation */
    0xA1,
              /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xDF,
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
#define SIZE sizeof( chars ) / sizeof( unsigned char )
```

```
void main()
             {
                                    j, k;
               int
               const unsigned char *prev;
               _setmbcp( 932 );
               prev = &chars[ SIZE - 1 ];
               do {
                 prev = _mbsdec( chars, prev );
                 j = mblen( prev, MB_CUR_MAX );
                 if(j == 0) {
                   k = 0;
                 } else if ( j == 1 ) {
                   k = *prev;
                 } else if( j == 2 ) {
                   k = *(prev) <<8 | *(prev+1);
                 printf( "Previous character %#6.4x\n", k );
               } while( prev != chars );
           produces the following:
           Previous character 0xe0a1
           Previous character 0x00df
           Previous character 0x00a6
           Previous character 0x00a1
           Previous character 0x8342
           Previous character 0x82a6
           Previous character 0x8260
           Previous character 0x8140
           Previous character 0x0041
           Previous character 0x0031
           Previous character 0x002e
           Previous character 0x0020
Classification: WATCOM
Systems:
           _mbsdec - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
          _fmbsdec - DOS, Windows, OS/2 1.x(all)
           _strdec - MACRO
           _wcsdec - MACRO
```

#### **Synopsis:** #include <mbstring.h>

```
unsigned char *_mbsinc( const unsigned char *current );
unsigned char __far *_fmbsinc( const unsigned char __far *current );
#include <tchar.h>
char *_strinc( const char *current );
wchar_t *_wcsinc( const wchar_t *current );
```

## **Description:**

The \_mbsinc function returns a pointer to the next multi-byte character in the string pointed to by current. You must ensure that current does not point into the middle of a multi-byte or wide character.

The \_fmbsinc function is a data model independent form of the \_mbsinc function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The header file <tchar.h> defines the generic-text macro \_tcsinc.

The \_tcsinc macro maps to \_mbsinc if \_MBCS has been defined, or to the \_wcsinc macro if \_UNICODE has been defined, otherwise it maps to \_strinc macro.

\_strinc and \_wcsinc are single-byte character string and wide character string versions of \_mbsinc.

The \_strinc and \_wcsinc macros are provided only for this mapping and should not be used otherwise.

**Returns:** These functions return a pointer to the next character (multi-byte, wide, or single-byte).

See Also: \_mbsdec, \_mbsninc

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char chars[] = {
    ′.′,
    11',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
               /* single-byte Katakana punctuation */
               /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xDF,
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
#define SIZE sizeof( chars ) / sizeof( unsigned char )
void main()
  {
    int
                         j, k;
    const unsigned char *next;
    _setmbcp( 932 );
    next = chars;
    do {
      next = _mbsinc( next );
      j = mblen( next, MB_CUR_MAX );
      if(j == 0) {
        k = 0;
      } else if ( j == 1 ) {
        k = *next;
      } else if( j == 2 ) {
        k = *(next) << 8 | *(next+1);
      printf( "Next character %#6.4x\n", k );
    } while( next != &chars[ SIZE - 1 ] );
produces the following:
Next character 0x002e
Next character 0x0031
Next character 0x0041
Next character 0x8140
Next character 0x8260
Next character 0x82a6
Next character 0x8342
Next character 0x00a1
Next character 0x00a6
Next character 0x00df
Next character 0xe0a1
Next character 0000
```

## **Classification:** WATCOM

\_mbsinc - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, **Systems:** 

\_fmbsinc - DOS, Windows, OS/2 1.x(all)

\_strinc - MACRO \_wcsinc - MACRO

Synopsis: #include <wchar.h>

int mbsinit( const mbstate\_t \*ps );

\*\* deprecated \*\*

int sisinit( const mbstate\_t \*ps );

**Description:** If *ps* is not a null pointer, the mbsinit function determines whether the pointed-to mbstate\_t

object describes an initial conversion state.

The sisinit function is deprecated, use mbsinit instead.

**Returns:** The mbsinit function returns nonzero if ps is a null pointer or if the pointed-to object describes an

initial conversion state; otherwise, it returns zero.

See Also: \_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira,

\_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, btowc, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb,

wctomb\_s

```
#include <stdio.h>
#include <wchar.h>
#include <mbctype.h>
#include <errno.h>
const char chars[] = {
   , ,
   ·.·,
    11,
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
               /* single-byte Katakana punctuation */
    0xA1,
    0xA6,
               /* single-byte Katakana alphabetic */
    0xDF,
              /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
void main( void )
    int
                i, j, k;
    wchar_t
                pwc;
    mbstate_t pstate = { 0 };
    _setmbcp( 932 );
    j = 1;
    for(i = 0; j > 0; i += j) {
      printf( "We are %sin an initial conversion state\n",
              mbsinit( &pstate ) ? "not " : "" );
      j = mbrtowc( &pwc, &chars[i], MB_CUR_MAX, &pstate );
      printf( "%d bytes in character ", j );
      if( errno == EILSEQ ) {
        printf( " - illegal multibyte character\n" );
      } else {
        if(j == 0) {
          k = 0;
        } else if ( j == 1 ) {
          k = chars[i];
        \} else if( j == 2 ) {
          k = chars[i] << 8 | chars[i+1];
        printf( "(%#6.4x->%#6.4x)\n", k, pwc );
      }
    }
}
```

produces the following:

We are in an initial conversion state 1 bytes in character (0x0020->0x0020)We are in an initial conversion state 1 bytes in character (0x002e->0x002e)We are in an initial conversion state 1 bytes in character (0x0031->0x0031)We are in an initial conversion state 1 bytes in character (0x0041->0x0041)We are in an initial conversion state 2 bytes in character (0x8140->0x3000)We are in an initial conversion state 2 bytes in character (0x8260->0xff21) We are in an initial conversion state 2 bytes in character (0x82a6->0x3048)We are in an initial conversion state 2 bytes in character (0x8342->0x30a3)We are in an initial conversion state 1 bytes in character (0x00a1->0xff61)We are in an initial conversion state 1 bytes in character (0x00a6->0xff66) We are in an initial conversion state 1 bytes in character (0x00df -> 0xff9f)We are in an initial conversion state 2 bytes in character (0xe0a1->0x720d) We are in an initial conversion state 0 bytes in character ( 0000-> 0000)

Classification: ISO C95

sisinit is WATCOM

Systems: mbsinit - All, Linux, RDOS, Netware

sisinit - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

#### **Synopsis:** #include <mbstring.h>

```
unsigned char *_mbsnbcat( unsigned char *dst,
                    const unsigned char *src,
                                  size_t n );
unsigned char __far *_fmbsnbcat( unsigned char __far *dst,
                           const unsigned char __far *src,
                                               size_t n );
```

#### **Description:**

The \_mbsnbcat function appends not more than n bytes of the string pointed to by src to the end of the string pointed to by dst. If the byte immediately preceding the null character in dst is a lead byte, the initial byte of src overwrites this lead byte. Otherwise, the initial byte of src overwrites the terminating null character at the end of dst. If the last byte to be copied from src is a lead byte, the lead byte is not copied and a null character replaces it in dst. In any case, a terminating null character is always appended to the result.

The \_fmbsnbcat function is a data model independent form of the \_mbsnbcat function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The \_mbsnbcat function returns the value of *dst*.

See Also: \_mbsnbcmp, \_mbsnbcpy, \_mbsnbicmp, \_mbsnbset, \_mbsnccnt, strncat, strcat

```
#include <stdio.h>
#include <string.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char str1[] = {
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
};
const unsigned char str2[] = {
    0x81,0x40, /* double-byte space */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
    0x00
};
void main()
  {
    unsigned char big_string[10];
    int
                    i;
    _setmbcp( 932 );
    memset( (char *) big_string, 0xee, 10 );
    big\_string[9] = 0x00;
    printf( "Length of string = %d\n",
            strlen( (char *) big_string ) );
    for( i = 0; i < 10; i++ )
        printf( "%2.2x ", big_string[i] );
    printf( "\n" );
```

```
_mbsnset( big_string, 0x8145, 5 );
               for( i = 0; i < 10; i++)
                   printf( "%2.2x ", big_string[i] );
               printf( "\n" );
               big\_string[0] = 0x00;
               _mbsnbcat(big_string, str1, 3);
               for( i = 0; i < 10; i++)
                   printf( "%2.2x ", big_string[i] );
               printf( "\n" );
               big\_string[2] = 0x84;
               big\_string[3] = 0x00;
               for( i = 0; i < 10; i++)
                   printf( "%2.2x ", big_string[i] );
               printf( "\n" );
               _mbsnbcat( big_string, str2, 5 );
               for( i = 0; i < 10; i++)
                   printf( "%2.2x ", big_string[i] );
               printf( "\n" );
             }
           produces the following:
           Length of string = 9
           ee ee ee ee ee ee ee 00
           81 45 81 45 81 45 81 45 20 00
           81 40 00 00 81 45 81 45 20 00
           81 40 84 00 81 45 81 45 20 00
           81 40 81 40 82 a6 00 00 20 00
Classification: WATCOM
Systems:
           _mbsnbcat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
           _fmbsnbcat - DOS, Windows, OS/2 1.x(all)
```

```
Synopsis:
           #include <mbstring.h>
           int _mbsnbcmp( const unsigned char *s1,
                           const unsigned char *s2,
                           size_t n );
           int _fmbsnbcmp( const unsigned char __far *s1,
                           const unsigned char __far *s2,
```

size\_t n );

**Description:** The \_mbsnbcmp lexicographically compares not more than n bytes from the string pointed to by s1 to the string pointed to by s2.

> The \_fmbsnbcmp function is a data model independent form of the \_mbsnbcmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** 

The \_mbsnbcmp function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by sI is less than, equal to, or greater than the string pointed to by s2. \_mbsnbcmp is similar to \_mbsncmp, except that \_mbsnbcmp compares strings by length in bytes rather than by length in characters.

See Also: \_mbsnbcat, \_mbsnbicmp, strncmp, \_strnicmp

**Example:** 

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char str1[] = {
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x00
};
const unsigned char str2[] = {
    0x81,0x40, /* double-byte space */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
    0x00
} ;
void main()
  {
    _setmbcp( 932 );
    printf( "%d\n", _mbsnbcmp( str1, str2, 3 ) );
produces the following:
0
```

```
Systems:
           _mbsnbcmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
           _fmbsnbcmp - DOS, Windows, OS/2 1.x(all)
```

_mbsnbcmp,	_fmbsnbcmp			

**Synopsis:** #include <mbstring.h>

```
unsigned char *_mbsnbcpy( unsigned char *dst,
                    const unsigned char *src,
                    size_t n );
unsigned char __far *_fmbsnbcpy( unsigned char __far *dst,
                           const unsigned char __far *src,
                           size_t n );
```

**Description:** 

The \_mbsnbcpy function copies no more than n bytes from the string pointed to by src into the array pointed to by dst. Copying of overlapping objects is not guaranteed to work properly.

If the string pointed to by src is shorter than n bytes, null characters are appended to the copy in the array pointed to by dst, until n bytes in all have been written. If the string pointed to by src is longer than n characters, then the result will not be terminated by a null character.

The \_fmbsnbcpy function is a data model independent form of the \_mbsnbcpy function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The \_mbsnbcpy function returns the value of dst.

See Also: strcpy, strdup

**Example:** 

```
#include <stdio.h>
           #include <mbctype.h>
           #include <mbstring.h>
           const unsigned char chars[] = {
               ′.′,
               11',
               'A',
               0x81,0x40, /* double-byte space */
               0x82,0x60, /* double-byte A */
               0x82,0xA6, /* double-byte Hiragana */
               0x83,0x42, /* double-byte Katakana */
                          /* single-byte Katakana punctuation */
                          /* single-byte Katakana alphabetic */
               0xA6,
                         /* single-byte Katakana alphabetic */
               0xDF,
               0xE0,0xA1, /* double-byte Kanji */
               0x00
           };
           void main()
               unsigned char chars2[20];
                               i;
               int
               _setmbcp( 932 );
               _mbsnset( chars2, 0xFF, 20 );
               _mbsnbcpy( chars2, chars, 11 );
               for( i = 0; i < 20; i++)
                   printf( "%2.2x ", chars2[i] );
               printf( "\n" );
               _mbsnbcpy( chars2, chars, 20 );
               for(i = 0; i < 20; i++)
                   printf( "%2.2x ", chars2[i] );
               printf( "\n" );
             }
           produces the following:
           20 2e 31 41 81 40 82 60 82 a6 83 ff ff ff ff ff ff ff ff
           20 2e 31 41 81 40 82 60 82 a6 83 42 a1 a6 df e0 a1 00 00 00
Classification: WATCOM
           _mbsnbcpy - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
Systems:
           _fmbsnbcpy - DOS, Windows, OS/2 1.x(all)
```

```
Synopsis:
```

```
#include <mbstring.h>
int _mbsnbicmp( const unsigned char *s1,
               const unsigned char *s2,
               size_t n );
int _fmbsnbicmp( const unsigned char __far *s1,
                const unsigned char __far *s2,
                size_t n );
```

#### **Description:**

The function lexicographically compares not more than n bytes from the string pointed to by sI to the string pointed to by s2. The comparison is insensitive to case. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_fmbsnbicmp function is a data model independent form of the \_mbsnbicmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

#### **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by sI is less than, equal to, or greater than the string pointed to by s2. \_mbsnbicmp is similar to \_mbsnicmp, except that \_mbsnbicmp compares strings by length in bytes rather than by length in characters.

See Also: \_mbsnbcat, \_mbsnbcmp, strncmp, \_strnicmp

#### **Example:**

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char str1[] = {
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0x79, /* double-byte Z */
};
const unsigned char str2[] = {
    0x81,0x40, /* double-byte space */
    0x82,0x81, /* double-byte a */
    0x82,0x9a, /* double-byte z */
    0x00
};
void main()
  {
    _setmbcp( 932 );
    printf( "%d\n", _mbsnbicmp( str1, str2, 5 ) );
produces the following:
0
```

```
Systems:
```

```
_mbsnbicmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
_fmbsnbicmp - DOS, Windows, OS/2 1.x(all)
```

_mbsnbicmp,	_fmbsnbicmp			

#### **Synopsis:** #include <mbstring.h>

```
unsigned char *_mbsnbset( unsigned char *s,
                          unsigned int fill,
                          size_t count );
unsigned char __far *_fmbsnbset( unsigned char __far *s,
                                  unsigned int fill,
                                  size_t count );
```

#### **Description:**

The \_mbsnbset function fills the string s with the value of the argument fill. When the value of len is greater than the length of the string, the entire string is filled. Otherwise, that number of characters at the start of the string are set to the fill character.

\_mbsnbset is similar to \_mbsnset, except that it fills in count bytes rather than count characters. If the number of bytes to be filled is odd and fill is a double-byte character, the partial byte at the end is filled with an ASCII space character.

The \_fmbsnbset function is a data model independent form of the \_mbsnbset function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The address of the original string *s* is returned.

See Also: \_strnset, \_strset

#### **Example:**

```
#include <stdio.h>
#include <string.h>
#include <mbctype.h>
#include <mbstring.h>
void main()
  {
   unsigned char big_string[10];
    int
                    i;
   _setmbcp( 932 );
   memset( (char *) big_string, 0xee, 10 );
   big\_string[9] = 0x00;
    for( i = 0; i < 10; i++)
        printf( "%2.2x ", big_string[i] );
   printf( "\n" );
   _mbsnbset(big_string, 0x8145, 5);
   for( i = 0; i < 10; i++)
        printf( "%2.2x ", big_string[i] );
   printf( "\n" );
  }
```

produces the following:

```
ee ee ee ee ee ee ee 00
81 45 81 45 20 ee ee ee ee 00
```

```
Systems:
           _mbsnbset - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
           _fmbsnbset - DOS, Windows, OS/2 1.x(all)
```

_mbsnbset,	_fmbsnbset			

```
Synopsis:
           #include <mbstring.h>
```

```
size_t _mbsnbcnt( const unsigned char *string, size_t n );
size_t _mbsnccnt( const unsigned char *string, size_t n );
size_t _fmbsnbcnt( const unsigned char __far *string, size_t n );
size_t _fmbsnccnt( const unsigned char __far *string, size_t n );
#include <tchar.h>
size_t _strncnt( const char *string, size_t n );
size_t _wcsncnt( const wchar_t *string, size_t n ) {
```

**Description:** The \_mbsnbcnt function counts the number of bytes in the first n multibyte characters of the string

string.

The \_mbsnccnt function counts the number of multibyte characters in the first n bytes of the string string. If \_mbsnccnt finds a null byte as the second byte of a double-byte character, the first (lead) byte is not included in the count.

Note: \_mbsnbcnt function was called mtob and \_mbsnccnt function was called btom in earlier versions.

The \_fmbsnbcnt function is a data model independent form of the \_mbsnbcnt function that accepts far pointer arguments.

The \_fmbsnccnt function is a data model independent form of the fmbsnccnt function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The \_fmbsnbcnt function is a data model independent form of the \_mbsnbcnt function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The header file <tchar.h> defines the generic-text macros \_tcsnbcnt and \_tcsnccnt. The \_tcsnbcnt macro maps to \_mbsnbcnt if \_MBCS has been defined, or to the \_wcsncnt macro if \_UNICODE has been defined, otherwise it maps to \_strncnt macro.

The \_tcsnccnt macro maps to \_strncnt if \_MBCS has been defined, or to the macro if \_UNICODE has been defined, otherwise it maps to \_wcsncnt macro.

The \_strncnt and \_wcsncnt macros are provided only for this mapping and should not be used otherwise.

**Returns:** 

The \_mbsnbcnt functions return the number of bytes in the string from the beginning of the string up to the specified number of characters n.

The \_mbsncont functions return the number of characters in the string from the beginning of the string up to the specified number of bytes n or until a null character is encountered. The null character is not included in the count. If the character preceding the null character was a lead byte, the lead byte is not included in the count.

See Also: \_mbsnbcat

**Example:** 

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char chars[] = {
    '.',
    11',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
              /* single-byte Katakana punctuation */
    0xA1,
              /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
void main()
  {
    _setmbcp( 932 );
   printf( "%d bytes found\n",
            _mbsnbcnt(chars, 10));
   printf( "%d characters found\n",
            _mbsnccnt( chars, 10 ) );
  }
```

#### produces the following:

14 bytes found
7 characters found

```
_mbsnbcnt - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS _fmbsnbcnt - DOS, Windows, OS/2 1.x(all) _mbsnccnt - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS _fmbsnccnt - DOS, Windows, OS/2 1.x(all) _strncnt - MACRO _wcsncnt - MACRO
```

#### **Synopsis:** #include <mbstring.h>

```
unsigned int _mbsnextc( const unsigned char *s );
unsigned int _fmbsnextc( const unsigned char __far *s );
#include <tchar.h>
unsigned int _strnextc( const char *s );
unsigned int _wcsnextc( const wchar_t *s ) {
```

#### **Description:**

The \_mbsnextc function returns the integer value of the next multi-byte character in s, without advancing the string pointer. \_mbsnextc recognizes multi-byte character sequences according to the multi-byte character code page currently in use.

The \_fmbsnextc function is a data model independent form of the \_mbsnextc function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The header file <tchar.h> defines the generic-text macro \_tcsnextc.

The \_tcsnextc macro maps to \_mbsnextc if \_MBCS has been defined, or to the \_wcsnextc macro if \_UNICODE has been defined, otherwise it maps to \_strnextc macro.

\_strnextc and \_wcsnextc are single-byte character string and wide character string versions of \_mbsnextc.

The \_strnextc and \_wcsnextc macros are provided only for this mapping and should not be used otherwise.

#### **Returns:**

These functions return the integer value of the next character (multi-byte, wide, or single-byte) pointed to by s.

See Also: \_mbsdec, \_mbsinc, \_mbsninc

#### **Example:**

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char chars[] = {
   , ,
    ′.′,
    '1',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
    0xA1,
             /* single-byte Katakana punctuation */
              /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
void main()
  {
   _setmbcp( 932 );
   printf( \%#6.4x\n", _mbsnextc( &chars[2] ) );
   printf( \%#6.4x\n", _mbsnextc( &chars[4] ) );
   printf( \%#6.4x\n", _mbsnextc( &chars[12] ) );
  }
```

#### produces the following:

0x0031 0x8140 0x00a1

```
Systems: _mbsnextc - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS _fmbsnextc - DOS, Windows, OS/2 1.x(all) _strnextc - MACRO _wcsnextc - MACRO
```

#### **Synopsis:**

```
#include <mbstring.h>
unsigned char *_mbsninc( const unsigned char *s, size_t count );
unsigned char ___far *_fmbsninc( const unsigned char ___far *s,
                                size_t count );
#include <tchar.h>
char *_strninc( const char *s, size_t count );
wchar_t *_wcsninc( const wchar_t *s, size_t count );
```

#### **Description:**

The \_mbsninc function increments s by count of multi-byte characters. \_mbsninc recognizes multi-byte character sequences according to the multi-byte character code page currently in use.

The \_fmbsninc function is a data model independent form of the \_mbsninc function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The header file <tchar.h> defines the generic-text macro \_tcsninc.

The \_tcsninc macro maps to \_mbsninc if \_MBCS has been defined, or to the \_wcsninc macro if \_UNICODE has been defined, otherwise it maps to \_strninc macro.

\_strning and \_wcsning are single-byte character string and wide character string versions of \_mbsninc.

The \_strninc and \_wcsninc macros are provided only for this mapping and should not be used otherwise.

#### **Returns:**

These functions return a pointer to s after it has been incremented by *count* of characters (multi-byte, wide, or single-byte) or NULL if s was NULL. If count exceeds the number of characters remaining in the string, the result is undefined.

See Also: \_mbsdec, \_mbsinc

**Example:** 

```
#include <stdio.h>
#include <mbctype.h>
#include <mbstring.h>
const unsigned char chars[] = {
    ′.′,
    11',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
               /* single-byte Katakana punctuation */
               /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xDF,
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
#define SIZE sizeof( chars ) / sizeof( unsigned char )
void main()
  {
    int
                         j, k;
    const unsigned char *next;
    _setmbcp( 932 );
    next = chars;
    do {
      next = _mbsninc( next, 1 );
      j = mblen( next, MB_CUR_MAX );
      if(j == 0) {
        k = 0;
      } else if ( j == 1 ) {
        k = *next;
      } else if( j == 2 ) {
        k = *(next) << 8 | *(next+1);
      printf( "Next character %#6.4x\n", k );
    } while( next != &chars[ SIZE - 1 ] );
produces the following:
Next character 0x002e
Next character 0x0031
Next character 0x0041
Next character 0x8140
Next character 0x8260
Next character 0x82a6
Next character 0x8342
Next character 0x00a1
Next character 0x00a6
Next character 0x00df
Next character 0xe0a1
Next character 0000
```

### **Classification:** WATCOM

\_mbsninc - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS **Systems:** 

\_fmbsninc - DOS, Windows, OS/2 1.x(all)

\_strninc - MACRO \_wcsninc - MACRO

#### **Synopsis:**

#### Safer C:

The Safer C Library extension provides the mbsrtowcs\_s function which is a safer alternative to mbsrtowcs.

#### **Description:**

The mbsrtowcs function converts a sequence of multibyte characters that begins in the shift state described by ps from the array indirectly pointed to by src into a sequence of corresponding wide characters, which, if dst is not a null pointer, are then stored into the array pointed to by dst. Conversion continues up to and including a terminating null character, but the terminating null wide character will not be stored. Conversion will stop earlier in two cases: when a sequence of bytes is reached that does not form a valid multibyte character, or (if dst is not a null pointer) when len codes have been stored into the array pointed to by dst. Each conversion takes place as if by a call to the mbrtowc function.

If *dst* is not a null pointer, the pointer object pointed to by *src* will be assigned either a null pointer (if conversion stopped due to reaching a terminating null character) or the address just past the last multibyte character converted. If conversion stopped due to reaching a terminating null character and if *dst* is not a null pointer, the resulting state described will be the initial conversion state.

The \_fmbsrtowcs function is a data model independent form of the mbsrtowcs function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The restartable multibyte/wide string conversion functions differ from the corresponding internal-state multibyte string functions ( mbstowcs and wcstombs) in that they have an extra argument, ps, of type pointer to mbstate\_t that points to an object that can completely describe the current conversion state of the associated multibyte character sequence. If ps is a null pointer, each function uses its own internal mbstate\_t object instead. You are guaranteed that no other function in the library calls these functions with a null pointer for ps, thereby ensuring the stability of the state.

Also unlike their corresponding functions, the conversion source argument, *src*, has a pointer-to-pointer type. When the function is storing conversion results (that is, when *dst* is not a null pointer), the pointer object pointed to by this argument will be updated to reflect the amount of the source processed by that invocation.

If the encoding is state-dependent, on entry each function takes the described conversion state (either internal or pointed to by ps) as current and then, if the destination pointer, dst, is not a null pointer, the conversion state described by the pointed-to object is altered as needed to track the shift state of the associated multibyte character sequence. For encodings without state dependency, the pointer to the mbstate\_t argument is ignored.

#### **Returns:**

If the input string does not begin with a valid multibyte character, an encoding error occurs: the mbsrtowcs function stores the value of the macro EILSEQ in errno and returns (size\_t)-1; but the conversion state is unspecified. Otherwise, it returns the number of multibyte characters successfully converted, which is the same as the number of array elements modified when *dst* is not a null pointer.

See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** 

```
#include <stdio.h>
#include <wchar.h>
#include <mbctype.h>
#include <errno.h>
const char chars[] = {
   · ·,
   '.',
    11',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
              /* single-byte Katakana punctuation */
    0xA1,
              /* single-byte Katakana alphabetic */
    0xA6,
              /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
void main()
    int
               i;
               elements;
   size_t
   const char *src;
               wc[50];
   wchar_t
   mbstate_t pstate;
   _setmbcp( 932 );
   src = chars;
   elements = mbsrtowcs( wc, &src, 50, &pstate );
   if( errno == EILSEQ ) {
        printf( "Error in multibyte character string\n" );
        for(i = 0; i < elements; i++) {
            printf( \%#6.4x\n", wc[i] );
    }
}
```

produces the following:

# $mbsrtowcs, \_fmbsrtowcs$

```
0x0020
0x002e
0x0031
0x0041
0x3000
0xff21
0x3048
0x30a3
0xff61
0xff66
0xff9f
0x720d
```

Classification: ISO C95

Systems: mbsrtowcs - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,

Linux, RDOS

\_fmbsrtowcs - DOS, Windows, OS/2 1.x(all)

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__
#include <wchar.h>
errno_t mbsrtowcs_s( size_t * restrict retval,
                     wchar_t * restrict dst, rsize_t dstmax,
                     const char ** restrict src, rsize_t len,
                     mbstate_t * restrict ps);
errno_t _fmbsrtowcs_s( size_t __far * restrict retval,
                       wchar_t __far * restrict dst, rsize_t dstmax,
                       const char __far * __far * restrict src, rsize
_t len,
                       mbstate_t __far * restrict ps);
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and mbsrtowcs\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

None of retval, src, \*src, or ps shall be null pointers. If dst is not a null pointer, then neither len nor dstmax shall be greater than RSIZE\_MAX. If dst is a null pointer, then dstmax shall equal zero. If dst is not a null pointer, then dstmax shall not equal zero. If dst is not a null pointer and len is not less than dstmax, then a null character shall occur within the first dstmax multibyte characters of the array pointed to by \*src.

If there is a runtime-constraint violation, then mbsrtowcs\_s does the following. If retval is not a null pointer, then the mbsrtowcs\_s sets \*retval to (size\_t) -1. If dst is not a null pointer and dstmax is greater than zero and less than RSIZE\_MAX, then mbsrtowcs\_s sets dst[0] to the null wide character.

#### **Description:**

The mbsrtowcs\_s function converts a sequence of multibyte characters that begins in the conversion state described by the object pointed to by ps, from the array indirectly pointed to by src into a sequence of corresponding wide characters. If dst is not a null pointer, the converted characters are stored into the array pointed to by dst. Conversion continues up to and including a terminating null character, which is also stored.

Conversion stops earlier in two cases: when a sequence of bytes is encountered that does not form a valid multibyte character, or (if dst is not a null pointer) when len wide characters have been stored into the array pointed to by dst. If dst is not a null pointer and no null wide character was stored into the array pointed to by dst, then dst[len] is set to the null wide character. Each conversion takes place as if by a call to the mbrtowc function.

If dst is not a null pointer, the pointer object pointed to by src is assigned either a null pointer (if conversion stopped due to reaching a terminating null character) or the address just past the last multibyte character converted (if any). If conversion stopped due to reaching a terminating null character and if dst is not a null pointer, the resulting state described is the initial conversion state.

Regardless of whether dst is or is not a null pointer, if the input conversion encounters a sequence of bytes that do not form a valid multibyte character, an encoding error occurs: the mbsrtowcs\_s function stores the value (size\_t) -1 into \*retval and the conversion state is unspecified. Otherwise, the mbsrtowcs\_s function stores into \*retval the number of multibyte characters successfully converted, not including the terminating null character (if any).

All elements following the terminating null wide character (if any) written by mbsrtowcs\_s in the array of dstmax wide characters pointed to by dst take unspecified values when mbsrtowcs\_s returns.

If copying takes place between objects that overlap, the objects take on unspecified values.

The \_fmbsrtowcs\_s function is a data model independent form of the mbsrtowcs\_s function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** 

The mbsrtowcs\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

\_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <wchar.h>
#include <mbctype.h>
#include <errno.h>
const char chars[] = {
   · ·,
   '.',
    11',
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x60, /* double-byte A */
    0x82,0xA6, /* double-byte Hiragana */
    0x83,0x42, /* double-byte Katakana */
    0xA1,
              /* single-byte Katakana punctuation */
    0xA6,
              /* single-byte Katakana alphabetic */
              /* single-byte Katakana alphabetic */
    0xE0,0xA1, /* double-byte Kanji */
    0x00
};
int main()
{
   int
               i;
   size_t
              retval;
   const char *src;
   wchar_t
              wc[50];
   mbstate_t pstate;
   errno_t
               rc;
   _setmbcp( 932 );
    src = chars;
   rc = mbsrtowcs( &retval, wc, 50, &src, sizeof(chars), &pstate);
    if( rc != 0 ) {
        printf( "Error in multibyte character string\n" );
    } else {
        for( i = 0; i < retval; i++ ) {
            printf( "%#6.4x\n", wc[i] );
    return(0);
}
```

Classification: TR 24731

\_fmbsrtowcs\_s is WATCOM

**Systems:** mbsrtowcs\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,

Linux, RDOS

\_fmbsrtowcs\_s - DOS, Windows, OS/2 1.x(all)

# **Synopsis:** #include <mbstring.h> unsigned char \*\_mbsspnp( const unsigned char \*s, const unsigned char \*charset ); unsigned char \_\_far \*\_fmbsspnp( const unsigned char \_\_\_far \*s, const unsigned char \_\_far \*charset ); #include <tchar.h> char \*\_strspnp( const char \*s, const char \*charset ); wchar\_t \*\_wcsspnp( const wchar\_t \*s, const wchar\_t \*charset ); **Description:** The \_mbsspnp function returns a pointer to the first multi-byte character in s that does not belong to the set of multi-byte characters in charset. The terminating null character is not considered to be part of charset. The \_fmbsspnp function is a data model independent form of the \_mbsspnp function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications. The header file <tchar.h> defines the generic-text macro \_tcsspnp. The \_tcsspnp macro maps to \_mbsspnp if \_MBCS has been defined, or to the \_wcsspnp macro if \_UNICODE has been defined, otherwise it maps to \_strspnp macro. \_strspnp and \_wcsspnp are single-byte character string and wide character string versions of The \_strspnp and \_wcsspnp macros are provided only for this mapping and should not be used otherwise. **Returns:** These functions return NULL if s consists entirely of characters (multi-byte, wide, or single-byte) from charset (multi-byte, wide, or single-byte). See Also: strspnp, strcspn, strspn **Example:** #include <stdio.h> #include <string.h> void main() { printf( $\space{1mm}$ strspnp( "out to lunch", "aeiou" ) ); printf( "%s\n", strspnp( "out to lunch", "xyz" ) ); produces the following: t to lunch out to lunch

```
Systems: _mbsspnp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS _fmbsspnp - DOS, Windows, OS/2 1.x(all) _strspnp - All, Linux, RDOS, Netware _wcsspnp - All, Linux
```

_mbsspnp, _fmbsspnp, _strspnp, _wcsspnp

```
Synopsis:
             #include <stdlib.h>
             size_t mbstowcs( wchar_t *pwcs, const char *s, size_t n );
             #include <mbstring.h>
             size_t _fmbstowcs( const wchar_t __far *pwcs,
                                     char __far *s,
                                     size_t n );
Safer C:
             The Safer C Library extension provides the mbstowcs_s function which is a safer alternative to
             mbstowcs.
Description:
             The mbstowcs function converts a sequence of multibyte characters pointed to by s into their
             corresponding wide character codes and stores not more than n codes into the array pointed to by pwcs.
             The mbstowcs function does not convert any multibyte characters beyond the null character. At most
             n elements of the array pointed to by pwcs will be modified.
             The _fmbstowcs function is a data model independent form of the mbstowcs function that accepts
             far pointer arguments. It is most useful in mixed memory model applications.
Returns:
             If an invalid multibyte character is encountered, the mbstowcs function returns (size_t)-1.
             Otherwise, the mbstowcs function returns the number of array elements modified, not including the
             terminating zero code if present.
See Also:
             mbstowcs_s, mblen, mbtowc, wctomb, wctomb_s, wcstombs, wcstombs_s
Example:
             #include <stdio.h>
             #include <stdlib.h>
             void main()
                {
                  char *wc = "string";
                  wchar_t wbuffer[50];
                  int
                           i, len;
                  len = mbstowcs( wbuffer, wc, 50 );
                  if ( len !=-1 ) {
                     wbuffer[len] = ' \setminus 0';
                     printf( "%s(%d)\n", wc, len );
                     for( i = 0; i < len; i++ )
                       printf( "/%4.4x", wbuffer[i] );
                     printf( "\n" );
                }
             produces the following:
             string(6)
             /0073/0074/0072/0069/006e/0067
```

mbstowcs - All, Linux, RDOS, Netware
\_fmbstowcs - DOS, Windows, OS/2 1.x(all)

Classification: ISO C95

**Systems:** 

		mbstowcs,	_fmbstowcs

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdlib.h>
errno_t mbstowcs_s( size_t * restrict retval,
                   wchar_t * restrict dst,
                   rsize_t dstmax,
                    const char * restrict src, rsize_t len);
errno_t _fmbstowcs_s( size_t __far * restrict retval,
                    wchar_t __far * restrict dst,
                    rsize_t dstmax,
                    const char __far * restrict src, rsize_t len);
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and mbstowcs\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither retval nor src shall be a null pointer. If dst is not a null pointer, then neither len nor dstmax shall be greater than RSIZE MAX. If dst is a null pointer, then dstmax shall equal zero. If dst is not a null pointer, then dstmax shall not equal zero. If dst is not a null pointer and len is not less than dstmax, then a null character shall occur within the first dstmax multibyte characters of the array pointed to by Src.

> If there is a runtime-constraint violation, then mbstowcs\_s does the following. If retval is not a null pointer, then the mbstowcs\_s sets \*retval to (size\_t)-1. If dst is not a null pointer and dstmax is greater than zero and less than RSIZE\_MAX, then mbstowcs\_s sets dst[0] to the null wide character.

#### **Description:**

The mbstowcs\_s function converts a sequence of multibyte characters that begins in the initial shift state from the array pointed to by src into a sequence of corresponding wide characters. If dst is not a null pointer, the converted characters are stored into the array pointed to by dst.

Conversion continues up to and including a terminating null character, which is also stored. Conversion stops earlier in two cases: when a sequence of bytes is encountered that does not form a valid multibyte character, or (if dst is not a null pointer) when len wide characters have been stored into the array pointed to by dst. If dst is not a null pointer and no null wide character was stored into the array pointed to by dst, then dst[len] is set to the null wide character. Each conversion takes place as if by a call to the mbrtowc function.

Regardless of whether dst is or is not a null pointer, if the input conversion encounters a sequence of bytes that do not form a valid multibyte character, an encoding error occurs: the mbstowcs\_s function stores the value (size\_t)-1 into \*retval. Otherwise, the mbstowcs\_s function stores into \*retval the number of multibyte characters successfully converted, not including the terminating null character (if any).

All elements following the terminating null wide character (if any) written by mbstowcs\_s in the array of dstmax wide characters pointed to by dst take unspecified values when mbstowcs\_s returns.

If copying takes place between objects that overlap, the objects take on unspecified values.

The \_fmbstowcs\_s function is a data model independent form of the mbstowcs\_s function that accepts far pointer arguments. It is most useful in mixed memory model applications.

#### **Returns:**

The mbstowcs\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

```
See Also:
           mbstowcs, mblen, mbtowc, wctomb, wctomb_s, wcstombs_s
Example:
           #define __STDC_WANT_LIB_EXT1__ 1
           #include <stdio.h>
           #include <stdlib.h>
           int main()
               char
                      *wc = "string";
               wchar_t wbuffer[50];
               int
                    i;
               errno_t rc;
               size_t retval;
               rc = mbstowcs_s( &retval, wbuffer, 50, wc, 10);
               if(rc == 0)
                 wbuffer[retval] = L' \setminus 0';
                 printf( "%s(%d)\n", wc, retval );
                 for( i = 0; i < retval; i++ )</pre>
                   printf( "/%4.4x", wbuffer[i] );
                 printf( "\n" );
               return(0);
           }
           produces the following:
           string(6)
           /0073/0074/0072/0069/006e/0067
Classification: TR 24731
           _fmbstowcs_s is WATCOM
Systems:
           mbstowcs_s - All, Linux, RDOS, Netware
           _fmbstowcs_s - DOS, Windows, OS/2 1.x(all)
```

Synopsis: #include <mbstring.h>
 int \_mbterm( const unsigned char \*ch );

int \_fmbterm( const unsigned char \_\_far \*ch );

**Description:** The \_mbterm function determines if the next multibyte character in the string pointed to by *ch* is a null character or a valid lead byte followed by a null character.

The \_fmbterm function is a data model independent form of the \_mbterm function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The \_mbterm function returns 1 if the multibyte character pointed to by *ch* is a null character. The \_mbterm function returns 2 if the multibyte character pointed to by *ch* is a valid lead byte character

followed by a null character. Otherwise, the \_mbterm function returns 0.

See Also: \_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

Example: #include <stdio.h>

```
#include <mbctype.h>
#include <mbstring.h>
const unsigned char chars[] = {
    ' ',
    11,
    'A',
    0x81,0x40, /* double-byte space */
    0x82,0x00 /* invalid double-byte */
};
#define SIZE sizeof( chars ) / sizeof( unsigned char )
void main()
    int
            i;
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
        printf( "0x%2.2x %d\n", chars[i],
                _mbterm( &chars[i] ) );
}
```

produces the following:

```
0x20 0
0x2e 0
0x31 0
0x41 0
0x81 0
0x40 0
0x82 2
0x00 1
```

### **Classification:** WATCOM

\_mbterm - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS **Systems:** \_fmbterm - DOS, Windows, OS/2 1.x(all)

#### **Synopsis:**

#### **Description:**

The mbtowc function converts a single multibyte character pointed to by s into the wide character code that corresponds to that multibyte character. The code for the null character is zero. If the multibyte character is valid and pwc is not a NULL pointer, the code is stored in the object pointed to by pwc. At most n bytes of the array pointed to by s will be examined.

The mbtowc function does not examine more than MB\_CUR\_MAX bytes.

The \_fmbtowc function is a data model independent form of the mbtowc function that accepts far pointer arguments. It is most useful in mixed memory model applications.

#### **Returns:**

If s is a NULL pointer, the mbtowc function returns zero if multibyte character encodings are not state dependent, and non-zero otherwise. If s is not a NULL pointer, the mbtowc function returns:

#### Value Meaning

*o* if *s* points to the null character

*len* the number of bytes that comprise the multibyte character (if the next *n* or fewer bytes form a valid multibyte character)

-1 if the next n bytes do not form a valid multibyte character

See Also: mblen, wctomb, mbstowcs, wcstombs

## Example:

```
#include <stdio.h>
#include <stdlib.h>
#include <mbctype.h>
void main()
  {
    char *wc = "string";
    wchar_t wbuffer[10];
    int
          i, len;
    _setmbcp( 932 );
    printf( "Character encodings are sstate dependent n",
            ( mbtowc( wbuffer, NULL, 0 ) )
            ? "" : "not " );
    len = mbtowc( wbuffer, wc, MB_CUR_MAX );
    wbuffer[len] = ' \setminus 0';
    printf( "%s(%d)\n", wc, len );
    for( i = 0; i < len; i++)
        printf( "/%4.4x", wbuffer[i] );
    printf( "\n" );
```

## produces the following:

Character encodings are not state dependent string(1) /0073

Classification: ISO C

**Systems:** mbtowc - All, Linux, RDOS, Netware

\_fmbtowc - DOS, Windows, OS/2 1.x(all)

```
Synopsis:
            #include <mbstring.h>
            unsigned char *_mbvtop( unsigned int ch,
                                        unsigned char *addr );
            unsigned char __far *_fmbvtop( unsigned int ch,
                                        unsigned char __far *addr );
Description:
            The _mbvtop function stores the multibyte character ch into the string pointed to by addr.
            The _fmbvtop function is a data model independent form of the _mbvtop function. It accepts far
            pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.
Returns:
            The _mbvtop function returns the value of the argument addr.
See Also:
            _mbccmp, _mbccpy, _mbcicmp, _mbcjistojms, _mbcjmstojis, _mbclen, _mbctohira,
            _mbctokata, _mbctolower, _mbctombb, _mbctoupper, mblen, mbrlen, mbrtowc,
            mbsrtowcs, mbsrtowcs_s, mbstowcs, mbstowcs_s, mbtowc, mbsinit, btowc, wcrtomb,
            wcrtomb_s, wcsrtombs, wcsrtombs_s, wcstombs, wcstombs_s, wctob, wctomb,
            wctomb_s
Example:
            #include <stdio.h>
            #include <mbctype.h>
            #include <mbstring.h>
            void main()
                 unsigned char string[10];
                 unsigned char *p;
                 int
                                 i;
                 _setmbcp( 932 );
                 p = string;
                _mbvtop('.', p);
                p++;
                 _mbvtop( '1', p );
                p++;
                 _mbvtop('A', p);
                 p++;
                 _mbvtop( 0x8140, p );
                 p += 2;
                 _mbvtop( 0x8260, p );
                 p += 2;
                 _mbvtop( 0x82A6, p );
                 p += 2;
                 _mbvtop( '\0', p );
                 for( i = 0; i < 10; i++)
                   printf( "%2.2x ", string[i] );
                 printf( "\n" );
            produces the following:
            2e 31 41 81 40 82 60 82 a6 00
```

**Classification:** WATCOM

\_mbvtop - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS **Systems:** 

\_fmbvtop - DOS, Windows, OS/2 1.x(all)

Synopsis: #include <malloc.h>
 size\_t \_memavl( void );

**Description:** The \_memavl function returns the number of bytes of memory available for dynamic memory

allocation in the near heap (the default data segment). In the tiny, small and medium memory models, the default data segment is only extended as needed to satisfy requests for memory allocation.

Therefore, you will need to call  $\_$ nheapgrow in these memory models before calling  $\_$ memavl in

order to get a meaningful result.

The number returned by \_memavl may not represent a single contiguous block of memory. Use the

\_memmax function to find the largest contiguous block of memory that can be allocated.

**Returns:** The \_memavl function returns the number of bytes of memory available for dynamic memory allocation in the near heap (the default data segment).

See Also: calloc Functions, \_freect, \_memmax, \_heapgrow Functions, malloc Functions, realloc

Functions

Example: #include <stdio.h>

```
#include <malloc.h>

void main()
{
    char *p;
    char *fmt = "Memory available = %u\n";

    printf( fmt, _memavl() );
    _nheapgrow();
    printf( fmt, _memavl() );
    p = (char *) malloc( 2000 );
    printf( fmt, _memavl() );
}
```

produces the following:

```
Memory available = 0
Memory available = 62732
Memory available = 60730
```

**Classification:** WATCOM

Systems: All, Linux, RDOS

```
Synopsis:
             #include <string.h>
             void *memccpy( void *dest, const void *src,
                               int c, size_t cnt );
             void __far *_fmemccpy( void __far *dest,
                                          const void __far *src,
                                          int c, size_t cnt );
             void *_memccpy( void *dest, const void *src,
                                int c, size_t cnt );
Description:
             The memcopy function copies bytes from src to dest up to and including the first occurrence of the
             character c or until cnt bytes have been copied, whichever comes first.
             The _fmemccpy function is a data model independent form of the memccpy function. It accepts far
             pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.
Returns:
             The memccpy function returns a pointer to the byte in dest following the character c if one is found and
             copied, otherwise it returns NULL.
See Also:
             memcpy, memmove, memset
Example:
             #include <stdio.h>
             #include <string.h>
             char *msg = "This is the string: not copied";
             void main()
               {
                  auto char buffer[80];
                  memset ( buffer, ' \setminus 0', 80 );
                  memccpy( buffer, msg, ':', 80 );
                  printf( "%s\n", buffer );
               }
             produces the following:
             This is the string:
Classification: WATCOM
```

memccpy - All, Linux, RDOS, Netware

\_memccpy - All, Linux, RDOS, Netware

\_fmemccpy - All, Linux, RDOS

```
Synopsis:
             #include <string.h>
             void *memchr( const void *buf, int ch, size_t length );
             void __far *_fmemchr( const void __far *buf,
                                        int ch,
                                        size_t length );
             #include <wchar.h>
             wchar_t *wmemchr( const wchar_t *buf, wchar_t ch, size_t length );
Description:
             The memchr function locates the first occurrence of ch (converted to an unsigned char) in the first
             length characters of the object pointed to by buf.
             The _fmemchr function is a data model independent form of the memchr function. It accepts far
             pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.
             The wmemchr function is a wide character version of memchr that operates with wide character
             strings. The argument length is interpreted to mean the number of wide characters.
Returns:
             The memchr function returns a pointer to the located character, or NULL if the character does not occur
             in the object.
See Also:
             memcmp, memcpy, _memicmp, memset
Example:
             #include <stdio.h>
             #include <string.h>
             void main( void )
                  char buffer[80];
                  char *where;
                  strcpy( buffer, "video x-rays" );
                  where = (char *) memchr(buffer, 'x', 6);
                  if ( where == NULL )
                       printf( "'x' not found\n" );
                  else
                      printf( "%s\n", where );
                  where = (char *) memchr(buffer, 'r', 9);
                  if ( where == NULL )
                      printf( "'r' not found\n" );
                      printf( "%s\n", where );
             }
Classification: ISO C
             fmemchr is WATCOM
             wmemchr is ISO C95
```

memchr - All, Linux, RDOS, Netware

\_fmemchr - All, Linux, RDOS

wmemchr - All, Linux

memchr, _fmemchr, wmemch

#### **Synopsis:**

#### **Description:**

The memcmp function compares the first *length* characters of the object pointed to by s1 to the object pointed to by s2.

The \_fmemcmp function is a data model independent form of the memcmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The wmemcmp function is a wide character version of memcmp that operates with wide character strings. The argument *length* is interpreted to mean the number of wide characters.

#### **Returns:**

The memcmp function returns an integer less than, equal to, or greater than zero, indicating that the object pointed to by sI is less than, equal to, or greater than the object pointed to by s2.

See Also:

memchr, memcpy, \_memicmp, memset

#### **Example:**

```
#include <stdio.h>
#include <string.h>

void main( void )
{
    auto char buffer[80];

    strcpy( buffer, "world" );
    if( memcmp( buffer, "Hello ", 6 ) < 0 ) {
        printf( "Less than\n" );
    }
}</pre>
```

#### **Classification:** ISO C

\_fmemcmp is WATCOM wmemcmp is ISO C95

```
memcmp - All, Linux, RDOS, Netware
_fmemcmp - All, Linux, RDOS
wmemcmp - All, Linux
```

memcmp, _fmemcmp, wmemcmp

```
Synopsis:
             #include <string.h>
             void *memcpy( void *dst,
                               const void *src,
                               size_t length );
             void __far *_fmemcpy( void __far *dst,
                                         const void __far *src,
                                          size_t length );
             #include <wchar.h>
             wchar_t *wmemcpy( wchar_t *dst,
                                     const wchar_t *src,
                                     size_t length );
Safer C:
             The Safer C Library extension provides the memcpy_s function which is a safer alternative to
             memcpy.
Description:
             The memcpy function copies length characters from the buffer pointed to by src into the buffer pointed
             to by dst. Copying of overlapping objects is not guaranteed to work properly. See the memmove
             function if you wish to copy objects that overlap.
             The _fmemcpy function is a data model independent form of the memcpy function. It accepts far
             pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.
             The wmemcpy function is a wide character version of memcpy that operates with wide character
             strings. The argument length is interpreted to mean the number of wide characters.
Returns:
             The original value of dst is returned.
             memchr, memcmp, _memicmp, memmove, memset, memcpy_s, memmove_s
See Also:
Example:
             #include <stdio.h>
             #include <string.h>
             void main( void )
              {
                   auto char buffer[80];
                  memcpy( buffer, "Hello", 5 );
                  buffer[5] = ' \setminus 0';
                  printf( "%s\n", buffer );
              }
Classification: ISO C
             _fmemcpy is WATCOM
             wmemcpy is ISO C95
```

memcpy - All, Linux, RDOS, Netware

\_fmemcpy - All, Linux, RDOS

wmemcpy - All, Linux

	me	emcpy, _fme	тсру, wтетсру
			<del></del>

#### **Synopsis:**

```
#define ___STDC_WANT_LIB_EXT1__
#include <string.h>
errno_t memcpy_s( void * restrict s1,
                  rsize_t s1max,
                  const void * restrict s2,
                  rsize_t n );
#include <wchar.h>
errno_t wmemcpy_s( wchar_t * restrict s1,
                   rsize_t s1max,
                   const wchar_t * restrict s2,
                   size_t n );
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and memcpy\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither s1 nor s2 shall be a null pointer. Neither s1max nor n shall be greater than RSIZE\_MAX. n shall not be greater than s1max. Copying shall not take place between objects that overlap.

If there is a runtime-constraint violation, the memcpy\_s function stores zeros in the first slmax characters of the object pointed to by sI if sI is not a null pointer and sImax is not greater than RSIZE\_MAX.

#### **Description:**

The memcpy\_s function copies n characters from the buffer pointed to by s2 into the buffer pointed to by s1. Copying between overlapping objects is not allowed. See the memmove\_s function if you wish to copy objects that overlap.

The wmemcpy\_s function is a wide character version of memcpy\_s that operates with wide character strings. The arguments sImax and n are interpreted to mean the number of wide characters.

#### **Returns:**

The memcpy\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

memcpy, memchr, memcmp, memcpy, \_memicmp, memmove, memset, memmove\_s

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <string.h>
void main( void )
{
    char buffer[80];
    memcpy_s( buffer, sizeof( buffer ), "Hello", 5 );
    buffer[5] = ' \setminus 0';
    printf( "%s\n", buffer );
}
```

Classification: TR 24731

**Systems:** 

memcpy\_s - All, Linux, RDOS, Netware wmemcpy\_s - All, Linux

memcpy_s, wmemcpy_s

#### **Synopsis:**

#### **Description:**

The function compares, without case sensitivity (upper- and lowercase characters are equivalent), the first *length* characters of the object pointed to by s1 to the object pointed to by s2. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_fmemicmp function is a data model independent form of the \_memicmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The memicmp function is deprecated, use \_memicmp instead.

#### **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the object pointed to by s1 is less than, equal to, or greater than the object pointed to by s2.

See Also: men

memchr, memcmp, memcpy, memset

### **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    char buffer[80];

    if( _memicmp( buffer, "Hello", 5 ) < 0 ) {
        printf( "Less than\n" );
    }
}</pre>
```

**Classification:** WATCOM

```
Systems:
```

```
_memicmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
Linux, RDOS
_fmemicmp - All, Linux, RDOS
memicmp - All, Linux, RDOS, Netware
```

memicmn	_fmemicmp, memicmp
	memicinp, memicinp

Synopsis: #include <malloc.h>
 size\_t \_memmax( void );

**Description:** The \_memmax function returns the size of the largest contiguous block of memory available for

dynamic memory allocation in the near heap (the default data segment). In the tiny, small and medium memory models, the default data segment is only extended as needed to satisfy requests for memory allocation. Therefore, you will need to call \_nheapgrow in these memory models before calling

\_memmax in order to get a meaningful result.

**Returns:** The \_memmax function returns the size of the largest contiguous block of memory available for

dynamic memory allocation in the near heap. If 0 is returned, then there is no more memory available

in the near heap.

See Also: calloc, \_freect, \_memavl, \_heapgrow, malloc

Example: #include <stdio.h>
#include <malloc.h>

```
void main()
{
   char *p;
   size_t size;

   size = _memmax();
   printf( "Maximum memory available is %u\n", size );
   _nheapgrow();
   size = _memmax();
   printf( "Maximum memory available is %u\n", size );
   p = (char *) _nmalloc( size );
   size = _memmax();
   printf( "Maximum memory available is %u\n", size );
}
```

produces the following:

Maximum memory available is 0 Maximum memory available is 62700 Maximum memory available is 0

**Classification:** WATCOM

Systems: All, Linux, RDOS

#### **Synopsis:** #include <string.h> void \*memmove( void \*dst, const void \*src, size\_t length ); void \_\_far \*\_fmemmove( void \_\_far \*dst, const void \_\_far \*src, size\_t length ); #include <wchar.h> wchar\_t \*wmemmove( wchar\_t \*dst, const wchar\_t \*src,

Safer C: The Safer C Library extension provides the memmove\_s function which is a safer alternative to memmove.

size\_t length );

**Description:** The memmove function copies *length* characters from the buffer pointed to by *src* to the buffer pointed to by dst. Copying of overlapping objects will take place properly. See the memcpy function to copy objects that do not overlap.

> The \_fmemmove function is a data model independent form of the memmove function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wmemmove function is a wide character version of memmove that operates with wide character strings. The argument *length* is interpreted to mean the number of wide characters.

**Returns:** The memmove function returns *dst*.

See Also: memchr, memcmp, memcpy, \_memicmp, memset, memmove\_s, memcpy\_s

```
Example:
           #include <string.h>
           void main( void )
               char buffer[80];
               memmove( buffer + 1, buffer, 79 );
               buffer[0] = '*';
           }
```

Classification: ISO C

fmemmove is WATCOM wmemmove is ISO C95

**Systems:** memmove - All, Linux, RDOS, Netware \_fmemmove - All, Linux, RDOS wmemmove - All, Linux

 	 	_

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__
#include <string.h>
errno_t memmove_s( void * restrict s1,
                   rsize_t s1max,
                   const void * restrict s2,
                   rsize_t n );
#include <wchar.h>
errno_t wmemmove_s( wchar_t * restrict s1,
                    rsize t slmax,
                    const wchar_t * restrict s2,
                    size_t n );
```

Constraints: If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and memmove\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither s1 nor s2 shall be a null pointer. Neither s1 max nor n shall be greater than RSIZE MAX. n shall not be greater than s1max.

If there is a runtime-constraint violation, the memmove\_s function stores zeros in the first sImax characters of the object pointed to by sI if sI is not a null pointer and sImax is not greater than RSIZE MAX.

#### **Description:**

The memmove\_s function copies n characters from the buffer pointed to by s2 into the buffer pointed to by sI. This copying takes place as if the n characters from the buffer pointed to by s2 are first copied into a temporary array of n characters that does not overlap the objects pointed to by s1 or s2, and then the n characters from the temporary array are copied into the object pointed to by s1.

See the *memcpy\_s* function if you wish to copy objects that do not overlap.

The wmemmove\_s function is a wide character version of memmove\_s that operates with wide character strings. The arguments s1max and n are interpreted to mean the number of wide characters.

#### **Returns:**

The memmove\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

#### See Also:

memchr, memcmp, memcpy, \_memicmp, memmove, memset, memcpy\_s

#### **Example:**

```
#define STDC WANT LIB EXT1 1
#include <string.h>
void main( void )
    char buffer[80] = "0123456789";
   memmove_s( buffer + 1, sizeof( buffer ), buffer, 79 );
   buffer[0] = '*';
   printf( buffer );
}
```

produces the following:

\*0123456789

Classification: TR 24731

## memmove\_s, wmemmove\_s

Systems: memmove\_s - All, Linux, RDOS, Netware

wmemmove\_s - All

**Synopsis:** #include <mmintrin.h> void \_m\_empty(void);

**Description:** The \_m\_empty function empties the multimedia state. The values in the Multimedia Tag Word (TW) are set to empty (i.e., all ones). This will indicate that no Multimedia registers are in use.

> This function is useful for applications that mix floating-point (FP) instructions with multimedia instructions. Intel maps the multimedia registers onto the floating-point registers. For this reason, you are discouraged from intermixing MM code and FP code. The recommended way to write an application with FP instructions and MM instructions is:

- Split the FP code and MM code into two separate instruction streams such that each stream contains only instructions of one type.
- Do not rely on the contents of FP/MM registers across transitions from one stream to the other.
- Leave the MM state empty at the end of an MM stream using the \_m\_empty function.
- Similarly, leave the FP stack empty at the end of an FP stream.

**Returns:** The \_m\_empty function does not return a value.

See Also: \_m\_from\_int, \_m\_to\_int, \_m\_packsswb, \_m\_paddb, \_m\_pand, \_m\_pcmpeqb, \_m\_pmaddwd, \_m\_psllw, \_m\_psraw, \_m\_psrlw, \_m\_psubb, \_m\_punpckhbw

**Example:** 

```
#include <stdio.h>
#include <mmintrin.h>
long featureflags( void );
#pragma aux featureflags = \
    ".586"
    "mov eax,1"
    "cpuid"
    "mov eax,edx"
    __modify [__eax __ebx __ecx __edx]
#define MM_EXTENSION 0x00800000
void main( void )
    if( featureflags() & MM_EXTENSION ) {
        sequence of code that uses Multimedia functions
    */
        _m_empty();
```

```
/*
    sequence of code that uses floating-point
    .
    .
    */
}
```

Classification: Intel

Systems: MACRO

```
Synopsis:
           #include <string.h>
           void *memset( void *dst, int c, size_t length );
           void __far *_fmemset( void __far *dst, int c,
                                 size_t length );
           wchar_t *wmemset( wchar_t *dst,
                              wchar_t c,
                              size_t length );
```

**Description:** The memset function fills the first *length* characters of the object pointed to by *dst* with the value c.

> The \_fmemset function is a data model independent form of the memset function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wmemset function is a wide character version of memset that operates with wide character strings. The argument *length* is interpreted to mean the number of wide characters.

**Returns:** The memset function returns the pointer dst.

See Also: memchr, memcmp, memcpy, \_memicmp, memmove

```
Example:
           #include <string.h>
           void main( void )
               char buffer[80];
               memset ( buffer, '=', 80 );
```

Classification: ISO C

\_fmemset is WATCOM wmemset is ISO C95

```
memset - All, Linux, RDOS, Netware
_fmemset - All, Linux, RDOS
wmemset - All, Linux
```

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_from_int(int i);
Description:
            The _m_from_int function forms a 64-bit MM value from an unsigned 32-bit integer value.
Returns:
            The 64-bit result of loading MM0 with an unsigned 32-bit integer value is returned.
See Also:
             _m_empty, _m_to_int, _m_packsswb, _m_paddb, _m_pand, _m_empty, _m_pcmpeqb,
             _m_pmaddwd, _m_psllw, _m_psraw, _m_psrlw, _m_empty, _m_psubb, _m_punpckhbw
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             ___m64
                      a;
            int
                     k = 0xF1F2F3F4;
            void main()
               {
                 a = _mfrom_int(k);
                 printf( "int=%8.81x m=%8.81x%8.81x\n",
                      k, a._32[1], a._32[0]);
               }
            produces the following:
```

int=f1f2f3f4 m=0000000f1f2f3f4

Classification: Intel

Systems: MACRO

```
Synopsis:
           #include <stdlib.h>
           \#define min(a,b) (((a) < (b)) ? (a) : (b))
```

**Description:** The min macro will evaluate to be the lesser of two values. It is implemented as follows.

```
#define min(a,b)
                 (((a) < (b)) ? (a) : (b))
```

**Returns:** The min macro will evaluate to the smaller of the two values passed.

See Also: max

```
Example:
           #include <stdio.h>
           #include <stdlib.h>
           void main()
             {
               int a;
                * The following line will set the variable "a" to 1
                * since 10 is greater than 1.
               a = min(1, 10);
               printf( "The value is: %d\n", a );
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <sys/types.h>

#include <direct.h>
int mkdir( const char \*path );
int \_mkdir( const char \*path );
int \_wmkdir( const wchar\_t \*path );

**Description:** 

The mkdir function creates a new subdirectory with name *path*. The *path* can be either relative to the current working directory or it can be an absolute path name.

The \_mkdir function is identical to mkdir. Use \_mkdir for ANSI naming conventions.

The \_wmkdir function is a wide character version of mkdir that operates with wide character strings.

**Returns:** The mkdir function returns zero if successful, and a non-zero value otherwise.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning
 EACCES Search permission is denied for a component of path or write permission is denied on the parent directory of the directory to be created.
 EEXIST The named file exists.

**ENOENT** The specified *path* does not exist or *path* is an empty string.

See Also: chdir, chmod, getcwd, rmdir, stat, umask

**Example:** To make a new directory called \watcom on drive C:

```
#include <sys/types.h>
#include <direct.h>

void main( void )
{
    mkdir( "c:\\watcom" );
}
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

Classification: POSIX 1003.1

\_mkdir conforms to ANSI naming conventions

Systems: mkdir - All, Linux, RDOS, Netware \_mkdir - All, Linux, RDOS, Netware

\_wmkdir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

mkdir, _mkdir, _wmkdir

**Systems:** 

MACRO

```
Synopsis:
            #include <i86.h>
            void __far *MK_FP( unsigned int segment,
                                   unsigned int offset );
Description:
            The MK_FP macro can be used to obtain the far pointer value given by the segment segment value and
            the offset offset value. These values may be obtained by using the FP_SEG and FP_OFF macros.
Returns:
            The macro returns a far pointer.
See Also:
            FP_OFF, FP_SEG, segread
Example:
             #include <i86.h>
             #include <stdio.h>
            void main()
               {
                 unsigned short __far *bios_prtr_port_1;
                 bios_prtr_port_1 =
                           (unsigned short __far *) MK_FP( 0x40, 0x8 );
                 printf( "Port address is %x\n", *bios_prtr_port_1 );
Classification: Intel
```

```
Synopsis:
           #include <stdlib.h>
           int mkstemp( char *template );
```

**Description:** 

The mkstemp function creates a file with unique name by modifying the template argument, and returns its file handle open for reading and writing in binary mode. The use of mkstemp prevents any possible race condition between testing whether the file exists and opening it for use.

The string template has the form baseXXXXXX where base is the fixed part of the generated filename and XXXXXX is the variable part of the generated filename. Each of the 6 X's is a placeholder for a character supplied by mkstemp. Each placeholder character in template must be an uppercase "X". mkstemp preserves base and replaces the first of the 6 trailing X's with a unique sequence of alphanumeric characters. The string template therefore must be writable.

mkstemp checks to see if a file with the generated name already exists and if so selects another name, until it finds a file that doesn't exist. If it is unsuccessful at finding a name for a file that does not already exist or is unable to create a file, mkstemp returns -1.

**Returns:** 

The mkstemp function returns a file handle. When an error occurs while creating the file, -1 is returned.

See Also: fopen, freopen, \_mktemp, \_tempnam, tmpfile, tmpnam

**Example:** 

```
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <unistd.h>
                     "_txxxxxx"
#define TEMPLATE
#define MAX_TEMPS
void main( void )
{
            name[sizeof( TEMPLATE )];
    char
    int.
            i;
    int
            handles[MAX_TEMPS];
    for( i = 0; i < MAX_TEMPS; i++ ) {</pre>
        strcpy( name, TEMPLATE );
        handles[i] = mkstemp( name );
        if (handles[i] == -1) {
            printf( "Failed to create temporary file\n" );
        } else {
            printf( "Created temporary file '%s'\n", name );
    for( i = 0; i < MAX_TEMPS; i++ ) {</pre>
        if ( handles[i] !=-1 ) {
            close( handles[i] );
        }
    }
```

Classification: POSIX 1003.1

# mkstemp

Systems: All, Linux, Netware

**Synopsis:** #include <io.h>

```
char *_mktemp( char *template );
#include <wchar.h>
wchar_t *_wmktemp( wchar_t *template );
```

**Description:** 

The \_mktemp function creates a unique filename by modifying the template argument. \_mktemp automatically handles multi-byte character string arguments as appropriate, recognizing multi-byte character sequences according to the multibyte code page currently in use by the run-time system.

The \_wmktemp function is a wide character version of \_mktemp that operates with wide character strings.

The string template has the form baseXXXXXX where base is the fixed part of the generated filename and XXXXXX is the variable part of the generated filename. Each of the 6 X's is a placeholder for a character supplied by mktemp. Each placeholder character in template must be an uppercase "X". \_mktemp preserves base and replaces the first of the 6 trailing X's with a lowercase alphabetic character (a-z). \_mktemp replaces the following 5 trailing X's with a five-digit value; this value is a unique number identifying the calling process or thread.

\_mktemp checks to see if a file with the generated name already exists and if so selects another letter, in succession, from "a" to "z" until it finds a file that doesn't exist. If it is unsuccessful at finding a name for a file that does not already exist, \_mktemp returns NULL. At most, 26 unique file names can be returned to the calling process or thread.

**Returns:** 

The \_mktemp function returns a pointer to the modified template. The \_mktemp function returns NULL if template is badly formed or no more unique names can be created from the given template.

**Errors:** 

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also:

fopen, freopen, mkstemp, \_tempnam, tmpfile, tmpnam

**Example:** 

```
#include <stdio.h>
#include <string.h>
#include <io.h>
#define TMPLTE "_tXXXXXX"
void main()
   char name[sizeof(TMPLTE)];
   char *mknm;
    int i;
   FILE *fp;
    for(i = 0; i < 30; i++) {
      strcpy( name, TMPLTE );
      mknm = _mktemp( name );
      if( mknm == NULL )
        printf( "Name is badly formed\n" );
      else {
       printf( "Name is %s\n", mknm );
        fp = fopen( mknm, "w" );
        if( fp != NULL ) {
          fprintf( fp, "Name is %s\n", mknm );
          fclose( fp );
      }
    }
  }
```

**Classification:** WATCOM

```
Systems: _mktemp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32 _wmktemp - Win32
```

#### **Synopsis:**

```
#include <time.h>
time_t mktime( struct tm *timeptr );
struct tm {
  int tm_sec; /* seconds after the minute -- [0,61] */
  int tm_min; /* minutes after the hour -- [0,59] */
 int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
  int tm_mon;    /* months since Januar;
int tm_year;    /* years since 1900
  int tm_isdst; /* Daylight Savings Time flag
};
```

#### **Description:**

The mktime function converts the local time information in the structure pointed to by timeptr into a calendar time (Coordinated Universal Time) with the same encoding used by the time function. The original values of the fields tm\_sec, tm\_min, tm\_hour, tm\_mday, and tm\_mon are not restricted to ranges described for struct tm. If these fields are not in their proper ranges, they are adjusted so that they are in the proper ranges. Values for the fields tm\_wday and tm\_yday are computed after all the other fields have been adjusted.

If the original value of tm\_isdst is negative, this field is computed also. Otherwise, a value of 0 is treated as "daylight savings time is not in effect" and a positive value is treated as "daylight savings time is in effect".

Whenever mktime is called, the tzset function is also called.

**Returns:** 

The mktime function returns the converted calendar time.

See Also:

asctime Functions, asctime\_s, clock, ctime Functions, ctime\_s, difftime, gmtime, gmtime\_s, localtime, localtime\_s, strftime, time, tzset

#### **Example:**

```
#include <stdio.h>
#include <time.h>
static const char *week_day[] = {
    "Sunday", "Monday", "Tuesday", "Wednesday",
    "Thursday", "Friday", "Saturday"
};
void main()
  {
    struct tm new_year;
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

**Synopsis:** #include <sys/mman.h>

int mlock(void \*address, size\_t len)

**Description:** The mlock function causes memory located at address measuring len bytes to be held in physical

memory until unlocked or the process terminates.

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The argument address is not a multiple of the page size or the len is zero or causes an

overflow

**ENOMEM** The arguments do not correspond to a region of the process's address space or the requested

lock region exceeds an allowable limit

EAGAIN Some portion of the memory could not be locked

**EPERM** The calling process lacks the approriate permissions

See Also: mlockall, munlock, munlockall

Classification: POSIX 1003.1

**Systems:** Linux

### mlockall

Synopsis: #include <sys/mman.h>

int mlockall(int flags)

Description: The mlockall function causes all memory in the current process's address space to reside in physical

memory until unlocked. The *flags* argument may be one or a combination of the following:

MCL\_CURRENT Lock all pages currently mapped for the process

**MCL\_FUTURE** Lock all pages that may be mapped in the future for this process

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EINVAL** The argument *flags* is zero or invalid

**ENOMEM** The amount of memory requested for locking exceeds an allowable limit

EAGAIN Some portion of the memory could not be locked

**EPERM** The calling process lacks the approriate permissions

See Also: mlock, munlock, munlockall

Classification: POSIX 1003.1

**Systems:** Linux

**Synopsis:** #include <sys/mman.h>

void \*mmap(void \*address, size\_t len, int prot, int flags, int fd, of

f\_t offset)

**Description:** The mmap function creates a mapping of a file specified by fd and the process address space, allowing

the file to be accessed via the returned pointer.

The argument address provides the kernel a "suggestion" as to where to locate the pointer returned by this function. The argmuent address is normally set to NULL, however.

The argument *len* specifies the number of bytes of the file to map.

The *prot* argument specifies allowed access, being one of:

**PROT\_READ** Data can be read

**PROT\_WRITE** Data can be written

**PROT\_EXEC** Data can be executed

**PROT\_NONE** No access allowed

The *flags* argument specifies flags related to memory mapping, and may be one or a combination of the following:

**MAP ANONYMOUS** Don't use an actual file, ignoring fd entirely

**MAP\_FIXED** Use address exactly

**MAP LOCKED** Lock the memory contents

MAP\_NORESERVE Memory for the file is not reserved in swap

MAP\_POPULATE Populate (prefault) page tables

**MAP\_PRIVATE** Changes to the file are private

MAP\_SHARED Share changes to the file

An additional flag, MAP\_ANON, is an alias for MAP\_ANONYMOUS.

The argument fd is a file descriptor for mapping. It is ignored if MAP\_ANONYMOUS is specified.

The offset argument specifies the offset within the file or device to be mapped, in bytes, at which mapping will start.

**Returns:** If successful, the function will return a pointer to mapped file. Upon failure, the function will return

MAP\_FAILED, and errno will be set appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected. Constant Meaning

EINVAL The value of address could not be read or the len is zero, or value of any argument was invalid

**ENOMEM** Memory could not be allocated

EOVERFLOW An overflow occurred due to the len value

**EPERM** The memory could not be locked when requested

**EACCES** Access was denied for the specified *fd* file descriptor

**ENODEV** Memory mapping is unavailable for the requested device

See Also: munmap

Classification: POSIX 1003.1

**Systems:** Linux

**Synopsis:** #include <math.h> double modf( double value, double \*iptr );

**Description:** The modf function breaks the argument value into integral and fractional parts, each of which has the

same sign as the argument. It stores the integral part as a double in the object pointed to by iptr.

**Returns:** The modf function returns the signed fractional part of value.

See Also: frexp, ldexp

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
    double integral_value, fractional_part;
    fractional_part = modf( 4.5, &integral_value );
   printf( "%f %f\n", fractional_part, integral_value );
    fractional_part = modf( -4.5, &integral_value );
    printf( "%f %f\n", fractional_part, integral_value );
  }
```

produces the following:

0.500000 4.000000 -0.500000 -4.000000

Classification: ISO C

**Systems:** Math Synopsis: #include <string.h>

**Description:** The movedata function copies *length* bytes from the far pointer calculated as

 $(src\_segment:src\_offset)$  to a target location determined as a far pointer  $(tgt\_segment:tgt\_offset)$ .

Overlapping data may not be correctly copied. When the source and target areas may overlap, copy the areas one character at a time.

The function is useful to move data when the near address(es) of the source and/or target areas are not known.

**Returns:** No value is returned.

**See Also:** FP\_SEG, FP\_OFF, memcpy, segread

Example:

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

```
Synopsis:
           #include <graph.h>
           struct xycoord _FAR _moveto( short x, short y );
           struct _wxycoord _FAR _moveto_w( double x, double y );
```

**Description:** The \_moveto functions set the current output position for graphics. The \_moveto function uses the view coordinate system. The \_moveto\_w function uses the window coordinate system.

> The current output position is set to be the point at the coordinates (x, y). Nothing is drawn by the function. The \_lineto function uses the current output position as the starting point when a line is drawn.

> Note that the output position for graphics output differs from that for text output. The output position for text output can be set by use of the \_settextposition function.

**Returns:** The \_moveto functions return the previous value of the output position for graphics.

See Also: \_getcurrentposition, \_lineto, \_settextposition

```
Example:
           #include <conio.h>
           #include <graph.h>
           main()
               _setvideomode( _VRES16COLOR );
               _moveto( 100, 100 );
               _lineto( 540, 100 );
               _lineto( 320, 380 );
               _lineto( 100, 100 );
               getch();
               _setvideomode( _DEFAULTMODE );
           }
```


Classification: PC Graphics

**Systems:** \_moveto - DOS \_moveto\_w - DOS

Library Functions and Macros 809

**Description:** 

Convert signed packed double-words into signed packed words by packing (with signed saturation) the low-order words of the signed double-word elements from m1 and m2 into the respective signed words of the result. If the signed values in the word elements of m1 and m2 are smaller than 0x8000, the result elements are clamped to 0x8000. If the signed values in the word elements of m1 and m2 are larger than 0x7fff, the result elements are clamped to 0x7fff.



**Returns:** The result of packing, with signed saturation, 32-bit signed double-words into 16-bit signed words is returned.

See Also: \_m\_empty, \_m\_packsswb, \_m\_packuswb

**Example:** 

```
#include <stdio.h>
#include <mmintrin.h>
#define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                 "%2.2x %2.2x %2.2x %2.2x"
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
#define AS_DWORDS "%8.81x %8.81x"
__m64
       a;
___m64
      b = \{ 0x0000567800001234 \};
_{m64} c = { 0xfffffffe00010101 };
void main()
  {
    a = _m_packssdw(b, c);
    printf( "m2="AS_DWORDS" "
            "m1="AS_DWORDS"\n"
            "mm="AS_WORDS"\n",
        c._32[1], c._32[0],
        b._32[1], b._32[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
produces the following:
```

m2=ffffffe 00010101 m1=00005678 00001234

mm=fffe 7fff 5678 1234

m packssdw
------------

Classification: Intel

**Description:** 

Convert signed packed words into signed packed bytes by packing (with signed saturation) the low-order bytes of the signed word elements from m1 and m2 into the respective signed bytes of the result. If the signed values in the word elements of m1 and m2 are smaller than 0x80, the result elements are clamped to 0x80. If the signed values in the word elements of m1 and m2 are larger than 0x7f, the result elements are clamped to 0x7f.



**Returns:** The result of packing, with signed saturation, 16-bit signed words into 8-bit signed bytes is returned.

See Also: \_m\_empty, \_m\_packssdw, \_m\_packuswb

**Example:** 

```
#include <stdio.h>
#include <mmintrin.h>
#define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                  "%2.2x %2.2x %2.2x %2.2x"
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
#define AS_DWORDS "%8.81x %8.81x"
__m64
___m64
       b = \{ 0x0004000300020001 \};
       c = \{ 0xff7fff800080007f \};
__m64
void main()
  {
    a = _m_packsswb(b, c);
    printf( "m2="AS_WORDS" "
            "m1="AS_WORDS"\n"
            "mm="AS_BYTES"\n",
        c._16[3], c._16[2], c._16[1], c._16[0],
        b._16[3], b._16[2], b._16[1], b._16[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```


produces the following:

m2=ff7f ff80 0080 007f m1=0004 0003 0002 0001 mm=80 80 7f 7f 04 03 02 01

Classification: Intel

**Description:** 

Convert signed packed words into unsigned packed bytes by packing (with unsigned saturation) the low-order bytes of the signed word elements from m1 and m2 into the respective unsigned bytes of the result. If the signed values in the word elements of m1 and m2 are too large to be represented in an unsigned byte, the result elements are clamped to 0xf.



**Returns:** The result of packing, with unsigned saturation, 16-bit signed words into 8-bit unsigned bytes is

returned.

**See Also:** \_m\_empty, \_m\_packssdw, \_m\_packsswb

**Example:** 

```
#include <stdio.h>
#include <mmintrin.h>
#define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                  "%2.2x %2.2x %2.2x %2.2x"
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
#define AS_DWORDS "%8.81x %8.81x"
__m64
___m64
        b = \{ 0x0004000300020001 \};
        c = \{ 0xff7fff800080007f \};
__m64
void main()
  {
    a = _m_packuswb(b, c);
    printf( "m2="AS_WORDS" "
            "m1="AS_WORDS"\n"
            "mm="AS_BYTES"\n",
        c._16[3], c._16[2], c._16[1], c._16[0],
        b._16[3], b._16[2], b._16[1], b._16[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```

produces the following:

m2=ff7f ff80 0080 007f m1=0004 0003 0002 0001 mm=00 00 80 7f 04 03 02 01

Classification: Intel

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_paddb(__m64 *m1, __m64 *m2);
Description:
            The signed or unsigned 8-bit bytes of m2 are added to the respective signed or unsigned 8-bit bytes of
            m1 and the result is stored in memory. If any result element does not fit into 8 bits (overflow), the
            lower 8 bits of the result elements are stored (i.e., truncation takes place).
Returns:
            The result of adding the packed bytes of two 64-bit multimedia values is returned.
See Also:
            _m_empty, _m_paddd, _m_paddsb, _m_paddsw, _m_paddusb, _m_paddusw, _m_paddw
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                                "%2.2x %2.2x %2.2x %2.2x"
             m64
                     a;
                     b = \{ 0x0123456789abcdef \};
             m64
             m64
                     c = \{ 0xfedcba9876543210 \};
            void main()
               {
                 a = _m_paddb(b, c);
                 printf( "m1="AS_BYTES"\n"
                           m2=AS_BYTES'n
                           "mm="AS_BYTES"\n",
                      b._8[7], b._8[6], b._8[5], b._8[4],
                      b._8[3], b._8[2], b._8[1], b._8[0],
                      c._8[7], c._8[6], c._8[5], c._8[4],
                      c._8[3], c._8[2], c._8[1], c._8[0],
                      a._8[7], a._8[6], a._8[5], a._8[4],
                      a._8[3], a._8[2], a._8[1], a._8[0]);
               }
            produces the following:
            m1=01 23 45 67 89 ab cd ef
            m2=fe dc ba 98 76 54 32 10
            mm=ff ff ff ff ff ff ff
```

Classification: Intel

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_paddd(__m64 *m1, __m64 *m2);
```

**Description:** The signed or unsigned 32-bit double-words of m2 are added to the respective signed or unsigned 32-bit

double-words of m1 and the result is stored in memory. If any result element does not fit into 32 bits (overflow), the lower 32-bits of the result elements are stored (i.e., truncation takes place).

**Returns:** The result of adding the packed double-words of two 64-bit multimedia values is returned.

See Also: \_m\_empty, \_m\_paddb, \_m\_paddsb, \_m\_paddsw, \_m\_paddusb, \_m\_paddusw, \_m\_paddw

**Example:** #include <stdio.h> #include <mmintrin.h>

```
#define AS_DWORDS "%8.81x %8.81x"
```

```
m64
m64
        b = \{ 0x0123456789abcdef \};
        c = \{ 0xfedcba9876543210 \};
 m64
void main()
  {
    a = _m_paddd(b, c);
    printf( "m1="AS_DWORDS"\n"
            "m2="AS_DWORDS"\n"
            "mm="AS_DWORDS"\n",
        b._32[1], b._32[0],
        c._32[1], c._32[0],
        a._32[1], a._32[0]);
  }
```

produces the following:

```
m1=01234567 89abcdef
m2=fedcba98 76543210
mm=ffffffff ffffffff
```

Classification: Intel

**MACRO Systems:** 

**Description:** The signed 8-bit bytes of m2 are added to the respective signed 8-bit bytes of m1 and the result is stored

in memory. Saturation occurs when a result exceeds the range of a signed byte. In the case where a result is a byte larger than 0x7f (overflow), it is clamped to 0x7f. In the case where a result is a byte

smaller than 0x80 (underflow), it is clamped to 0x80.

**Returns:** The result of adding the packed signed bytes, with saturation, of two 64-bit multimedia values is

returned.

See Also: \_m\_empty, \_m\_paddb, \_m\_paddd, \_m\_paddsw, \_m\_paddusb, \_m\_paddusw, \_m\_paddw

Example: #include <stdio.h>
#include <mmintrin.h>

```
"%2.2x %2.2x %2.2x %2.2x"
m64
        a;
___m64
       b = \{ 0x8aacceef02244668 \};
___m64
       c = \{ 0x76543211fedcba98 \};
void main()
  {
    a = _m_paddsb(b, c);
    printf( "m1="AS_BYTES"\n"
            m2=AS_BYTES'n
            "mm="AS_BYTES"\n",
        b._8[7], b._8[6], b._8[5], b._8[4],
        b._8[3], b._8[2], b._8[1], b._8[0],
        c._8[7], c._8[6], c._8[5], c._8[4],
        c._8[3], c._8[2], c._8[1], c._8[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
```

a.\_8[3], a.\_8[2], a.\_8[1], a.\_8[0]);

#define AS\_BYTES "%2.2x %2.2x %2.2x %2.2x " \

produces the following:

}

```
m1{=}8a ac ce ef 02 24 46 68 m2{=}76 54 32 11 fe dc ba 98 mm{=}00 00 00 00 00 00 00 00
```

**Classification:** Intel

		_m_paddsb

**Description:** The signed 16-bit words of m2 are added to the respective signed 16-bit words of m1 and the result is

stored in memory. Saturation occurs when a result exceeds the range of a signed word. In the case where a result is a word larger than 0x7fff (overflow), it is clamped to 0x7fff. In the case where a result

is a word smaller than 0x8000 (underflow), it is clamped to 0x8000.

**Returns:** The result of adding the packed signed words, with saturation, of two 64-bit multimedia values is

returned.

See Also: \_m\_empty, \_m\_paddb, \_m\_paddd, \_m\_paddsb, \_m\_paddusb, \_m\_paddusw, \_m\_paddw

Example: #include <stdio.h>
#include <mmintrin.h>

produces the following:

}

```
m1=8aac ceef 0224 4668
m2=7654 3211 fedc ba98
mm=0100 0100 0100 0100
```

Classification: Intel

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_paddusb(__m64 *m1, __m64 *m2);
```

**Description:** The unsigned 8-bit bytes of m2 are added to the respective unsigned 8-bit bytes of m1 and the result is stored in memory. Saturation occurs when a result exceeds the range of an unsigned byte. In the case

where a result is a byte larger than 0xff (overflow), it is clamped to 0xff.

**Returns:** The result of adding the packed unsigned bytes, with saturation, of two 64-bit multimedia values is returned.

See Also: \_m\_empty,\_m\_paddb,\_m\_paddd,\_m\_paddsb,\_m\_paddsw,\_m\_paddusw,\_m\_paddw

**Example:** #include <stdio.h> #include <mmintrin.h>

```
#define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                 "%2.2x %2.2x %2.2x %2.2x"
__m64
        a;
m64
        b = \{ 0x8aacceef02244668 \};
___m64
        c = \{ 0x76543211fedcba98 \};
void main()
  {
    a = _m_paddusb(b, c);
    printf( "m1="AS_BYTES"\n"
            m2=AS_BYTES'n
            "mm="AS BYTES"\n",
        b._8[7], b._8[6], b._8[5], b._8[4],
        b._8[3], b._8[2], b._8[1], b._8[0],
        c._8[7], c._8[6], c._8[5], c._8[4],
        c._8[3], c._8[2], c._8[1], c._8[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```

produces the following:

```
m1=8a ac ce ef 02 24 46 68
m2=76 54 32 11 fe dc ba 98
mm=ff ff ff ff ff ff ff
```

**Classification:** Intel

_m_paddusb				

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_paddusw(__m64 *m1, __m64 *m2);
```

**Description:** The unsigned 16-bit words of m2 are added to the respective unsigned 16-bit words of m1 and the result is stored in memory. Saturation occurs when a result exceeds the range of an unsigned word. In the

case where a result is a word larger than 0xffff (overflow), it is clamped to 0xffff.

**Returns:** The result of adding the packed unsigned words, with saturation, of two 64-bit multimedia values is

returned.

See Also: \_m\_empty, \_m\_paddb, \_m\_paddd, \_m\_paddsb, \_m\_paddsw, \_m\_paddusb, \_m\_paddw

```
Example:
           #include <stdio.h>
           #include <mmintrin.h>
```

```
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
 m64
        a;
       b = \{ 0x8aacceef02244668 \};
m64
       c = \{ 0x76543211fedcba98 \};
___m64
void main()
   a = _m_paddusw(b, c);
   printf( "m1="AS_WORDS"\n"
            m2=MS_WORDS'' n
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        c._16[3], c._16[2], c._16[1], c._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

```
m1=8aac ceef 0224 4668
m2=7654 3211 fedc ba98
mm=ffff ffff ffff
```

Classification: Intel

**Systems:** 

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_paddw(__m64 *m1, __m64 *m2);
Description:
            The signed or unsigned 16-bit words of m2 are added to the respective signed or unsigned 16-bit words
             of m1 and the result is stored in memory. If any result element does not fit into 16 bits (overflow), the
            lower 16 bits of the result elements are stored (i.e., truncation takes place).
Returns:
            The result of adding the packed words of two 64-bit multimedia values is returned.
See Also:
             _m_empty, _m_paddb, _m_paddd, _m_paddsb, _m_paddsw, _m_paddusb, _m_paddusw
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
              m64
             m64
                      b = \{ 0x0123456789abcdef \};
                      c = \{ 0xfedcba9876543210 \};
              m64
            void main()
               {
                 a = _m_paddw(b, c);
                 printf( "m1="AS_WORDS"\n"
                           "m2="AS_WORDS"\n"
                           "mm="AS_WORDS"\n",
                      b._16[3], b._16[2], b._16[1], b._16[0],
                      c._16[3], c._16[2], c._16[1], c._16[0],
                      a._16[3], a._16[2], a._16[1], a._16[0]);
               }
             produces the following:
            m1=0123 4567 89ab cdef
            m2=fedc ba98 7654 3210
            mm=ffff ffff ffff
Classification: Intel
```

**MACRO** 

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_pand(__m64 *m1, __m64 *m2);
Description:
            A bit-wise logical AND is performed between 64-bit multimedia operands m1 and m2 and the result is
            stored in memory.
Returns:
            The bit-wise logical AND of two 64-bit values is returned.
See Also:
            _m_empty, _m_pandn, _m_por, _m_pxor
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_QWORD "%16.16Lx"
            ___m64
                     a;
            ___m64
                    b = \{ 0x0123456789abcdef \};
            _{m64} c = { 0xfedcba9876543210 };
            void main()
               {
                 a = _m_pand(b, c);
                 printf( "m1="AS_QWORD"\n"
                           m2=AS_QWORD'' n
                           "mm="AS_QWORD"\n",
                          b, c, a);
               }
            produces the following:
            m1=0123456789abcdef
            m2=fedcba9876543210
            mm = 000000000000000000
Classification: Intel
```

**MACRO** 

**Systems:** 

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_pandn(__m64 *m1, __m64 *m2);
Description:
             A bit-wise logical AND is performed on the logical inversion of 64-bit multimedia operand m1 and
             64-bit multimedia operand m2 and the result is stored in memory.
Returns:
             The bit-wise logical AND of an inverted 64-bit value and a non-inverted value is returned.
See Also:
             _m_empty, _m_pand, _m_por, _m_pxor
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_QWORD "%16.16Lx"
             ___m64
                      a;
             ___m64
                    b = \{ 0x0123456789abcdef \};
             _{m64} c = { 0xfedcba9876543210 };
             void main()
               {
                 a = _m_pandn(b, c);
                 printf( "m1="AS_QWORD"\n"
                           "m2="AS_QWORD"\n"
                           "mm="AS_QWORD"\n",
                           b, c, a);
               }
             produces the following:
             m1=0123456789abcdef
             m2=fedcba9876543210
             mm=fedcba9876543210
Classification: Intel
Systems:
            MACRO
```

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_pcmpeqb(\_\_m64 \*m1, \_\_m64 \*m2); **Description:** If the respective bytes of m1 are equal to the respective bytes of m2, the respective bytes of the result are set to all ones, otherwise they are set to all zeros. **Returns:** The result of comparing the packed bytes of two 64-bit multimedia values is returned as a sequence of bytes (0xff for equal, 0x00 for not equal). See Also: \_m\_empty, \_m\_pcmpeqd, \_m\_pcmpeqw, \_m\_pcmpgtb, \_m\_pcmpgtd, \_m\_pcmpgtw **Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_BYTES "%2.2x %2.2x %2.2x %2.2x " \ "%2.2x %2.2x %2.2x %2.2x" m64 a;  $b = \{ 0x0004000300020001 \};$ m64  $_{m64}$  c = { 0xff7fff800080007f }; void main() {  $a = _m_pcmpeqb(b, c);$ printf( "m1="AS\_BYTES"\n"  $m2="AS_BYTES"\n"$ "mm="AS\_BYTES"\n", b.\_8[7], b.\_8[6], b.\_8[5], b.\_8[4], b.\_8[3], b.\_8[2], b.\_8[1], b.\_8[0], c.\_8[7], c.\_8[6], c.\_8[5], c.\_8[4], c.\_8[3], c.\_8[2], c.\_8[1], c.\_8[0], a.\_8[7], a.\_8[6], a.\_8[5], a.\_8[4], a.\_8[3], a.\_8[2], a.\_8[1], a.\_8[0]); } produces the following: m1=00 04 00 03 00 02 00 01 m2=ff 7f ff 80 00 80 00 7f mm=00 00 00 00 ff 00 ff 00 Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_pcmpeqd(\_\_m64 \*m1, \_\_m64 \*m2); **Description:** If the respective double-words of m1 are equal to the respective double-words of m2, the respective double-words of the result are set to all ones, otherwise they are set to all zeros. **Returns:** The result of comparing the 32-bit packed double-words of two 64-bit multimedia values is returned as a sequence of double-words (0xffffffff for equal, 0x00000000 for not equal). See Also: \_m\_empty, \_m\_pcmpeqb, \_m\_pcmpeqw, \_m\_pcmpgtb, \_m\_pcmpgtd, \_m\_pcmpgtw **Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_DWORDS "%8.81x %8.81x" m64  $b = \{ 0x0004000300020001 \};$ m64 m64 c = { 0x000400030002007f }; void main() {  $a = _m_pcmpeqd(b, c);$ printf( "m1="AS\_DWORDS"\n" "m2="AS\_DWORDS"\n" "mm="AS\_DWORDS"\n", b.\_32[1], b.\_32[0],  $c._32[1], c._32[0],$ a.\_32[1], a.\_32[0]); } produces the following: m1=00040003 00020001 m2=00040003 0002007f mm=fffffff 00000000

Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_pcmpeqw(\_\_m64 \*m1, \_\_m64 \*m2);

**Description:** If the respective words of m1 are equal to the respective words of m2, the respective words of the result are set to all ones, otherwise they are set to all zeros.

**Returns:** The result of comparing the packed words of two 64-bit multimedia values is returned as a sequence of words (0xffff for equal, 0x0000 for not equal).

See Also: \_m\_empty, \_m\_pcmpeqb, \_m\_pcmpeqd, \_m\_pcmpgtb, \_m\_pcmpgtd, \_m\_pcmpgtw

**Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x"

```
m64
      b = \{ 0x0004000300020001 \};
m64
      c = \{ 0x0004ff8000800001 \};
m64
void main()
  {
    a = _m_pcmpeqw(b, c);
   printf( "m1="AS_WORDS"\n"
            "m2="AS_WORDS"\n"
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        c._16[3], c._16[2], c._16[1], c._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

m1=0004 0003 0002 0001 m2=0004 ff80 0080 0001 mm=ffff 0000 0000 ffff

Classification: Intel

**MACRO Systems:** 

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_pcmpgtb(__m64 *m1, __m64 *m2);
Description:
            If the respective signed bytes of m1 are greater than the respective signed bytes of m2, the respective
            bytes of the result are set to all ones, otherwise they are set to all zeros.
Returns:
            The result of comparing the packed signed bytes of two 64-bit multimedia values is returned as a
            sequence of bytes (0xff for greater than, 0x00 for not greater than).
See Also:
            _m_empty,_m_pcmpeqb,_m_pcmpeqd,_m_pcmpeqw,_m_pcmpgtd,_m_pcmpgtw
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                                "%2.2x %2.2x %2.2x %2.2x"
             m64
                     a;
                   b = \{ 0x0004000300020001 \};
             m64
             _{m64} c = { 0xff7fff800080007f };
            void main()
               {
                 a = _m_pcmpgtb(b, c);
                 printf( "m1="AS_BYTES"\n"
                          "m2="AS_BYTES"\n"
                          "mm="AS_BYTES"\n",
                     b._8[7], b._8[6], b._8[5], b._8[4],
                     b._8[3], b._8[2], b._8[1], b._8[0],
                     c._8[7], c._8[6], c._8[5], c._8[4],
                     c._8[3], c._8[2], c._8[1], c._8[0],
                     a._8[7], a._8[6], a._8[5], a._8[4],
                     a._8[3], a._8[2], a._8[1], a._8[0]);
               }
            produces the following:
            m1=00 04 00 03 00 02 00 01
            m2=ff 7f ff 80 00 80 00 7f
            mm=ff 00 ff ff 00 ff 00 00
```

Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_pcmpgtd(\_\_m64 \*m1, \_\_m64 \*m2);

**Description:** If the respective signed double-words of m1 are greater than the respective signed double-words of m2,

the respective double-words of the result are set to all ones, otherwise they are set to all zeros.

**Returns:** The result of comparing the 32-bit packed signed double-words of two 64-bit multimedia values is

returned as a sequence of double-words (0xffffffff for greater than, 0x00000000 for not greater than).

See Also: \_m\_empty, \_m\_pcmpeqb, \_m\_pcmpeqd, \_m\_pcmpeqw, \_m\_pcmpgtb, \_m\_pcmpgtw

**Example:** #include <stdio.h> #include <mmintrin.h>

#define AS\_DWORDS "%8.81x %8.81x"

```
m64
      b = \{ 0x0004000400020001 \};
m64
       c = \{ 0x000400030080007f \};
 m64
void main()
  {
    a = _m_pcmpqtd(b, c);
    printf( "m1="AS_DWORDS"\n"
            "m2="AS_DWORDS"\n"
            "mm="AS_DWORDS"\n",
        b._32[1], b._32[0],
        c._32[1], c._32[0],
        a._32[1], a._32[0]);
  }
```

produces the following:

m1=00040004 00020001 m2=00040003 0080007f mm=fffffff 00000000

Classification: Intel

**MACRO Systems:** 

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_pcmpgtw(\_\_m64 \*m1, \_\_m64 \*m2); **Description:** If the respective signed words of m1 are greater than the respective signed words of m2, the respective words of the result are set to all ones, otherwise they are set to all zeros. **Returns:** The result of comparing the 16-bit packed signed words of two 64-bit multimedia values is returned as a sequence of words (0xffff for greater than, 0x0000 for not greater than). See Also: \_m\_empty, \_m\_pcmpeqb, \_m\_pcmpeqd, \_m\_pcmpeqw, \_m\_pcmpgtb, \_m\_pcmpgtd **Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x" m64  $b = \{ 0x0005000300020001 \};$ m64  $c = \{ 0x0004ff8000800001 \};$ m64 void main() {  $a = _m_pcmpqtw(b, c);$ printf( "m1="AS\_WORDS" $\n"$ "m2="AS\_WORDS"\n" "mm="AS\_WORDS" $\n$ ", b.\_16[3], b.\_16[2], b.\_16[1], b.\_16[0], c.\_16[3], c.\_16[2], c.\_16[1], c.\_16[0], a.\_16[3], a.\_16[2], a.\_16[1], a.\_16[0]); } produces the following: m1=0005 0003 0002 0001 m2=0004 ff80 0080 0001 mm=ffff ffff 0000 0000 Classification: Intel

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_pmaddwd(__m64 *m1, __m64 *m2);
```

**Description:** The signed 16-bit words of m1 are multiplied with the respective signed 16-bit words of m2. The 32-bit intermediate results are summed by pairs producing two 32-bit integers.

```
MM[63-32] = M1[63-48] \times M2[63-48]
            + M1[47-32] \times M2[47-32]
MM[31-0] = M1[31-16] \times M2[31-16]
            + M1[15-0] \times M2[15-0]
```

In cases which overflow, the results are truncated. These two integers are packed into their respective elements of the result.

**Returns:** The result of multiplying the packed signed 16-bit words of two 64-bit multimedia values and adding the 32-bit results pairwise is returned as packed double-words.

```
See Also:
            _m_empty,_m_pmulhw,_m_pmullw
```

## **Example:** #include <stdio.h> #include <mmintrin.h>

```
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
#define AS_DWORDS "%8.81x %8.81x"
___m64
        b = \{ 0x0000006000123456 \};
___m64
        c = \{ 0x0000000200010020 \};
___m64
void main()
 {
    a = _m_p maddwd(b, c);
    printf( "m1="AS_WORDS"\n"
            "m2="AS_WORDS"\n"
            "mm="AS_DWORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        c._16[3], c._16[2], c._16[1], c._16[0],
        a._32[1], a._32[0]);
  }
```

produces the following:

```
m1=0000 0060 0012 3456
m2=0000 0002 0001 0020
mm=000000c0 00068ad2
```

Classification: Intel

_m_pmaddwd				

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_pmulhw(\_\_m64 \*m1, \_\_m64 \*m2);

**Description:** The signed 16-bit words of m1 are multiplied with the respective signed 16-bit words of m2. The

high-order 16-bits of each result are placed in the respective elements of the result.

**Returns:** The packed 16-bit words in m1 are multiplied with the packed 16-bit words in m2 and the high-order

16-bits of the results are returned.

See Also: \_m\_empty, \_m\_pmaddwd, \_m\_pmullw

**Example:** #include <stdio.h> #include <mmintrin.h>

#define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x"

```
m64
       b = \{ 0x4000006000123456 \};
m64
       c = \{ 0x0008000210000020 \};
 m64
void main()
  {
    a = _m_pmulhw(b, c);
   printf( "m1="AS_WORDS"\n"
            "m2="AS_WORDS"\n"
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        c._16[3], c._16[2], c._16[1], c._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

```
m1=4000 0060 0012 3456
m2=0008 0002 1000 0020
mm=0002 0000 0001 0006
```

Classification: Intel

**MACRO Systems:** 

```
Synopsis:
            #include <mmintrin.h>
             __m64 _m_pmullw(__m64 *m1, __m64 *m2);
Description:
            The signed or unsigned 16-bit words of m1 are multiplied with the respective signed or unsigned 16-bit
            words of m2. The low-order 16-bits of each result are placed in the respective elements of the result.
Returns:
            The packed 16-bit words in m1 are multiplied with the packed 16-bit words in m2 and the low-order
            16-bits of the results are returned.
See Also:
             _m_empty, _m_pmaddwd, _m_pmulhw
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
              m64
                    b = \{ 0x4000006000123456 \};
             m64
                    c = \{ 0x0008000210000020 \};
              m64
            void main()
               {
                 a = _m_pmullw(b, c);
                 printf( "m1="AS_WORDS"\n"
                           "m2="AS_WORDS"\n"
                           "mm="AS_WORDS"\n",
                      b._16[3], b._16[2], b._16[1], b._16[0],
                      c._16[3], c._16[2], c._16[1], c._16[0],
                      a._16[3], a._16[2], a._16[1], a._16[0]);
               }
            produces the following:
            m1=4000 0060 0012 3456
            m2=0008 0002 1000 0020
            mm=0000 00c0 2000 8ac0
Classification: Intel
            MACRO
Systems:
```

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_por(\_\_m64 \*m1, \_\_m64 \*m2); **Description:** A bit-wise logical OR is performed between 64-bit multimedia operands m1 and m2 and the result is stored in memory. **Returns:** The bit-wise logical OR of two 64-bit values is returned. See Also: \_m\_empty, \_m\_pand, \_m\_pandn, \_m\_pxor **Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_QWORD "%16.16Lx" \_\_\_m64 a; \_\_\_m64  $b = \{ 0x0123456789abcdef \};$  $_{m64}$  c = { 0xfedcba9876543210 }; void main() {  $a = _m_por(b, c);$ printf( "m1="AS\_QWORD"\n"  $m2=AS_QWORD'' n$ "mm="AS\_QWORD"\n", b, c, a); } produces the following: m1=0123456789abcdef m2=fedcba9876543210 mm=fffffffffffffff Classification: Intel

**MACRO** 

**Systems:** 

Synopsis: #include <sys/mman.h>

int mprotect(void \*address, size\_t len, int flags)

**Description:** The mprotect function writes changes the protections for the pages encompassing the memory

mapping at address and measuring len bytes based on the flags argument as specified.

The *flags* argument may be one or a combination of the following:

**Constant Meaning** 

**PROT\_NONE** No protections

**PROT\_READ** Read only

**PROT\_WRITE** Write only

**PROT\_EXEC** Allow execution

The flags may be either exclusively PROT\_NONE or a combination of one or more of the remaining

three values.

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EACCES** The value of *flags* violates a the permissions that a process has to the mapped data.

EAGAIN Write access was requested when the memory was originally mapped with the

MAP\_PRIVATE flag and the system lacks the resources to create a private page.

EINVAL The argument address is not a multiple of the page size or the flags argument is invalid

**ENOMEM** The arguments do not correspond to a region of the process's address space or exceed the

process's address space

**ENOTSUP** The specified combination of *flags* is not supported on the underlying system

See Also: mmap

Classification: POSIX 1003.1

**Systems:** Linux

		mprotect

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_pslld(__m64 *m, __m64 *count);
Description:
            The 32-bit double-words in m are each independently shifted to the left by the scalar shift count in
            count. The low-order bits of each element are filled with zeros. The shift count is interpreted as
            unsigned. Shift counts greater than 31 yield all zeros.
Returns:
            Shift left each 32-bit double-word in m by an amount specified in count while shifting in zeros.
See Also:
            _m_empty, _m_pslldi, _m_psllq, _m_psllqi, _m_psllwi
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_DWORDS "%8.81x %8.81x"
            #define AS_QWORD "%16.16Lx"
            m64
                     a;
                   b = \{ 0x3f04800300020001 \};
            ___m64
             void main()
              {
                a = _m_pslld(b, c);
                printf( "m1="AS_DWORDS"\n"
                          m2=MS_QWORD'' n''
                          "mm="AS_DWORDS"\n",
                     b._32[1], b._32[0],
                     a._32[1], a._32[0]);
              }
            produces the following:
            m1=3f048003 00020001
            mm=fc12000c 00080004
Classification: Intel
```

**MACRO** 

**Systems:** 

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_pslldi(__m64 *m, int count);
Description:
             The 32-bit double-words in m are each independently shifted to the left by the scalar shift count in
             count. The low-order bits of each element are filled with zeros. The shift count is interpreted as
             unsigned. Shift counts greater than 31 yield all zeros.
Returns:
             Shift left each 32-bit double-word in m by an amount specified in count while shifting in zeros.
See Also:
             _m_empty, _m_pslld, _m_psllq, _m_psllqi, _m_psllwi
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_DWORDS "%8.81x %8.81x"
             m64
                       b = \{ 0x3f04800300020001 \};
             m64
             void main()
                  a = _m_pslldi(b, 2);
                  printf( "m ="AS_DWORDS"\n"
                            "mm="AS_DWORDS"\n",
                       b._32[1], b._32[0],
```

a.\_32[1], a.\_32[0]);

produces the following:

}

m = 3f048003 00020001mm=fc12000c 00080004

Classification: Intel

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_psllq(__m64 *m, __m64 *count);
Description:
            The 64-bit quad-word in m is shifted to the left by the scalar shift count in count. The low-order bits are
            filled with zeros. The shift count is interpreted as unsigned. Shift counts greater than 63 yield all zeros.
Returns:
            Shift left the 64-bit quad-word in m by an amount specified in count while shifting in zeros.
See Also:
            _m_empty, _m_pslld, _m_pslldi, _m_psllqi, _m_psllw, _m_psllwi
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_QWORD "%16.16Lx"
            ___m64
                     a;
            ___m64
                   b = \{ 0x3f04800300020001 \};
            void main()
              {
                 a = _m_psllq(b, c);
                printf( "m1="AS_QWORD"\n"
                          m2=MS_QWORD'' n
                          "mm="AS_QWORD"\n",
                          b, c, a);
              }
            produces the following:
            m1=3f04800300020001
            mm=fc12000c00080004
Classification: Intel
Systems:
            MACRO
```

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_psllqi(__m64 *m, int count);
             The 64-bit quad-word in m is shifted to the left by the scalar shift count in count. The low-order bits are
Description:
             filled with zeros. The shift count is interpreted as unsigned. Shift counts greater than 63 yield all zeros.
Returns:
             Shift left the 64-bit quad-word in m by an amount specified in count while shifting in zeros.
See Also:
             _m_empty, _m_pslld, _m_pslldi, _m_psllq, _m_psllw, _m_psllwi
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_QWORD "%16.16Lx"
             ___m64
                       a;
             ___m64
                     b = \{ 0x3f04800300020001 \};
             void main()
                {
                  a = _m_psllqi(b, 2);
                  printf( "m ="AS_QWORD"\n"
                            "mm="AS_QWORD"\n",
                            b, a);
                }
             produces the following:
             m = 3f04800300020001
             mm=fc12000c00080004
Classification: Intel
```

**Systems:** 

**MACRO** 

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_psllw(__m64 *m, __m64 *count);
Description:
            The 16-bit words in m are each independently shifted to the left by the scalar shift count in count. The
            low-order bits of each element are filled with zeros. The shift count is interpreted as unsigned. Shift
            counts greater than 15 yield all zeros.
Returns:
            Shift left each 16-bit word in m by an amount specified in count while shifting in zeros.
See Also:
            _m_empty, _m_pslld, _m_pslldi, _m_psllq, _m_psllqi, _m_psllwi
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
            #define AS_QWORD "%16.16Lx"
            m64
                     a;
                   b = \{ 0x3f04800300020001 \};
            ___m64
             void main()
              {
                a = _m_psllw(b, c);
                printf( "m1="AS_WORDS"\n"
                          m2=MS_QWORD'' n
                          "mm="AS_WORDS"\n",
                     b._16[3], b._16[2], b._16[1], b._16[0],
                     a._16[3], a._16[2], a._16[1], a._16[0]);
              }
            produces the following:
            m1=3f04 8003 0002 0001
            mm=fc10 000c 0008 0004
Classification: Intel
```

**MACRO** 

**Systems:** 

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_psllwi(__m64 *m, int count);
```

**Description:** The 16-bit words in m are each independently shifted to the left by the scalar shift count in *count*. The low-order bits of each element are filled with zeros. The shift count is interpreted as unsigned. Shift

counts greater than 15 yield all zeros.

**Returns:** Shift left each 16-bit word in *m* by an amount specified in *count* while shifting in zeros.

```
See Also:
            _m_empty, _m_pslld, _m_pslldi, _m_psllq, _m_psllqi, _m_psllw
```

**Example:** #include <stdio.h> #include <mmintrin.h>

```
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
```

```
m64
        b = \{ 0x3f04800300020001 \};
m64
void main()
  {
    a = _m_psllwi(b, 2);
   printf( "m ="AS_WORDS"\n"
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

```
m = 3f04 8003 0002 0001
mm=fc10 000c 0008 0004
```

Classification: Intel

Synopsis: #include <mmintrin.h>
 \_\_m64 \_m\_psrad(\_\_m64 \*m, \_\_m64 \*count);

**Description:** The 32-bit signed double-words in m are each independently shifted to the right by the scalar shift count

in *count*. The high-order bits of each element are filled with the initial value of the sign bit of each element. The shift count is interpreted as unsigned. Shift counts greater than 31 yield all ones or zeros

depending on the initial value of the sign bit.

**Returns:** Shift right each 32-bit double-word in m by an amount specified in *count* while shifting in sign bits.

See Also: \_m\_empty, \_m\_psradi, \_m\_psraw, \_m\_psrawi

Example: #include <stdio.h>
#include <mmintrin.h>

```
#define AS_DWORDS "%8.81x %8.81x"
#define AS_QWORD "%16.16Lx"
___m64
        a;
      b = \{ 0x3f04800300020001 \};
___m64
      c = \{ 0x000000000000000002 \};
___m64
void main()
  {
    a = _m_psrad(b, c);
    printf( "m1="AS_DWORDS"\n"
            m2=MS_QWORD'' n'
            "mm="AS DWORDS"\n",
        b._32[1], b._32[0],
        a._32[1], a._32[0]);
  }
```

produces the following:

m1=3f048003 00020001 m2=0000000000000000000000 mm=0fc12000 00008000

Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_psradi(\_\_m64 \*m, int count);

**Description:** The 32-bit signed double-words in m are each independently shifted to the right by the scalar shift count

in count. The high-order bits of each element are filled with the initial value of the sign bit of each element. The shift count is interpreted as unsigned. Shift counts greater than 31 yield all ones or zeros

depending on the initial value of the sign bit.

**Returns:** Shift right each 32-bit double-word in m by an amount specified in *count* while shifting in sign bits.

See Also: \_m\_empty,\_m\_psrad,\_m\_psraw,\_m\_psrawi

**Example:** #include <stdio.h> #include <mmintrin.h>

#define AS\_DWORDS "%8.81x %8.81x"

```
__m64
        a;
__m64
        b = \{ 0x3f04800300020001 \};
void main()
  {
    a = _m_psradi(b, 2);
   printf( "m ="AS_DWORDS"\n"
            "mm="AS_DWORDS"\n",
        b._32[1], b._32[0],
        a._32[1], a._32[0]);
  }
```

produces the following:

m = 3f048003 00020001mm=0fc12000 00008000

Classification: Intel

Synopsis: #include <mmintrin.h>
 \_\_m64 \_m\_psraw(\_\_m64 \*m, \_\_m64 \*count);

**Description:** The 16-bit signed words in m are each independently shifted to the right by the scalar shift count in

*count*. The high-order bits of each element are filled with the initial value of the sign bit of each element. The shift count is interpreted as unsigned. Shift counts greater than 15 yield all ones or zeros

depending on the initial value of the sign bit.

**Returns:** Shift right each 16-bit word in *m* by an amount specified in *count* while shifting in sign bits.

See Also: \_m\_empty, \_m\_psrad, \_m\_psradi, \_m\_psrawi

Example: #include <stdio.h>
#include <mmintrin.h>

```
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
#define AS_QWORD "%16.16Lx"
___m64
        a;
       b = \{ 0x3f04800300040001 \};
___m64
      c = \{ 0x0000000000000000002 \};
___m64
void main()
  {
    a = _m_psraw(b, c);
    printf( "m1="AS_WORDS"\n"
            m2=MS_QWORD'' n
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_psrawi(\_\_m64 \*m, int count);

**Description:** The 16-bit signed words in m are each independently shifted to the right by the scalar shift count in

count. The high-order bits of each element are filled with the initial value of the sign bit of each element. The shift count is interpreted as unsigned. Shift counts greater than 15 yield all ones or zeros

depending on the initial value of the sign bit.

**Returns:** Shift right each 16-bit word in m by an amount specified in *count* while shifting in sign bits.

See Also: \_m\_empty, \_m\_psrad, \_m\_psradi, \_m\_psraw

**Example:** #include <stdio.h> #include <mmintrin.h>

#define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x"

```
__m64
        a;
__m64
        b = \{ 0x3f04800300040001 \};
void main()
  {
    a = _m_psrawi(b, 2);
    printf( "m ="AS_WORDS"\n"
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

m = 3f04 8003 0004 0001mm=0fc1 e000 0001 0000

Classification: Intel

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_psrld(__m64 *m, __m64 *count);
Description:
            The 32-bit double-words in m are each independently shifted to the right by the scalar shift count in
            count. The high-order bits of each element are filled with zeros. The shift count is interpreted as
            unsigned. Shift counts greater than 31 yield all zeros.
Returns:
            Shift right each 32-bit double-word in m by an amount specified in count while shifting in zeros.
See Also:
            _m_empty, _m_psrldi, _m_psrlq, _m_psrlqi, _m_psrlwi
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_DWORDS "%8.81x %8.81x"
            #define AS_QWORD "%16.16Lx"
            m64
                     a;
            m64 b = { 0x3f04800300020001 };
             void main()
              {
                a = _m_psrld(b, c);
                printf( "m1="AS_DWORDS"\n"
                         m2=MS_QWORD'' n''
                         "mm="AS_DWORDS"\n",
                     b._32[1], b._32[0],
                     a._32[1], a._32[0]);
              }
            produces the following:
            m1=3f048003 00020001
            mm=0fc12000 00008000
Classification: Intel
```

**MACRO** 

**Systems:** 

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_psrldi(__m64 *m, int count);
```

**Description:** The 32-bit double-words in m are each independently shifted to the right by the scalar shift count in

count. The high-order bits of each element are filled with zeros. The shift count is interpreted as

unsigned. Shift counts greater than 31 yield all zeros.

**Returns:** Shift right each 32-bit double-word in m by an amount specified in *count* while shifting in zeros.

See Also: \_m\_empty, \_m\_psrld, \_m\_psrlq, \_m\_psrlqi, \_m\_psrlw, \_m\_psrlwi

**Example:** #include <stdio.h> #include <mmintrin.h>

m64

}

#define AS\_DWORDS "%8.81x %8.81x"

 $b = \{ 0x3f04800300020001 \};$ m64 void main() {  $a = _m_psrldi(b, 2);$ printf( "m ="AS\_DWORDS"\n" "mm="AS\_DWORDS"\n", b.\_32[1], b.\_32[0], a.\_32[1], a.\_32[0]);

produces the following:

m = 3f048003 00020001mm=0fc12000 00008000

Classification: Intel

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_psrlq(__m64 *m, __m64 *count);
Description:
            The 64-bit quad-word in m is shifted to the right by the scalar shift count in count. The high-order bits
             are filled with zeros. The shift count is interpreted as unsigned. Shift counts greater than 63 yield all
             zeros.
Returns:
             Shift right the 64-bit quad-word in m by an amount specified in count while shifting in zeros.
See Also:
             _m_empty, _m_psrld, _m_psrldi, _m_psrlqi, _m_psrlwi
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_QWORD "%16.16Lx"
              __m64
             m64
                    b = \{ 0x3f04800300020001 \};
                    c = \{ 0x00000000000000002 \};
              m64
             void main()
               {
                 a = _m_psrlq(b, c);
                 printf( "m1="AS_QWORD"\n"
                           m2=AS_QWORD''n
                           "mm="AS_QWORD"\n",
                           b, c, a);
               }
             produces the following:
             m1=3f04800300020001
             m2 = 00000000000000000
             mm=0fc12000c0008000
Classification: Intel
Systems:
             MACRO
```

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_psrlqi(__m64 *m, int count);
Description:
             The 64-bit quad-word in m is shifted to the right by the scalar shift count in count. The high-order bits
             are filled with zeros. The shift count is interpreted as unsigned. Shift counts greater than 63 yield all
             zeros.
Returns:
             Shift right the 64-bit quad-word in m by an amount specified in count while shifting in zeros.
See Also:
             _m_empty, _m_psrld, _m_psrldi, _m_psrlq, _m_psrlw, _m_psrlwi
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_QWORD "%16.16Lx"
             m64
                       b = \{ 0x3f04800300020001 \};
             m64
             void main()
                {
                  a = _m_psrlqi(b, 2);
                  printf( "m ="AS_QWORD"\n"
                            "mm="AS_QWORD"\n",
                            b, a);
                }
             produces the following:
             m = 3f04800300020001
             mm=0fc12000c0008000
Classification: Intel
```

**Systems:** 

**MACRO** 

Library Functions and Macros 853

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_psrlw(__m64 *m, __m64 *count);
Description:
            The 16-bit words in m are each independently shifted to the right by the scalar shift count in count. The
            high-order bits of each element are filled with zeros. The shift count is interpreted as unsigned. Shift
            counts greater than 15 yield all zeros.
Returns:
            Shift right each 16-bit word in m by an amount specified in count while shifting in zeros.
See Also:
            _m_empty, _m_psrld, _m_psrldi, _m_psrlq, _m_psrlqi, _m_psrlwi
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
            #define AS_QWORD "%16.16Lx"
            m64
                     a;
            \underline{\phantom{a}}m64 b = { 0x3f04800300040001 };
             void main()
              {
                 a = _mpsrlw(b, c);
                 printf( "m1="AS_WORDS"\n"
                          m2=MS_QWORD'' n
                          "mm="AS_WORDS"\n",
                     b._16[3], b._16[2], b._16[1], b._16[0],
                     a._16[3], a._16[2], a._16[1], a._16[0]);
              }
            produces the following:
            m1=3f04 8003 0004 0001
            mm=0fc1 2000 0001 0000
Classification: Intel
```

**MACRO** 

**Systems:** 

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_psrlwi(__m64 *m, int count);
```

**Description:** The 16-bit words in m are each independently shifted to the right by the scalar shift count in *count*. The

high-order bits of each element are filled with zeros. The shift count is interpreted as unsigned. Shift counts greater than 15 yield all zeros.

**Returns:** Shift right each 16-bit word in *m* by an amount specified in *count* while shifting in zeros.

See Also: \_m\_empty, \_m\_psrld, \_m\_psrldi, \_m\_psrlq, \_m\_psrlqi, \_m\_psrlw

**Example:** #include <stdio.h> #include <mmintrin.h>

m64

#define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x"

```
b = \{ 0x3f04800300040001 \};
m64
void main()
  {
    a = _m_psrlwi(b, 2);
   printf( "m ="AS_WORDS"\n"
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

```
m = 3f04 8003 0004 0001
mm=0fc1 2000 0001 0000
```

Classification: Intel

```
Synopsis:
             #include <mmintrin.h>
              __m64 _m_psubb(__m64 *m1, __m64 *m2);
Description:
             The signed or unsigned 8-bit bytes of m2 are subtracted from the respective signed or unsigned 8-bit
             bytes of m1 and the result is stored in memory. If any result element does not fit into 8 bits (underflow
             or overflow), the lower 8 bits of the result elements are stored (i.e., truncation takes place).
Returns:
             The result of subtracting the packed bytes of one 64-bit multimedia value from another is returned.
See Also:
              _m_empty, _m_psubd, _m_psubsb, _m_psubsw, _m_psubusb, _m_psubusw, _m_psubw
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                                   "%2.2x %2.2x %2.2x %2.2x"
              m64
                       a;
                       b = \{ 0x0123456789abcdef \};
               m64
               m64
                       c = \{ 0xfedcba9876543210 \};
```

produces the following:

void main()

{

}

m1=01 23 45 67 89 ab cd ef m2=fe dc ba 98 76 54 32 10 mm=03 47 8b cf 13 57 9b df

a = \_m\_psubb( b, c );
printf( "m1="AS\_BYTES"\n"

"m2="AS\_BYTES"\n"
"mm="AS\_BYTES"\n",

b.\_8[7], b.\_8[6], b.\_8[5], b.\_8[4], b.\_8[3], b.\_8[2], b.\_8[1], b.\_8[0], c.\_8[7], c.\_8[6], c.\_8[5], c.\_8[4], c.\_8[3], c.\_8[2], c.\_8[1], c.\_8[0], a.\_8[7], a.\_8[6], a.\_8[5], a.\_8[4], a.\_8[3], a.\_8[2], a.\_8[1], a.\_8[0]);

Classification: Intel

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_psubd(__m64 *m1, __m64 *m2);
```

**Description:** The signed or unsigned 32-bit double-words of m2 are subtracted from the respective signed or

> unsigned 32-bit double-words of m1 and the result is stored in memory. If any result element does not fit into 32 bits (underflow or overflow), the lower 32-bits of the result elements are stored (i.e.,

truncation takes place).

**Returns:** The result of subtracting one set of packed double-words from a second set of packed double-words is

returned.

See Also: \_m\_empty, \_m\_psubb, \_m\_psubsb, \_m\_psubsw, \_m\_psubusb, \_m\_psubusw, \_m\_psubw

**Example:** #include <stdio.h> #include <mmintrin.h>

```
#define AS_DWORDS "%8.81x %8.81x"
___m64
        a;
__m64
       b = \{ 0x0123456789abcdef \};
       c = \{ 0xfedcba9876543210 \};
___m64
void main()
    a = _m_psubd(b, c);
    printf( "m1="AS_DWORDS"\n"
            "m2="AS_DWORDS"\n"
            "mm="AS_DWORDS"\n",
        b._32[1], b._32[0],
        c._32[1], c._32[0],
        a._32[1], a._32[0]);
  }
```

produces the following:

m1=01234567 89abcdef m2=fedcba98 76543210 mm=02468acf 13579bdf

Classification: Intel

**Description:** The signed 8-bit bytes of m2 are subtracted from the respective signed 8-bit bytes of m1 and the result is

stored in memory. Saturation occurs when a result exceeds the range of a signed byte. In the case where a result is a byte larger than 0x7f (overflow), it is clamped to 0x7f. In the case where a result is a

byte smaller than 0x80 (underflow), it is clamped to 0x80.

**Returns:** The result of subtracting the packed signed bytes, with saturation, of one 64-bit multimedia value from

a second multimedia value is returned.

See Also: \_m\_empty, \_m\_psubb, \_m\_psubd, \_m\_psubsw, \_m\_psubusb, \_m\_psubusw, \_m\_psubw

Example: #include <stdio.h>
#include <mmintrin.h>

```
#define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                 "%2.2x %2.2x %2.2x %2.2x"
m64
        a;
___m64
       b = \{ 0x8aacceef02244668 \};
___m64
        c = \{ 0x76543211fedcba98 \};
void main()
  {
    a = _m_psubsb(b, c);
    printf( "m1="AS_BYTES"\n"
            "m2="AS_BYTES"\n"
            "mm="AS_BYTES"\n",
        b._8[7], b._8[6], b._8[5], b._8[4],
        b._8[3], b._8[2], b._8[1], b._8[0],
        c._8[7], c._8[6], c._8[5], c._8[4],
        c._8[3], c._8[2], c._8[1], c._8[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```

produces the following:

```
m1=8a ac ce ef 02 24 46 68 m2=76 54 32 11 fe dc ba 98 mm=80 80 9c de 04 48 7f 7f
```

**Classification:** Intel

		_m_psubsb

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_psubsw(__m64 *m1, __m64 *m2);
```

**Description:** The signed 16-bit words of m2 are subtracted from the respective signed 16-bit words of m1 and the

result is stored in memory. Saturation occurs when a result exceeds the range of a signed word. In the case where a result is a word larger than 0x7fff (overflow), it is clamped to 0x7fff. In the case where a

result is a word smaller than 0x8000 (underflow), it is clamped to 0x8000.

**Returns:** The result of subtracting the packed signed words, with saturation, of one 64-bit multimedia value from

a second multimedia value is returned.

See Also: \_m\_empty,\_m\_psubb,\_m\_psubd,\_m\_psubsb,\_m\_psubusb,\_m\_psubusw,\_m\_psubw

```
Example:
           #include <stdio.h>
           #include <mmintrin.h>
```

```
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
___m64
        a;
___m64
       b = \{ 0x8aacceef02244668 \};
m64
       c = \{ 0x76543211fedcba98 \};
void main()
    a = _m_psubsw(b, c);
    printf( "m1="AS_WORDS"\n"
            "m2="AS_WORDS"\n"
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        c._16[3], c._16[2], c._16[1], c._16[0],
        a._16[3], a._16[2], a._16[1], a._16[0]);
  }
```

produces the following:

```
m1=8aac ceef 0224 4668
m2=7654 3211 fedc ba98
mm=8000 9cde 0348 7fff
```

Classification: Intel

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_psubusb(__m64 *m1, __m64 *m2);
```

**Description:** The unsigned 8-bit bytes of m2 are subtracted from the respective unsigned 8-bit bytes of m1 and the result is stored in memory. Saturation occurs when a result is less than zero. If a result is less than zero, it is clamped to 0xff.

**Returns:** The result of subtracting the packed unsigned bytes, with saturation, of one 64-bit multimedia value from a second multimedia value is returned.

See Also: \_m\_empty, \_m\_psubb, \_m\_psubd, \_m\_psubsb, \_m\_psubsw, \_m\_psubusw, \_m\_psubw

**Example:** #include <stdio.h> #include <mmintrin.h>

```
#define AS_BYTES "%2.2x %2.2x %2.2x %2.2x " \
                 "%2.2x %2.2x %2.2x %2.2x"
__m64
        a;
m64
        b = \{ 0x8aacceef02244668 \};
___m64
        c = \{ 0x76543211fedcba98 \};
void main()
  {
    a = _m_psubusb(b, c);
    printf( "m1="AS_BYTES"\n"
            m2=AS_BYTES'n
            "mm="AS BYTES"\n",
        b._8[7], b._8[6], b._8[5], b._8[4],
        b._8[3], b._8[2], b._8[1], b._8[0],
        c._8[7], c._8[6], c._8[5], c._8[4],
        c._8[3], c._8[2], c._8[1], c._8[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```

produces the following:

```
m1=8a ac ce ef 02 24 46 68
m2=76 54 32 11 fe dc ba 98
mm=14 58 9c de 00 00 00 00
```

**Classification:** Intel

_m_psubusb			

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_psubusw(\_\_m64 \*m1, \_\_m64 \*m2);

**Description:** The unsigned 16-bit words of m2 are subtracted from the respective unsigned 16-bit words of m1 and

the result is stored in memory. Saturation occurs when a result is less than zero. If a result is less than

zero, it is clamped to 0xffff.

a;

**Returns:** The result of subtracting the packed unsigned words, with saturation, of one 64-bit multimedia value

from a second multimedia value is returned.

See Also: \_m\_empty, \_m\_psubb, \_m\_psubd, \_m\_psubsb, \_m\_psubsw, \_m\_psubusb, \_m\_psubw

**Example:** #include <stdio.h> #include <mmintrin.h>

\_m64

}

```
#define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
```

```
b = \{ 0x8aacceef02244668 \};
m64
        c = \{ 0x76543211fedcba98 \};
___m64
void main()
    a = _m_psubusw(b, c);
    printf( "m1="AS_WORDS"\n"
            m2=MS_WORDS'' n
            "mm="AS_WORDS"\n",
        b._16[3], b._16[2], b._16[1], b._16[0],
        c._16[3], c._16[2], c._16[1], c._16[0],
```

a.\_16[3], a.\_16[2], a.\_16[1], a.\_16[0]);

produces the following:


m1=8aac ceef 0224 4668 m2=7654 3211 fedc ba98 mm=1458 9cde 0000 0000

Classification: Intel

```
Synopsis:
             #include <mmintrin.h>
             __m64 _m_psubw(__m64 *m1, __m64 *m2);
Description:
            The signed or unsigned 16-bit words of m2 are subtracted from the respective signed or unsigned 16-bit
             words of m1 and the result is stored in memory. If any result element does not fit into 16 bits
             (underflow or overflow), the lower 16 bits of the result elements are stored (i.e., truncation takes place).
Returns:
             The result of subtracting the packed words of two 64-bit multimedia values is returned.
See Also:
             _m_empty, _m_psubb, _m_psubd, _m_psubsb, _m_psubsw, _m_psubusb, _m_psubusw
Example:
             #include <stdio.h>
             #include <mmintrin.h>
             #define AS_WORDS "%4.4x %4.4x %4.4x %4.4x"
              m64
             m64
                      b = \{ 0x0123456789abcdef \};
                      c = \{ 0xfedcba9876543210 \};
              m64
             void main()
               {
                 a = _m_psubw(b, c);
                 printf( "m1="AS_WORDS"\n"
                            "m2="AS_WORDS"\n"
                           "mm="AS_WORDS"\n",
                      b._16[3], b._16[2], b._16[1], b._16[0],
                      c._16[3], c._16[2], c._16[1], c._16[0],
                      a._16[3], a._16[2], a._16[1], a._16[0]);
               }
             produces the following:
             m1=0123 4567 89ab cdef
             m2=fedc ba98 7654 3210
             mm=0247 8acf 1357 9bdf
Classification: Intel
Systems:
             MACRO
```

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_punpckhbw(__m64 *m1, __m64 *m2);
```

**Description:** The \_m\_punpckhbw function performs an interleaved unpack of the high-order data elements of m1 and m2. It ignores the low-order bytes. When unpacking from a memory operand, the full 64-bit operand is accessed from memory but only the high-order 32 bits are utilized. By choosing m1 or m2 to be zero, an unpacking of byte elements into word elements is performed.



**Returns:** The result of the interleaved unpacking of the high-order bytes of two multimedia values is returned.

See Also: \_m\_empty,\_m\_punpckhdq,\_m\_punpckhwd,\_m\_punpcklbw,\_m\_punpckldq, \_m\_punpcklwd

**Example:** #include <stdio.h> #include <mmintrin.h> #define AS BYTES "%2.2x %2.2x %2.2x %2.2x " \ "%2.2x %2.2x %2.2x %2.2x" m64 a;

```
b = \{ 0x0004000300020001 \};
m64
       c = \{ 0xff7fff800080007f \};
m64
void main()
  {
    a = _m_punpckhbw(b, c);
   printf( "m2="AS_BYTES" "
            m1="AS_BYTES"\n"
            "mm="AS_BYTES"\n",
        c._8[7], c._8[6], c._8[5], c._8[4],
        c._8[3], c._8[2], c._8[1], c._8[0],
        b._8[7], b._8[6], b._8[5], b._8[4],
        b._8[3], b._8[2], b._8[1], b._8[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```

produces the following:


```
m2=ff 7f ff 80 00 80 00 7f m1=00 04 00 03 00 02 00 01
mm=ff 00 7f 04 ff 00 80 03
```

## \_m\_punpckhbw

Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_punpckhdq(\_\_m64 \*m1, \_\_m64 \*m2);

The \_m\_punpckhdq function performs an interleaved unpack of the high-order data elements of m1 **Description:** and m2. It ignores the low-order double-words. When unpacking from a memory operand, the full 64-bit operand is accessed from memory but only the high-order 32 bits are utilized.



**Returns:** The result of the interleaved unpacking of the high-order double-words of two multimedia values is returned.

See Also: \_m\_empty, \_m\_punpckhbw, \_m\_punpckhwd, \_m\_punpcklbw, \_m\_punpckldq, \_m\_punpcklwd

**Example:** #include <stdio.h> #include <mmintrin.h>

> m64  $b = \{ 0x0004000300020001 \};$ m64 m64  $c = \{ 0xff7fff800080007f \};$ void main() {  $a = _m_punpckhdq(b, c);$ printf( "m2="AS\_DWORDS" " "m1="AS\_DWORDS"\n" "mm="AS\_DWORDS"\n",  $c._32[1], c._32[0],$ b.\_32[1], b.\_32[0], a.\_32[1], a.\_32[0]);

#define AS DWORDS "%8.81x %8.81x"

produces the following:

}

m2=ff7fff80 0080007f m1=00040003 00020001 mm=ff7fff80 00040003

Classification: Intel

_m_punpckhdq			

```
Synopsis:
           #include <mmintrin.h>
            __m64 _m_punpckhwd(__m64 *m1, __m64 *m2);
```

**Description:** The \_m\_punpckhwd function performs an interleaved unpack of the high-order data elements of m1 and m2. It ignores the low-order words. When unpacking from a memory operand, the full 64-bit operand is accessed from memory but only the high-order 32 bits are utilized. By choosing m1 or m2 to be zero, an unpacking of word elements into double-word elements is performed.



**Returns:** The result of the interleaved unpacking of the high-order words of two multimedia values is returned.

See Also: \_m\_empty,\_m\_punpckhbw,\_m\_punpckhdq,\_m\_punpcklbw,\_m\_punpckldq, \_m\_punpcklwd

**Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x" m64 m64  $b = \{ 0x0004000300020001 \};$ 

 $c = \{ 0xff7fff800080007f \};$ m64 void main() {  $a = _m_punpckhwd(b, c);$ printf( "m2="AS\_WORDS" " "m1="AS\_WORDS"\n" "mm="AS\_WORDS"\n", c.\_16[3], c.\_16[2], c.\_16[1], c.\_16[0], b.\_16[3], b.\_16[2], b.\_16[1], b.\_16[0], a.\_16[3], a.\_16[2], a.\_16[1], a.\_16[0]); }

produces the following:

m2=ff7f ff80 0080 007f m1=0004 0003 0002 0001 mm=ff7f 0004 ff80 0003

Classification: Intel

_m_punpckhwd			

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_punpcklbw(__m64 *m1, __m64 *m2);
```

**Description:** The \_m\_punpcklbw function performs an interleaved unpack of the low-order data elements of m1 and m2. It ignores the high-order bytes. When unpacking from a memory operand, 32 bits are accessed and all are utilized by the instruction. By choosing m1 or m2 to be zero, an unpacking of byte elements into word elements is performed.



**Returns:** The result of the interleaved unpacking of the low-order bytes of two multimedia values is returned.

See Also: \_m\_empty, \_m\_punpckhbw, \_m\_punpckhdq, \_m\_punpckhwd, \_m\_punpckldq, \_m\_punpcklwd

**Example:** #include <stdio.h> #include <mmintrin.h> #define AS BYTES "%2.2x %2.2x %2.2x %2.2x " \ "%2.2x %2.2x %2.2x %2.2x"

```
b = \{ 0x000200013478bcf0 \};
m64
      c = \{ 0x0080007f12569ade \};
m64
void main()
  {
    a = _m_punpcklbw(b, c);
    printf( "m2="AS_BYTES" "
            "m1="AS_BYTES"\n"
            "mm="AS_BYTES"\n",
        c._8[7], c._8[6], c._8[5], c._8[4],
        c._8[3], c._8[2], c._8[1], c._8[0],
        b._8[7], b._8[6], b._8[5], b._8[4],
        b._8[3], b._8[2], b._8[1], b._8[0],
        a._8[7], a._8[6], a._8[5], a._8[4],
        a._8[3], a._8[2], a._8[1], a._8[0]);
  }
```

produces the following:

m64

a;

```
m2=00 80 00 7f 12 56 9a de m1=00 02 00 01 34 78 bc f0
mm=12 34 56 78 9a bc de f0
```

## \_m\_punpcklbw

Classification: Intel

**Synopsis:** #include <mmintrin.h> \_\_m64 \_m\_punpckldq(\_\_m64 \*m1, \_\_m64 \*m2);

The \_m\_punpckldq function performs an interleaved unpack of the low-order data elements of m1 **Description:** and m2. It ignores the high-order double-words. When unpacking from a memory operand, 32 bits are accessed and all are utilized by the instruction.



**Returns:** The result of the interleaved unpacking of the low-order double-words of two multimedia values is returned.

See Also: \_m\_empty, \_m\_punpckhbw, \_m\_punpckhdq, \_m\_punpckhwd, \_m\_punpcklbw, \_m\_punpcklwd

**Example:** #include <stdio.h> #include <mmintrin.h> #define AS DWORDS "%8.81x %8.81x"

> m64  $b = \{ 0x0004000300020001 \};$ m64 m64  $c = \{ 0xff7fff800080007f \};$ void main() {  $a = _m_punpckldq(b, c);$ printf( "m2="AS\_DWORDS" " "m1="AS\_DWORDS"\n" "mm="AS\_DWORDS"\n",  $c._32[1], c._32[0],$ b.\_32[1], b.\_32[0], a.\_32[1], a.\_32[0]); }

produces the following:


m2=ff7fff80 0080007f m1=00040003 00020001 mm=0080007f 00020001

Classification: Intel

_m_punpckldq			

```
Synopsis:
           #include <mmintrin.h>
           __m64 _m_punpcklwd(__m64 *m1, __m64 *m2);
```

**Description:** The \_m\_punpcklwd function performs an interleaved unpack of the low-order data elements of m1 and m2. It ignores the high-order words. When unpacking from a memory operand, 32 bits are accessed and all are utilized by the instruction. By choosing m1 or m2 to be zero, an unpacking of word elements into double-word elements is performed.



**Returns:** The result of the interleaved unpacking of the low-order words of two multimedia values is returned.

See Also: \_m\_empty,\_m\_punpckhbw,\_m\_punpckhdq,\_m\_punpckhwd,\_m\_punpcklbw, \_m\_punpckldq

**Example:** #include <stdio.h> #include <mmintrin.h> #define AS\_WORDS "%4.4x %4.4x %4.4x %4.4x" m64 m64  $b = \{ 0x0004000300020001 \};$  $c = \{ 0xff7fff800080007f \};$ m64

void main() {  $a = _m_punpcklwd(b, c);$ printf( "m2="AS\_WORDS" " "m1="AS\_WORDS"\n" "mm="AS\_WORDS"\n", c.\_16[3], c.\_16[2], c.\_16[1], c.\_16[0], b.\_16[3], b.\_16[2], b.\_16[1], b.\_16[0], a.\_16[3], a.\_16[2], a.\_16[1], a.\_16[0]); }

produces the following:

m2=ff7f ff80 0080 007f m1=0004 0003 0002 0001 mm=0080 0002 007f 0001

Classification: Intel

_m_punpcklwd			

```
Synopsis:
            #include <mmintrin.h>
            __m64 _m_pxor(__m64 *m1, __m64 *m2);
Description:
            A bit-wise logical XOR is performed between 64-bit multimedia operands m1 and m2 and the result is
            stored in memory.
Returns:
            The bit-wise logical exclusive OR of two 64-bit values is returned.
See Also:
            _m_empty, _m_pand, _m_pandn, _m_por
Example:
            #include <stdio.h>
            #include <mmintrin.h>
            #define AS_QWORD "%16.16Lx"
            ___m64
                     a;
            ___m64
                    b = \{ 0x0123456789abcdef \};
            _{m64} c = { 0xfedcba9876543210 };
            void main()
               {
                 a = _m_pxor(b, c);
                 printf( "m1="AS_QWORD"\n"
                          m2=AS_QWORD'' n
                          "mm="AS_QWORD"\n",
                          b, c, a);
               }
            produces the following:
            m1=0123456789abcdef
            m2=fedcba9876543210
            mm=fffffffffffffff
Classification: Intel
```

**MACRO** 

**Systems:** 

```
Synopsis: #include <malloc.h>
    size_t _msize( void *buffer );
    size_t _bmsize( __segment seg, void __based(void) *buffer );
    size_t _fmsize( void __far *buffer );
    size_t _nmsize( void __near *buffer );
```

**Description:** The \_msize functions return the size of the memory block pointed to by *buffer* that was allocated by a call to the appropriate version of the calloc, malloc, or realloc functions.

You must use the correct \_msize function as listed below depending on which heap the memory block belongs to.

## Function Heap \_msize Depends on data model of the program \_bmsize Based heap specified by seg value \_fmsize Far heap (outside the default data segment) \_nmsize Near heap (inside the default data segment)

In small data models (small and medium memory models), \_msize maps to \_nmsize. In large data models (compact, large and huge memory models), \_msize maps to \_fmsize.

**Returns:** The \_msize functions return the size of the memory block pointed to by *buffer*.

See Also: calloc Functions, \_expand Functions, free Functions, halloc, hfree, malloc Functions, realloc Functions, sbrk

```
Example: #include <stdio.h>
    #include <malloc.h>

void main()
    {
       void *buffer;
```

produces the following:

Size of block is 1000 bytes

**Classification:** WATCOM

```
Systems:

_msize - All, Linux, RDOS, Netware

_bmsize - DOS/16, Windows, OS/2 1.x(all)

_fmsize - DOS/16, Windows, OS/2 1.x(all)

_nmsize - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

_msize Functions

Synopsis: #include <sys/mman.h>

int msync(void \*address, size\_t len, int flags)

**Description:** The msync function writes all modified data to permanent storage corresponding to the memory

mapping at address measuring len bytes.

The *flags* argument may be one or a combination of the following:

**Constant Meaning** 

MS\_ASYNC Perform asynchronous writes

MS\_SYNC Perform synchronous writes

MS\_INVALIDATE Invalidate any cached data

The flags MS\_ASYNC and MS\_SYNC may not be combined.

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The argument address is not a multiple of the page size or the flags argument is invalid

**ENOMEM** The arguments do not correspond to a region of the process's address space or exceed the

process's address space

EBUSY A portion of or all of the address space specified is currently locked

See Also: mlock, mlockall, mmap, munlock, munlockall, munmap

Classification: POSIX 1003.1

**Systems:** Linux

**Synopsis:** #include <mmintrin.h> \_m\_to\_int(\_\_m64 \*\_\_m); **Description:** The \_m\_to\_int function returns the low-order 32 bits of a multimedia value. **Returns:** The low-order 32 bits of a multimedia value are fetched and returned as the result. See Also: \_m\_empty, \_m\_from\_int, \_m\_packsswb, \_m\_paddb, \_m\_pand, \_m\_empty, \_m\_pcmpeqb, \_m\_pmaddwd, \_m\_psllw, \_m\_psraw, \_m\_psrlw, \_m\_empty, \_m\_psubb, \_m\_punpckhbw **Example:** #include <stdio.h> #include <mmintrin.h> \_\_\_m64  $b = \{ 0x0123456789abcdef \};$ int j; void main()  $j = _m_to_int(b);$ printf( "m=%16.16Lx int=%8.8lx\n", b, j); produces the following: m=0123456789abcdef int=89abcdef Classification: Intel

**Systems:** MACRO

# munlock

Synopsis: #include <sys/mman.h>

int munlock(void \*address, size\_t len)

**Description:** The munlock function causes memory located at address measuring len bytes to be released regardless

of the number of prior calls to lock the referenced memory.

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The argument address is not a multiple of the page size or the len is zero or causes an

overflow

**ENOMEM** The arguments do not correspond to a region of the process's address space

See Also: mlock, mlockall, munlockall

Classification: POSIX 1003.1

Systems: Linux

**Synopsis:** #include <sys/mman.h>

int munlockall( )

**Description:** The munlockall function unlocks all memory for a process. If, in the preceding call to mlockall

function, the flag MCL\_FUTURE was specified, all future pages mapped for the process will also not be

locked unless another call to mlockall specifies such behavior.

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

See Also: mlock, mlockall, munlock

Classification: POSIX 1003.1

**Systems:** Linux

## munmap

Synopsis: #include <sys/mman.h>

int munmap(void \*address, size\_t len)

**Description:** The munmap function removes any mapping at the address address measuring len bytes from the

process address space.

**Returns:** If successful, the function will return 0. Upon failure, the function will return -1, and errno will be set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

*EINVAL* Either one or both of the arguments was invalid.

See Also: mmap

Classification: POSIX 1003.1

**Systems:** Linux

```
Synopsis:
           #include <math.h>
           float nanf( const char *s );
           double nan( const char *s );
           long double nanl( const char *s );
```

**Description:** The nan function returns not-a-number, or NAN. The argument *s* is ignored.

**Returns:** The proper not-a-number value.

```
Example:
           #include <stdio.h>
           #include <math.h>
           void main()
               printf( "%f\n", nan("") );
```

produces the following:

nan

Classification: ISO C99

**Systems:** Math **Description:** The nearbyint function rounds the argument x to a nearby integer without the possibility of

throwing an exception. The direction of the rounding is determined by the current value of

fegetround.

**Returns:** The rounded value of x.

See Also: fegetround, fesetround, rint, round, trunc

Example: #include <stdio.h>
#include <math.h>

void main()
{
 fesetround(FE\_TONEAREST);
 printf( "%f\n", nearbyint( 1.2 ) );
}

produces the following:

1.000000

Classification: ISO C99

**Systems:** Math

**Synopsis:** #include <math.h>

double nextafter( double x, double y);

**Description:** The next after function returns the next machine floating point number of x in the direction towards

**Returns:** The next representable floating point value after or before *x* in the direction of *y*.

**Example:** #include <stdio.h>

```
#include <math.h>
void main()
   printf( "%f\n", nextafter( 8.0, 9.0 ) );
```

produces the following:

8.000000

Classification: ISO C99

**Systems:** Math

Synopsis: #include <langinfo.h>

char \*nl\_langinfo( int item );

**Description:** The nl\_langinfo function retrieves language information, purportedly based on the current locale.

The item argument specifies which language element to retrieve, and may be one of the following:

Member	Meaning
CODESET	The character encoding supported by this locale
$D\_T\_FMT$	The date and time format string
D_FMT	The date format string
T_FMT	The 24-hour time format string
T_FMT_AMPM	The 12-hour time format string
AM_STR	The string representing ante-meridiem time
PM_STR	The string representing post-meridiem time
DAY_1	The name of the first day of the week
DAY_2	The name of the second day of the week
DAY_3	The name of the third day of the week
DAY_4	The name of the fourth day of the week

DAY_5	The name of the fifth day of the week
DAY_6	The name of the sixth day of the week
DAY_7	The name of the seventh day of the week
ABDAY_1	The abbreviated name of the first day of the week
ABDAY_2	The abbreviated name of the second day of the week
ABDAY_3	The abbreviated name of the third day of the week
ABDAY_4	The abbreviated name of the fourth day of the week
ABDAY_5	The abbreviated name of the fifth day of the week
ABDAY_6	The abbreviated name of the sixth day of the week
ABDAY_7	The abbreviated name of the seventh day of the week
MON_1	The name of the first month of the year
MON_2	The name of the second month of the year

MON_3	The name of the third month of the year
MON_4	The name of the fourth month of the year
MON_5	The name of the fifth month of the year
MON_6	The name of the sixth month of the year
MON_7	The name of the seventh month of the year
MON_8	The name of the eighth month of the year
MON_9	The name of the ninth month of the year
MON_10	The name of the tenth month of the year
MON_11	The name of the eleventh month of the year
MON_12	The name of the twelfth month of the year
ABMON_1	The abbreviated name of the first month of the year
ABMON_2	The abbreviated name of the second month of the year
ABMON_3	The name of the third month of the year

ABMON_4	The abbreviated name of the fourth month of the year
ABMON_5	The abbreviated name of the fifth month of the year
ABMON_6	The abbreviated name of the sixth month of the year
ABMON_7	The abbreviated name of the seventh month of the year
ABMON_8	The abbreviated name of the eighth month of the year
ABMON_9	The abbreviated name of the ninth month of the year
ABMON_10	The abbreviated name of the tenth month of the year
ABMON_11	The abbreviated name of the eleventh month of the year
ABMON_12	The abbreviated name of the twelfth month of the year
RADIXCHAR	The radix character
THOUSEP	The separator for thousands
YESEXPR	The string for indicating

affirmative responses

NOEXPR The string for

indicating negative responses

In the default locale (C), some values may be U.S.A.-centric, specifically the RADIXCHAR and

THOUSEP. Additionally, names are in English presently.

**Returns:** The function returns a pointer to a statically allocated string that must not be freed. If *item* is either

unsupported or unknown, an empty string will be returned.

Classification: POSIX 1003.1

Systems: Linux

```
Synopsis:
           #include <i86.h>
           void nosound( void );
```

**Description:** The nosound function turns off the PC's speaker.

**Returns:** The nosound function has no return value.

See Also: delay, sound

```
Example:
           #include <i86.h>
           void main()
               sound( 200 );
               delay( 500 ); /* delay for 1/2 second */
               nosound();
```

Classification: Intel

DOS, Windows, Win386 **Systems:** 

Synopsis: #include <stddef.h>
 size\_t offsetof( composite, name );

**Description:** The offsetof macro returns the offset of the element *name* within the struct or union *composite*.

This provides a portable method to determine the offset.

**Returns:** The offset of function returns the offset of *name*.

```
Example: #include <stdio.h>
#include <stddef.h>
```

produces the following:

In a small data model, the following would result:

first:0 second:2 third:12

In a large data model, the following would result:

first:0 second:4 third:14

Classification: ISO C

**Systems:** MACRO

```
Synopsis:
           ** deprecated **
           #include <stdlib.h>
           onexit_t _onexit( _onexit_t func );
           onexit_t onexit( onexit_t func );
```

**Description:** 

The \_onexit function is passed the address of function func to be called when the program terminates normally. Successive calls to \_onexit create a list of functions that will be executed on a "last-in, first-out" basis. No more than 32 functions can be registered with the \_onexit function.

The functions have no parameters and do not return values.

NOTE: The \_onexit function is not an ISO C function. The ISO C standard function atexit does the same thing.

The \_onexit function is deprecated, use atexit instead. The onexit function is deprecated, use atexit instead.

**Returns:** The \_onexit function returns *func* if the registration succeeds, NULL if it fails.

See Also: abort, atexit, exit, \_Exit, \_exit

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
void main()
  {
    extern void func1(void), func2(void), func3(void);
    _onexit( func1 );
    _onexit( func2 );
    _onexit(func3);
    printf( "Do this first.\n" );
  }
void func1(void) { printf( "last.\n" ); }
void func2(void) { printf( "this " ); }
void func3(void) { printf( "Do " ); }
produces the following:
Do this first.
```

**Classification:** WATCOM

\_onexit - All, Linux, RDOS, Netware **Systems:** onexit - All, Linux, RDOS, Netware

Do this last.

_onexit, onexit			

#### **Synopsis:**

```
#include <sys/types.h>
#include <sys/stat.h>
#include <fcntl.h>
int open( const char *path, int access, ...);
int _open( const char *path, int access, ... );
int _wopen( const wchar_t *path, int access, ... );
```

#### **Description:**

The open function opens a file at the operating system level. The name of the file to be opened is given by path. The file will be accessed according to the access mode specified by access. The optional argument is the file permissions to be used when the O\_CREAT flag is on in the access mode.

The \_open function is identical to open. Use \_open for ANSI naming conventions.

The \_wopen function is identical to open except that it accepts a wide character string argument for path.

The access mode is established by a combination of the bits defined in the <fcntl.h> header file. The following bits may be set:

Mode	Meaning
O_RDONLY	permit the file to be only read.
O_WRONLY	permit the file to be only written.
O_RDWR	permit the file to be both read and written.
O_APPEND	causes each record that is written to be written at the end of the file.
O_CREAT	has no effect when the file indicated by <i>filename</i> already exists; otherwise, the file is created;
O_TRUNC	causes the file to be truncated to contain no data when the file exists; has no effect when the file does not exist.
O_BINARY	causes the file to be opened in binary mode which means that data will be transmitted to and from the file unchanged.
O_TEXT	causes the file to be opened in text mode which means that carriage-return characters are written before any linefeed character that is written and causes carriage-return characters to be removed when encountered during reads.
O_NOINHERIT	indicates that this file is not to be inherited by a child process.
O_EXCL	indicates that this file is to be opened for exclusive access. If the file exists and O_CREAT was also specified then the open will fail (i.e., use O_EXCL to ensure that the file does not already exist).

When neither O\_TEXT nor O\_BINARY are specified, the default value in the global variable \_fmode is used to set the file translation mode. When the program begins execution, this variable has a value of O\_TEXT.

O\_CREAT must be specified when the file does not exist and it is to be written.

When the file is to be created (O\_CREAT is specified), an additional argument must be passed which contains the file permissions to be used for the new file. The access permissions for the file or directory are specified as a combination of bits (defined in the <sys/stat.h> header file).

The following bits define permissions for the owner.

Permission	Meaning		
S_IRWXU	Read, write, execute/search		
S_IRUSR	Read permission		
S_IWUSR	Write permission		
S_IXUSR	Execute/search permission		

The following bits define permissions for the group.

Meaning			
Read, write, execute/search Read permission Write permission Execute/search permission			

The following bits define permissions for others.

Permission	Meaning		
S_IRWXO	Read, write, execute/search		
S_IROTH	Read permission		
S_IWOTH	Write permission		
S_IXOTH	Execute/search permission		

The following bits define miscellaneous permissions used by other implementations.

Permission	Meaning
S_IREAD	is equivalent to S_IRUSR (read permission)
S_IWRITE	is equivalent to S_IWUSR (write permission)
S_IEXEC	is equivalent to S_IXUSR (execute/search permission)

All files are readable with DOS; however, it is a good idea to set S\_IREAD when read permission is intended for the file.

The open function applies the current file permission mask to the specified permissions (see the umask function).

**Returns:** If successful, open returns a handle for the file. When an error occurs while opening the file, -1 is returned.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

```
Constant
                            Meaning
            EACCES
                            Access denied because path specifies a directory or a volume ID, or attempting to
                            open a read-only file for writing
            EMFILE
                            No more handles available (too many open files)
            ENOENT
                            Path or file not found
See Also:
            _chsize, close, creat, dup, dup2, _eof, exec..., fdopen, _filelength, fileno,
            fstat, _grow_handles, isatty, lseek, read, _setmode, _sopen, stat, _tell, write,
            umask
Example:
            #include <sys/stat.h>
            #include <sys/types.h>
            #include <fcntl.h>
            void main()
              {
                int handle;
                /* open a file for output
                /* replace existing file if it exists
                                                                */
                handle = open( "file",
                              O_WRONLY | O_CREAT | O_TRUNC,
                              S_IRUSR | S_IWUSR | S_IRGRP |
                                                               S_IWGRP );
                /* read a file which is assumed to exist
                                                                */
                handle = open( "file", O_RDONLY );
                /* append to the end of an existing file
                /* write a new file if file does not exist */
                handle = open( "file",
                              O_WRONLY O_CREAT O_APPEND,
                              S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
              }
Classification: POSIX 1003.1
            _open conforms to ANSI naming conventions
            open - All, Linux, RDOS, Netware
Systems:
            _open - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
            _wopen - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux
```

open, _open, _wopen			

```
Synopsis:
           #include <direct.h>
           DIR *opendir( const char *dirname );
           WDIR *_wopendir( const wchar_t *dirname );
```

**Description:** 

The opendir function is used in conjunction with the functions readdir and closedir to obtain the list of file names contained in the directory specified by dirname. The path indicated by dirname can be either relative to the current working directory or it can be an absolute path name. As an extension to POSIX, the last part of dirname can contain the characters '?' and '\*' for matching multiple files within a directory.

The file <direct.h> contains definitions for the structure dirent.

```
#if defined(__OS2__) | defined(__NT__)
#define NAME_MAX 255
                               /* maximum for HPFS or NTFS */
#else
#define NAME_MAX 12  /* 8 chars + '.' + 3 chars */
#endif
struct dirent {
     char d_dta[21]; /* disk transfer area */
    char d_attr; /* file's attribute */
unsigned short d_time; /* file's time */
unsigned short d_date; /* file's date */
long d_size; /* file's size */
char d_name[NAME_MAX+1]; /* file's name */
     unsigned short d_ino; /* serial number */
char d_first; /* flag for 1st time */
};
```

The file attribute field d\_attr field is a set of bits representing the following attributes.

```
_A_RDONLY
              /* Read-only file */
              /* Hidden file */
_A_HIDDEN
             /* System file */
_A_SYSTEM
             /* Volume-ID entry (only MSFT knows) */
_A_VOLID
_A_SUBDIR
             /* Subdirectory */
              /* Archive file */
_A_ARCH
```

If the \_A\_RDONLY bit is off, then the file is read/write.

The format of the d\_time field is described by the following structure (this structure is not defined in any Open Watcom header file).

```
typedef struct {
    unsigned short twosecs : 5; /* seconds / 2 */ unsigned short minutes : 6; /* minutes (0,59) */
     unsigned short hours : 5; /* hours (0,23) */
} ftime_t;
```

The format of the d\_date field is described by the following structure (this structure is not defined in any Open Watcom header file).

```
typedef struct {
   unsigned short day : 5;  /* day (1,31) */
   unsigned short month : 4;  /* month (1,12) */
   unsigned short year : 7;  /* 0 is 1980 */
} fdate_t;
```

See the sample program below for an example of the use of these structures.

More than one directory can be read at the same time using the opendir, readdir, and closedir functions.

The \_wopendir function is identical to opendir except that it accepts a wide character string argument and returns a pointer to a \_wdirent structure that can be used with the \_wreaddir and \_wclosedir functions.

The file <direct.h> contains definitions for the structure \_wdirent.

#### **Returns:**

The opendir function, if successful, returns a pointer to a structure required for subsequent calls to readdir to retrieve the file names matching the pattern specified by *dirname*. The opendir function returns NULL if *dirname* is not a valid pathname, or if there are no files matching *dirname*.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning
EACCES	Search permission is denied for a component of <i>dirname</i> or read permission is denied for <i>dirname</i> .
ENOENT	The named directory does not exist.
closedir, _dos_ _wrewinddir	_find, readdir, rewinddir, _wopendir, _wreaddir,

Example:

See Also:

To get a list of files contained in the directory \watcom\h on your default disk:

```
#include <stdio.h>
#include <direct.h>
typedef struct {
   unsigned short twosecs : 5;
                                  /* seconds / 2 */
   unsigned short minutes : 6;
    unsigned short hours : 5;
} ftime_t;
typedef struct {
   unsigned short day
                           : 5;
   unsigned short month : 4;
    unsigned short year : 7;
} fdate_t;
void main()
 {
   DIR *dirp;
    struct dirent *direntp;
    ftime_t *f_time;
    fdate_t *f_date;
    dirp = opendir( "\\watcom\\h" );
    if( dirp != NULL ) {
      for(;;) {
        direntp = readdir( dirp );
        if( direntp == NULL ) break;
        f_time = (ftime_t *)&direntp->d_time;
        f_date = (fdate_t *)&direntp->d_date;
        printf( "%-12s %d/%2.2d/%2.2d "
                "%2.2d:%2.2d:%2.2d \n",
            direntp->d_name,
            f_date->year + 1980,
            f_date->month,
            f_date->day,
            f_time->hours,
            f_time->minutes,
            f_time->twosecs * 2 );
      closedir( dirp );
    }
  }
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

### Classification: POSIX 1003.1

```
Systems:
           opendir - All, Linux, RDOS, Netware
           _wopendir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

opendir, _wopendir			

**Synopsis:** #include <io.h>

int \_open\_osfhandle( long osfhandle, int access );

**Description:** 

The \_open\_osfhandle function allocates a POSIX-level file handle and sets it to point to the operating system's internal file handle specified by osfhandle. The value returned by  $\_ \texttt{get} \_ \texttt{osfhandle}$  can be used as an argument to the  $\_ \texttt{open} \_ \texttt{osfhandle}$  function.

The access mode is established by a combination of the bits defined in the <fcntl.h> header file. The following bits may be set:

Mode	Meaning
O_RDONLY	permit the file to be only read.
O_WRONLY	permit the file to be only written.
O_RDWR	permit the file to be both read and written.
O_APPEND	causes each record that is written to be written at the end of the file.
O_CREAT	has no effect when the file indicated by <i>filename</i> already exists; otherwise, the file is created;
O_TRUNC	causes the file to be truncated to contain no data when the file exists; has no effect when the file does not exist.
O_BINARY	causes the file to be opened in binary mode which means that data will be transmitted to and from the file unchanged.
O_TEXT	causes the file to be opened in text mode which means that carriage-return characters are written before any linefeed character that is written and causes carriage-return characters to be removed when encountered during reads.
O_NOINHERIT	indicates that this file is not to be inherited by a child process.
O_EXCL	indicates that this file is to be opened for exclusive access. If the file exists and O_CREAT was also specified then the open will fail (i.e., use O_EXCL to ensure that the file does not already exist).

When neither O\_TEXT nor O\_BINARY are specified, the default value in the global variable \_fmode is used to set the file translation mode. When the program begins execution, this variable has a value of O\_TEXT.

O\_CREAT must be specified when the file does not exist and it is to be written.

When two or more manifest constants are used to form the *flags* argument, the constants are combined with the bitwise-OR operator ().

The example below demonstrates the use of the \_get\_osfhandle and \_open\_osfhandle functions. Note that the example shows how the dup2 function can be used to obtain almost identical functionality.

When the POSIX-level file handles associated with one OS file handle are closed, the first one closes successfully but the others return an error (since the first call close the file and released the OS file handle). So it is important to call close at the right time, i.e., after all I/O operations are completed to the file.

**Returns:** If successful, \_open\_osfhandle returns a POSIX-style file handle. Otherwise, it returns -1. See Also: close, \_dos\_open, dup2, fdopen, fopen, freopen, \_fsopen, \_get\_osfhandle, \_grow\_handles, \_hdopen, open, \_os\_handle, \_popen, \_sopen **Example:** #include <stdio.h> #include <stdlib.h> #include <io.h> #include <fcntl.h> void main() long os\_handle; int fh1, fh2, rc; fh1 = open( "file", O\_WRONLY | O\_CREAT | O\_TRUNC | O\_BINARY, S\_IRUSR | S\_IWUSR | S\_IRGRP | S\_IWGRP ); if(fh1 == -1) { printf( "Could not open output file\n" ); exit( EXIT\_FAILURE ); printf( "First POSIX handle %d\n", fh1 ); #if defined(USE\_DUP2) fh2 = 6;if (dup2(fh1, fh2) == -1) fh2 = -1;#else os\_handle = \_get\_osfhandle( fh1 ); printf( "OS Handle %ld\n", os\_handle ); fh2 = \_open\_osfhandle( os\_handle, O\_WRONLY | O\_BINARY ); #endif if(fh2 == -1) { printf( "Could not open with second handle\n" ); exit( EXIT\_FAILURE ); printf( "Second POSIX handle %d\n", fh2 );  $rc = write(fh2, "trash\x0d\x0a", 7);$ printf( "Write file using second handle %d\n", rc ); rc = close(fh2);printf( "Closing second handle %d\n", rc ); rc = close(fh1);printf( "Closing first handle %d\n", rc );

**Classification:** WATCOM

0	pen	osfl	han	dle
_				

**Systems:** All, Linux, Netware Synopsis: #include <io.h>
 int \_os\_handle( int handle );

**Description:** The \_os\_handle function takes a POSIX-style file handle specified by *handle*. It returns the

corresponding operating system level handle.

**Returns:** The \_os\_handle function returns the operating system handle that corresponds to the specified

POSIX-style file handle.

See Also: close, fdopen, \_get\_osfhandle, \_hdopen, open, \_open\_osfhandle

Example: #include <stdio.h>
#include <io.h>

```
void main()
{
   int handle;
   FILE *fp;

   fp = fopen( "file", "r" );
   if( fp != NULL ) {
     handle = _os_handle( fileno( fp ) );
     fclose( fp );
   }
}
```

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, Netware

```
Synopsis:
           #include <graph.h>
           void _FAR _outgtext( char _FAR *text );
```

**Description:** The \_outgtext function displays the character string indicated by the argument text. The string must be terminated by a null character ('\0').

> The string is displayed starting at the current position (see the \_moveto function) in the current color and in the currently selected font (see the \_setfont function). The current position is updated to follow the displayed text.

When no font has been previously selected with \_setfont, a default font will be used. The default font is an 8-by-8 bit-mapped font.

The graphics library can display text in three different ways.

- The \_outtext and \_outmem functions can be used in any video mode. However, this variety of text can be displayed in only one size.
- The \_grtext function displays text as a sequence of line segments, and can be drawn in different sizes, with different orientations and alignments.
- The \_outgtext function displays text in the currently selected font. Both bit-mapped and vector fonts are supported; the size and type of text depends on the fonts that are available.

**Returns:** The \_outgtext function does not return a value.

```
See Also:
           _registerfonts, _unregisterfonts, _setfont, _getfontinfo, _getgtextextent,
           _setgtextvector, _getgtextvector, _outtext, _outmem, _grtext
```

**Example:** #include <conio.h> #include <stdio.h> #include <graph.h>

main()

```
int i, n;
char buf[ 10 ];
setvideomode ( VRES16COLOR );
n = _registerfonts( "*.fon" );
for(i = 0; i < n; ++i) {
    sprintf( buf, "n%d", i );
    _setfont(buf);
    _moveto( 100, 100 );
    _outgtext( "WATCOM Graphics" );
    getch();
    _clearscreen( _GCLEARSCREEN );
_unregisterfonts();
_setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

}

_outgtext		
Systems:	DOS	

```
Synopsis:
           #include <graph.h>
           void _FAR _outmem( char _FAR *text, short length );
```

**Description:** 

The \_outmem function displays the character string indicated by the argument text. The argument length specifies the number of characters to be displayed. Unlike the \_outtext function, \_outmem will display the graphical representation of characters such as ASCII 10 and 0, instead of interpreting them as control characters.

The text is displayed using the current text color (see the \_settextcolor function), starting at the current text position (see the \_settextposition function). The text position is updated to follow the end of the displayed text.

The graphics library can display text in three different ways.

- The \_outtext and \_outmem functions can be used in any video mode. However, this variety of text can be displayed in only one size.
- The \_qrtext function displays text as a sequence of line segments, and can be drawn in different sizes, with different orientations and alignments.
- The \_outgtext function displays text in the currently selected font. Both bit-mapped and vector fonts are supported; the size and type of text depends on the fonts that are available.

**Returns:** The \_outmem function does not return a value.

```
See Also:
            _settextcolor, _settextposition, _settextwindow, _grtext, _outtext,
            _outgtext
```

**Example:** 

```
#include <conio.h>
#include <graph.h>
main()
    int i;
    char buf[ 1 ];
    _clearscreen( _GCLEARSCREEN );
    for(i = 0; i \le 255; ++i) {
        _settextposition(1 + i % 16,
                          1 + 5 * ( i / 16 ) );
        buf[0] = i;
        _outmem( buf, 1 );
    getch();
}
```

**Classification:** PC Graphics

**Systems:** DOS

_outmem			

**Synopsis:** #include <conio.h> unsigned int outp( int port, int value );

**Description:** The outp function writes one byte, determined by value, to the 80x86 hardware port whose number is

given by port.

A hardware port is used to communicate with a device. One or two bytes can be read and/or written from each port, depending upon the hardware. Consult the technical documentation for your computer to determine the port numbers for a device and the expected usage of each port for a device.

**Returns:** The value transmitted is returned.

See Also: inp, inpd, inpw, outpd, outpw

**Example:** #include <conio.h> void main() { /\* turn off speaker \*/ outp( 0x61, inp( 0x61 ) & 0xFC ); }

Classification: Intel

**Systems:** All, Linux, RDOS, Netware Synopsis: #include <conio.h>

unsigned long outpd( int port,

unsigned long value );

**Description:** 

The outpd function writes a double-word (four bytes), determined by *value*, to the 80x86 hardware part whose number is given by part

port whose number is given by port.

A hardware port is used to communicate with a device. One or two bytes can be read and/or written from each port, depending upon the hardware. Consult the technical documentation for your computer to determine the port numbers for a device and the expected usage of each port for a device.

**Returns:** The value transmitted is returned.

See Also: inp, inpd, inpw, outp, outpw

Example: #include <conio.h>

#define DEVICE 34

void main()
 {
 outpd( DEVICE, 0x12345678 );
}

Classification: Intel

Systems: DOS/32, Win386, Win32, OS/2-32, Linux, RDOS, Netware

```
Synopsis:
           #include <conio.h>
           unsigned int outpw( int port,
                                unsigned int value );
```

**Description:** The outpw function writes a word (two bytes), determined by value, to the 80x86 hardware port whose

number is given by *port*.

A hardware port is used to communicate with a device. One or two bytes can be read and/or written from each port, depending upon the hardware. Consult the technical documentation for your computer to determine the port numbers for a device and the expected usage of each port for a device.

**Returns:** The value transmitted is returned.

See Also: inp, inpd, inpw, outp, outpd

**Example:** #include <conio.h> #define DEVICE 34 void main() { outpw( DEVICE, 0x1234 );

Classification: Intel

**Systems:** All, Linux, RDOS, Netware

```
Synopsis: #include <graph.h>
    void _FAR _outtext( char _FAR *text );
```

**Description:** 

The \_outtext function displays the character string indicated by the argument *text*. The string must be terminated by a null character ('\0'). When a line-feed character ('\n') is encountered in the string, the characters following will be displayed on the next row of the screen.

The text is displayed using the current text color (see the \_settextcolor function), starting at the current text position (see the \_settextposition function). The text position is updated to follow the end of the displayed text.

The graphics library can display text in three different ways.

- 1. The \_outtext and \_outmem functions can be used in any video mode. However, this variety of text can be displayed in only one size.
- 2. The \_grtext function displays text as a sequence of line segments, and can be drawn in different sizes, with different orientations and alignments.
- 3. The \_outgtext function displays text in the currently selected font. Both bit-mapped and vector fonts are supported; the size and type of text depends on the fonts that are available.

**Returns:** The \_outtext function does not return a value.

```
See Also: __settextcolor, _settextposition, _settextwindow, _grtext, _outmem, _outgtext
```

**Example:** 

```
#include <conio.h>
#include <graph.h>

main()
{
    _setvideomode( _TEXTC80 );
    _settextposition( 10, 30 );
    _outtext( "WATCOM Graphics" );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: DOS

**Synopsis:** #include <stdio.h>

int pclose(FILE \*fp);

**Description:** The pclose function closes the pipe associated with fp and waits for the subprocess created by popen

to terminate.

**Returns:** The pclose function returns the termination status of the command language interpreter. If an error

occured, pclose returns (-1) with errno set appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

> Constant Meaning

**EINTR** The pclose function was interrupted by a signal while waiting for the child

process to terminate.

**ECHILD** The pclose function was unable to obtain the termination status of the child

process.

See Also: perror, popen

**Example:** See example provided with popen.

Classification: POSIX 1003.1

**Systems:** Linux Synopsis: #include <stdio.h>

int \_pclose( FILE \*fp );

**Description:** The  $\_pclose$  function closes the pipe associated with fp and waits for the subprocess created by

\_popen to terminate.

**Returns:** The \_pclose function returns the termination status of the command language interpreter. If an error

occured, \_pclose returns (-1) with errno set appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning

EINTR The \_pclose function was interrupted by a signal while waiting for the child

process to terminate.

**ECHILD** The \_pclose function was unable to obtain the termination status of the child

process

See Also: perror, \_pipe, \_popen

**Example:** See example provided with \_popen.

**Classification:** WATCOM

**Systems:** Win32, OS/2 1.x(all), OS/2-32, Linux

**Synopsis:** #include <stdio.h> void perror( const char \*prefix ); void \_wperror( const wchar\_t \*prefix );

**Description:** 

The perror function prints, on the file designated by stderr, the error message corresponding to the error number contained in errno. The perror function writes first the string pointed to by prefix to stderr. This is followed by a colon (":"), a space, the string returned by strerror (errno), and a newline character.

The \_wperror function is a wide character version of perror that operates with wide character strings.

**Returns:** 

The perror function returns no value. Because perror uses the fprintf function, errno can be set when an error is detected during the execution of that function.

See Also: clearerr, feof, ferror, strerror

Example:

```
#include <stdio.h>
void main()
  {
   FILE *fp;
    fp = fopen( "data.fil", "r" );
    if( fp == NULL ) {
        perror( "Unable to open file" );
  }
```

Classification: ISO C

**Systems:** 

```
perror - All, Linux, RDOS, Netware
_wperror - All, Linux
```

```
Synopsis: #include <pgchart.h>
```

## **Description:**

The \_pg\_analyzechart functions analyze either a single-series or a multi-series bar, column or line chart. These functions calculate default values for chart elements without actually displaying the chart.

The \_pg\_analyzechart function analyzes a single-series bar, column or line chart. The chart environment structure *env* is filled with default values based on the type of chart and the values of the *cat* and *values* arguments. The arguments are the same as for the \_pg\_chart function.

The \_pg\_analyzechartms function analyzes a multi-series bar, column or line chart. The chart environment structure *env* is filled with default values based on the type of chart and the values of the *cat*, *values* and *labels* arguments. The arguments are the same as for the \_pg\_chartms function.

**Returns:** The \_pg\_analyzechart functions return zero if successful; otherwise, a non-zero value is returned.

## See Also:

```
_pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
_pg_chartscatter, _pg_analyzepie, _pg_analyzescatter
```

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
           #else
                              __far
               #define _FAR
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           };
           main()
               chartenv env;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_COLUMNCHART, _PG_PLAINBARS );
               strcpy( env.maintitle.title, "Column Chart" );
               _pg_analyzechart( &env,
                                  categories, values, NUM_VALUES );
               /* use manual scaling */
               env.yaxis.autoscale = 0;
               env.yaxis.scalemin = 0.0;
               env.yaxis.scalemax = 100.0;
               env.yaxis.ticinterval = 25.0;
               _pg_chart( &env, categories, values, NUM_VALUES );
               getch();
               _setvideomode( _DEFAULTMODE );
Classification: PC Graphics
Systems:
           _pg_analyzechart - DOS
           _pg_analyzechartms - DOS
```

Synopsis: #include <pgchart.h>

**Description:** The \_pg\_analyzepie function analyzes a pie chart. This function calculates default values for chart

elements without actually displaying the chart.

The chart environment structure *env* is filled with default values based on the values of the *cat*, *values* and *explode* arguments. The arguments are the same as for the \_pg\_chartpie function.

**Returns:** The \_pg\_analyzepie function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie,

\_pg\_chartscatter, \_pg\_analyzechart, \_pg\_analyzescatter

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
           #else
                              __far
               #define _FAR
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           };
           short explode[ NUM_VALUES ] = {
               1, 0, 0, 0
           main()
               chartenv env;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_PIECHART, _PG_NOPERCENT );
               strcpy( env.maintitle.title, "Pie Chart" );
               env.legend.place = _PG_BOTTOM;
               _pg_analyzepie( &env, categories,
                                values, explode, NUM_VALUES );
               /* make legend window same width as data window */
               env.legend.autosize = 0;
               env.legend.legendwindow.x1 = env.datawindow.x1;
               env.legend.legendwindow.x2 = env.datawindow.x2;
               _pg_chartpie( &env, categories,
                             values, explode, NUM_VALUES );
               getch();
               _setvideomode( _DEFAULTMODE );
           }
```

**Systems:** DOS

_pg_analyzepie			

**Synopsis:** #include <pqchart.h>

```
short _FAR _pq_analyzescatter( chartenv _FAR *env,
                                float _FAR *x,
                                float _FAR *y, short n );
short _FAR _pg_analyzescatterms(
                      chartenv _FAR *env,
                      float _FAR *x, float _FAR *y,
                      short nseries, short n, short dim,
                      char _FAR * _FAR *labels );
```

**Description:** 

The \_pg\_analyzescatter functions analyze either a single-series or a multi-series scatter chart. These functions calculate default values for chart elements without actually displaying the chart.

The \_pg\_analyzescatter function analyzes a single-series scatter chart. The chart environment structure env is filled with default values based on the values of the x and y arguments. The arguments are the same as for the \_pg\_chartscatter function.

The \_pg\_analyzescatterms function analyzes a multi-series scatter chart. The chart environment structure *env* is filled with default values based on the values of the x, y and *labels* arguments. The arguments are the same as for the \_pg\_chartscatterms function.

**Returns:** 

The \_pg\_analyzescatter functions return zero if successful; otherwise, a non-zero value is returned.

See Also:

```
_pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
_pg_chartscatter, _pg_analyzechart, _pg_analyzepie
```

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
                              __far
               #define _FAR
           #endif
           #define NUM_VALUES 4
           #define NUM_SERIES 2
           char _FAR *labels[ NUM_SERIES ] = {
               "Jan", "Feb"
           };
           float x[ NUM_SERIES ][ NUM_VALUES ] = {
               5, 15, 30, 40, 10, 20, 30, 45
           };
           float y[ NUM_SERIES ][ NUM_VALUES ] = {
               10, 15, 30, 45, 40, 30, 15, 5
           };
           main()
           {
               chartenv env;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_SCATTERCHART, _PG_POINTANDLINE );
               strcpy( env.maintitle.title, "Scatter Chart" );
               _pg_analyzescatterms( &env, x, y, NUM_SERIES,
                                      NUM_VALUES, NUM_VALUES, labels );
               /* display x-axis labels with 2 decimal places */
               env.xaxis.autoscale = 0;
               env.xaxis.ticdecimals = 2;
               _pg_chartscatterms( &env, x, y, NUM_SERIES,
                                    NUM_VALUES, NUM_VALUES, labels );
               getch();
               _setvideomode( _DEFAULTMODE );
Classification: PC Graphics
Systems:
           _pg_analyzescatter - DOS
           _pg_analyzescatterms - DOS
```

_pg_analyzescatter Functions

**Synopsis:** 

```
#include <pqchart.h>
short _FAR _pg_chart( chartenv _FAR *env,
                      char _FAR * _FAR *cat,
                      float _FAR *values, short n );
short _FAR _pg_chartms( chartenv _FAR *env,
                        char _FAR * _FAR *cat,
                        float _FAR *values, short nseries,
                        short n, short dim,
                        char _FAR * _FAR *labels );
```

**Description:** 

The \_pg\_chart functions display either a single-series or a multi-series bar, column or line chart. The type of chart displayed and other chart options are contained in the env argument. The argument cat is an array of strings. These strings describe the categories against which the data in the values array is charted.

The \_pg\_chart function displays a bar, column or line chart from the single series of data contained in the *values* array. The argument *n* specifies the number of values to chart.

The \_pq\_chartms function displays a multi-series bar, column or line chart. The argument nseries specifies the number of series of data to chart. The argument values is assumed to be a two-dimensional array defined as follows:

```
float values[ nseries ][ dim ];
```

The number of values used from each series is given by the argument n, where n is less than or equal to dim. The argument labels is an array of strings. These strings describe each of the series and are used in the chart legend.

**Returns:** The \_pg\_chart functions return zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chartpie, \_pg\_chartscatter, \_pg\_analyzechart, \_pg\_analyzepie, \_pg\_analyzescatter

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
```

#if defined ( \_\_\_386\_\_\_ )

```
#define _FAR
#else
    #define _FAR
                   __far
#endif
#define NUM_VALUES 4
char _FAR *categories[ NUM_VALUES ] = {
    "Jan", "Feb", "Mar", "Apr"
};
float values[ NUM_VALUES ] = {
    20, 45, 30, 25
};
main()
    chartenv env;
    _setvideomode( _VRES16COLOR );
```

strcpy( env.maintitle.title, "Column Chart" ); \_pg\_chart( &env, categories, values, NUM\_VALUES );

\_PG\_COLUMNCHART, \_PG\_PLAINBARS );

produces the following:

}

getch();

\_pg\_initchart();

\_pg\_defaultchart( &env,

\_setvideomode( \_DEFAULTMODE );



Systems: \_pg\_chart - DOS

\_pg\_chartms - DOS

**Synopsis:** #include <pqchart.h>

```
short _FAR _pg_chartpie( chartenv _FAR *env,
                         char _FAR * _FAR *cat,
                         float _FAR *values,
                         short _FAR *explode, short n );
```

**Description:** The \_pg\_chartpie function displays a pie chart. The chart is displayed using the options specified in the env argument.

> The pie chart is created from the data contained in the *values* array. The argument n specifies the number of values to chart.

The argument cat is an array of strings. These strings describe each of the pie slices and are used in the chart legend. The argument explode is an array of values corresponding to each of the pie slices. For each non-zero element in the array, the corresponding pie slice is drawn "exploded", or slightly offset from the rest of the pie.

**Returns:** The \_pg\_chartpie function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartscatter, \_pg\_analyzechart, \_pg\_analyzepie, \_pg\_analyzescatter

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
               #define _FAR
                              __far
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           short explode[ NUM_VALUES ] = {
               1, 0, 0, 0
           main()
           {
               chartenv env;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_PIECHART, _PG_NOPERCENT );
               strcpy( env.maintitle.title, "Pie Chart" );
               _pg_chartpie( &env, categories,
                             values, explode, NUM_VALUES );
               getch();
               _setvideomode( _DEFAULTMODE );
           }
```

produces the following:



DOS **Systems:** 

Synopsis: #include <pgchart.h>

**Description:** 

The \_pg\_chartscatter functions display either a single-series or a multi-series scatter chart. The chart is displayed using the options specified in the *env* argument.

The pg\_chartscatter function displays a scatter chart from the single series of data contained in the arrays x and y. The argument n specifies the number of values to chart.

The \_pg\_chartscatterms function displays a multi-series scatter chart. The argument *nseries* specifies the number of series of data to chart. The arguments *x* and *y* are assumed to be two-dimensional arrays defined as follows:

```
float x[ nseries ][ dim ];
```

The number of values used from each series is given by the argument n, where n is less than or equal to dim. The argument labels is an array of strings. These strings describe each of the series and are used in the chart legend.

**Returns:** The \_pg\_chartscatter functions return zero if successful; otherwise, a non-zero value is returned.

See Also:

```
_pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
_pg_analyzechart, _pg_analyzepie, _pg_analyzescatter
```

## **Example:** #include <graph.h> #include <pgchart.h> #include <string.h> #include <conio.h> #if defined ( \_\_\_386\_\_\_ ) #define \_FAR #else \_\_far #define \_FAR #endif #define NUM\_VALUES 4 #define NUM\_SERIES 2 char \_FAR \*labels[ NUM\_SERIES ] = { "Jan", "Feb" }; float x[ NUM\_SERIES ][ NUM\_VALUES ] = { 5, 15, 30, 40, 10, 20, 30, 45 }; float y[ NUM\_SERIES ][ NUM\_VALUES ] = { 10, 15, 30, 45, 40, 30, 15, 5 }; main() { chartenv env; \_setvideomode( \_VRES16COLOR ); \_pg\_initchart(); \_pg\_defaultchart( &env, \_PG\_SCATTERCHART, \_PG\_POINTANDLINE ); strcpy( env.maintitle.title, "Scatter Chart" ); \_pg\_chartscatterms( &env, x, y, NUM\_SERIES, NUM\_VALUES, NUM\_VALUES, labels ); getch(); \_setvideomode( \_DEFAULTMODE );

}

produces the following:



Systems: \_pg\_chartscatter - DOS

\_pg\_chartscatterms - DOS

**Synopsis:** #include <pqchart.h>

```
short _FAR _pg_defaultchart( chartenv _FAR *env,
```

short type, short style );

**Description:** The \_pg\_defaultchart function initializes the chart structure env to contain default values before a

> chart is drawn. All values in the chart structure are initialized, including blanking of all titles. The chart type in the structure is initialized to the value type, and the chart style is initialized to style.

The argument *type* can have one of the following values:

\_PG\_BARCHART Bar chart (horizontal bars)

\_PG\_COLUMNCHART Column chart (vertical bars)

\_PG\_LINECHART Line chart

\_PG\_SCATTERCHART Scatter chart

\_PG\_PIECHART Pie chart

Each type of chart can be drawn in one of two styles. For each chart type the argument style can have one of the following values:

Туре	Style 1	Style 2
Bar	_PG_PLAINBARS	_PG_STACKEDBARS
Column	_PG_PLAINBARS	_PG_STACKEDBARS
Line	_PG_POINTANDLINE	_PG_POINTONLY
Scatter	_PG_POINTANDLINE	_PG_POINTONLY
Pie	PG PERCENT	PG NOPERCENT

For single-series bar and column charts, the chart style is ignored. The "plain" (clustered) and "stacked" styles only apply when there is more than one series of data. The "percent" style for pie charts causes percentages to be displayed beside each of the pie slices.

**Returns:** The \_pg\_defaultchart function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_initchart, \_pg\_chart, \_pg\_chartpie, \_pg\_chartscatter

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
           #else
               #define _FAR
                              __far
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           };
           main()
               chartenv env;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_COLUMNCHART, _PG_PLAINBARS );
               strcpy( env.maintitle.title, "Column Chart" );
               _pg_chart( &env, categories, values, NUM_VALUES );
               getch();
               _setvideomode( _DEFAULTMODE );
           }
```

Systems: DOS

```
Synopsis:
            #include <pqchart.h>
            short _FAR _pg_getchardef( short ch,
                                            unsigned char _FAR *def );
            The _pg_getchardef function retrieves the current bit-map definition for the character ch. The
Description:
            bit-map is placed in the array def. The current font must be an 8-by-8 bit-mapped font.
Returns:
            The _pg_getchardef function returns zero if successful; otherwise, a non-zero value is returned.
See Also:
            _pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
            _pg_chartscatter, _pg_setchardef
Example:
            #include <graph.h>
            #include <pgchart.h>
            #include <string.h>
            #include <conio.h>
            #define NUM_VALUES 4
            float x[ NUM_VALUES ] = {
                 5, 25, 45, 65
            };
            float y[ NUM_VALUES ] = {
                 5, 45, 25, 65
            };
            char diamond[ 8 ] = {
                 0x10, 0x28, 0x44, 0x82, 0x44, 0x28, 0x10, 0x00
            } ;
            main()
            {
                 chartenv env;
                 char old_def[ 8 ];
                 _setvideomode( _VRES16COLOR );
                 _pg_initchart();
                 _pg_defaultchart( &env,
                                      _PG_SCATTERCHART, _PG_POINTANDLINE );
                 strcpy( env.maintitle.title, "Scatter Chart" );
                 /* change asterisk character to diamond */
                _pg_getchardef( '*', old_def );
_pg_setchardef( '*', diamond );
                _pg_chartscatter( &env, x, y, NUM_VALUES );
                 _pg_setchardef( '*', old_def );
                 getch();
                 _setvideomode( _DEFAULTMODE );
            }
```

**Systems:** DOS

**Classification:** PC Graphics

_pg_getchardef				

**Synopsis:** #include <pqchart.h>

short \_FAR \_pg\_getpalette( paletteentry \_FAR \*pal );

The \_pg\_getpalette function retrieves the internal palette of the presentation graphics system. **Description:** 

The palette controls the colors, line styles, fill patterns and plot characters used to display each series of

data in a chart.

The argument pal is an array of palette structures that will contain the palette. Each element of the

palette is a structure containing the following fields:

color color used to display series

style line style used for line and scatter charts

fill fill pattern used to fill interior of bar and pie sections

plotchar character plotted on line and scatter charts

**Returns:** The \_pg\_getpalette function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie,

\_pg\_chartscatter, \_pg\_setpalette, \_pg\_resetpalette

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
           #else
                              __far
               #define _FAR
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           };
           char bricks[ 8 ] = {
               0xff, 0x80, 0x80, 0x80, 0xff, 0x08, 0x08, 0x08
           main()
           {
               chartenv env;
               palettetype pal;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_COLUMNCHART, _PG_PLAINBARS );
               strcpy( env.maintitle.title, "Column Chart" );
               /* get default palette and change 1st entry */
               _pg_getpalette( &pal );
               pal[ 1 ].color = 12;
               memcpy( pal[ 1 ].fill, bricks, 8 );
               /* use new palette */
               _pg_setpalette( &pal );
               _pg_chart( &env, categories, values, NUM_VALUES );
               /* reset palette to default */
               _pg_resetpalette();
               getch();
               _setvideomode( _DEFAULTMODE );
```

Systems: DOS

		_pg_getpale	tte

## \_pg\_getstyleset

Synopsis: #include <pgchart.h>

void \_FAR \_pg\_getstyleset( unsigned short \_FAR \*style );

**Description:** The \_pg\_getstyleset function retrieves the internal style-set of the presentation graphics system.

The style-set is a set of line styles used for drawing window borders and grid-lines. The argument style

is an array that will contain the style-set.

**Returns:** The \_pg\_getstyleset function does not return a value.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie,

\_pg\_chartscatter, \_pg\_setstyleset, \_pg\_resetstyleset

**Example:** 

```
#include <graph.h>
#include <pgchart.h>
#include <string.h>
#include <conio.h>
#if defined ( ___386___ )
    #define _FAR
#else
    #define _FAR
                    __far
#endif
#define NUM_VALUES 4
char _FAR *categories[ NUM_VALUES ] = {
    "Jan", "Feb", "Mar", "Apr"
};
float values[ NUM_VALUES ] = {
    20, 45, 30, 25
main()
    chartenv env;
    styleset style;
    _setvideomode( _VRES16COLOR );
    _pg_initchart();
    _pg_defaultchart( &env,
                      _PG_COLUMNCHART, _PG_PLAINBARS );
    strcpy( env.maintitle.title, "Column Chart" );
    /* turn on yaxis grid, and use style 2 */
    env.yaxis.grid = 1;
    env.yaxis.gridstyle = 2;
    /* get default style-set and change entry 2 */
    _pg_getstyleset( &style );
    style[2] = 0x8888;
    /* use new style-set */
    _pg_setstyleset( &style );
    _pg_chart( &env, categories, values, NUM_VALUES );
    /* reset style-set to default */
    _pg_resetstyleset();
    getch();
    _setvideomode( _DEFAULTMODE );
```

**Systems:** DOS

_pg_getstyleset			

```
Synopsis:
           #include <pqchart.h>
           short _FAR _pg_hlabelchart( chartenv _FAR *env,
                                         short x, short y,
                                         short color,
                                         char _FAR *label );
```

**Description:** The \_pg\_hlabelchart function displays the text string label on the chart described by the env chart structure. The string is displayed horizontally starting at the point (x, y), relative to the upper left corner of the chart. The *color* specifies the palette color used to display the string.

**Returns:** The \_pg\_hlabelchart function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie, \_pg\_chartscatter, \_pg\_vlabelchart

#include <graph.h>

**Example:** 

```
#include <pgchart.h>
#include <string.h>
#include <conio.h>
#if defined ( __386__ )
    #define _FAR
#else
                   __far
    #define _FAR
#endif
#define NUM_VALUES 4
char _FAR *categories[ NUM_VALUES ] = {
    "Jan", "Feb", "Mar", "Apr"
};
float values[ NUM_VALUES ] = {
    20, 45, 30, 25
};
main()
    chartenv env;
   _setvideomode( _VRES16COLOR );
   _pg_initchart();
   _pg_defaultchart( &env,
                       _PG_COLUMNCHART, _PG_PLAINBARS );
    strcpy( env.maintitle.title, "Column Chart" );
    _pg_chart( &env, categories, values, NUM_VALUES );
    _pg_hlabelchart( &env, 64, 32, 1, "Horizontal label" );
    _pg_vlabelchart(&env, 48, 32, 1, "Vertical label");
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

**Systems:** DOS

_pg_hlabelchart			

```
Synopsis:
           #include <pqchart.h>
           short _FAR _pg_initchart( void );
```

**Description:** The \_pq\_initchart function initializes the presentation graphics system. This includes initializing the internal palette and style-set used when drawing charts. This function must be called before any of the other presentation graphics functions.

> The initialization of the presentation graphics system requires that a valid graphics mode has been selected. For this reason the \_setvideomode function must be called before \_pq\_initchart is called. If a font has been selected (with the \_setfont function), that font will be used when text is displayed in a chart. Font selection should also be done before initializing the presentation graphics system.

**Returns:** The \_pg\_initchart function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_chart, \_pg\_chartpie, \_pg\_chartscatter, \_setvideomode, \_setfont, \_registerfonts

**Example:** 

```
#include <graph.h>
#include <pgchart.h>
#include <string.h>
#include <conio.h>
#if defined ( ___386___ )
    #define _FAR
#else
    #define _FAR
                    far
#endif
#define NUM_VALUES 4
char _FAR *categories[ NUM_VALUES ] = {
    "Jan", "Feb", "Mar", "Apr"
};
float values[ NUM_VALUES ] = {
    20, 45, 30, 25
};
main()
    chartenv env;
    _setvideomode( _VRES16COLOR );
    _pg_initchart();
    _pg_defaultchart( &env,
                       _PG_COLUMNCHART, _PG_PLAINBARS );
    strcpy( env.maintitle.title, "Column Chart" );
    _pg_chart( &env, categories, values, NUM_VALUES );
    getch();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

_pg_initc	hart			
Systems:	DOS			

**Synopsis:** #include <pgchart.h>

short \_FAR \_pg\_resetpalette( void );

**Description:** The \_pg\_resetpalette function resets the internal palette of the presentation graphics system to

default values. The palette controls the colors, line styles, fill patterns and plot characters used to display each series of data in a chart. The default palette chosen is dependent on the current video

mode.

**Returns:** The \_pg\_resetpalette function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie,

\_pg\_chartscatter, \_pg\_getpalette, \_pg\_setpalette

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
                              __far
               #define _FAR
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           };
           char bricks[ 8 ] = {
               0xff, 0x80, 0x80, 0x80, 0xff, 0x08, 0x08, 0x08
           main()
           {
               chartenv env;
               palettetype pal;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_COLUMNCHART, _PG_PLAINBARS );
               strcpy( env.maintitle.title, "Column Chart" );
               /* get default palette and change 1st entry */
               _pg_getpalette( &pal );
               pal[ 1 ].color = 12;
               memcpy( pal[ 1 ].fill, bricks, 8 );
               /* use new palette */
               _pg_setpalette( &pal );
               _pg_chart( &env, categories, values, NUM_VALUES );
               /* reset palette to default */
               _pg_resetpalette();
               getch();
               _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

Systems: DOS

		_pg_resetpalette

```
Synopsis:
            #include <pqchart.h>
            void _FAR _pg_resetstyleset( void );
Description:
           The _pg_resetstyleset function resets the internal style-set of the presentation graphics system
            to default values. The style-set is a set of line styles used for drawing window borders and grid-lines.
Returns:
           The _pg_resetstyleset function does not return a value.
See Also:
           _pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
           _pg_chartscatter, _pg_getstyleset, _pg_setstyleset
Example:
            #include <graph.h>
            #include <pgchart.h>
            #include <string.h>
            #include <conio.h>
            #if defined ( ___386___ )
                #define _FAR
            #else
                #define _FAR
                                ___far
            #endif
            #define NUM_VALUES 4
            char _FAR *categories[ NUM_VALUES ] = {
                "Jan", "Feb", "Mar", "Apr"
            };
            float values[ NUM_VALUES ] = {
                20, 45, 30, 25
            };
           main()
                chartenv env;
                styleset style;
                _setvideomode( _VRES16COLOR );
                _pg_initchart();
                _pg_defaultchart( &env,
                                    _PG_COLUMNCHART, _PG_PLAINBARS );
                strcpy( env.maintitle.title, "Column Chart" );
                /* turn on yaxis grid, and use style 2 */
                env.yaxis.grid = 1;
                env.yaxis.gridstyle = 2;
                /* get default style-set and change entry 2 */
                _pg_getstyleset( &style );
                style[2] = 0x8888;
                /* use new style-set */
                _pg_setstyleset( &style );
                _pg_chart( &env, categories, values, NUM_VALUES );
                /* reset style-set to default */
                _pg_resetstyleset();
                getch();
                _setvideomode( _DEFAULTMODE );
            }
```

Classification: PC Graphics

**Systems:** DOS

```
Synopsis:
            #include <pqchart.h>
            short _FAR _pg_setchardef( short ch,
                                           unsigned char _FAR *def );
Description:
            The _pg_setchardef function sets the current bit-map definition for the character ch. The bit-map
            is contained in the array def. The current font must be an 8-by-8 bit-mapped font.
Returns:
            The _pg_setchardef function returns zero if successful; otherwise, a non-zero value is returned.
See Also:
            _pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
            _pg_chartscatter, _pg_getchardef
Example:
            #include <graph.h>
            #include <pgchart.h>
            #include <string.h>
            #include <conio.h>
            #define NUM_VALUES 4
            float x[ NUM_VALUES ] = {
                 5, 25, 45, 65
            };
            float y[ NUM_VALUES ] = {
                 5, 45, 25, 65
            };
            char diamond[ 8 ] = {
                 0x10, 0x28, 0x44, 0x82, 0x44, 0x28, 0x10, 0x00
            } ;
            main()
            {
                 chartenv env;
                char old_def[ 8 ];
                _setvideomode( _VRES16COLOR );
                _pg_initchart();
                _pg_defaultchart( &env,
                                     _PG_SCATTERCHART, _PG_POINTANDLINE );
                 strcpy( env.maintitle.title, "Scatter Chart" );
                 /* change asterisk character to diamond */
                _{\rm pg\_getchardef(\ '*',\ old\_def\ );}
                _pg_setchardef( '*', diamond );
                _pg_chartscatter( &env, x, y, NUM_VALUES );
                _pg_setchardef( '*', old_def );
                getch();
                 _setvideomode( _DEFAULTMODE );
            }
Classification: PC Graphics
```

DOS

**Systems:** 

_pg_setchardet

# \_pg\_setpalette

Synopsis: #include <pgchart.h>

short \_FAR \_pg\_setpalette( paletteentry \_FAR \*pal );

**Description:** The \_pg\_setpalette function sets the internal palette of the presentation graphics system. The

palette controls the colors, line styles, fill patterns and plot characters used to display each series of data

in a chart.

The argument pal is an array of palette structures containing the new palette. Each element of the

palette is a structure containing the following fields:

color used to display series

style line style used for line and scatter charts

fill pattern used to fill interior of bar and pie sections

plotchar character plotted on line and scatter charts

**Returns:** The \_pg\_setpalette function returns zero if successful; otherwise, a non-zero value is returned.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie,

\_pg\_chartscatter, \_pg\_getpalette, \_pg\_resetpalette

```
Example:
           #include <graph.h>
           #include <pgchart.h>
           #include <string.h>
           #include <conio.h>
           #if defined ( ___386___ )
               #define _FAR
           #else
                              __far
               #define _FAR
           #endif
           #define NUM_VALUES 4
           char _FAR *categories[ NUM_VALUES ] = {
               "Jan", "Feb", "Mar", "Apr"
           };
           float values[ NUM_VALUES ] = {
               20, 45, 30, 25
           };
           char bricks[ 8 ] = {
               0xff, 0x80, 0x80, 0x80, 0xff, 0x08, 0x08, 0x08
           main()
               chartenv env;
               palettetype pal;
               _setvideomode( _VRES16COLOR );
               _pg_initchart();
               _pg_defaultchart( &env,
                                  _PG_COLUMNCHART, _PG_PLAINBARS );
               strcpy( env.maintitle.title, "Column Chart" );
               /* get default palette and change 1st entry */
               _pg_getpalette( &pal );
               pal[ 1 ].color = 12;
               memcpy( pal[ 1 ].fill, bricks, 8 );
               /* use new palette */
               _pg_setpalette( &pal );
               _pg_chart( &env, categories, values, NUM_VALUES );
               /* reset palette to default */
               _pg_resetpalette();
               getch();
               _setvideomode( _DEFAULTMODE );
```

**Classification:** PC Graphics

**Systems:** DOS

_pg_setpalette			

**Synopsis:** #include <pgchart.h>

void \_FAR \_pg\_setstyleset( unsigned short \_FAR \*style );

**Description:** The \_pg\_setstyleset function retrieves the internal style-set of the presentation graphics system.

The style-set is a set of line styles used for drawing window borders and grid-lines. The argument style

is an array containing the new style-set.

**Returns:** The \_pg\_setstyleset function does not return a value.

See Also: \_pg\_defaultchart, \_pg\_initchart, \_pg\_chart, \_pg\_chartpie,

\_pg\_chartscatter, \_pg\_getstyleset, \_pg\_resetstyleset

**Example:** 

```
#include <graph.h>
#include <pgchart.h>
#include <string.h>
#include <conio.h>
#if defined ( ___386___ )
    #define _FAR
#else
    #define _FAR
                    __far
#endif
#define NUM_VALUES 4
char _FAR *categories[ NUM_VALUES ] = {
    "Jan", "Feb", "Mar", "Apr"
};
float values[ NUM_VALUES ] = {
    20, 45, 30, 25
main()
    chartenv env;
    styleset style;
    _setvideomode( _VRES16COLOR );
    _pg_initchart();
    _pg_defaultchart( &env,
                      _PG_COLUMNCHART, _PG_PLAINBARS );
    strcpy( env.maintitle.title, "Column Chart" );
    /* turn on yaxis grid, and use style 2 */
    env.yaxis.grid = 1;
    env.yaxis.gridstyle = 2;
    /* get default style-set and change entry 2 */
    _pg_getstyleset( &style );
    style[2] = 0x8888;
    /* use new style-set */
    _pg_setstyleset( &style );
    _pg_chart( &env, categories, values, NUM_VALUES );
    /* reset style-set to default */
    _pg_resetstyleset();
    getch();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

Systems: DOS

		_pg_setstyleset

```
Synopsis:
            #include <pqchart.h>
            short _FAR _pg_vlabelchart( chartenv _FAR *env,
                                             short x, short y,
                                             short color,
                                             char _FAR *label );
Description:
            The _pg_vlabelchart function displays the text string label on the chart described by the env chart
            structure. The string is displayed vertically starting at the point (x, y), relative to the upper left
            corner of the chart. The color specifies the palette color used to display the string.
Returns:
            The _pg_vlabelchart function returns zero if successful; otherwise, a non-zero value is returned.
See Also:
            _pg_defaultchart, _pg_initchart, _pg_chart, _pg_chartpie,
            _pg_chartscatter, _pg_hlabelchart
Example:
            #include <graph.h>
            #include <pgchart.h>
            #include <string.h>
            #include <conio.h>
            #if defined ( ___386___ )
                 #define _FAR
            #else
                 #define _FAR ___far
            #endif
            #define NUM_VALUES 4
            char _FAR *categories[ NUM_VALUES ] = {
                 "Jan", "Feb", "Mar", "Apr"
            };
            float values[ NUM_VALUES ] = {
                 20, 45, 30, 25
            };
            main()
            {
                 chartenv env;
                _setvideomode( _VRES16COLOR );
                _pg_initchart();
                 _pg_defaultchart( &env,
                                      _PG_COLUMNCHART, _PG_PLAINBARS );
                 strcpy( env.maintitle.title, "Column Chart" );
                 _pg_chart( &env, categories, values, NUM_VALUES );
                 _pg_hlabelchart( &env, 64, 32, 1, "Horizontal label" );
                 _pg_vlabelchart( &env, 48, 32, 1, "Vertical label" );
                 getch();
                 _setvideomode( _DEFAULTMODE );
            }
Classification: PC Graphics
```

DOS

**Systems:** 

	_pg_vlabelchart

### **Synopsis:**

#### **Description:**

The \_pie functions draw pie-shaped wedges. The \_pie function uses the view coordinate system. The \_pie\_w and \_pie\_wxy functions use the window coordinate system.

The pie wedges are drawn by drawing an elliptical arc (in the way described for the \_arc functions) and then joining the center of the rectangle that contains the ellipse to the two endpoints of the arc.

The elliptical arc is drawn with its center at the center of the rectangle established by the points (x1,y1) and (x2,y2). The arc is a segment of the ellipse drawn within this bounding rectangle. The arc starts at the point on this ellipse that intersects the vector from the centre of the ellipse to the point (x3,y3). The arc ends at the point on this ellipse that intersects the vector from the centre of the ellipse to the point (x4,y4). The arc is drawn in a counter-clockwise direction with the current plot action using the current color and the current line style.

The following picture illustrates the way in which the bounding rectangle and the vectors specifying the start and end points are defined.



When the coordinates (x1, y1) and (x2, y2) establish a line or a point (this happens when one or more of the x-coordinates or y-coordinates are equal), nothing is drawn.

The argument fill determines whether the figure is filled in or has only its outline drawn. The argument can have one of two values:

GFILLINTERIOR

fill the interior by writing pixels with the current plot action using the current

color and the current fill mask

\_GBORDER

leave the interior unchanged; draw the outline of the figure with the current

plot action using the current color and line style

**Returns:** 

The \_pie functions return a non-zero value when the figure was successfully drawn; otherwise, zero is returned.


See Also:

```
_arc, _ellipse, _setcolor, _setfillmask, _setlinestyle, _setplotaction
```

**Example:** 

```
#include <conio.h>
#include <graph.h>
main()
    _setvideomode( _VRES16COLOR );
   _pie( _GBORDER, 120, 90, 520, 390,
                    140, 20, 190, 460);
    getch();
    _setvideomode( _DEFAULTMODE );
```

produces the following:



# \_pie Functions

Classification: PC Graphics

Systems: \_pie - DOS

\_pie\_w - DOS \_pie\_wxy - DOS **Synopsis:** #include <io.h>

int \_pipe( int \*phandles, unsigned psize, int textmode );

**Description:** 

The \_pipe function creates a pipe (an unnamed FIFO) and places a file descriptor for the read end of the pipe in *phandles[0]* and a file descriptor for the write end of the pipe in *phandles[1]*. Their integer values are the two lowest available at the time of the \_pipe function call. The O\_NONBLOCK flag is cleared for both file descriptors. (The call can be used to set the O\_NONBLOCK flag.)

Data can be written to file descriptor *phandles[1]* and read from file descriptor *phandles[0]*. A read on file descriptor *phandles[0]* returns the data written to *phandles[1]* on a first-in-first-out (FIFO) basis.

This function is typically used to connect together standard utilities to act as filters, passing the write end of the pipe to the data producing process as its STDOUT\_FILENO and the read end of the pipe to the data consuming process as its STDIN\_FILENO. (either via the traditional fork/dup2/exec or the more efficient spawn calls).

If successful, \_pipe marks for update the st\_ftime, st\_ctime, st\_atime and st\_mtime fields of the pipe for updating.

**Returns:** 

The \_pipe function returns zero on success. Otherwise, (-1) is returned and errno is set to indicate the error.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected. If any of the following conditions occur, the \_pipe function shall return (-1) and set errno to the corresponding value:

Constant	Meaning
<b>EMFILE</b>	The calling process does not have at least 2 unused file descriptors available.
ENFILE	The number of simultaneously open files in the system would exceed the configured limit.
ENOSPC	There is insufficient space available to allocate the pipe buffer.
EROFS	The pipe pathname space is a read-only filesystem.

See Also:

open, \_pclose, perror, \_popen, read, write

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
#include <stddef.h>
#include <fcntl.h>
#include <io.h>
#include cess.h>
static int handles[2] = { 0, 0 };
static int pid;
```

```
create_pipe()
    if( _pipe( (int *)&handles, 2048, _O_BINARY ) == -1 ) {
        perror( "create_pipe" );
        exit( EXIT_FAILURE );
}
create_child( char *name )
    char buff[10];
    itoa( handles[0], buff, 10 );
    pid = spawnl( P_NOWAIT, name,
                  "_pipe", buff, NULL );
    close( handles[0] );
    if(pid == -1) {
        perror( "create_child" );
        close( handles[1] );
        exit( EXIT_FAILURE );
    }
}
fill_pipe()
    int i;
    int rc;
    for( i = 1; i <= 10; i++ ) {
        printf( "Child, what is 5 times dn, i);
        rc = write( handles[1], &i, sizeof( int ) );
        if( rc < sizeof( int ) ) {</pre>
            perror( "fill_pipe" );
            close( handles[1] );
            exit( EXIT_FAILURE );
        }
    /* indicate that we are done */
    i = -1;
    write( handles[1], &i, sizeof( int ) );
    close( handles[1] );
}
```

```
empty_pipe( int in_pipe )
    int i;
    int amt;
    for(;;) {
        amt = read( in_pipe, &i, sizeof( int ) );
        if (amt != sizeof(int) || i == -1)
        printf( "Parent, 5 times %d is %d\n", i, 5*i );
    if ( amt == -1 ) {
        perror( "empty_pipe" );
        exit( EXIT_FAILURE );
    close( in_pipe );
}
void main( int argc, char *argv[] )
    if( argc <= 1 ) {
        /* we are the spawning process */
        create_pipe();
        create_child( argv[0] );
        fill_pipe();
    } else {
        /* we are the spawned process */
        empty_pipe( atoi( argv[1] ) );
    exit( EXIT_SUCCESS );
}
produces the following:
Child, what is 5 times 1
Child, what is 5 times 2
Parent, 5 times 1 is 5
Parent, 5 times 2 is 10
Child, what is 5 times 3
Child, what is 5 times 4
Parent, 5 times 3 is 15
Parent, 5 times 4 is 20
Child, what is 5 times 5
Child, what is 5 times 6
Parent, 5 times 5 is 25
Parent, 5 times 6 is 30
Child, what is 5 times 7
Child, what is 5 times 8
Parent, 5 times 7 is 35
Parent, 5 times 8 is 40
Child, what is 5 times 9
Child, what is 5 times 10
Parent, 5 times 9 is 45
Parent, 5 times 10 is 50
```

**Classification:** WATCOM

**Systems:** Win32, OS/2 1.x(all), OS/2-32

_pipe			

# **Synopsis:**

```
#include <graph.h>
short _FAR _polygon( short fill, short numpts,
                     struct xycoord _FAR *points );
short _FAR _polygon_w( short fill, short numpts,
                       double _FAR *points );
short _FAR _polygon_wxy( short fill, short numpts,
                         struct _wxycoord _FAR *points );
```

# **Description:**

The \_polygon functions draw polygons. The \_polygon function uses the view coordinate system. The \_polygon\_w and \_polygon\_wxy functions use the window coordinate system.

The polygon is defined as containing *numpts* points whose coordinates are given in the array *points*.

The argument *fill* determines whether the polygon is filled in or has only its outline drawn. The argument can have one of two values:

\_GFILLINTERIOR

fill the interior by writing pixels with the current plot action using the current

color and the current fill mask

\_GBORDER

leave the interior unchanged; draw the outline of the figure with the current plot action using the current color and line style

**Returns:** 

The \_polygon functions return a non-zero value when the polygon was successfully drawn; otherwise, zero is returned.

See Also:

\_setcolor, \_setfillmask, \_setlinestyle, \_setplotaction

# **Example:**

```
#include <conio.h>
#include <graph.h>
struct xycoord points[ 5 ] = {
    319, 140, 224, 209, 261, 320,
    378, 320, 415, 209
};
main()
    _setvideomode( _VRES16COLOR );
    _polygon( _GBORDER, 5, points );
    getch();
    _setvideomode( _DEFAULTMODE );
```

produces the following:



Classification: PC Graphics

**Systems:** 

\_polygon - DOS \_polygon\_w - DOS \_polygon\_wxy - DOS **Synopsis:** #include <stdio.h>

FILE \*popen( const char \*command, const char \*mode );

**Description:** 

The popen function executes the command specified by command and creates a pipe between the calling process and the executed command.

Depending on the *mode* argument, the stream pointer returned may be used to read from or write to the pipe.

The executed command has an environment the same as its parents. The command will be started as follows:

```
execl("/bin/sh", "sh", "-c", command, (char *) NULL);
```

The *mode* argument to popen is a string that specifies an I/O mode for the pipe.

Mode	Meaning
'' <u>r</u> ''	The calling process will read from the standard output of the child process using the stream pointer returned by popen
''w''	The calling process will write to the standard input of the child process using the stream pointer returned by popen

A stream opened by popen should be closed by the pclose function.

**Returns:** 

The popen function returns a non-NULL stream pointer upon successful completion. If popen is unable to create either the pipe or the subprocess, a NULL stream pointer is returned and errno is set appropriately.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning

**EINVAL** The *mode* argument is invalid.

popen may also set errno values as described by the,, and exec1 functions.

See Also: pclose, exec...

**Example:** 

```
/*
 * Executes the 'ls' command and prints all
 * its output preceded by an arrow.
 */
#include <stdio.h>
int main()
{
   FILE *fp;
   char readbuf[256];

   fp = popen("ls", "r");
   if(fp == NULL) {
      printf("Failed to open pipe\n");
      exit(1);
   }

   while(fgets(readbuf, 256, fp))
      printf("-> %s", readbuf);

   pclose(fp);
   return 0;
}
```

Classification: POSIX 1003.1

**Systems:** Linux

**Synopsis:** #include <stdio.h>

```
FILE *_popen( const char *command, const char *mode );
FILE *_wpopen( const wchar_t *command, const wchar_t *mode );
```

**Description:** 

The popen function executes the command specified by command and creates a pipe between the calling process and the executed command.

Depending on the *mode* argument, the stream pointer returned may be used to read from or write to the pipe.

The executed command has an environment the same as its parents. The command will be started as follows: spawnl(<shell\_path>, <shell>, "-c", command, (char \*)NULL);

where <shell\_path> is an unspecified path for the shell utility and <shell> is one of "command.com" (DOS, Windows 95) or "cmd.exe" (Windows NT/2000, OS/2).

The *mode* argument to \_popen is a string that specifies an I/O mode for the pipe.

Mode	Meaning
''r''	The calling process will read from the standard output of the child process using the stream pointer returned by _popen
''w''	The calling process will write to the standard input of the child process using the stream pointer returned by popen

The letter "t" may be added to any of the above modes to indicate that the file is (or must be) a text file (i.e., CR/LF pairs are converted to newline characters).

The letter "b" may be added to any of the above modes to indicate that the file is (or must be) a binary file (an ISO C requirement for portability to systems that make a distinction between text and binary

When default file translation is specified (i.e., no "t" or "b" is specified), the value of the global variable \_fmode establishes whether the file is to treated as a binary or a text file. Unless this value is changed by the program, the default will be text mode.

A stream opened by \_popen should be closed by the \_pclose function.

**Returns:** 

The \_popen function returns a non-NULL stream pointer upon successful completion. If \_popen is unable to create either the pipe or the subprocess, a NULL stream pointer is returned and errno is set appropriately.

**Errors:** 

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

Constant Meaning

**EINVAL** The *mode* argument is invalid.

\_popen may also set errno values as described by the \_pipe and spawnl functions.

See Also:

\_grow\_handles, \_pclose, perror, \_pipe

```
Example:
            * Executes a given program, converting all
            * output to upper case.
            */
           #include <stdio.h>
           #include <stdlib.h>
           #include <string.h>
           #include <ctype.h>
           char
                 buffer[256];
           void main( int argc, char **argv )
               int i;
               int c;
               FILE *f;
               for( i = 1; i < argc; i++ ) {
                 strcat( buffer, argv[i] );
                 strcat( buffer, " " );
               if( ( f = popen(buffer, "r")) == NULL) {
                 perror( "_popen" );
                 exit(1);
               while ( ( c = getc(f) ) != EOF ) {
                 if( islower( c ) )
                     c = toupper( c );
                 putchar( c );
               _pclose( f );
Classification: WATCOM
Systems:
           _popen - Win32, OS/2 1.x(all), OS/2-32, Linux
           _wpopen - Win32, OS/2 1.x(all), OS/2-32
```

**Synopsis:** #include <math.h>

double pow( double x, double y);

**Description:** The pow function computes x raised to the power y. A domain error occurs if x is zero and y is less than

or equal to 0, or if x is negative and y is not an integer. A range error may occur.

**Returns:** The pow function returns the value of x raised to the power y. When the argument is outside the

> permissible range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using

the stderr stream.

See Also: exp, log, sqrt

**Example:** #include <stdio.h> #include <math.h>

```
void main()
  {
    printf( "%f\n", pow( 1.5, 2.5 ) );
```

produces the following:

2.755676

Classification: ISO C

**Systems:** Math

```
Synopsis: #include <stdio.h>
    int printf( const char *format, ... );
    #include <wchar.h>
    int wprintf( const wchar_t *format, ... );
```

**Safer C:** The Safer C Library extension provides the printf\_s function which is a safer alternative to printf.

**Description:** The printf function writes output to the file designated by stdout under control of the argument *format*. The *format* string is described below.

The wprintf function is a wide character version of printf. It accepts a wide character string argument for *format* and produces wide character output.

**Returns:** The printf function returns the number of characters written, or a negative value if an output error occurred.

The wprintf function returns the number of wide characters written, or a negative value if an output error occurred. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: \_\_bprintf, cprintf, fprintf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vswprintf, vswprintf

f1 = 23.4500 f2 = 3.14E+003 x = 0x0001db i = -1

**Format Control String:** The format control string consists of *ordinary characters*, that are written exactly as they occur in the format string, and *conversion specifiers*, that cause argument values to be written as they are encountered during the processing of the format string. An ordinary character in the format string is any character, other than a percent character (%), that is not part of a conversion specifier. A conversion specifier is a sequence of characters in the format string that begins with a percent character (%) and is followed, in sequence, by the following:

- zero or more format control flags that can modify the final effect of the format directive;
- an optional decimal integer, or an asterisk character ('\*'), that specifies a minimum field width to be reserved for the formatted item:
- an optional precision specification in the form of a period character (.), followed by an optional decimal integer or an asterisk character (\*);
- an optional type length specification: one of "hh", "h", "l", "ll", "j", "z", "t", "L", "I64", "w", "N" or "W" and
- a character that specifies the type of conversion to be performed: one of the characters "bcCdeEfFgGinopsSuxX".

The valid format control flags are:

- "-" the formatted item is left-justified within the field; normally, items are right-justified
- "+" a signed, positive object will always start with a plus character (+); normally, only negative items begin with a sign
- a signed, positive object will always start with a space character; if both "+" and " " are specified, "+" overrides " "
- "#" an alternate conversion form is used:
  - for "b" (unsigned binary) and "o" (unsigned octal) conversions, the precision is incremented, if necessary, so that the first digit is "0".
  - for "x" or "X" (unsigned hexadecimal) conversions, a non-zero value is prepended with "0x" or "0X" respectively.
  - for "e", "E", "f", "F", "g" or "G" (any floating-point) conversions, the result always contains a decimal-point character, even if no digits follow it; normally, a decimal-point character appears in the result only if there is a digit to follow it.
  - in addition to the preceding, for "g" or "G" conversions, trailing zeros are not removed from the result.

If no field width is specified, or if the value that is given is less than the number of characters in the converted value (subject to any precision value), a field of sufficient width to contain the converted value is used. If the converted value has fewer characters than are specified by the field width, the value is padded on the left (or right, subject to the left-justification flag) with spaces or zero characters ("0"). If the field width begins with "0" and no precision is specified, the value is padded with zeros; otherwise the value is padded with spaces. If the field width is "\*", a value of type int from the argument list is used (before a precision argument or a conversion argument) as the minimum field width. A negative field width value is interpreted as a left-justification flag, followed by a positive field width.

As with the field width specifier, a precision specifier of "\*" causes a value of type int from the argument list to be used as the precision specifier. If no precision value is given, a precision of 0 is used. The precision value affects the following conversions:

- For "b", "d", "i", "o", "u", "x" and "X" (integer) conversions, the precision specifies the minimum number of digits to appear.
- For "e", "E", "f" and "F" (fixed-precision, floating-point) conversions, the precision specifies the number of digits to appear after the decimal-point character.
- For "g" and "G" (variable-precision, floating-point) conversions, the precision specifies the maximum number of significant digits to appear.
- For "s" or "S" (string) conversions, the precision specifies the maximum number of characters to appear.

A type length specifier affects the conversion as follows:

- "hh" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) format conversion to treat the argument as a signed char or unsigned char argument. Note that, although the argument may have been promoted to an int as part of the function call, the value is converted to the smaller type before it is formatted.
- "hh" causes an "n" (converted length assignment) operation to assign the converted length to an object of type signed char.
- "h" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) format conversion to treat the argument as a short int or unsigned short int argument. Note that, although the argument may have been promoted to an int as part of the function call, the value is converted to the smaller type before it is formatted.
- "h" causes an "f" format conversion to interpret a long argument as a fixed-point number consisting of a 16-bit signed integer part and a 16-bit unsigned fractional part. The integer part is in the high 16 bits and the fractional part is in the low 16 bits.

```
struct fixpt {
    unsigned short fraction; /* Intel architecture! */
        signed short integral;
};

struct fixpt foo1 =
    { 0x8000, 1234 }; /* represents 1234.5 */
struct fixpt foo2 =
    { 0x8000, -1 }; /* represents -0.5 (-1+.5) */
```

The value is formatted with the same rules as for floating-point values. This is a Open Watcom extension.

- "h" causes an "n" (converted length assignment) operation to assign the converted length to an object of type short int.
- "h" causes an "s" operation to treat the argument string as an ASCII character string composed of 8-bit characters.

For printf and related byte input/output functions, this specifier is redundant. For wprintf and related wide character input/output functions, this specifier is required if the argument string is to be treated as an 8-bit ASCII character string; otherwise it will be treated as a wide character string.

```
printf( "%s%d", "Num=", 12345 );
wprintf( L"%hs%d", "Num=", 12345 );
```

- "l" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) conversion to process a long int or unsigned long int argument.
- "I" causes an "n" (converted length assignment) operation to assign the converted length to an object of type long int.
- "l" or "w" cause an "s" operation to treat the argument string as a wide character string (a string composed of characters of type wchar\_t).

For printf and related byte input/output functions, this specifier is required if the argument string is to be treated as a wide character string; otherwise it will be treated as an 8-bit ASCII character string. For wprintf and related wide character input/output functions, this specifier is redundant.

```
printf( "%ls%d", L"Num=", 12345 );
wprintf( L"%s%d", L"Num=", 12345 );
```

- "ll" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) conversion to process a long long or unsigned long long argument (e.g., %lld).
- "ll" causes an "n" (converted length assignment) operation to assign the converted length to an object of type long long int.
- "j" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) conversion to process an intmax\_t or uintmax targument.
- "j" causes an "n" (converted length assignment) operation to assign the converted length to an object of type intmax\_t.
- "z" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) conversion to process a size\_t or the corresponding signed integer type argument.
- "z" causes an "n" (converted length assignment) operation to assign the converted length to an object of signed integer type corresponding to size\_t.
- "t" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) conversion to process a ptrdiff\_t or the corresponding unsigned integer type argument.
- "t" causes an "n" (converted length assignment) operation to assign the converted length to an object of type ptrdiff\_t.
- "I64" causes a "b", "d", "i", "o", "u", "x" or "X" (integer) conversion to process an \_\_\_int64 or unsigned \_\_int64 argument (e.g., %I64d).
- "L" causes an "e", "E", "f", "F", "g", "G" (double) conversion to process a long double argument.
- "W" causes the pointer associated with "n", "p", "s" conversions to be treated as a far pointer.
- "N" causes the pointer associated with "n", "p", "s" conversions to be treated as a near pointer.

The valid conversion type specifiers are:

- **b** An argument of type int is converted to an unsigned binary notation and written to the output stream. The default precision is 1, but if more digits are required, leading zeros are added.
- c An argument of type int is converted to a value of type char and the corresponding ASCII character code is written to the output stream.
- C An argument of type wchar\_t is converted to a multibyte character and written to the output stream.
- d, i An argument of type int is converted to a signed decimal notation and written to the output stream. The default precision is 1, but if more digits are required, leading zeros are added.
- e, E An argument of type double is converted to a decimal notation in the form [-]d.dde[+|-]ddd similar to FORTRAN exponential (E) notation. The leading sign appears (subject to the format control flags) only if the argument is negative. If the argument is non-zero, the digit before the decimal-point character is non-zero. The precision is used as the number of digits following the decimal-point character. If the precision is not specified, a default precision of six is used. If the precision is 0, the decimal-point character is suppressed. The value is rounded to the appropriate number of digits. For "E" conversions, the exponent begins with the character "E" rather than "e". The exponent sign and a three-digit number (that indicates the power of ten by which the decimal fraction is multiplied) are always produced.
- f, F An argument of type double is converted to a decimal notation in the form [-]ddd.ddd similar to FORTRAN fixed-point (F) notation. The leading sign appears (subject to the format control flags) only if the argument is negative. The precision is used as the number of digits following the decimal-point character. If the precision is not specified, a default precision of six is used. If the precision is 0, the decimal-point character is suppressed, otherwise, at least one digit is produced before the decimal-point character. The value is rounded to the appropriate number of digits.
- g, G An argument of type double is converted using either the "f" or "e" (or "F" or "E", for a "G" conversion) style of conversion depending on the value of the argument. In either case, the precision specifies the number of significant digits that are contained in the result. "e" style conversion is used only if the exponent from such a conversion would be less than -4 or greater than the precision. Trailing zeros are removed from the result and a decimal-point character only appears if it is followed by a digit.
- n The number of characters that have been written to the output stream is assigned to the integer pointed to by the argument. No output is produced.
- An argument of type int is converted to an unsigned octal notation and written to the output stream. The default precision is 1, but if more digits are required, leading zeros are added.
- p, P An argument of type void \* is converted to a value of type int and the value is formatted as for a hexadecimal ("x") conversion.
- S Characters from the string specified by an argument of type char \* or wchar\_t \*, up to, but not including the terminating null character ('\0'), are written to the output stream. If a precision is specified, no more than that many characters (bytes) are written (e.g., %.7s)
  - For printf this specifier refers to an ASCII character string unless the "l" or "w" modifiers are used to indicate a wide character string.

For wprintf, this specifier refers to a wide character string unless the "h" modifier is used to indicate an ASCII character string. \*.

- Characters from the string specified by an argument of type wchar\_t \*, up to, but not including the terminating null wide character (L'\0'), are converted to multibyte characters and written to the output stream. If a precision is specified, no more than that many characters (bytes) are written (e.g., %.7S)
- An argument of type int is converted to an unsigned decimal notation and written to the output stream. The default precision is 1, but if more digits are required, leading zeros are added.
- x, X An argument of type int is converted to an unsigned hexadecimal notation and written to the output stream. The default precision is 1, but if more digits are required, leading zeros are added. Hexadecimal notation uses the digits "0" through "9" and the characters "a" through "f" or "A" through "F" for "x" or "X" conversions respectively, as the hexadecimal digits. Subject to the alternate-form control flag, "0x" or "0X" is prepended to the output.

Any other conversion type specifier character, including another percent character (%), is written to the output stream with no special interpretation.

The arguments must correspond with the conversion type specifiers, left to right in the string; otherwise, indeterminate results will occur.

If the value corresponding to a floating-point specifier is infinity, or not a number (NaN), then the output will be "inf" or "-inf" for infinity, and "nan" or "-nan" for NaN's. If the conversion specifier is an uppercase character (ie. "E", "F", or "G"), the output will be uppercase as well ("INF", "NAN"), otherwise the output will be lowercase as noted above.

The pointer size specification ("N" or "W") is only effective on platforms that use a segmented memory model, although it is always recognized.

For example, a specifier of the form "%8.\*f" will define a field to be at least 8 characters wide, and will get the next argument for the precision to be used in the conversion.

**Classification:** ISO C (except for N, W pointer size modifiers and b, I64 specifiers) wprintf is ISO C95

**Systems:** printf - All, Linux, RDOS, Netware wprintf - All, Linux

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
int printf_s( const char * restrict format, ... );
#include <wchar.h>
int wprintf_s( const wchar_t * restrict format, ... );
```

# **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and printf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

The *format* argument shall not be a null pointer. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by *format*. Any argument to printf\_s corresponding to a %s specifier shall not be a null pointer.

If there is a runtime-constraint violation, the printf\_s function does not attempt to produce further output, and it is unspecified to what extent printf\_s produced output before discovering the runtime-constraint violation.

# **Description:**

The printf\_s function is equivalent to the printf function except for the explicit runtime-constraints listed above.

The wprintf\_s function is a wide character version of printf\_s. It accepts a wide character string argument for *format* and produces wide character output.

#### **Returns:**

The printf\_s function returns the number of characters written, or a negative value if an output error or runtime-constraint violation occurred.

The wprintf\_s function returns the number of wide characters written, or a negative value if an output error or runtime-constraint violation occurred.

#### See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

# **Example:**

f1 = 23.4500 f2 = 3.14E+003 x = 0x0001db i = -1

Saturday, April 18, 1987

**Classification:** TR 24731

**Systems:** printf\_s - All, Linux, RDOS, Netware

wprintf\_s - All, Linux

**Synopsis:** 

```
#include <stdio.h>
int putc( int c, FILE *fp );
#include <stdio.h>
#include <wchar.h>
wint_t putwc( wint_t c, FILE *fp );
```

**Description:** 

The putc function is equivalent to fputc, except it may be implemented as a macro. The putc function writes the character specified by the argument c to the output stream designated by fp.

The putwo function is identical to putc except that it converts the wide character specified by c to a multibyte character and writes it to the output stream.

**Returns:** 

The putc function returns the character written or, if a write error occurs, the error indicator is set and putc returns EOF.

The putwc function returns the wide character written or, if a write error occurs, the error indicator is set and putwc returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fopen, fputc, fputchar, fputs, putchar, puts, ferror

**Example:** 

```
void main()
{
   FILE *fp;
   int c;

   fp = fopen( "file", "r" );
   if( fp != NULL ) {
     while( (c = fgetc( fp )) != EOF )
        putc( c, stdout );
     fclose( fp );
   }
}
```

#include <stdio.h>

Classification: ISO C

**Systems:** 

putc - All, Linux, RDOS, Netware
putwc - All, Linux

```
Synopsis:
           #include <conio.h>
           int putch( int c );
```

**Description:** The putch function writes the character specified by the argument c to the console.

**Returns:** The putch function returns the character written.

See Also: getch, getche, kbhit, ungetch

```
Example:
           #include <conio.h>
           #include <stdio.h>
           void main()
             {
               FILE *fp;
               int c;
               fp = fopen( "file", "r" );
               if ( fp != NULL ) {
                 while( (c = fgetc( fp )) != EOF )
                   putch( c );
               fclose( fp );
```

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware **Synopsis:** 

```
#include <stdio.h>
int putchar( int c );
#include <wchar.h>
wint_t putwchar( wint_t c );
```

**Description:** 

The putchar function writes the character specified by the argument c to the output stream stdout.

The function is equivalent to

```
fputc( c, stdout );
```

The putwchar function is identical to putchar except that it converts the wide character specified by c to a multibyte character and writes it to the output stream.

**Returns:** 

The putchar function returns the character written or, if a write error occurs, the error indicator is set and putchar returns EOF.

The putwchar function returns the wide character written or, if a write error occurs, the error indicator is set and putwchar returns WEOF.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

fopen, fputc, fputchar, fputs, putc, puts, ferror

**Example:** 

```
#include <stdio.h>
```

```
void main()
{
   FILE *fp;
   int c;

   fp = fopen( "file", "r" );
   c = fgetc( fp );
   while( c != EOF ) {
      putchar( c );
      c = fgetc( fp );
   }
   fclose( fp );
}
```

**Classification:** ISO C

putwchar is ISO C95

**Systems:** 

```
putchar - All, Linux, Netware
putwchar - All, Linux
```

		putchar, putwchar

Synopsis: #include <stdlib.h>

```
int putenv( const char *env_name );
int _putenv( const char *env_name );
int _wputenv( const wchar_t *env_name );
```

**Description:** 

The environment list consists of a number of environment names, each of which has a value associated with it. Entries can be added to the environment list with the DOS set command or with the putenv function. All entries in the environment list can be displayed by using the DOS set command with no arguments. A program can obtain the value for an environment variable by using the getenv function.

When the value of *env\_name* has the format

```
env_name=value
```

an environment name and its value is added to the environment list. When the value of *env\_name* has the format

```
env_name=
```

the environment name and value is removed from the environment list.

The matching is case-insensitive; all lowercase letters are treated as if they were in upper case.

The space into which environment names and their values are placed is limited. Consequently, the putenv function can fail when there is insufficient space remaining to store an additional value.

The \_putenv function is identical to putenv. Use \_putenv for ANSI naming conventions.

The \_wputenv function is a wide character version of putenv the *env\_name* argument to \_wputenv is a wide character string.

putenv and \_wputenv affect only the environment that is local to the current process; you cannot use them to modify the command-level environment. That is, these functions operate only on data structures accessible to the run-time library and not on the environment "segment" created for a process by the operating system. When the current process terminates, the environment reverts to the level of the calling process (in most cases, the operating-system level). However, the modified environment can be passed to any new processes created by \_spawn, \_exec, or system, and these new processes get any new items added by putenv and \_wputenv.

With regard to environment entries, observe the following cautions:

- Do not change an environment entry directly; instead, use putenv or \_wputenv to change it. To modify the return value of putenv or \_wputenv without affecting the environment table, use strdup or strcpy to make a copy of the string.
- If the argument *env\_name* is not a literal string, you should duplicate the string, since putenv does not copy the value; for example,

```
putenv( strdup( buffer ) );
```

• Never free a pointer to an environment entry, because the environment variable will then point to freed space. A similar problem can occur if you pass putenv or \_wputenv a pointer to a local variable, then exit the function in which the variable is declared.

putenv use the global variable environ to access the \_wputenv use wenviron. putenv and \_wputenv may change the value of \_environ and \_wenviron, thus putenv and \_wputenv to global variables, see environ, wenviron.

To assign a string to a variable and place it in the environment list:

```
C>SET INCLUDE=C:\WATCOM\H
```

To see what variables are in the environment list, and their current assignments:

```
C>SET
COMSPEC=C:\COMMAND.COM
PATH=C:\;C:\WATCOM
INCLUDE=C:\WATCOM\H
C>
```

**Returns:** The putenv function returns zero when it is successfully executed and returns -1 when it fails.

**Errors:** When an error has occurred, erroc contains a value indicating the type of error that has been detected.

> **ENOMEM** Not enough memory to allocate a new environment string.

See Also: exec..., \_wexec..., clearenv, getenv, getenv\_s, \_searchenv, setenv, unsetenv, \_wgetenv,\_wputenv,\_wsearchenv,\_wsetenv,\_wunsetenv,spawn...,\_wspawn..., system, \_wsystem

**Example:** The following gets the string currently assigned to INCLUDE and displays it, assigns a new value to it, gets and displays it, and then removes the environment name and value.

```
#include <stdio.h>
#include <stdlib.h>
void main()
    char *path;
    path = getenv( "INCLUDE" );
    if( path != NULL )
        printf( "INCLUDE=%s\n", path );
    if( putenv( "INCLUDE=mylib; yourlib" ) != 0 )
       printf( "putenv failed" );
    path = getenv( "INCLUDE" );
    if ( path != NULL )
        printf( "INCLUDE=%s\n", path );
    if( putenv( "INCLUDE=" ) != 0 )
        printf( "putenv failed" );
  }
```

produces the following:

```
INCLUDE=C:\WATCOM\H
INCLUDE=mylib; yourlib
```

#### Classification: POSIX 1003.1

\_putenv conforms to ANSI naming conventions

# putenv, \_putenv, \_wputenv

**Systems:** 

putenv - All, Linux, RDOS
\_putenv - All, Linux, RDOS

\_wputenv - All, Linux

**Synopsis:** #include <graph.h>

```
void _FAR _putimage( short x, short y,
                     char _HUGE *image, short mode );
void _FAR _putimage_w( double x, double y,
                       char _HUGE *image, short mode );
```

**Description:** 

The \_putimage functions display the screen image indicated by the argument *image*. The \_putimage function uses the view coordinate system. The \_putimage\_w function uses the window coordinate system.

The image is displayed upon the screen with its top left corner located at the point with coordinates (x,y) . The image was previously saved using the  $\_\texttt{getimage}$  functions. The image is displayed in a rectangle whose size is the size of the rectangular image saved by the \_qetimage functions.

The image can be displayed in a number of ways, depending upon the value of the *mode* argument. This argument can have the following values:

\_GPSET replace the rectangle on the screen by the saved image

\_GPRESET replace the rectangle on the screen with the pixel values of the saved image

inverted; this produces a negative image

\_GAND produce a new image on the screen by ANDing together the pixel values

from the screen with those from the saved image

\_GOR produce a new image on the screen by ORing together the pixel values from

the screen with those from the saved image

**GXOR** produce a new image on the screen by exclusive ORing together the pixel

> values from the screen with those from the saved image; the original screen is restored by two successive calls to the \_putimage function with this value,

providing an efficient method to produce animated effects

**Returns:** The \_putimage functions do not return a value.

See Also: \_getimage, \_imagesize

```
Example:
           #include <conio.h>
           #include <graph.h>
           #include <malloc.h>
           main()
               char *buf;
               int y;
               _setvideomode( _VRES16COLOR );
               _ellipse( _GFILLINTERIOR, 100, 100, 200, 200 );
               buf = (char*) malloc(
                              _imagesize( 100, 100, 201, 201 ) );
               if( buf != NULL ) {
                   _getimage( 100, 100, 201, 201, buf );
                   _putimage( 260, 200, buf, _GPSET );
                   _putimage( 420, 100, buf, _GPSET );
                   for (y = 100; y < 300;)
                       _putimage( 420, y, buf, _GXOR );
                       y += 20;
                       _putimage( 420, y, buf, _GXOR );
                   free ( buf );
               getch();
               _setvideomode( _DEFAULTMODE );
Classification: PC Graphics
Systems:
           _putimage - DOS
           _putimage_w - DOS
```

**Synopsis:** 

```
#include <stdio.h>
int puts ( const char *buf );
#include <stdio.h>
int _putws( const wchar_t *bufs );
```

**Description:** 

The puts function writes the character string pointed to by buf to the output stream designated by stdout, and appends a new-line character to the output. The terminating null character is not written.

The \_putws function is identical to puts except that it converts the wide character string specified by buf to a multibyte character string and writes it to the output stream.

**Returns:** 

The puts function returns EOF if an error occurs; otherwise, it returns a non-negative value (the number of characters written including the new-line character). The \_putws function returns EOF if a write or encoding error occurs; otherwise, it returns a non-negative value (the number of characters written including the new-line character). When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: fopen, fputc, fputchar, fputs, putc, putchar, ferror

#include <stdio.h>

**Example:** 

```
void main()
 {
    FILE *fp;
    char buffer[80];
    fp = freopen( "file", "r", stdin );
    while( gets( buffer ) != NULL ) {
        puts( buffer );
    fclose( fp );
```

Classification: ISO C

**Systems:** 

```
puts - All, Linux, RDOS, Netware
_putws - All, Linux
```

Synopsis: #include <stdio.h>
 int \_putw( int binint, FILE \*fp );

**Description:** The \_putw function writes a binary value of type *int* to the current position of the stream *fp*. \_putw does not affect the alignment of items in the stream, nor does it assume any special alignment.

\_putw is provided primarily for compatibility with previous libraries. Portability problems may occur with \_putw because the size of an *int* and the ordering of bytes within an *int* differ across systems.

**Returns:** The \_putw function returns the value written or, if a write error occurs, the error indicator is set and \_putw returns EOF. Since EOF is a legitimate value to write to *fp*, use ferror to verify that an error has occurred.

See Also: ferror, fopen, fputc, fputchar, fputs, putc, putchar, puts

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

```
Synopsis:
           #include <stdlib.h>
           void qsort ( void *base,
                        size_t num,
                        size_t width,
                        int (*compar) (const void *,
                                         const void *) );
```

Safer C: The Safer C Library extension provides the qsort\_s function which is a safer alternative to qsort.

**Description:** 

The qsort function sorts an array of *num* elements, which is pointed to by *base*, using a modified version of Sedgewick's Quicksort algorithm. Each element in the array is width bytes in size. The comparison function pointed to by *compar* is called with two arguments that point to elements in the array. The comparison function shall return an integer less than, equal to, or greater than zero if the first argument is less than, equal to, or greater than the second argument.

The version of the Quicksort algorithm that is employed was proposed by Jon Louis Bentley and M. Douglas McIlroy in the article "Engineering a sort function" published in Software -- Practice and Experience, 23(11):1249-1265, November 1993.

**Returns:** The qsort function returns no value.

See Also: qsort\_s, bsearch, bsearch\_s

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
char *CharVect[] = { "last", "middle", "first" };
int compare( const void *op1, const void *op2 )
    const char **p1 = (const char **) op1;
    const char **p2 = (const char **) op2;
    return( strcmp( *p1, *p2 ) );
void main()
    qsort( CharVect, sizeof(CharVect)/sizeof(char *),
          sizeof(char *), compare );
    printf( "%s %s %s\n",
            CharVect[0], CharVect[1], CharVect[2] );
}
produces the following:
```

first last middle

Classification: ISO C

All, Linux, RDOS, Netware **Systems:** 

qsort			

**Synopsis:** 

**Constraints:** 

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and qsort\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *nmemb* nor *size* shall be greater than RSIZE\_MAX. If *nmemb* is not equal to zero, then neither *base* nor *compar* shall be a null pointer. If there is a runtime-constraint violation, the qsort\_s function does not sort the array.

**Description:** 

The qsort\_s function sorts an array of *nmemb* objects, the initial element of which is pointed to by *base*. The size of each object is specified by *size*. The contents of the array are sorted into ascending order according to a comparison function pointed to by *compar*, which is called with three arguments. The first two point to the objects being compared. The function shall return an integer less than, equal to, or greater than zero if the first argument is considered to be respectively less than, equal to, or greater than the second. The third argument to the comparison function is the *context* argument passed to qsort\_s The sole use of *context* by qsort\_s is to pass it to the comparison function. If two elements compare as equal, their relative order in the resulting sorted array is unspecified.

**Returns:** 

The qsort\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

qsort, bsearch, bsearch\_s

**Example:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
char *CharVect[] = { "last", "middle", "first" };
int compare( const void *op1, const void *op2, void *context )
    const char **p1 = (const char **) op1;
   const char **p2 = (const char **) op2;
   return( strcmp( *p1, *p2 ) );
}
void main()
   void * context = NULL;
    qsort_s( CharVect, sizeof(CharVect)/sizeof(char *),
          sizeof(char *), compare, context );
    printf( "%s %s %s\n",
            CharVect[0], CharVect[1], CharVect[2] );
}
```

produces the following:

# qsort\_s

first last middle

**Classification:** TR 24731

Systems: All, Linux, RDOS, Netware

```
Synopsis: #include <signal.h>
    int raise( int condition );
```

**Description:** The raise function signals the exceptional condition indicated by the *condition* argument. The possible conditions are defined in the <signal.h> header file and are documented with the signal

function. The signal function can be used to specify the action which is to take place when such a

condition occurs.

**Returns:** The raise function returns zero when the condition is successfully raised and a non-zero value otherwise. There may be no return of control following the function call if the action for that condition

otherwise. There may be no return of control following the function call if the action for that condition is to terminate the program or to transfer control using the longjmp function.

See Also: signal

Example:

```
* This program waits until a SIGINT signal
 * is received.
 */
#include <stdio.h>
#include <signal.h>
sig_atomic_t signal_count;
sig_atomic_t signal_number;
static void alarm_handler( int signum )
    ++signal_count;
    signal_number = signum;
void main()
    unsigned long i;
    signal_count = 0;
    signal_number = 0;
    signal( SIGINT, alarm_handler );
    printf("Signal will be auto-raised on iteration "
           "10000 or hit CTRL-C.\n");
    printf("Iteration:
                            ");
    for(i = 0; i < 100000; ++i)
     printf("\b\b\b\b\**d", 5, i);
      if( i == 10000 ) raise(SIGINT);
      if( signal_count > 0 ) break;
```

Classification: ISO C

Systems: All, Linux, RDOS, Netware

```
Synopsis: #include <stdlib.h>
int rand( void );
```

**Description:** The rand function computes a sequence of pseudo-random integers in the range 0 to RAND\_MAX

(32767). The sequence can be started at different values by calling the srand function.

**Returns:** The rand function returns a pseudo-random integer.

See Also: srand

Example: #include <stdio.h>
#include <stdlib.h>

void main()
{
 int i;

 for( i=1; i < 10; ++i ) {
 printf( "%d\n", rand() );
 }
}</pre>

**Classification:** ISO C

Systems: All, Linux, RDOS, Netware

### **Synopsis:**

# **Description:**

The read function reads data at the operating system level. The number of bytes transmitted is given by *len* and the data is transmitted starting at the address specified by *buffer*.

The readv function performs the same action as read, but places the data into the iovent buffers specified by the members of the iov array: iov[0], iov[1], ..., iov[iovent-1].

The handle value is returned by the open function. The access mode must have included either O\_RDONLY or O\_RDWR when the open function was invoked. The data is read starting at the current file position for the file in question. This file position can be determined with the \_tell function and can be set with the lseek function.

When O\_BINARY is included in the access mode, the data is transmitted unchanged. When O\_TEXT is included in the access mode, the data is transmitted with the extra carriage return character removed before each linefeed character encountered in the original data.

The \_read function is identical to read. Use \_read for ANSI naming conventions.

#### **Returns:**

The read function returns the number of bytes of data transmitted from the file to the buffer (this does not include any carriage-return characters that were removed during the transmission). Normally, this is the number given by the *len* argument. When the end of the file is encountered before the read completes, the return value will be less than the number of bytes requested.

A value of -1 is returned when an input/output error is detected. When an error has occurred, error contains a value indicating the type of error that has been detected.

See Also:

close, creat, fread, open, write

# **Example:**

# Classification: POSIX 1003.1

\_read conforms to ANSI naming conventions

readv is WATCOM

Systems: read - All, RDOS, Netware

\_read - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

readv - Linux, Netware

```
Synopsis: #include <direct.h>
    struct dirent *readdir( DIR *dirp );
    struct _wdirent *_wreaddir( WDIR *dirp );
```

**Description:** 

The readdir function obtains information about the next matching file name from the argument *dirp*. The argument *dirp* is the value returned from the opendir function. The readdir function can be called repeatedly to obtain the list of file names contained in the directory specified by the pathname given to opendir. The function closedir must be called to close the directory and free the memory allocated by opendir.

The file <direct.h> contains definitions for the structure dirent.

The file attribute field d\_attr field is a set of bits representing the following attributes.

If the \_A\_RDONLY bit is off, then the file is read/write.

The format of the d\_time field is described by the following structure (this structure is not defined in any Open Watcom header file).

```
typedef struct {
   unsigned short twosecs : 5;    /* seconds / 2  */
   unsigned short minutes : 6;    /* minutes (0,59) */
   unsigned short hours : 5;    /* hours (0,23)  */
} ftime_t;
```

The format of the d\_date field is described by the following structure (this structure is not defined in any Open Watcom header file).

```
typedef struct {
   unsigned short day : 5;  /* day (1,31) */
   unsigned short month : 4;  /* month (1,12) */
   unsigned short year : 7;  /* 0 is 1980 */
} fdate_t;
```

See the sample program below for an example of the use of these structures.

The \_wreaddir function is identical to readdir except that it reads a directory of wide character filenames.

The file <direct.h> contains definitions for the structure \_wdirent.

```
struct _wdirent {
                                   /* disk transfer area
   char
                 d_dta[21];
                 d_attr;
                                   /* file's attribute
   char
                                   /* file's time
   unsigned short d_time;
   unsigned short d_date;
                                   /* file's date
                 d_size;
                                   /* file's size
   long
   wchar_t
                 d_name[NAME_MAX+1]; /* file's name
   unsigned short d_ino;
                                   /* serial number(not used)
                                   /* flag for 1st time
   char
                 d_first;
};
```

**Returns:** 

When successful, readdir returns a pointer to an object of type *struct dirent*. When an error occurs, readdir returns the value NULL and errno is set to indicate the error. When the end of the directory is encountered, readdir returns the value NULL and errno is unchanged.

When successful, \_wreaddir returns a pointer to an object of type *struct \_wdirent*. When an error occurs, \_wreaddir returns the value NULL and errno is set to indicate the error. When the end of the directory is encountered, \_wreaddir returns the value NULL and errno is unchanged.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

**EBADF** The argument *dirp* does not refer to an open directory stream.

See Also:

```
closedir, _dos_find..., opendir, rewinddir, _wopendir, _wreaddir,
_wrewinddir
```

**Example:** 

To get a list of files contained in the directory \watcom\h on your default disk:

```
#include <stdio.h>
#include <direct.h>
typedef struct {
                                  /* seconds / 2 */
   unsigned short twosecs : 5;
   unsigned short minutes : 6;
    unsigned short hours : 5;
} ftime_t;
typedef struct {
   unsigned short day
   unsigned short month : 4;
    unsigned short year : 7;
} fdate_t;
void main()
 {
   DIR *dirp;
    struct dirent *direntp;
    ftime_t *f_time;
    fdate_t *f_date;
    dirp = opendir( "\\watcom\\h" );
    if( dirp != NULL ) {
      for(;;) {
        direntp = readdir( dirp );
        if( direntp == NULL ) break;
        f_time = (ftime_t *)&direntp->d_time;
        f_date = (fdate_t *)&direntp->d_date;
        printf( "%-12s %d/%2.2d/%2.2d "
                "%2.2d:%2.2d:%2.2d \n",
            direntp->d_name,
            f_date->year + 1980,
            f_date->month,
            f_date->day,
            f_time->hours,
            f_time->minutes,
            f_time->twosecs * 2 );
      closedir( dirp );
  }
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

# Classification: POSIX 1003.1

```
Systems: readdir - All, Linux, RDOS, Netware
_wreaddir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

		readdir, _	wreaddir

Synopsis: #include <unistd.h>

**Description:** The readlink function places the contents of the symbolic link named by path into the buffer pointed

to by buf, which has a size of bufsiz. The contents of the returned symbolic link don't include a NULL terminator. Its length must be determined from the stat structure returned by the 1stat function, or

by the return value of the readlink call.

If readlink is successful, up to bufsiz bytes from the contents of the symbolic link are placed in buf.

**Returns:** On success, the number of bytes placed in the buffer *buf*. Otherwise, -1 is returned, and errno is set to

indicate the error.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant Meaning
 EACCES Search permission is denied for a component of the path prefix.
 EINVAL The named file isn't a symbolic link.
 ELOOP A loop exists in the symbolic links encountered during resolution of the path argument, and more than SYMLOOP\_MAX symbolic links were encountered.

ENAMETOOLONG A component of the path exceeded NAME\_MAX characters, or the entire

pathname exceeded PATH\_MAX characters.

**ENOENT** The named file doesn't exist.

**ENOSYS** Links aren't supported by the resource manager associated with path.

**ENOTDIR** A component of the path prefix named by path isn't a directory.

See Also: read, close, creat, fread, open, write

Example: #include <limits.h>

#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>

```
char buf[PATH_MAX + 1];
int main( int argc, char **argv )
{
   int n;
   int len;
   int ecode = 0;

   for( n = 1; n < argc; ++n ) {
      if( (len = readlink( argv[n], buf, PATH_MAX )) == -1 ) {
        perror( argv[n] );
        ecode++;
      } else {
        buf[len] = '\0';
        printf( "%s -> %s\n", argv[n], buf );
      }
   }
   return( ecode );
}
```

Classification: POSIX 1003.1

Systems: Linux

### **Synopsis:**

#### **Description:**

When the value of the *old\_blk* argument is NULL, a new block of memory of *size* bytes is allocated.

If the value of size is zero, the corresponding free function is called to release the memory pointed to by  $old\_blk$ .

Otherwise, the realloc function re-allocates space for an object of size bytes by either:

- shrinking the allocated size of the allocated memory block *old\_blk* when *size* is sufficiently smaller than the size of *old\_blk*.
- extending the allocated size of the allocated memory block *old\_blk* if there is a large enough block of unallocated memory immediately following *old\_blk*.
- allocating a new block and copying the contents of *old\_blk* to the new block.

Because it is possible that a new block will be allocated, any pointers into the old memory should not be maintained. These pointers will point to freed memory, with possible disastrous results, when a new block is allocated.

The function returns NULL when the memory pointed to by *old\_blk* cannot be re-allocated. In this case, the memory pointed to by *old\_blk* is not freed so care should be exercised to maintain a pointer to the old memory block.

```
buffer = (char *) realloc( buffer, 100 );
```

In the above example, buffer will be set to NULL if the function fails and will no longer point to the old memory block. If buffer was your only pointer to the memory block then you will have lost access to this memory.

Each function reallocates memory from a particular heap, as listed below:

Function	Неар
realloc	Depends on data model of the program
_brealloc	Based heap specified by seg value
_frealloc	Far heap (outside the default data segment)
_nrealloc	Near heap (inside the default data segment)

In a small data memory model, the realloc function is equivalent to the \_nrealloc function; in a large data memory model, the realloc function is equivalent to the \_frealloc function.

**Returns:** 

The realloc functions return a pointer to the start of the re-allocated memory. The return value is NULL if there is insufficient memory available or if the value of the *size* argument is zero. The \_brealloc function returns \_NULLOFF if there is insufficient memory available or if the requested size is zero.

See Also:

calloc Functions, \_expand Functions, free Functions, halloc, hfree, malloc Functions,
\_msize Functions, sbrk

**Example:** 

```
#include <stdlib.h>
#include <malloc.h>

void main()
{
    char *buffer;
    char *new_buffer;

    buffer = (char *) malloc( 80 );
    new_buffer = (char *) realloc( buffer, 100 );
    if( new_buffer == NULL ) {
        /* not able to allocate larger buffer */
    } else {
        buffer = new_buffer;
    }
}
```

**Classification:** ISO C

**Systems:** 

```
realloc - All, Linux, RDOS, Netware
_brealloc - DOS/16, Windows, OS/2 1.x(all)
_frealloc - DOS/16, Windows, OS/2 1.x(all)
_nrealloc - DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT),
OS/2-32, Linux, RDOS
```

**Description:** 

The \_rectangle functions draw rectangles. The \_rectangle function uses the view coordinate system. The \_rectangle\_w and \_rectangle\_wxy functions use the window coordinate system.

The rectangle is defined with opposite corners established by the points (x1, y1) and (x2, y2).

The argument *fill* determines whether the rectangle is filled in or has only its outline drawn. The argument can have one of two values:

\_GFILLINTERIOR fill the interior by writing pixels with the current plot action using the current

color and the current fill mask

**\_GBORDER** leave the interior unchanged; draw the outline of the figure with the current

plot action using the current color and line style

**Returns:** The \_rectangle functions return a non-zero value when the rectangle was successfully drawn;

otherwise, zero is returned.

**See Also:** \_setcolor, \_setfillmask, \_setlinestyle, \_setplotaction

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    _setvideomode( _VRES16COLOR );
    _rectangle( _GBORDER, 100, 100, 540, 380 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

Systems: \_rectangle - DOS

\_rectangle\_w - DOS \_rectangle\_wxy - DOS Synopsis: #include <graph.h>
 short \_FAR \_registerfonts( char \_FAR \*path );

**Description:** The \_registerfonts function initializes the font graphics system. Fonts must be registered, and a font selected, before text can be displayed with the \_outgtext function.

The argument *path* specifies the location of the font files. This argument is a file specification, and can contain drive and directory components and may contain wildcard characters. The \_registerfonts function opens each of the font files specified and reads the font information. Memory is allocated to store the characteristics of the font. These font characteristics are used by the \_setfont function when selecting a font.

**Returns:** The \_registerfonts function returns the number of fonts that were registered if the function is successful; otherwise, a negative number is returned.

See Also: \_unregisterfonts, \_setfont, \_getfontinfo, \_outgtext, \_getgtextextent, \_setgtextvector \_setgtextvector

Example: #include <conio.h>
#include <stdio.h>
#include <graph.h>

main()
{
 int i, n;
 char buf[ 10 ];

 \_setvideomode( \_VRES16COLOR );
 n = \_registerfonts( "\*.fon" );
 for( i = 0; i < n; ++i ) {
 sprintf( buf, "n%d", i );
 \_setfont( buf );
 \_moveto( 100, 100 );
 \_outgtext( "WATCOM Graphics" );
 getch();
 \_clearscreen( \_GCLEARSCREEN );
}

\_unregisterfonts();
 \_setvideomode( \_DEFAULTMODE );
}</pre>

Classification: PC Graphics

Systems: DOS

**Description:** The remainder function computes remainder of the division of x by y.

**Returns:** The remainder of the division of x by y.

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", remainder( 7.0, 2.0 ) );
}
```

produces the following:

1.00000

Classification: ISO C99

**Systems:** Math

Synopsis: #include <graph.h>
 short \_FAR \_remapallpalette( long \_FAR \*colors );

**Description:** The \_remapallpalette function sets (or remaps) all of the colors in the palette. The color values in the palette are replaced by the array of color values given by the argument *colors*. This function is

supported in all video modes, but only works with EGA, MCGA and VGA adapters.

The array *colors* must contain at least as many elements as there are supported colors. The newly mapped palette will cause the complete screen to change color wherever there is a pixel value of a changed color in the palette.

The representation of colors depends upon the hardware being used. The number of colors in the palette can be determined by using the \_qetvideoconfiq function.

**Returns:** The \_remapallpalette function returns (-1) if the palette is remapped successfully and zero

otherwise.

See Also: \_remappalette, \_getvideoconfig

Example: #include <conio.h>
#include <graph.h>

```
long colors[ 16 ] = {
   _BRIGHTWHITE, _YELLOW, _LIGHTMAGENTA, _LIGHTRED,
   _LIGHTCYAN, _LIGHTGREEN, _LIGHTBLUE, _GRAY, _WHITE,
   _BROWN, _MAGENTA, _RED, _CYAN, _GREEN, _BLUE, _BLACK,
};
main()
    int x, y;
    _setvideomode( _VRES16COLOR );
    for (y = 0; y < 4; ++y)
        for(x = 0; x < 4; ++x) {
            \_setcolor( x + 4 * y );
            _rectangle( _GFILLINTERIOR,
                    x * 160, y * 120,
                    (x + 1) * 160, (y + 1) * 120);
        }
    }
    getch();
    _remapallpalette( colors );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Systems: DOS

_remapallpalette

Synopsis: #include <graph.h>
long \_FAR \_remappalette( short pixval, long color );

**Description:** The \_remappalette function sets (or remaps) the palette color *pixval* to be the color *color*. This function is supported in all video modes, but only works with EGA, MCGA and VGA adapters.

The argument *pixval* is an index in the color palette of the current video mode. The argument *color* specifies the actual color displayed on the screen by pixels with pixel value *pixval*. Color values are selected by specifying the red, green and blue intensities that make up the color. Each intensity can be in the range from 0 to 63, resulting in 262144 possible different colors. A given color value can be conveniently specified as a value of type long. The color value is of the form 0x00bbggrr, where bb is the blue intensity, gg is the green intensity and rr is the red intensity of the selected color. The file graph.h defines constants containing the color intensities of each of the 16 default colors.

The \_remappalette function takes effect immediately. All pixels on the complete screen which have a pixel value equal to the value of *pixval* will now have the color indicated by the argument *color*.

**Returns:** The \_remappalette function returns the previous color for the pixel value if the palette is remapped successfully; otherwise, (-1) is returned.

See Also: \_remapallpalette, \_setvideomode

Example: #include <conio.h>
#include <graph.h>

```
long colors[ 16 ] = {
    _BLACK, _BLUE, _GREEN, _CYAN,
    _RED, _MAGENTA, _BROWN, _WHITE,
    _GRAY, _LIGHTBLUE, _LIGHTGREEN, _LIGHTCYAN,
    _LIGHTRED, _LIGHTMAGENTA, _YELLOW, _BRIGHTWHITE
};

main()
{
    int col;
    _setvideomode( _VRES16COLOR );
    for( col = 0; col < 16; ++col ) {
        _remappalette( 0, colors[ col ] );
        getch();
    }
    _setvideomode( _DEFAULTMODE );
}</pre>
```

**Classification:** PC Graphics

Systems: DOS

		_remappale

Synopsis: #include <stdio.h>

int remove( const char \*filename );
int \_wremove( const wchar\_t \*filename );

**Description:** The remove function deletes the file whose name is the string pointed to by *filename*.

The \_wremove function is a wide character version of remove that operates with wide character strings.

Returns:

The remove function returns zero if the operation succeeds, non-zero if it fails. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

Example: #include <stdio.h>

```
void main()
     {
      remove( "vm.tmp" );
    }
```

**Classification:** ISO C

Systems: remove - All, Linux, RDOS, Netware

 $\_$ wremove - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

Synopsis: #include <stdio.h>

```
int rename( const char *old, const char *new );
int _wrename( const wchar_t *old, const wchar_t *new );
```

**Description:** 

The rename function causes the file whose name is indicated by the string *old* to be renamed to the name given by the string *new*.

The \_wrename function is a wide character version of rename that operates with wide character strings.

**Returns:** 

The rename function returns zero if the operation succeeds, a non-zero value if it fails. When an error has occurred, errno contains a value indicating the type of error that has been detected.

Example: #include <stdio.h>

```
void main()
{
    rename( "old.dat", "new.dat" );
}
```

Classification: ISO C

Systems: rename - All, Linux, RDOS, Netware

 $\_$ wrename - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

```
Synopsis: #include <stdio.h>
    void rewind( FILE *fp );
```

**Description:** The rewind function sets the file position indicator for the stream indicated to by fp to the beginning

of the file. It is equivalent to

```
fseek( fp, OL, SEEK_SET );
```

except that the error indicator for the stream is cleared.

**Returns:** The rewind function returns no value.

See Also: fopen, clearerr

Example: #include <stdio.h>

```
static assemble_pass( int passno )
{
    printf( "Pass %d\n", passno );
}

void main()
{
    FILE *fp;

    if( (fp = fopen( "program.asm", "r")) != NULL ) {
        assemble_pass( 1 );
        rewind( fp );
        assemble_pass( 2 );
        fclose( fp );
    }
}
```

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware

```
Synopsis: #include <sys/types.h>
#include <direct.h>
void rewinddir( DIR *dirp );
void _wrewinddir( WDIR *dirp );
```

**Description:** The rewinddir function resets the position of the directory stream to which *dirp* refers to the beginning of the directory. It also causes the directory stream to refer to the current state of the corresponding directory, as a call to opendir would have done.

The \_wrewinddir function is identical to rewinddir except that it rewinds a directory of wide character filenames opened by \_wopendir.

**Returns:** The rewinddir function does not return a value.

See Also: closedir, \_dos\_find..., opendir, readdir, \_wopendir, \_wreaddir, \_wrewinddir

**Example:** The following example lists all the files in a directory, creates a new file, and then relists the directory.

```
#include <stdio.h>
#include <sys/types.h>
#include <sys/stat.h>
#include <direct.h>
void main()
    DIR *dirp;
    struct dirent *direntp;
    int handle;
    dirp = opendir( "\\watcom\\h\\*.*" );
    if( dirp != NULL ) {
        printf( "Old directory listing\n" );
        for(;;) {
            direntp = readdir( dirp );
            if( direntp == NULL )
                break;
            printf( "%s\n", direntp->d_name );
        }
        handle = creat( "\\watcom\\h\\file.new",
                      S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
        close( handle );
        rewinddir( dirp );
        printf( "New directory listing\n" );
        for(;;) {
            direntp = readdir( dirp );
            if( direntp == NULL )
                break;
            printf( "%s\n", direntp->d_name );
        closedir( dirp );
    }
}
```

# rewinddir, \_wrewinddir

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

Classification: POSIX 1003.1

Systems: rewinddir - All, Linux, RDOS

\_wrewinddir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

**Description:** The rint function rounds the argument *x* to a nearby integer. The direction of the rounding is

determined by the current value of fegetround. floating point error if an overflow occurs due to the

current rounding mode.

**Returns:** The rounded value of x.

See Also: fegetround, fesetround, nearbyint, round, trunc

Example: #include <stdio.h>
#include <math.h>

```
void main()
{
   fesetround(FE_TONEAREST);
   printf( "%f\n", rint( 1.2 ) );
}
```

produces the following:

1.000000

Classification: ISO C99

**Systems:** Math

# Synopsis: #include <sys/types.h>

```
#include <direct.h>
int rmdir( const char *path );
int _rmdir( const char *path );
int _wrmdir( const wchar_t *path );
```

## **Description:**

The rmdir function removes (deletes) the specified directory. The directory must not contain any files or directories. The *path* can be either relative to the current working directory or it can be an absolute path name.

The \_rmdir function is identical to rmdir. Use \_rmdir for ANSI naming conventions.

The \_wrmdir function is a wide character version of rmdir that operates with wide character strings.

**Returns:** The rmdir function returns zero if successful and -1 otherwise.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: chdir, chmod, getcwd, mkdir, stat, umask

**Example:** To remove the directory called \watcom on drive C:

```
#include <sys/types.h>
#include <direct.h>

void main( void )
{
    rmdir( "c:\\watcom" );
}
```

Note the use of two adjacent backslash characters (\) within character-string constants to signify a single backslash.

## Classification: POSIX 1003.1

\_rmdir conforms to ANSI naming conventions

```
Systems: rmdir - All, Linux, RDOS, Netware
```

```
_rmdir - All, Linux, RDOS, Netware
_wrmdir - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

**Description:** The \_rot1 function rotates the unsigned integer, determined by *value*, to the left by the number of bits

specified in shift. If you port an application using \_rotl between a 16-bit and a 32-bit environment,

you will get different results because of the difference in the size of integers.

**Returns:** The rotated value is returned.

See Also: \_lrotl, \_lrotr, \_rotr

Example: #include <stdio.h>
#include <stdlib.h>

unsigned int mask = 0x0F00;

void main()
 {
 mask = \_rotl( mask, 4 );
 printf( "%04X\n", mask );

produces the following:

F000

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Description:** The \_rotr function rotates the unsigned integer, determined by *value*, to the right by the number of

bits specified in *shift*. If you port an application using \_rotr between a 16-bit and a 32-bit environment, you will get different results because of the difference in the size of integers.

**Returns:** The rotated value is returned.

See Also: \_lrotl, \_lrotr, \_rotl

Example: #include <stdio.h>
#include <stdlib.h>

```
unsigned int mask = 0x1230;

void main()
{
    mask = _rotr( mask, 4 );
    printf( "%04X\n", mask );
}
```

produces the following:

0123

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Description:** The round function rounds the argument x to the nearest integer. Values halfway between integers

always rounded away from zero.

**Returns:** The rounded value of x.

See Also: nearbyint, rint, trunc

Example: #include <stdio.h>
#include <math.h>

produces the following:

2.000000

Classification: ISO C99

**Systems:** Math

Synopsis: #include <stdlib.h>
 void \_\_near \*sbrk( int increment );

#### **Description:**

Change data segment size, the "break" value. Under 16-bit DOS, Phar Lap's 386|DOS-Extender and Linux, the data segment is grown contiguously. Under other systems, heap allocation is discontiguous. The "break" value is the address of the first byte of unallocated memory. When a program starts execution, the break value is placed following the code and constant data for the program. As memory is allocated, this pointer will advance when there is no freed block large enough to satisfy an allocation request. The sbrk function can be used to set a new "break" value for the program by adding the value of *increment* to the current break value. This increment may be positive or negative.

Under other systems, heap allocation is discontiguous. The sbrk function can only be used to allocate additional discontiguous blocks of memory. The value of *increment* is used to determine the minimum size of the block to be allocated and may not be zero or negative. The actual size of the block that is allocated is rounded up to a multiple of 4K.

The variable \_amblksiz defined in <stdlib.h> contains the default increment by which the "break" pointer for memory allocation will be advanced when there is no freed block large enough to satisfy a request to allocate a block of memory. This value may be changed by a program at any time.

Under 16-bit DOS, a new process started with one of the spawn... or exec... functions is loaded following the break value. Consequently, decreasing the break value leaves more space available to the new process. Similarly, for a resident program (a program which remains in memory while another program executes), increasing the break value will leave more space available to be allocated by the resident program after other programs are loaded.

#### **Returns:**

If the call to sbrk succeeds, a pointer to the start of the new block of memory is returned. Under 16-bit DOS, this corresponds to the old break value. If the call to sbrk fails, -1 is returned. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

#### See Also:

calloc Functions, \_expand Functions, free Functions, halloc, hfree, malloc Functions, \_msize Functions, realloc Functions

### **Example:**

```
#include <stdio.h>
#include <stdlib.h>

#if defined(M_I86)
#define alloc( x, y ) sbrk( x ); y = sbrk( 0 );
#else
#define alloc( x, y ) y = sbrk( x );
#endif

void main()
{
    void *brkval;
```

```
#if defined(M_I86)
   alloc( 0x0000, brkval );
    /* calling printf will cause an allocation */
   printf( "Original break value %p\n", brkval );
   printf( "Current amblksiz value x\n", _amblksiz );
   alloc( 0x0000, brkval );
   printf ( "New break value after printf \t \p\n", brkval );
#endif
   alloc( 0x3100, brkval );
   printf( "New break value after sbrk( 0x3100 ) tpn",
            brkval );
   alloc( 0x0200, brkval );
   printf( "New break value after sbrk( 0x0200 ) \t^{p}n",
            brkval);
#if defined(M_I86)
    alloc( -0x0100, brkval );
   printf( "New break value after sbrk( -0x0100 ) \t^{p}n",
            brkval );
#endif
```

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x, OS/2 1.x(MT), OS/2-32, Linux, RDOS

**Description:** The scalbn function computes  $x * (2^{**} y)$  via exponent manipulation.

```
fmax(x - y, 0.0);
```

**Returns:** The value of x times two raised to y.

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", scalbn( 1.0, 3.0 ) );
    }
```

produces the following:

8.000000

Classification: ISO C99

**Systems:** Math

Synopsis: #include <stdio.h>

```
int scanf( const char *format, ... );
#include <wchar.h>
int wscanf( const wchar_t *format, ... );
```

Safer C: The Safer C Library extension provides the scanf\_s function which is a safer alternative to scanf.

**Description:** 

The scanf function scans input from the file designated by stdin under control of the argument *format*. The *format* string is described below. Following the format string is the list of addresses of items to receive values.

The wscanf function is identical to scanf except that it accepts a wide character string argument for *format*.

**Returns:** 

The scanf function returns EOF if an input failure occured before any conversion. Otherwise, the number of input arguments for which values were successfully scanned and stored is returned.

See Also:

cscanf, fscanf, sscanf, vcscanf, vfscanf, vscanf, vscanf, fwscanf, wscanf, swscanf, vfwscanf, vswscanf

**Example:** 

To scan a date in the form "Saturday April 18 1987":

```
#include <stdio.h>
void main( void )
{
   int day, year;
   char weekday[10], month[10];
   scanf( "%s %s %d %d", weekday, month, &day, &year );
}
```

**Format Control String:** The format control string consists of zero or more *format directives* that specify acceptable input file data. Subsequent arguments are pointers to various types of objects that are assigned values as the format string is processed.

A format directive can be a sequence of one or more white-space characters, an *ordinary character*, or a *conversion specifier*. An ordinary character in the format string is any character, other than a white-space character or the percent character (%), that is not part of a conversion specifier. A conversion specifier is a sequence of characters in the format string that begins with a percent character (%) and is followed, in sequence, by the following:

- an optional assignment suppression indicator: the asterisk character (\*);
- an optional decimal integer that specifies the *maximum field width* to be scanned for the conversion:
- an optional *pointer-type* specification: one of "N" or "W";
- an optional type length specification: one of "hh", "h", "l", "ll", "j", "z", "t", "L" or "I64";
- a character that specifies the type of conversion to be performed: one of the characters "cCdeEfFgGinopsSuxX[".

As each format directive in the format string is processed, the directive may successfully complete, fail because of a lack of input data, or fail because of a matching error as defined by the particular directive. If end-of-file is encountered on the input data before any characters that match the current directive have been processed (other than leading white-space where permitted), the directive fails for lack of data. If end-of-file occurs after a matching character has been processed, the directive is completed (unless a matching error occurs), and the function returns without processing the next directive. If a directive fails because of an input character mismatch, the character is left unread in the input stream. Trailing white-space characters, including new-line characters, are not read unless matched by a directive. When a format directive fails, or the end of the format string is encountered, the scanning is completed and the function returns.

When one or more white-space characters (space " ", horizontal tab "\t", vertical tab "\v", form feed "\f", carriage return "\r", new line or linefeed "\n") occur in the format string, input data up to the first non-white-space character is read, or until no more data remains. If no white-space characters are found in the input data, the scanning is complete and the function returns.

An ordinary character in the format string is expected to match the same character in the input stream.

A conversion specifier in the format string is processed as follows:

- for conversion types other than "[", "c", "C" and "n", leading white-space characters are skipped
- for conversion types other than "n", all input characters, up to any specified maximum field length, that can be matched by the conversion type are read and converted to the appropriate type of value; the character immediately following the last character to be matched is left unread; if no characters are matched, the format directive fails
- unless the assignment suppression indicator ("\*") was specified, the result of the conversion is assigned to the object pointed to by the next unused argument (if assignment suppression was specified, no argument is skipped); the arguments must correspond in number, type and order to the conversion specifiers in the format string

A pointer-type specification is used to indicate the type of pointer used to locate the next argument to be scanned:

W pointer is a far pointer

N pointer is a near pointer

The pointer-type specification is only effective on platforms that use a segmented memory model, although it is always recognized.

The pointer type defaults to that used for data in the memory model for which the program has been compiled.

A type length specifier affects the conversion as follows:

- "hh" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type signed char or unsigned char.
- "hh" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of type signed char.

- "h" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type short int or unsigned short int.
- "h" causes an "f" conversion to assign a fixed-point number to an object of type long consisting of a 16-bit signed integer part and a 16-bit unsigned fractional part. The integer part is in the high 16 bits and the fractional part is in the low 16 bits.

```
struct fixpt {
    unsigned short fraction; /* Intel architecture! */
        signed short integral;
};

struct fixpt foo1 =
    { 0x8000, 1234 }; /* represents 1234.5 */
struct fixpt foo2 =
    { 0x8000, -1 }; /* represents -0.5 (-1+.5) */
```

- "h" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of type short int. \*.
- "h" causes an "s" operation to convert the input string to an ASCII character string. For scanf this specifier is redundant. For wscanf, this specifier is required if the wide character input string is to be converted to an ASCII character string; otherwise it will not be converted. \*.
- "l" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type long int or unsigned long int.
- "l" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of type long int.
- "l" causes an "e", "f" or "g" (floating-point) conversion to assign the converted value to an object of type double.
- "I" or "w" cause an "s" operation to convert the input string to a wide character string. For scanf this specifier is required if the input ASCII string is to be converted to a wide character string; otherwise it will not be converted. \*.
- "ll" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type long long or unsigned long long (e.g., %lld).
- "Il" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of type long long int.
- "j" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type intmax\_t or uintmax\_t.
- "j" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of type intmax\_t.
- "z" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type size\_t or the corresponding signed integer type.
- "z" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of signed integer type corresponding to size\_t.

- "t" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type ptrdiff\_t or the corresponding unsigned integer type.
- "t" causes an "n" (read length assignment) operation to assign the number of characters that have been read to an object of type ptrdiff\_t.
- "I64" causes a "d", "i", "o", "u" or "x" (integer) conversion to assign the converted value to an object of type \_\_int64 or unsigned \_\_int64 (e.g., %I64d).
- "L" causes an "e", "f" or "g" (floating-point) conversion to assign the converted value to an object of type long double.

The valid conversion type specifiers are:

- c Any sequence of characters in the input stream of the length specified by the field width, or a single character if no field width is specified, is matched. The argument is assumed to point to the first element of a character array of sufficient size to contain the sequence, without a terminating null character ('\0'). For a single character assignment, a pointer to a single object of type char is sufficient.
- A sequence of multibyte characters in the input stream is matched. Each multibyte character is converted to a wide character of type wchar\_t. The number of wide characters matched is specified by the field width (1 if no field width is specified). The argument is assumed to point to the first element of an array of wchar\_t of sufficient size to contain the sequence. No terminating null wide character (L'\0') is added. For a single wide character assignment, a pointer to a single object of type wchar\_t is sufficient.
- d A decimal integer, consisting of an optional sign, followed by one or more decimal digits, is matched. The argument is assumed to point to an object of type int.
- e, f, g A floating-point number, consisting of an optional sign ("+" or "-"), followed by one or more decimal digits, optionally containing a decimal-point character, followed by an optional exponent of the form "e" or "E", an optional sign and one or more decimal digits, is matched. The exponent, if present, specifies the power of ten by which the decimal fraction is multiplied. The argument is assumed to point to an object of type float.
- i An optional sign, followed by an octal, decimal or hexadecimal constant is matched. An octal constant consists of "0" and zero or more octal digits. A decimal constant consists of a non-zero decimal digit and zero or more decimal digits. A hexadecimal constant consists of the characters "0x" or "0X" followed by one or more (upper- or lowercase) hexadecimal digits. The argument is assumed to point to an object of type int.
- No input data is processed. Instead, the number of characters that have already been read is assigned to the object of type unsigned int that is pointed to by the argument. The number of items that have been scanned and assigned (the return value) is not affected by the "n" conversion type specifier.
- An octal integer, consisting of an optional sign, followed by one or more (zero or non-zero) octal digits, is matched. The argument is assumed to point to an object of type int.
- A hexadecimal integer, as described for "x" conversions below, is matched. The converted value is further converted to a value of type void\* and then assigned to the object pointed to by the argument.

- s A sequence of non-white-space characters is matched. The argument is assumed to point to the first element of a character array of sufficient size to contain the sequence and a terminating null character, which is added by the conversion operation.
- A sequence of multibyte characters is matched. None of the multibyte characters in the sequence may be single-byte white-space characters. Each multibyte character is converted to a wide character. The argument is assumed to point to the first element of an array of wchar\_t of sufficient size to contain the sequence and a terminating null wide character, which is added by the conversion operation.
- u An unsigned decimal integer, consisting of one or more decimal digits, is matched. The argument is assumed to point to an object of type unsigned int.
- x A hexadecimal integer, consisting of an optional sign, followed by an optional prefix "0x" or "0X", followed by one or more (upper- or lowercase) hexadecimal digits, is matched. The argument is assumed to point to an object of type int.
- [c1c2...] The longest, non-empty sequence of characters, consisting of any of the characters c1, c2, ... called the *scanset*, in any order, is matched. c1 cannot be the caret character ('^'). If c1 is "]", that character is considered to be part of the scanset and a second "]" is required to end the format directive. The argument is assumed to point to the first element of a character array of sufficient size to contain the sequence and a terminating null character, which is added by the conversion operation.
- [^c1c2...] The longest, non-empty sequence of characters, consisting of any characters other than the characters between the "^" and "]", is matched. As with the preceding conversion, if c1 is "]", it is considered to be part of the scanset and a second "]" ends the format directive. The argument is assumed to point to the first element of a character array of sufficient size to contain the sequence and a terminating null character, which is added by the conversion operation.

For example, the specification  $[^n]$  will match an entire input line up to but not including the newline character.

A conversion type specifier of "%" is treated as a single ordinary character that matches a single "%" character in the input data. A conversion type specifier other than those listed above causes scanning to terminate and the function to return.

Conversion type specifiers "E", "F", "G", "X" have meaning identical to their lowercase equivalents.

### The line

```
scanf( "%s%*f%3hx%d", name, &hexnum, &decnum )
with input
some_string 34.555e-3 abc1234
```

will copy "some\_string" into the array name, skip 34.555e-3, assign 0xabc to hexnum and 1234 to decnum. The return value will be 3.

The program

```
#include <stdio.h>
            void main( void )
                 char string1[80], string2[80];
                 scanf( "%[abcdefghijklmnopqrstuvwxyz"
                         "ABCDEFGHIJKLMNOPQRSTUVWZ ]%*2s%[^\n]",
                         string1, string2 );
                 printf( "%s\n%s\n", string1, string2 );
            }
            with input
            They may look alike, but they don't perform alike.
            will assign
            "They may look alike"
            to string1, skip the comma (the "%*2s" will match only the comma; the following blank terminates
            that field), and assign
            " but they don't perform alike."
            to string2.
Classification: ISO C90
            wscanf is ISO C95
            The N, W pointer size modifiers and the I64 modifier are extensions to ISO C.
Systems:
            scanf - All, Linux, RDOS, Netware
            wscanf - All, Linux
```

## **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
int scanf_s( const char * restrict format, ... );
#include <wchar.h>
int wscanf_s( const wchar_t * restrict format, ... );
```

### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and scanf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

The *format* argument shall not be a null pointer. Any argument indirected through in order to store converted input shall not be a null pointer.

If there is a runtime-constraint violation, the <code>scanf\_s</code> function does not attempt to perform further input, and it is unspecified to what extent <code>scanf\_s</code> performed input before discovering the runtime-constraint violation.

## **Description:**

The scanf\_s function is equivalent to fscanf\_s with the argument *stdin* interposed before the arguments to scanf\_s

The wscanf\_s function is identical to scanf\_s except that it accepts a wide character string argument for *format*.

#### **Returns:**

The scanf\_s function returns EOF if an input failure occurred before any conversion or if there was a runtime-constraint violation. Otherwise, the scanf\_s function returns the number of input items successfully assigned, which can be fewer than provided for, or even zero.

When a file input error occurs, the errno global variable may be set.

### See Also:

cscanf, fscanf, scanf, sscanf, vcscanf, vfscanf, vscanf, vsscanf, fwscanf, wscanf, swscanf, vfwscanf, vswscanf

#### Example:

To scan a date in the form "Friday August 13 2004":

### Classification: TR 24731

#### **Systems:**

scanf\_s - All, Linux, RDOS, Netware
wscanf\_s - All, Linux

scanf_s, wscanf_s		

Synopsis: #include <sched.h>

int sched\_getparam(pid\_t pid, struct sched\_param \*sp);

struct sched\_param {
 int sched\_priority;
};

**Description:** 

The sched\_getparam function retrieves scheduling parameters for the process specified by pid and

returns the parameters in the memory pointed to by the sp argument.

If pid is zero, the scheduling parameters for the calling process will be returned in the sp argument.

**Returns:** 

If successful, the function will return zero. If the call fails, the return value is -1 and errno is

appropriately set.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**ESRCH** The process ID *pid* is invalid or could not be found

**EPERM** The calling process does not have permission to access the parameters

**EFAULT** The memory at *sp* could not be written successfully

See Also: sched\_setparam

Classification: POSIX 1003.1

# sched\_get\_priority\_max

Synopsis: #include <sched.h>

int sched\_get\_priority\_max(pid\_t pid, int policy);

**Description:** The sched\_get\_priority\_max function returns the maximum priority for the scheduling policy

specified by the *policy* argument.

**Returns:** If successful, the function will return the maximum priority allowed for the given scheduling policy. If

the call fails, the return value is -1 and errno is appropriately set.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of policy does not represent a valid scheduling policy

See Also: sched\_get\_priority\_min

Classification: POSIX 1003.1

Synopsis: #include <sched.h>

int sched\_get\_priority\_min(pid\_t pid, int policy);

**Description:** The sched\_get\_priority\_min function returns the minimum priority for the scheduling policy

specified by the *policy* argument.

**Returns:** If successful, the function will return the minimum priority allowed for the given scheduling policy. If

the call fails, the return value is -1 and errno is appropriately set.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of policy does not represent a valid scheduling policy

See Also: sched\_get\_priority\_max

Classification: POSIX 1003.1

# sched\_getscheduler

Synopsis: #include <sched.h>

int sched\_getscheduler(pid\_t pid);

 $\textbf{Description:} \quad \text{The sched\_getscheduler function retrieves scheduling policy for the process specified by the } \textit{pid}$ 

argument.

If *pid* is zero, the policy for the calling process will be returned.

**Returns:** If successful, the function will return the kernel's scheduling policy for the specified process. If the call

fails, the return value is -1 and errno is appropriately set.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

ESRCH The process ID pid could not be found

**EINVAL** The process ID *pid* is invalid

See Also: sched\_setscheduler

Classification: POSIX 1003.1

Synopsis: #include <sched.h>

```
#include <time.h>
int sched_rr_get_interval(pid_t pid, struct timespec *ts);
struct timespec {
    time_t tv_sec;
    long tv_nsec;
};
```

**Description:** 

The sched\_rr\_get\_interval function retrieves the execution time limit for the process specified by the *pid* argument. The memory pointed to by *ts* will be populated with this time limit if the call is successful.

If pid is zero, the execution time limit for the calling process will be returned in the ts argument.

**Returns:** If successful, the function will return zero. If the call fails, the return value is -1 and errno is

appropriately set.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**ESRCH** The process ID *pid* is invalid or could not be found

**EPERM** The calling process does not have permission to access the parameters

**EFAULT** The memory at sp could not be written successfully

Classification: POSIX 1003.1

**Synopsis:** #include <sched.h>

int sched\_setparam(pid\_t pid, const struct sched\_param \*sp);

struct sched\_param { int sched\_priority; };

**Description:** 

The sched\_setparam function sets the scheduling parameters for the process specified by the pid

argument.

If *pid* is zero, the scheduling parameters for the calling process will be set.

**Returns:** 

If successful, the function will return zero. If the call fails, the return value is -1 and errno is

appropriately set.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**ESRCH** The process ID *pid* is invalid or could not be found

**EINVAL** The value of *pid* or *sp* is invalid

**EFAULT** The memory at *sp* could not be read

See Also: sched\_getparam

Classification: POSIX 1003.1

Synopsis: #include <sched.h>

int sched\_setscheduler(pid\_t pid, int policy,
 const struct sched\_param \*sp);

struct sched\_param {
 int sched\_priority;
};

**Description:** 

The sched\_setscheduler function sets the scheduling policy and parameters for the process

specified by the *pid* argument.

If *pid* is zero, the policy and parameters for the calling process will be set.

**Returns:** 

If successful, the function will return the kernel's former scheduling policy for the specified process. If

the call fails, the return value is -1 and errno is appropriately set.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**ESRCH** The process ID *pid* could not be found

EINVAL The process ID pid, policy value policy, or the pointer sp is invalid

**EFAULT** The memory at sp could not be read

See Also: sched\_getscheduler, sched\_setparam, sched\_getparam

Classification: POSIX 1003.1

# sched\_yield

Synopsis: #include <sched.h>
int sched\_yield();

**Description:** The sched\_yield function causes the calling thread to yield the processor to other threads until the

kernel assigns it to be the current thread once again.

**Returns:** If successful, the function will return zero. If the call fails, the return value is -1.

Classification: POSIX 1003.1

Synopsis: #include <graph.h>
 void FAR scrolltextwindow( short rows );

**Description:** The \_scrolltextwindow function scrolls the lines in the current text window. A text window is defined with the \_settextwindow function. By default, the text window is the entire screen.

The argument *rows* specifies the number of rows to scroll. A positive value means to scroll the text window up or towards the top of the screen. A negative value means to scroll the text window down or towards the bottom of the screen. Specifying a number of rows greater than the height of the text window is equivalent to clearing the text window with the \_clearscreen function.

Two constants are defined that can be used with the \_scrolltextwindow function:

**\_GSCROLLUP** the contents of the text window are scrolled up (towards the top of the

screen) by one row

**\_GSCROLLDOWN** the contents of the text window are scrolled down (towards the bottom of the

screen) by one row

**Returns:** The \_scrolltextwindow function does not return a value.

See Also: \_settextwindow, \_clearscreen, \_outtext, \_outmem, \_settextposition

Example: #include <conio.h>
 #include <graph.h>
#include <stdio.h>

main()
{
 int i;
 char buf[ 80 ];

 \_setvideomode( \_TEXTC80 );
 \_settextwindow( 5, 20, 20, 40 );
 for( i = 1; i <= 10; ++i ) {
 sprintf( buf, "Line %d\n", i );
 \_outtext( buf );
 }
 getch();
 \_scrolltextwindow( \_GSCROLLDOWN );
 getch();</pre>

\_scrolltextwindow( \_GSCROLLUP );

\_setvideomode( \_DEFAULTMODE );

**Classification:** PC Graphics

getch();

Systems: DOS

crolltextwindo	W			
		 	 <del></del> .	

**Synopsis:** 

**Description:** 

The \_searchenv function searches for the file specified by *name* in the list of directories assigned to the environment variable specified by *env\_var*. Common values for *env\_var* are PATH, LIB and INCLUDE.

The current directory is searched first to find the specified file. If the file is not found in the current directory, each of the directories specified by the environment variable is searched.

The full pathname is placed in the buffer pointed to by the argument *pathname*. If the specified file cannot be found, then *pathname* will contain an empty string. The *pathname* buffer should be at least \_MAX\_PATH characters long to accommodate the full length of the constructed path name. Otherwise, \_searchenv might overrun the pathname buffer and cause unexpected behavior.

The \_wsearchenv function is a wide character version of \_searchenv that operates with wide character strings.

**Returns:** The searchenv function returns no value.

See Also: exec..., \_wexec..., clearenv, getenv, getenv\_s, putenv, setenv, unsetenv, \_wgetenv, \_wputenv, \_wsearchenv, \_wsetenv, \_wunsetenv, spawn..., system, \_wsystem

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
void display_help( FILE *fp )
  {
    printf( "display_help T.B.I.\n" );
  }
void main()
  {
    FILE *help_file;
    char full_path[ _MAX_PATH ];
    _searchenv( "watcomc.hlp", "PATH", full_path );
    if( full_path[0] == '\0' ) {
      printf( "Unable to find help file\n" );
      help_file = fopen(full_path, "r");
      display_help( help_file );
      fclose( help_file );
  }
```

**Classification:** WATCOM

# \_searchenv, \_wsearchenv

```
Systems: _searchenv - All, Linux, RDOS _wsearchenv - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

**Description:** The segread function places the values of the segment registers into the structure located by

 $seg\_regs.$ 

**Returns:** No value is returned.

**See Also:** FP\_OFF, FP\_SEG, MK\_FP

Example: #include <stdio.h> #include <i86.h>

```
void main()
{
   struct SREGS sregs;

   segread( &sregs );
   printf( "Current value of CS is %04X\n", sregs.cs );
}
```

**Classification:** WATCOM

**Systems:** All, RDOS, Netware

**Synopsis:** #include <graph.h> short \_FAR \_selectpalette( short palnum );

**Description:** The \_selectpalette function selects the palette indicated by the argument palnum from the color

palettes available. This function is only supported by the video modes \_MRES4COLOR and

\_MRESNOCOLOR.

Mode \_MRES4COLOR supports four palettes of four colors. In each palette, color 0, the background color, can be any of the 16 possible colors. The color values associated with the other three pixel values, (1, 2 and 3), are determined by the selected palette.

The following table outlines the available color palettes:

Palette		Pixel Values	
Number	1	2	3
0	green	red	brown
1	cyan	magenta	white
2	light green	light red	yellow
3	light cyan	light magenta	bright white

**Returns:** The \_selectpalette function returns the number of the previously selected palette.

See Also: \_setvideomode, \_getvideoconfig

**Example:** #include <conio.h>

```
#include <graph.h>
main()
    int x, y, pal;
    _setvideomode( _MRES4COLOR );
    for (y = 0; y < 2; ++y)
        for(x = 0; x < 2; ++x) {
            \_setcolor( x + 2 * y );
            _rectangle( _GFILLINTERIOR,
                    x * 160, y * 100,
                    (x + 1) * 160, (y + 1) * 100);
    for ( pal = 0; pal < 4; ++pal ) {
        _selectpalette( pal );
        getch();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

}

**Systems:** DOS

_selectpalette

# sem\_destroy

Synopsis: #include <semaphore.h>

int sem\_destroy(sem\_t \*semaphore);

**Description:** The sem\_destroy function destroys a semaphore pointed to by the *semaphore* argument.

**Returns:** If successful, the function will return zero. If the call fails, the function returns -1 and errno is set

appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EBUSY** The semaphore is currently unavailable.

See Also: sem\_init, sem\_getvalue, sem\_post, sem\_trywait, sem\_wait

Classification: POSIX 1003.1

int sem\_getvalue(sem\_t \*semaphore, int \*dest);

**Description:** The sem\_getvalue function returns the current value of *semaphore* in the memory pointed to by the

dest pointer.

**Returns:** If successful, the function will return zero. If the call fails, the function returns -1 and errno is set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

*EINVAL* The pointer *value* is NULL

See Also: sem\_destroy, sem\_init, sem\_post, sem\_trywait, sem\_wait

Classification: POSIX 1003.1

int sem\_init(sem\_t \*semaphore, int flags, int value);

**Description:** The sem\_init function initializes a semaphore pointed to by semaphore using value as its initial

value. On Open Watcom, the *flags* argument must be zero as this runtime does not currently support

sharing semaphores across processes.

**Returns:** If successful, the function will return zero. If the call fails, the function returns -1 and errno is set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of the value argument exceeds SEM\_VALUE\_MAX

ENOSYS The value of flags was non-zero or semaphores are not supported on this CPU.

See Also: sem\_destroy, sem\_getvalue, sem\_post, sem\_trywait, sem\_wait

Classification: POSIX 1003.1

int sem\_post(sem\_t \*semaphore);

**Description:** The sem\_post function unlocks a semaphore pointed to by the *semaphore* argument. Unlocking

releases the semaphore and signals any waiting threads appropriately.

**Returns:** If successful, the function will return zero. If the call fails, the function returns -1 and errno is set

appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

*EINVAL* The pointer *semaphore* is NULL

See Also: sem\_destroy, sem\_init, sem\_trywait, sem\_wait

Classification: POSIX 1003.1

# sem\_trywait

Synopsis: #include <semaphore.h>

int sem\_trywait(sem\_t \*semaphore);

Description: The sem\_trywait function attempts to lock a semaphore pointed to by the semaphore argument, and

returns immediately regardless of success.

**Returns:** If the semaphore was successfully locked, the function will return zero. If the call fails or the

semaphore could not be locked, the function returns -1 and errno is set appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

*EINVAL* The pointer *semaphore* is NULL

*EAGAIN* The semaphore is currently locked.

See Also: sem\_destroy, sem\_getvalue, sem\_init, sem\_post, sem\_wait

Classification: POSIX 1003.1

int sem\_wait(sem\_t \*semaphore);

**Description:** The sem\_wait function attempts to lock a semaphore pointed to by the *semaphore* argument, and

blocks until the semaphore is successfully locked.

**Returns:** If the semaphore was successfully locked, the function will return zero. If the call fails or the

semaphore could not be locked, the function returns -1 and errno is set appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

*EINVAL* The pointer *semaphore* is NULL

See Also: sem\_destroy, sem\_getvalue, sem\_init, sem\_post, sem\_trywait

Classification: POSIX 1003.1

#### 

**Description:** The set\_constraint\_handler\_s function sets the runtime-constraint handler to be *handler*. The runtime-constraint handler is the function called when a library function detect a runtime-constraint violation. Only the most recent handler registered with set\_constraint\_handler\_s is called when a runtime-constraint violation occurs.

When the handler is called, it is passed the following arguments:

- 1. A pointer to a character string describing the runtime-constraint violation.
- 2. A null pointer or a pointer to an implementation defined object. This implementation passes a null pointer.
- 3. If the function calling the handler has a return type declared as errno\_t, the return value of the function is passed. Otherwise, a positive value of type errno\_t is passed.

If no calls to the set\_constraint\_handler\_s function have been made, a default constraint handler is used. This handler will display an error message and abort the program.

If the *handler* argument to set\_constraint\_handler\_s is a null pointer, the default handler becomes the current constraint handler.

**Returns:** The set\_constraint\_handler\_s function returns a pointer to the previously registered handler.

See Also: abort\_handler\_s, ignore\_handler\_s

```
Example: #define __STDC_WANT_LIB_EXT1__ 1
    #include <stdlib.h>
    #include <stdio.h>

void my_handler( const char *msg, void *ptr, errno_t error )
    {
        fprintf( stderr, "rt-constraint violation caught :" );
        fprintf( stderr, msg );
        fprintf( stderr, "\n" );
}

void main( void )
    {
        constraint_handler_t old_handler;

        old_handler = set_constraint_handler_s( my_handler );
        if( getenv_s( NULL, NULL, 0, NULL ) ) {
```

printf( "getenv\_s failed\n" );

set\_constraint\_handler\_s( old\_handler );

produces the following:

rt-constraint violation caught: getenv\_s, name == NULL.
getenv\_s failed

**Classification:** TR 24731

**Systems:** All, Linux, RDOS, Netware

Synopsis: #include <graph.h>
 short \_FAR \_setactivepage( short pagenum );

**Description:** The \_setactivepage function selects the page (in memory) to which graphics output is written.

The page to be selected is given by the pagenum argument.

Only some combinations of video modes and hardware allow multiple pages of graphics to exist. When multiple pages are supported, the active page may differ from the visual page. The graphics information in the visual page determines what is displayed upon the screen. Animation may be accomplished by alternating the visual page. A graphics page can be constructed without affecting the screen by setting the active page to be different than the visual page.

The number of available video pages can be determined by using the \_getvideoconfig function. The default video page is 0.

**Returns:** The \_setactivepage function returns the number of the previous page when the active page is set

successfully; otherwise, a negative number is returned.

See Also: \_getactivepage, \_setvisualpage, \_getvisualpage, \_getvideoconfig

Example: #include <conio.h>
#include <graph.h>

```
main()
    int old_apage;
    int old_vpage;
    _setvideomode( _HRES16COLOR );
    old_apage = _getactivepage();
    old_vpage = _getvisualpage();
    /* draw an ellipse on page 0 */
   _setactivepage(0);
   _setvisualpage(0);
    _ellipse( _GFILLINTERIOR, 100, 50, 540, 150 );
    /* draw a rectangle on page 1 */
    _setactivepage(1);
    _rectangle( _GFILLINTERIOR, 100, 50, 540, 150 );
    getch();
    /* display page 1 */
    _setvisualpage(1);
    getch();
    _setactivepage( old_apage );
   _setvisualpage( old_vpage );
   _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

_setactivepage

Synopsis: #include <graph.h>
long \_FAR \_setbkcolor( long color );

**Description:** The \_setbkcolor function sets the current background color to be that of the *color* argument. In

text modes, the background color controls the area behind each individual character. In graphics

modes, the background refers to the entire screen. The default background color is 0.

When the current video mode is a graphics mode, any pixels with a zero pixel value will change to the color of the *color* argument. When the current video mode is a text mode, nothing will immediately change; only subsequent output is affected.

**Returns:** The \_setbkcolor function returns the previous background color.

See Also: \_getbkcolor

Example: #include <conio.h>
#include <graph.h>

```
long colors[ 16 ] = {
   _BLACK, _BLUE, _GREEN, _CYAN,
   _RED, _MAGENTA, _BROWN, _WHITE,
   _GRAY, _LIGHTBLUE, _LIGHTGREEN, _LIGHTCYAN,
   _LIGHTRED, _LIGHTMAGENTA, _YELLOW, _BRIGHTWHITE
} ;
main()
    long old_bk;
    int bk;
    _setvideomode( _VRES16COLOR );
    old_bk = _getbkcolor();
    for ( bk = 0; bk < 16; ++bk ) {
        _setbkcolor( colors[ bk ] );
        getch();
    _setbkcolor( old_bk );
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

Synopsis: #include <stdio.h>
 void setbuf( FILE \*fp, char \*buffer );

**Description:** The setbuf function can be used to associate a buffer with the file designated by fp. If this function is

used, it must be called after the file has been opened and before it has been read or written. If the argument *buffer* is NULL, then all input/output for the file *fp* will be completely unbuffered. If the argument *buffer* is not NULL, then it must point to an array that is at least BUFSIZ characters in

length, and all input/output will be fully buffered.

**Returns:** The setbuf function returns no value.

See Also: fopen, setvbuf

Example: #include <stdio.h>
#include <stdlib.h>

```
void main()
{
    char *buffer;
    FILE *fp;

    fp = fopen( "file", "r" );
    buffer = (char *) malloc( BUFSIZ );
    setbuf( fp, buffer );
    /* . */
    /* . */
    /* . */
    fclose( fp );
}
```

Classification: ISO C

Systems: DOS/16, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware

```
Synopsis: #include <graph.h>
    void _FAR _setcharsize( short height, short width );

void _FAR _setcharsize_w( double height, double width );
```

**Description:** The \_setcharsize functions set the character height and width to the values specified by the

arguments *height* and *width*. For the \_setcharsize function, the arguments *height* and *width* represent a number of pixels. For the \_setcharsize\_w function, the arguments *height* and *width* 

represent lengths along the y-axis and x-axis in the window coordinate system.

These sizes are used when displaying text with the \_grtext function. The default character sizes are dependent on the graphics mode selected, and can be determined by the \_gettextsettings function.

**Returns:** The \_setcharsize functions do not return a value.

See Also: \_grtext, \_gettextsettings

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    struct textsettings ts;

    _setvideomode( _VRES16COLOR );
    _gettextsettings( &ts );
    _grtext( 100, 100, "WATCOM" );
    _setcharsize( 2 * ts.height, 2 * ts.width );
    _grtext( 100, 300, "Graphics" );
    _setcharsize( ts.height, ts.width );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:

WATCOM

Graphics

Classification: PC Graphics

Systems: \_setcharsize - DOS

\_setcharsize\_w - DOS

```
Synopsis: #include <graph.h>
    void _FAR _setcharspacing( short space );

void _FAR _setcharspacing_w( double space );
```

 $\textbf{Description:} \quad \text{The $\_$setcharspacing functions set the current character spacing to have the value of the argument} \quad \\$ 

*space*. For the \_setcharspacing function, *space* represents a number of pixels. For the \_setcharspacing\_w function, *space* represents a length along the x-axis in the window coordinate

system.

The character spacing specifies the additional space to leave between characters when a text string is displayed with the \_grtext function. A negative value can be specified to cause the characters to be drawn closer together. The default value of the character spacing is 0.

**Returns:** The \_setcharspacing functions do not return a value.

See Also: \_grtext, \_gettextsettings

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    _setvideomode( _VRES16COLOR );
    _grtext( 100, 100, "WATCOM" );
    _setcharspacing( 20 );
    _grtext( 100, 300, "Graphics" );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:

```
WATCOM
Graphics
```

Classification: PC Graphics

**Systems:** 

\_setcharspacing - DOS \_setcharspacing\_w - DOS

**Description:** The \_setcliprgn function restricts the display of graphics output to the clipping region. This region

is a rectangle whose opposite corners are established by the physical points (x1,y1) and (x2,y2).

The \_setcliprgn function does not affect text output using the \_outtext and \_outmem functions. To control the location of text output, see the \_settextwindow function.

**Returns:** The \_setcliprgn function does not return a value.

See Also: \_\_settextwindow, \_\_setvieworg, \_\_setviewport

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    short x1, y1, x2, y2;

    _setvideomode( _VRES16COLOR );
    _getcliprgn( &x1, &y1, &x2, &y2 );
    _setcliprgn( 130, 100, 510, 380 );
    _ellipse( _GBORDER, 120, 90, 520, 390 );
    getch();
    _setcliprgn( x1, y1, x2, y2 );
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Synopsis: #include <graph.h>
 short \_FAR \_setcolor( short pixval );

**Description:** The \_setcolor function sets the pixel value for the current color to be that indicated by the *pixval* 

argument. The current color is only used by the functions that produce graphics output; text output with \_outtext uses the current text color (see the \_settextcolor function). The default color value is

one less than the maximum number of colors in the current video mode.

**Returns:** The \_setcolor function returns the previous value of the current color.

See Also: \_getcolor, \_settextcolor

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    int col, old_col;

    _setvideomode( _VRES16COLOR );
    old_col = _getcolor();
    for( col = 0; col < 16; ++col ) {
        _setcolor( col );
        _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
        getch();
    }
    _setcolor( old_col );
    _setvideomode( _DEFAULTMODE );
}</pre>
```

Classification: PC Graphics

#### **Synopsis:**

### **Description:**

The environment list consists of a number of environment names, each of which has a value associated with it. Entries can be added to the environment list with the DOS set command or with the setenv function. All entries in the environment list can be displayed by using the DOS set command with no arguments. A program can obtain the value for an environment variable by using the getenv function.

The setenv function searches the environment list for an entry of the form name=value. If no such string is present, setenv adds an entry of the form name=newvalue to the environment list. Otherwise, if the *overwrite* argument is non-zero, setenv either will change the existing value to newvalue or will delete the string name=value and add the string name=newvalue.

If the *newvalue* pointer is NULL, all strings of the form *name=value* in the environment list will be deleted.

The value of the pointer environ may change across a call to the setenv function.

The setenv function will make copies of the strings associated with *name* and *newvalue*.

The matching is case-insensitive; all lowercase letters are treated as if they were in upper case.

Entries can also be added to the environment list with the DOS set command or with the puterny or seteny functions. All entries in the environment list can be obtained by using the geteny function.

To assign a string to a variable and place it in the environment list:

```
C>SET INCLUDE=C:\WATCOM\H
```

To see what variables are in the environment list, and their current assignments:

```
C>SET
COMSPEC=C:\COMMAND.COM
PATH=C:\;C:\WATCOM
INCLUDE=C:\WATCOM\H
C>
```

The \_setenv function is identical to setenv. Use \_setenv for ANSI naming conventions.

The \_wsetenv function is a wide character version of setenv that operates with wide character strings.

## **Returns:**

The setenv function returns zero upon successful completion. Otherwise, it will return a non-zero value and set errno to indicate the error.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

> **ENOMEM** Not enough memory to allocate a new environment string.

See Also: exec..., \_wexec..., clearenv, getenv, getenv\_s, putenv, \_searchenv, unsetenv, \_wgetenv, \_wputenv, \_wsearchenv, \_wsetenv, \_wunsetenv, spawn..., \_wspawn..., system, \_wsystem

**Example:** The following will change the string assigned to INCLUDE and then display the new string.

```
#include <stdio.h>
#include <stdlib.h>
void main()
 {
    char *path;
    if( setenv( "INCLUDE", "D:\\WATCOM\\H", 1 ) == 0 )
      if( (path = getenv( "INCLUDE" )) != NULL )
        printf( "INCLUDE=%s\n", path );
  }
```

**Classification:** WATCOM

\_setenv conforms to ANSI naming conventions

setenv - All, Linux, RDOS **Systems:** 

\_setenv - All, Linux, RDOS

\_wsetenv - All, Linux

Synopsis: #include <graph.h>
 void \_FAR \_setfillmask( char \_FAR \*mask );

**Description:** The \_setfillmask function sets the current fill mask to the value of the argument *mask*. When the value of the *mask* argument is NULL, there will be no fill mask set.

The fill mask is an eight-byte array which is interpreted as a square pattern (8 by 8) of 64 bits. Each bit in the mask corresponds to a pixel. When a region is filled, each point in the region is mapped onto the fill mask. When a bit from the mask is one, the pixel value of the corresponding point is set using the current plotting action with the current color; when the bit is zero, the pixel value of that point is not affected.


When the fill mask is not set, a fill operation will set all points in the fill region to have a pixel value of the current color. By default, no fill mask is set.

**Returns:** The \_setfillmask function does not return a value.

See Also: \_getfillmask,\_ellipse,\_floodfill,\_rectangle,\_polygon,\_pie,\_setcolor, \_setplotaction

Example: #include <conio.h>
#include <graph.h>

produces the following:



Classification: PC Graphics

Synopsis: #include <graph.h>

short \_FAR \_setfont( char \_FAR \*opt );

**Description:** 

The \_setfont function selects a font from the list of registered fonts (see the \_registerfonts function). The font selected becomes the current font and is used whenever text is displayed with the \_outgtext function. The function will fail if no fonts have been registered, or if a font cannot be found that matches the given characteristics.

The argument *opt* is a string of characters specifying the characteristics of the desired font. These characteristics determine which font is selected. The options may be separated by blanks and are not case-sensitive. Any number of options may be specified and in any order. The available options are:

*hX* character height X (in pixels)

wX character width X (in pixels)

f choose a fixed-width font

p choose a proportional-width font

r choose a raster (bit-mapped) font

v choose a vector font

**b** choose the font that best matches the options

*nX* choose font number X (the number of fonts is returned by the

\_registerfonts function)

*t'facename'* choose a font with specified facename

The facename option is specified as a "t" followed by a facename enclosed in single quotes. The available facenames are:

**Courier** fixed-width raster font with serifs

*Helv* proportional-width raster font without serifs

**Tms Rmn** proportional-width raster font with serifs

**Script** proportional-width vector font that appears similar to hand-writing

**Modern** proportional-width vector font without serifs

**Roman** proportional-width vector font with serifs

When "nX" is specified to select a particular font, the other options are ignored.

If the best fit option ("b") is specified, \_setfont will always be able to select a font. The font chosen will be the one that best matches the options specified. The following precedence is given to the options when selecting a font:

1. Pixel height (higher precedence is given to heights less than the specified height)

- 2. Facename
- 3. Pixel width
- 4. Font type (fixed or proportional)

When a pixel height or width does not match exactly and a vector font has been selected, the font will be stretched appropriately to match the given size.

**Returns:** The \_setfont function returns zero if successful; otherwise, (-1) is returned.

See Also: \_\_registerfonts, \_unregisterfonts, \_getfontinfo, \_outgtext, \_\_getgtextextent, \_setgtextvector, \_getgtextvector

Example: #include <conio.h>

```
#include <stdio.h>
#include <graph.h>
main()
    int i, n;
    char buf[ 10 ];
    _setvideomode( _VRES16COLOR );
    n = _registerfonts( "*.fon" );
    for( i = 0; i < n; ++i ) {
        sprintf( buf, "n%d", i );
        _setfont( buf );
        _moveto( 100, 100 );
        _outgtext( "WATCOM Graphics" );
        getch();
        _clearscreen( _GCLEARSCREEN );
    _unregisterfonts();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

Synopsis: #include <graph.h>
 struct xycoord \_FAR \_setgtextvector( short x, short y );

**Description:** The \_setgtextvector function sets the orientation for text output used by the \_outgtext

function to the vector specified by the arguments (x,y). Each of the arguments can have a value of -1, 0 or 1, allowing for text to be displayed at any multiple of a 45-degree angle. The default text

orientation, for normal left-to-right text, is the vector (1,0).

**Returns:** The \_setgtextvector function returns, as an xycoord structure, the previous value of the text

orientation vector.

See Also: \_\_registerfonts, \_unregisterfonts, \_setfont, \_getfontinfo, \_outgtext,

\_getgtextextent, \_getgtextvector

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    struct xycoord old_vec;

    _setvideomode( _VRES16COLOR );
    old_vec = _getgtextvector();
    _setgtextvector( 0, -1 );
    _moveto( 100, 100 );
    _outgtext( "WATCOM Graphics" );
    _setgtextvector( old_vec.xcoord, old_vec.ycoord );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

Synopsis: #include <netdb.h>

void sethostent( int stayopen );

**Description:** The sethostent function opens the network host database at /etc/hosts and sets the position for

reading to the first entry. If the network host database is already open, the position is reset to the first entry. The *stayopen* argument, if non-zero, will cause the database to remain open after subsequent

calls to the gethostent function.

See Also: gethostent, endhostent

Classification: POSIX 1003.1

Synopsis: #include <setjmp.h>
 int setjmp( jmp\_buf env );

**Description:** The set jmp function saves its calling environment in its jmp\_buf argument, for subsequent use by the longjmp function.

In some cases, error handling can be implemented by using setjmp to record the point to which a return will occur following an error. When an error is detected in a called function, that function uses longjmp to jump back to the recorded position. The original function which called setjmp must still be active (it cannot have returned to the function which called it).

Special care must be exercised to ensure that any side effects that are left undone (allocated memory, opened files, etc.) are satisfactorily handled.

**Returns:** The set jmp function returns zero when it is initially called. The return value will be non-zero if the

return is the result of a call to the longjmp function. An if statement is often used to handle these two returns. When the return value is zero, the initial call to setjmp has been made; when the return

value is non-zero, a return from a long imp has just occurred.

See Also: longjmp

Example: #include <stdio.h>
#include <setjmp.h>

```
jmp_buf env;

rtn()
    {
        printf( "about to longjmp\n" );
        longjmp( env, 14 );
    }

void main()
    {
        int ret_val = 293;

        if( 0 == ( ret_val = setjmp( env ) ) ) {
            printf( "after setjmp %d\n", ret_val );
            rtn();
            printf( "back from rtn %d\n", ret_val );
        }
        elso {
```

printf( "back from longjmp %d\n", ret\_val );

produces the following:

}

after setjmp 0 about to longjmp back from longjmp 14

**Classification:** ISO C

Systems: MACRO

setjmp

Synopsis: #include <graph.h>

void \_FAR \_setlinestyle( unsigned short style );

**Description:** The \_setlinestyle function sets the current line-style mask to the value of the *style* argument.

The line-style mask determines the style by which lines and arcs are drawn. The mask is treated as an array of 16 bits. As a line is drawn, a pixel at a time, the bits in this array are cyclically tested. When a bit in the array is 1, the pixel value for the current point is set using the current color according to the current plotting action; otherwise, the pixel value for the point is left unchanged. A solid line would result from a value of 0xFFFF and a dashed line would result from a value of 0xF0F0

The default line style mask is 0xFFFF

**Returns:** The \_setlinestyle function does not return a value.

See Also: \_getlinestyle, \_lineto, \_rectangle, \_polygon, \_setplotaction

Example: #include <conio.h>
#include <graph.h>

```
#define DASHED 0xf0f0

main()
{
    unsigned old_style;

    _setvideomode( _VRES16COLOR );
    old_style = _getlinestyle();
    _setlinestyle( DASHED );
    _rectangle( _GBORDER, 100, 100, 540, 380 );
    _setlinestyle( old_style );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

Synopsis: #include <locale.h>

```
char *setlocale( int category, const char *locale );
wchar_t *_wsetlocale( int category, const wchar_t *locale);
```

**Description:** 

The setlocale function selects a portion of a program's *locale* according to the category given by *category* and the locale specified by *locale*. A *locale* affects the collating sequence (the order in which characters compare with one another), the way in which certain character-handling functions operate, the decimal-point character that is used in formatted input/output and string conversion, and the format and names used in the time string produced by the strftime function.

Potentially, there may be many such environments. Open Watcom C/C++ supports only the "C" locale and so invoking this function will have no effect upon the behavior of a program at present. Specifying the "POSIX" locale is supported for POSIX compatibility and equivalent to specifying the "C" locale.

The possible values for the argument *category* are as follows:

Category	Meaning
LC_ALL	select entire environment
LC_COLLATE	select collating sequence
LC_CTYPE	select the character-handling
LC_MONETARY	select monetary formatting information
LC_NUMERIC	select the numeric-format environment
LC_TIME	select the time-related environment

At the start of a program, the equivalent of the following statement is executed.

```
setlocale( LC_ALL, "C" );
```

The \_wsetlocale function is a wide character version of setlocale that operates with wide character strings.

**Returns:** 

If the selection is successful, a string is returned to indicate the locale that was in effect before the function was invoked; otherwise, a NULL pointer is returned.

See Also: strcoll, strftime, strxfrm

**Example:** 

```
#include <stdio.h>
#include <string.h>
#include <locale.h>

char src[] = { "A sample STRING" };
char dst[20];

void main()
    {
        char *prev_locale;
        size_t len;
```

```
/* set native locale */
prev_locale = setlocale( LC_ALL, "" );
printf( "%s\n", prev_locale );
len = strxfrm( dst, src, 20 );
printf( "%s (%u)\n", dst, len );
}

produces the following:

C
A sample STRING (15)

Classification: ISO C

Systems: setlocale - All, Linux, RDOS, Netware
_wsetlocale - All, Linux
```

Synopsis: #include <math.h>
 void \_set\_matherr( int (\*rtn)( struct \_exception \*err\_info ) )

#### **Description:**

The default matherr function supplied in the library can be replaced so that the application can handle mathematical errors. To do this, the \_set\_matherr function must be called with the address of the new mathematical error handling routine.

**Note:** Under some systems, the default math error handler can be replaced by providing a user-written function of the same name, matherr, and using linking strategies to replace the default handler.

A program may contain a user-written version of matherr to take any appropriate action when an error is detected. When zero is returned by the user-written routine, an error message will be printed upon stderr and errno will be set as was the case with the default function. When a non-zero value is returned, no message is printed and errno is not changed. The value err\_info->retval is used as the return value for the function in which the error was detected.

When called, the user-written math error handler is passed a pointer to a structure of type struct \_exception which contains information about the error that has been detected:

The type field will contain one of the following values:

Value	Meaning
DOMAIN	A domain error has occurred, such as sqrt (-1e0).
SING	A singularity will result, such as pow ( $0e0, -2$ ).
OVERFLOW	An overflow will result, such as pow (10e0, 100).
UNDERFLOW	An underflow will result, such as pow(10e0,-100).
TLOSS	Total loss of significance will result, such as exp (1000).
PLOSS	Partial loss of significance will result, such as sin(10e70).

The name field points to a string containing the name of the function which detected the error. The fields arg1 and arg2 (if required) give the values which caused the error. The field retval contains the value which will be returned by the function. This value may be changed by a user-supplied version of the \_set\_matherr function.

**Returns:** The \_set\_matherr function returns no value.

```
Example:
           #include <stdio.h>
           #include <string.h>
           #include <math.h>
           /* Demonstrate error routine in which negative */
           /* arguments to "sqrt" are treated as positive */
           int my_matherr( struct _exception *err )
               if( strcmp( err->name, "sqrt" ) == 0 ) {
                   if( err->type == DOMAIN ) {
                       err->retval = sqrt( -(err->arg1) );
                       return( 1 );
                   } else
                       return(0);
               } else
                   return(0);
           }
           void main( void )
              _set_matherr( &my_matherr);
              printf( %e\n, sqrt( -5e0 ) );
               exit( 0 );
           }
```

**Classification:** WATCOM

**Systems:** Math

Synopsis: #include <mbctype.h>
 int \_setmbcp( int codepage );

**Description:** The \_setmbcp function sets the current code page number.

**Returns:** The \_setmbcp function returns zero if the code page is set successfully. If an invalid code page value

is supplied for *codepage*, the function returns -1 and the code page setting is unchanged.

See Also: \_\_getmbcp, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_ismbbalnum,

\_ismbbalpha, \_ismbbgraph, \_ismbbkalnum, \_ismbbkalpha, \_ismbbkana, \_ismbbkprint, \_ismbbkpunct, \_ismbblead, \_ismbbprint, \_ismbbpunct,

\_ismbbtrail, \_mbbtombc, \_mbcjistojms, \_mbcjmstojis, \_mbctombb, \_mbbtype,

\_mbsbtype

Example: #include <stdio.h>
#include <mbctype.h>

void main()
{
 printf( "%d\n", \_setmbcp( 932 ) );
 printf( "%d\n", \_getmbcp() );
}

produces the following:

0 932

**Classification:** WATCOM

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS

#### **Synopsis:**

```
#include <io.h>
#include <fcntl.h>
int _setmode( int handle, int mode );

** deprecated **
int setmode( int handle, int mode );
```

## **Description:**

The \_setmode function sets, at the operating system level, the translation mode to be the value of *mode* for the file whose file handle is given by *handle*. The mode, defined in the <fcntl.h> header file, can be one of:

### Mode

 $O_{TEXT}$ 

On input, a carriage-return character that immediately precedes a linefeed character is removed from the data that is read. On output, a carriage-return character is inserted before each linefeed character.

**O\_BINARY** Data is read or written unchanged.

Meaning

The setmode function is deprecated, use \_setmode instead.

#### **Returns:**

If successful, the \_setmode function returns the previous mode that was set for the file; otherwise, -1 is returned. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

\_chsize, close, creat, dup, dup2, \_eof, exec..., fdopen, \_filelength, fileno, fstat, \_grow\_handles, isatty, lseek, open, read, \_sopen, stat, \_tell, write, umask

# **Example:**

**Classification:** WATCOM

**Systems:** 

\_setmode - All, Linux, RDOS, Netware setmode - All, Linux, RDOS, Netware


Synopsis: #include <netdb.h>

void setnetent( int stayopen );

**Description:** The setnetent function opens or rewinds the network database for subsequent access by the

getnetent function. If stayopen is non-zero, the network database will remain open between calls to

the getnetent function. The database can be closed when endnetent is called.

This function is not thread-safe. Other calls to this function or to other functions accessing the

hostname database may affect the return value from this function.

See Also: getnetent, endnetent, getnetbyname, getnetbyaddr

Classification: POSIX 1003.1

Synopsis: #include <new.h>

PFV set\_new\_handler( PFV pNewHandler );
PFU \_set\_new\_handler( PFU pNewHandler );

**Description:** 

The set\_new\_handler functions are used to transfer control to a user-defined error handler if the operator fails to allocate memory. The argument *pNewHandler* is the name of a function of type PFV or PFU.

Type	Description
PFV	Pointer to a function that returns void (i.e., returns nothing) and takes an argument of type void (i.e., takes no argument).
PFU	Pointer to a function that returns int and takes an argument of type unsigned which is the amount of space to be allocated.

In a multi-threaded environment, handlers are maintained separately for each process and thread. Each new process lacks installed handlers. Each new thread gets a copy of its parent thread's new handlers. Thus, each process and thread is in charge of its own free-store error handling.

**Returns:** 

The set\_new\_handler functions return a pointer to the previous error handler so that the previous error handler can be reinstated at a later time.

The error handler specified as the argument to \_set\_new\_handler returns zero indicating that further attempts to allocate memory should be halted or non-zero to indicate that an allocation request should be re-attempted.

See Also: \_bfreeseg, \_bheapseg, calloc, free, malloc, realloc

**Example:** 

```
#include <stdio.h>
#include <new.h>

#if defined(__386__)
const size_t MemBlock = 8192;
#else
const size_t MemBlock = 2048;
#endif

/*
    Pre-allocate a memory block for demonstration
    purposes. The out-of-memory handler will return
    it to the system so that "new" can use it.
*/

long *failsafe = new long[MemBlock];
```

```
/*
   Declare a customized function to handle memory
   allocation failure.
int out_of_memory_handler( unsigned size )
   printf( "Allocation failed, " );
   printf( "%u bytes not available.\n", size );
    /* Release pre-allocated memory if we can */
    if( failsafe == NULL ) {
     printf( "Halting allocation.\n" );
      /* Tell new to stop allocation attempts */
      return(0);
    } else {
      delete failsafe;
      failsafe = NULL;
      printf( "Retrying allocation.\n" );
      /* Tell new to retry allocation attempt */
      return(1);
  }
void main( void )
  {
   int i;
    /* Register existence of a new memory handler */
   _set_new_handler( out_of_memory_handler );
   long *pmemdump = new long[MemBlock];
    for( i=1 ; pmemdump != NULL; i++ ) {
      pmemdump = new long[MemBlock];
      if( pmemdump != NULL )
        printf( "Another block allocated %d\n", i );
  }
```

**Classification:** WATCOM

set\_new\_handler - All, Netware
\_set\_new\_handler - All, Netware

**Systems:** 

```
Synopsis: #include <graph.h>
     short _FAR _setpixel( short x, short y );

short _FAR _setpixel_w( double x, double y );
```

**Description:** The \_setpixel function sets the pixel value of the point (x,y) using the current plotting action with the current color. The \_setpixel function uses the view coordinate system. The \_setpixel\_w function uses the window coordinate system.

A pixel value is associated with each point. The values range from 0 to the number of colors (less one) that can be represented in the palette for the current video mode. The color displayed at the point is the color in the palette corresponding to the pixel number. For example, a pixel value of 3 causes the fourth color in the palette to be displayed at the point in question.

**Returns:** The \_setpixel functions return the previous value of the indicated pixel if the pixel value can be set; otherwise, (-1) is returned.

See Also: \_getpixel, \_setcolor, \_setplotaction

Example: #include <conio.h>
#include <graph.h>
#include <stdlib.h>

main()

```
int x, y;
unsigned i;

_setvideomode( _VRES16COLOR );
_rectangle( _GBORDER, 100, 100, 540, 380 );
for( i = 0; i <= 60000; ++i ) {
    x = 101 + rand() % 439;
    y = 101 + rand() % 279;
    _setcolor( _getpixel( x, y ) + 1 );
    _setpixel( x, y );
}
getch();
_setvideomode( _DEFAULTMODE );</pre>
```

Classification: PC Graphics

Systems: \_setpixel - DOS \_setpixel\_w - DOS

Synopsis: #include <graph.h>
 short \_FAR \_setplotaction( short action );

**Description:** The \_setplotaction function sets the current plotting action to the value of the *action* argument.

The drawing functions cause pixels to be set with a pixel value. By default, the value to be set is obtained by replacing the original pixel value with the supplied pixel value. Alternatively, the replaced value may be computed as a function of the original and the supplied pixel values.

The plotting action can have one of the following values:

**\_GPSET** replace the original screen pixel value with the supplied pixel value

**\_GAND** replace the original screen pixel value with the *bitwise and* of the original

pixel value and the supplied pixel value

**\_GOR** replace the original screen pixel value with the *bitwise or* of the original pixel

value and the supplied pixel value

**\_GXOR** replace the original screen pixel value with the *bitwise exclusive-or* of the

original pixel value and the supplied pixel value. Performing this operation twice will restore the original screen contents, providing an efficient method

to produce animated effects.

**Returns:** The previous value of the plotting action is returned.

See Also: \_getplotaction

Example: #include <conio.h>
#include <graph.h>

```
main()
{
    int old_act;

    _setvideomode( _VRES16COLOR );
    old_act = _getplotaction();
    _setplotaction( _GPSET );
    _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
    getch();
    _setplotaction( _GXOR );
    _rectangle( _GFILLINTERIOR, 100, 100, 540, 380 );
    getch();
    _setplotaction( old_act );
    _setplotaction( old_act );
    _setvideomode( _DEFAULTMODE );
```

**Classification:** PC Graphics

_setplotaction				
	 	 	<del></del> -	

Synopsis: #include <netdb.h>

void setprotoent( int stayopen );

Description: The setprotoent function opens or rewinds the protocol database to allow reading starting at the

first entry. If stayopen is non-zero, the database will remain open between subsequent calls to

getprotoent until the endprotoent function is called.

This function is not thread-safe. Other calls to this function or to other functions accessing the protocol

database may affect the return value from this function.

See Also: getprotoent, endprotoent, getprotobyname, getprotobynumber

Classification: POSIX 1003.1

Synopsis: #include <pwd.h>
 void setpwent( void );

**Description:** The setpwent function returns pointer for iterating over the system's password database to the first

entry. It is normally called prior to using any of the POSIX functions that access the password database

to ensure starting at the first entry.

See Also: getpwent, endpwent, getpwnam, getpwuid

**Example:** The following program will print out each user and their user ID in the system's password database

```
#include <stdio.h>
#include <pwd.h>

void main()
{
    struct passwd *pw;
    setpwent();

    while((pw = getpwent()) != NULL) {
        printf("User id %d is %s\n", (int)pw->pw_uid, pw->pw_name);
    }

    endpwent();
}
```

Classification: POSIX 1003.1

Synopsis: #include <netdb.h>

void setservent( int stayopen );

**Description:** The setservent function opens or rewinds the service database. If *stayopen* is non-zero, the

database will be kept open between calls to getservent until endservent is called to close the

database.

This function is not thread-safe. Other calls to this function or to other functions accessing the

hostname database may affect the return value from this function.

See Also: getservent, endservent, getservbyname, getservbyport

Classification: POSIX 1003.1

void \_FAR \_settextalign( short horiz, short vert );

**Description:** 

The \_settextalign function sets the current text alignment to the values specified by the arguments horiz and vert. When text is displayed with the \_grtext function, it is aligned (justified) horizontally and vertically about the given point according to the current text alignment settings.

The horizontal component of the alignment can have one of the following values:

**\_NORMAL** use the default horizontal alignment for the current setting of the text path

**\_LEFT** the text string is left justified at the given point

**\_CENTER** the text string is centred horizontally about the given point

**\_RIGHT** the text string is right justified at the given point

The vertical component of the alignment can have one of the following values:

**\_NORMAL** use the default vertical alignment for the current setting of the text path

**\_TOP** the top of the text string is aligned at the given point

**\_CAP** the cap line of the text string is aligned at the given point

\_HALF the text string is centred vertically about the given point

**\_BASE** the base line of the text string is aligned at the given point

**\_BOTTOM** the bottom of the text string is aligned at the given point

The default is to use \_LEFT alignment for the horizontal component unless the text path is \_PATH\_LEFT, in which case \_RIGHT alignment is used. The default value for the vertical component is \_TOP unless the text path is \_PATH\_UP, in which case \_BOTTOM alignment is used.

**Returns:** The \_settextalign function does not return a value.

See Also: \_grtext, \_gettextsettings

Example:

```
#include <conio.h>
#include <graph.h>

main()
{
    _setvideomode( _VRES16COLOR );
    _grtext( 200, 100, "WATCOM" );
    _setpixel( 200, 100 );
    _settextalign( _CENTER, _HALF );
    _grtext( 200, 200, "Graphics" );
    _setpixel( 200, 200 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:

WATCOM

Graphics

Classification: PC Graphics

short \_FAR \_settextcolor( short pixval );

**Description:** 

The \_settextcolor function sets the current text color to be the color indicated by the pixel value of the *pixval* argument. This is the color value used for displaying text with the \_outtext and \_outmem functions. Use the \_setcolor function to change the color of graphics output. The default text color value is set to 7 whenever a new video mode is selected.

The pixel value *pixval* is a number in the range 0-31. Colors in the range 0-15 are displayed normally. In text modes, blinking colors are specified by adding 16 to the normal color values. The following table specifies the default colors in color text modes.

Pixel value	Color	Pixel value	Color
0	Black	8	Gray
1	Blue	9	Light Blue
2	Green	10	Light Green
3	Cyan	11	Light Cyan
4	Red	12	Light Red
5	Magenta	13	Light Magenta
6	Brown	14	Yellow
7	White	15	Bright White

**Returns:** The \_settextcolor function returns the pixel value of the previous text color.

See Also: \_gettextcolor, \_outtext, \_outmem, \_setcolor

Example:

```
#include <conio.h>
#include <graph.h>
main()
    int old_col;
    long old_bk;
    _setvideomode( _TEXTC80 );
    old_col = _gettextcolor();
    old_bk = _getbkcolor();
    _settextcolor(7);
    _setbkcolor( _BLUE );
    _outtext( " WATCOM \nGraphics");
    _settextcolor( old_col );
    _setbkcolor( old_bk );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

		_settextcolor
		_

short \_FAR \_settextcursor( short cursor );

**Description:** The \_settextcursor function sets the attribute, or shape, of the cursor in text modes. The

argument *cursor* specifies the new cursor shape. The cursor shape is selected by specifying the top and bottom rows in the character matrix. The high byte of *cursor* specifies the top row of the cursor; the

low byte specifies the bottom row.

Some typical values for cursor are:

Cursor	Shape
0x0607 0x0007	normal underline cursor full block cursor
0x0407	half-height block cursor
0x2000	no cursor

**Returns:** The \_settextcursor function returns the previous cursor shape when the shape is set successfully;

otherwise, (-1) is returned.

**See Also:** \_gettextcursor, \_displaycursor

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    int old_shape;

    old_shape = _gettextcursor();
    _settextcursor( 0x0007 );
    _outtext( "\nBlock cursor" );
    getch();
    _settextcursor( 0x0407 );
    _outtext( "\nHalf height cursor" );
    getch();
    _settextcursor( 0x2000 );
    _outtext( "\nNo cursor" );
    getch();
    _settextcursor( old_shape );
}
```

**Classification:** PC Graphics

_settextcursor

void \_FAR \_settextorient( short vecx, short vecy );

**Description:** The \_settextorient function sets the current text orientation to the vector specified by the

arguments (vecx, vecy). The text orientation specifies the direction of the base-line vector when a

text string is displayed with the \_grtext function. The default text orientation, for normal

left-to-right text, is the vector (1,0).


**Returns:** The \_settextorient function does not return a value.

**See Also:** \_grtext, \_gettextsettings

Example: #include <conio.h>
#include <graph.h>

```
main()
{
    _setvideomode( _VRES16COLOR );
    _grtext( 200, 100, "WATCOM" );
    _settextorient( 1, 1 );
    _grtext( 200, 200, "Graphics" );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

_settextories	nt

Synopsis: #include <graph.h>
 void \_FAR \_settextpath( short path );

**Description:** The \_settextpath function sets the current text path to have the value of the *path* argument. The

text path specifies the writing direction of the text displayed by the <code>\_grtext</code> function. The argument

can have one of the following values:

**\_PATH\_RIGHT** subsequent characters are drawn to the right of the previous character

**\_PATH\_LEFT** subsequent characters are drawn to the left of the previous character

**\_PATH\_UP** subsequent characters are drawn above the previous character

\_PATH\_DOWN subsequent characters are drawn below the previous character

The default value of the text path is \_PATH\_RIGHT.

**Returns:** The \_settextpath function does not return a value.

**See Also:** \_grtext, \_gettextsettings

Example: #include <conio.h>
#include <graph.h>

```
main()
{
    _setvideomode( _VRES16COLOR );
    _grtext( 200, 100, "WATCOM" );
    _settextpath( _PATH_DOWN );
    _grtext( 200, 200, "Graphics" );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

produces the following:



Classification: PC Graphics

**Description:** 

The \_settextposition function sets the current output position for text to be (row, col) where this position is in terms of characters, not pixels.

The text position is relative to the current text window. It defaults to the top left corner of the screen, (1,1), when a new video mode is selected, or when a new text window is set. The position is updated as text is drawn with the \_outtext and \_outmem functions.

Note that the output position for graphics output differs from that for text output. The output position for graphics output can be set by use of the \_moveto function.

Also note that output to the standard output file, stdout, is line buffered by default. It may be necessary to flush the output stream using fflush ( stdout ) after a printf call if your output does not contain a newline character. Mixing of calls to \_outtext and printf may cause overlapped text since \_outtext uses the output position that was set by \_settextposition.

**Returns:** 

The \_settextposition function returns, as an rccoord structure, the previous output position for text.

See Also: \_\_gettextposition, \_outtext, \_outmem, \_settextwindow, \_moveto

**Example:** 

```
#include <conio.h>
#include <graph.h>

main()
{
    struct rccoord old_pos;

    _setvideomode( _TEXTC80 );
    old_pos = _gettextposition();
    _settextposition( 10, 40 );
    _outtext( "WATCOM Graphics" );
    _settextposition( old_pos.row, old_pos.col );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

**Description:** 

The \_settextrows function selects the number of rows of text displayed on the screen. The number of rows is specified by the argument *rows*. Computers equipped with EGA, MCGA and VGA adapters can support different numbers of text rows. The number of rows that can be selected depends on the current video mode and the type of monitor attached.

If the argument *rows* has the value *MAXTEXTROWS*, the maximum number of text rows will be selected for the current video mode and hardware configuration. In text modes the maximum number of rows is 43 for EGA adapters, and 50 for MCGA and VGA adapters. Some graphics modes will support 43 rows for EGA adapters and 60 rows for MCGA and VGA adapters.

**Returns:** 

The \_settextrows function returns the number of screen rows when the number of rows is set successfully; otherwise, zero is returned.

See Also: \_getvideoconfig, \_setvideomode, \_setvideomoderows

**Example:** 

```
#include <conio.h>
#include <graph.h>
#include <stdio.h>
int valid_rows[] = {
    14, 25, 28, 30,
    34, 43, 50, 60
};
main()
    int i, j, rows;
    char buf[ 80 ];
    for(i = 0; i < 8; ++i) {
        rows = valid rows[ i ];
        if( _settextrows( rows ) == rows ) {
            for( j = 1; j <= rows; ++j ) {
                sprintf( buf, "Line %d", j );
                _settextposition( j, 1 );
                _outtext( buf );
            getch();
    _setvideomode( _DEFAULTMODE );
```

Classification: PC Graphics

_settextrows			

**Description:** The \_settextwindow function sets the text window to be the rectangle with a top left corner at (row1, col1) and a bottom right corner at (row2, col2). These coordinates are in terms of characters not pixels.

The initial text output position is (1,1). Subsequent text positions are reported (by the \_gettextposition function) and set (by the \_outtext, \_outmem and \_settextposition functions) relative to this rectangle.

Text is displayed from the current output position for text proceeding along the current row and then downwards. When the window is full, the lines scroll upwards one line and then text is displayed on the last line of the window.

**Returns:** The \_settextwindow function does not return a value.

See Also: \_gettextposition, \_outtext, \_outmem, \_settextposition

Example: #include <conio.h>
#include <graph.h>

#include <stdio.h>

main()
{
 int i;
 short r1, c1, r2, c2;
 char buf[ 80 ];

 \_setvideomode( \_TEXTC80 );
 \_gettextwindow( &r1, &c1, &r2, &c2 );
 \_settextwindow( 5, 20, 20, 40 );
 for( i = 1; i <= 20; ++i ) {
 sprintf( buf, "Line %d\n", i );
 \_outtext( buf );
 }
 getch();
 \_settextwindow( r1, c1, r2, c2 );</pre>

\_setvideomode( \_DEFAULTMODE );

Classification: PC Graphics

}


**Synopsis:** 

**Description:** 

The setvbuf function can be used to associate a buffer with the file designated by fp. If this function is used, it must be called after the file has been opened and before it has been read or written. The argument mode determines how the file fp will be buffered, as follows:

Mode Meaning
 \_IOFBF causes input/output to be fully buffered.
 \_IOLBF causes output to be line buffered (the buffer will be flushed when a new-line character is written, when the buffer is full, or when input is requested on a line buffered or unbuffered stream).

 \_IONBF causes input/output to be completely unbuffered.

If the argument *buf* is not NULL, the array to which it points will be used instead of an automatically allocated buffer. The argument *size* specifies the size of the array.

**Returns:** 

The setvbuf function returns zero on success, or a non-zero value if an invalid value is given for *mode* or *size*.

See Also: fopen, setbuf

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>

void main()
{
   char *buf;
   FILE *fp;

   fp = fopen( "file", "r" );
   buf = (char *) malloc( 1024 );
   setvbuf( fp, buf, _IOFBF, 1024 );
}
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

setvbuf			

short \_FAR \_setvideomode( short mode );

**Description:** The \_setvideomode function sets the video mode according to the value of the *mode* argument. The value of *mode* can be one of the following:

Mode	Туре	S	ize	Э	Colors	Adapter
_MAXRESMODE _MAXCOLORMODE	(grap	hics n	noc	de w	ith most	nest resolution)
_DEFAULTMODE						ginal mode)
_TEXTBW40	М, Т			25	16	MDPA, HGC, VGA, SVGA
_TEXTC40	C,T	40	Х	25	16	CGA, EGA, MCGA, VGA, SVGA
_TEXTBW80	M, T	80	Х	25	16	MDPA, HGC, VGA, SVGA
_TEXTC80	C,T	80	Х	25	16	CGA, EGA, MCGA, VGA, SVGA
_MRES4COLOR	C,G	320	Х	200	4	CGA, EGA, MCGA, VGA, SVGA
_MRESNOCOLOR	C,G	320	Х	200	4	CGA, EGA, MCGA, VGA, SVGA
_HRESBW	C,G	640	Х	200	2	CGA, EGA, MCGA, VGA, SVGA
_TEXTMONO	M, T	80	Х	25	16	MDPA, HGC, VGA, SVGA
_HERCMONO	M,G	720	Х	350	2	HGC
_MRES16COLOR	C,G	320	Х	200	16	EGA, VGA, SVGA
_HRES16COLOR	C,G	640	Х	200	16	EGA, VGA, SVGA
_ERESNOCOLOR	M,G	640	Х	350	4	EGA, VGA, SVGA
_ERESCOLOR	C,G	640	Х	350	4/16	EGA, VGA, SVGA
_VRES2COLOR	C,G	640	Х	480	2	MCGA, VGA, SVGA
_VRES16COLOR	C,G	640	Х	480	16	VGA, SVGA
_MRES256COLOR	C,G	320	Х	200	256	MCGA, VGA, SVGA
_URES256COLOR	C,G	640	Х	400	256	SVGA
_VRES256COLOR	C,G	640	Х	480	256	SVGA
_SVRES16COLOR	C,G	800	Х	600	16	SVGA
_SVRES256COLOR	C,G	800	Х	600	256	SVGA
_XRES16COLOR	C,G	1024	х	768	16	SVGA
_XRES256COLOR	C,G	1024	Х	768	256	SVGA

In the preceding table, the Type column contains the following letters:

M	indicates monochrome; multiple colors are shades of grey
$\boldsymbol{C}$	indicates color
$\boldsymbol{G}$	indicates graphics mode; size is in pixels

T indicates text mode; size is in columns and rows of characters

The Adapter column contains the following codes:

MDPA	IBM Monochrome Display/Printer Adapter
CGA	IBM Color Graphics Adapter
EGA	IBM Enhanced Graphics Adapter
VGA	IBM Video Graphics Array
MCGA	IBM Multi-Color Graphics Array
HGC	Hercules Graphics Adapter
SVGA	SuperVGA adapters

# setvideomode

The modes \_MAXRESMODE and \_MAXCOLORMODE will select from among the video modes supported by the current graphics adapter the one that has the highest resolution or the greatest number of colors. The video mode will be selected from the standard modes, not including the SuperVGA modes.

Selecting a new video mode resets the current output positions for graphics and text to be the top left corner of the screen. The background color is reset to black and the default color value is set to be one less than the number of colors in the selected mode.

**Returns:** The \_setvideomode function returns the number of text rows when the new mode is successfully

selected; otherwise, zero is returned.

See Also: \_getvideoconfig, \_settextrows, \_setvideomoderows

```
Example:
           #include <conio.h>
           #include <graph.h>
           #include <stdio.h>
           #include <stdlib.h>
           main()
                int mode;
               struct videoconfig vc;
               char buf[ 80 ];
               _getvideoconfig( &vc );
/* select "best" video mode */
                switch( vc.adapter ) {
               case \_VGA:
               case _SVGA :
                   mode = _VRES16COLOR;
                   break;
               case _MCGA :
                   mode = _MRES256COLOR;
                   break;
               case _EGA :
                    if( vc.monitor == _MONO ) {
                        mode = _ERESNOCOLOR;
                    } else {
                        mode = _ERESCOLOR;
                    }
                    break;
                case _CGA :
                   mode = \_MRES4COLOR;
                    break;
                case _HERCULES :
                    mode = _HERCMONO;
                    break;
                default :
                    puts( "No graphics adapter" );
                    exit(1);
                if( _setvideomode( mode ) ) {
                    _getvideoconfig( &vc );
                    sprintf( buf, "%d x %d x %d\n", vc.numxpixels,
                                      vc.numypixels, vc.numcolors );
                    _outtext( buf );
                    getch();
                    _setvideomode( _DEFAULTMODE );
           }
```

Classification: PC Graphics

**Synopsis:** #include <graph.h> short \_FAR \_setvideomoderows( short mode, short rows );

**Description:** The \_setvideomoderows function selects a video mode and the number of rows of text displayed

on the screen. The video mode is specified by the argument mode and is selected with the

\_setvideomode function. The number of rows is specified by the argument rows and is selected

with the \_settextrows function.

Computers equipped with EGA, MCGA and VGA adapters can support different numbers of text rows. The number of rows that can be selected depends on the video mode and the type of monitor attached.

**Returns:** The \_setvideomoderows function returns the number of screen rows when the mode and number of rows are set successfully; otherwise, zero is returned.

See Also:

\_getvideoconfig, \_setvideomode, \_settextrows

**Example:** #include <conio.h> #include <graph.h> #include <stdio.h> main() int rows; char buf[ 80 ]; rows = \_setvideomoderows( \_TEXTC80, \_MAXTEXTROWS ); if( rows != 0 ) { sprintf( buf, "Number of rows is %d\n", rows ); \_outtext( buf ); getch(); \_setvideomode( \_DEFAULTMODE ); }

Classification: PC Graphics

Synopsis: #include <graph.h>
struct xycoord \_FAR \_setvieworg( short x, short y );

**Description:** The  $\_$ setvieworg function sets the origin of the view coordinate system, (0,0), to be located at

the physical point (x,y) . This causes subsequently drawn images to be translated by the amount

(x,y).

**Note:** In previous versions of the software, the \_setvieworg function was called \_setlogorg.

**Returns:** The \_setvieworg function returns, as an xycoord structure, the physical coordinates of the

previous origin.

See Also: \_getviewcoord, \_getphyscoord, \_setcliprgn, \_setviewport

Example: #include <conio.h>

```
#include <graph.h>
main()
{
    _setvideomode( _VRES16COLOR );
    _setvieworg( 320, 240 );
    _ellipse( _GBORDER, -200, -150, 200, 150 );
    getch();
    _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

**Description:** The \_setviewport function restricts the display of graphics output to the clipping region and then sets the origin of the view coordinate system to be the top left corner of the region. This region is a rectangle whose opposite corners are established by the physical points (x1,y1) and (x2,y2).

The \_setviewport function does not affect text output using the \_outtext and \_outmem functions. To control the location of text output, see the \_settextwindow function.

**Returns:** The \_setviewport function does not return a value.

See Also: \_setcliprgn, \_setvieworg, \_settextwindow, \_setwindow

Example: #include <conio.h>
#include <graph.h>

#define XSIZE 380
#define YSIZE 280

main()
{
 \_\_setvideomode( \_VRES16COLOR );
 \_\_setviewport( 130, 100, 130 + XSIZE, 100 + YSIZE );
 \_\_ellipse( \_GBORDER, 0, 0, XSIZE, YSIZE );
 getch();
 \_\_setvideomode( \_DEFAULTMODE );
}

Classification: PC Graphics

Synopsis: #include <graph.h>
 short \_FAR \_setvisualpage( short pagenum );

**Description:** The \_setvisualpage function selects the page (in memory) from which graphics output is displayed. The page to be selected is given by the *pagenum* argument.

Only some combinations of video modes and hardware allow multiple pages of graphics to exist. When multiple pages are supported, the active page may differ from the visual page. The graphics information in the visual page determines what is displayed upon the screen. Animation may be accomplished by alternating the visual page. A graphics page can be constructed without affecting the screen by setting the active page to be different than the visual page.

The number of available video pages can be determined by using the \_getvideoconfig function. The default video page is 0.

**Returns:** The \_setvisualpage function returns the number of the previous page when the visual page is set successfully; otherwise, a negative number is returned.

See Also: \_getvisualpage, \_setactivepage, \_getactivepage, \_getvideoconfig

Example: #include <conio.h>
#include <graph.h>

```
main()
    int old_apage;
    int old_vpage;
    _setvideomode( _HRES16COLOR );
    old_apage = _getactivepage();
    old_vpage = _getvisualpage();
    /* draw an ellipse on page 0 */
   _setactivepage(0);
   _setvisualpage(0);
    _ellipse( _GFILLINTERIOR, 100, 50, 540, 150 );
    /* draw a rectangle on page 1 */
    _setactivepage(1);
    _rectangle( _GFILLINTERIOR, 100, 50, 540, 150 );
    getch();
    /* display page 1 */
    _setvisualpage(1);
    getch();
    _setactivepage( old_apage );
   _setvisualpage( old_vpage );
   _setvideomode( _DEFAULTMODE );
}
```

Classification: PC Graphics

_setvisualpage

double x1, double y1, double x2, double y2);

**Description:** 

The \_setwindow function defines a window for the window coordinate system. Window coordinates are specified as a user-defined range of values. This allows for consistent pictures regardless of the video mode.

The window is defined as the region with opposite corners established by the points (x1, y1) and (x2, y2). The argument *invert* specifies the direction of the y-axis. If the value is non-zero, the y values increase from the bottom of the screen to the top, otherwise, the y values increase as you move down the screen.

The window defined by the \_setwindow function is displayed in the current viewport. A viewport is defined by the \_setviewport function.

By default, the window coordinate system is defined with the point (0.0, 0.0) located at the lower left corner of the screen, and the point (1.0, 1.0) at the upper right corner.

**Returns:** 

The \_setwindow function returns a non-zero value when the window is set successfully; otherwise, zero is returned.

See Also: \_setviewport

**Example:** 

```
#include <conio.h>
#include <graph.h>
main()
{
    _setvideomode( _MAXRESMODE );
    draw_house( "Default window" );
    \_setwindow( 1, -0.5, -0.5, 1.5, 1.5 );
    draw_house( "Larger window" );
    _setwindow( 1, 0.0, 0.0, 0.5, 1.0 );
    draw_house( "Left side" );
    _setvideomode( _DEFAULTMODE );
}
draw_house( char *msq )
    _clearscreen( _GCLEARSCREEN );
    _outtext( msg );
    _rectangle_w( _GBORDER, 0.2, 0.1, 0.8, 0.6 );
    _moveto_w( 0.1, 0.5 );
    _lineto_w( 0.5, 0.9 );
    _{\text{lineto}_{\text{w}}(0.9,0.5)};
    _arc_w( 0.4, 0.5, 0.6, 0.3, 0.6, 0.4, 0.4, 0.4);
    _rectangle_w( _GBORDER, 0.4, 0.1, 0.6, 0.4 );
    getch();
```

Classification: PC Graphics

_setwindow	
------------	--

Systems: DOS

Synopsis: #include <signal.h>

void ( \*signal(int sig, void (\*func)(int)) ) ( int );

**Description:** 

The signal function is used to specify an action to take place when certain conditions are detected while a program executes. These conditions are defined to be:

Condition	Meaning
SIGABRT	abnormal termination, such as caused by the abort function
SIGBREAK	an interactive attention (Ctrl+Break on keyboard) is signalled
SIGFPE	an erroneous floating-point operation occurs (such as division by zero, overflow and underflow)
SIGILL	illegal instruction encountered
SIGINT	an interactive attention (Ctrl+C on keyboard) is signalled
SIGSEGV	an illegal memory reference is detected
SIGTERM	a termination request is sent to the program
SIGUSR1	OS/2 process flag A via DosFlagProcess
SIGUSR2	OS/2 process flag B via DosFlagProcess
SIGUSR3	OS/2 process flag C via DosFlagProcess

An action can be specified for each of the conditions, depending upon the value of the func argument:

function

When *func* is a function name, that function will be called equivalently to the following code sequence.

```
/* "sig_no" is condition being signalled */
signal( sig_no, SIG_DFL );
(*func)( sig_no );
```

The func function may terminate the program by calling the exit or abort functions or call the longjmp function. Because the next signal will be handled with default handling, the program must again call signal if it is desired to handle the next condition of the type that has been signalled.

After returning from the signal-catching function, the receiving process will resume execution at the point at which it was interrupted.

The signal catching function is described as follows:

```
void func( int sig_no )
{
    /* body of function */
}
```

Since signal-catching functions are invoked asynchronously with process execution, the type sig\_atomic\_t may be used to define variables on which an atomic operation (e.g., incrementation, decrementation) may be performed.

**SIG\_DFL** This value causes the default action for the condition to occur.

**SIG\_IGN** This value causes the indicated condition to be ignored.

When a condition is detected, it may be handled by a program, it may be ignored, or it may be handled by the usual default action (often causing an error message to be printed upon the stderr stream followed by program termination).

When the program begins execution, the equivalent of

```
signal( SIGABRT, SIG_DFL );
signal( SIGFPE, SIG_DFL );
signal( SIGILL, SIG_DFL );
signal( SIGINT, SIG_DFL );
signal( SIGSEGV, SIG_DFL );
signal( SIGTERM, SIG_DFL );
signal( SIGBREAK, SIG_DFL );
signal( SIGUSR1, SIG_IGN );
signal( SIGUSR2, SIG_IGN );
signal( SIGUSR3, SIG_IGN );
```

is executed.

The SIGINT signal is generated by pressing the Ctrl+C or Ctrl+Break key combination on the keyboard. Under DOS, if "BREAK=ON", a signal will be delivered at the next DOS call; otherwise, if "BREAK=OFF", a signal will be delivered only at the next standard input/output DOS call. The BREAK setting is configured in the CONFIG.SYS file.

Under OS/2, the SIGBREAK signal can only be received if Ctrl+Break is pressed and the keyboard is in binary (raw) mode. In ASCII (cooked) mode, which is the default, both Ctrl+C and Ctrl+Break combinations will raise the SIGINT signal.

A condition can be generated by a program using the raise function.

**Returns:** 

A return value of SIG\_ERR indicates that the request could not be handled, and errno is set to the value EINVAL.

Otherwise, the previous value of *func* for the indicated condition is returned.

See Also:

```
break..., raise
```

**Example:** 

```
#include <stdio.h>
#include <signal.h>
#include <i86.h>
/* SIGINT Test */
sig_atomic_t signal_count;
sig_atomic_t signal_number;
```

```
void MyIntHandler( int signo )
    signal_count++;
    signal_number = signo;
}
void MyBreakHandler( int signo )
    signal_count++;
    signal_number = signo;
}
int main ( void )
    int i;
    signal_count = 0;
    signal_number = 0;
    signal( SIGINT, MyIntHandler );
    signal( SIGBREAK, MyBreakHandler );
    printf( "Press Ctrl+C or Ctrl+Break\n" );
    for(i = 0; i < 50; i++) {
        printf( "Iteration # %d\n", i );
        delay( 500 ); /* sleep for 1/2 second */
        if( signal_count > 0 ) break;
    printf( "SIGINT count %d number %d\n",
                    signal_count, signal_number );
    signal_count = 0;
    signal_number = 0;
    signal( SIGINT, SIG_DFL );
                                    /* Default action */
    signal( SIGBREAK, SIG_DFL );
                                    /* Default action */
    printf( "Default signal handling\n" );
    for(i = 0; i < 50; i++) {
        printf( "Iteration # %d\n", i );
        delay( 500 ); /* sleep for 1/2 second */
        if( signal_count > 0 ) break; /* Won't happen */
    return( signal_count );
```

**Classification:** ISO C

**Systems:** All, Linux, RDOS, Netware

Synopsis: #include <math.h>
int signbit(x);

**Description:** The signbit macro determines whether the sign of its argument value is negative.

The argument x must be an expression of real floating type.

**Returns:** The signbit macro returns a nonzero value if and only if the sign of its argument has value is

negative.

See Also: fpclassify, isfinite, isinf, isnan, isnormal

Example: #include <math.h>
#include <stdio.h>

produces the following:

-4.5 is negative

Classification: ISO C

**Systems:** MACRO

**Description:** The  $\sin$  function computes the sine of x (measured in radians). A large magnitude argument may yield

a result with little or no significance.

**Returns:** The sin function returns the sine value.

See Also: acos, asin, atan, atan2, cos, tan

Example: #include <stdio.h>
#include <math.h>

void main()
 {
 printf( "%f\n", sin(.5) );

produces the following:

0.479426

Classification: ISO C

**Systems:** Math

Synopsis: #include <math.h>

double sinh(double x);

**Description:** The sinh function computes the hyperbolic sine of x. A range error occurs if the magnitude of x is too

large.

**Returns:** The sinh function returns the hyperbolic sine value. When the argument is outside the permissible

range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to ERANGE, and print a "RANGE error" diagnostic message using the stderr

stream.

See Also: cosh, tanh, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
     {
      printf( "%f\n", sinh(.5) );
    }
```

produces the following:

0.521095

**Classification:** ISO C

**Systems:** Math

```
Synopsis:
            #include <dos.h>
            unsigned sleep (unsigned seconds);
Description:
            The sleep function suspends execution by the specified number of seconds.
Returns:
            The sleep function always returns zero.
See Also:
            delay, timer_create, timer_gettime, timer_settime
Example:
             \star The following program sleeps for the
             * number of seconds specified in argv[1].
            #include <stdlib.h>
            #include <dos.h>
            void main( int argc, char *argv[] )
                unsigned seconds;
                seconds = (unsigned) strtol( argv[1], NULL, 0 );
                sleep( seconds );
Classification: WATCOM
```

**Systems:** All, Linux, RDOS, Netware

#### **Description:**

The \_snprintf function is equivalent to the fprintf function, except that the argument *buf* specifies a character array into which the generated output is placed, rather than to a file. The maximum number of characters to store is specified by *count*. A null character is placed at the end of the generated character string if fewer than *count* characters were stored. The *format* string is described under the description of the printf function.

The \_snwprintf function is a wide character version of \_snprintf. It accepts a wide character string argument for *format* and produces wide character output. The argument *buf* specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream. The maximum number of wide characters to store is specified by *count*. A null wide character is placed at the end of the generated wide character string if fewer than *count* wide characters were stored.

#### **Returns:**

The \_snprintf function returns the number of characters written into the array, not counting the terminating null character, or a negative value if more than *count* characters were requested to be generated. An error can occur while converting a value for output. The \_snwprintf function returns the number of wide characters written into the array, not counting the terminating null wide character, or a negative value if more than *count* wide characters were requested to be generated. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

#### See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

# **Example:**

#include <stdio.h>

```
/* Create temporary file names using a counter */
char namebuf[13];
int TempCount = 0;

char *make_temp_name()
    {
        _snprintf( namebuf, 13, "ZZ%.6o.TMP", TempCount++ );
        return( namebuf );
    }

void main()
    {
        FILE *tf1, *tf2;
```

```
tf1 = fopen( make_temp_name(), "w" );
tf2 = fopen( make_temp_name(), "w" );
fputs( "temp file 1", tf1 );
fputs( "temp file 2", tf2 );
fclose( tf1 );
fclose( tf2 );
```

**Classification:** WATCOM

Systems: \_snprintf - All, Linux, RDOS, Netware

\_snwprintf - All, Linux

Safer C:

The Safer C Library extension provides the snprintf\_s function which is a safer alternative to snprintf.

**Description:** 

The snprintf function is equivalent to the fprintf function, except that the argument *buf* specifies a character array into which the generated output is placed, rather than to a file. A null character is placed at the end of the generated character string. The maximum number of characters to store, including a terminating null character, is specified by *count*. The *format* string is described under the description of the printf function.

The snwprintf function is a wide character version of snprintf. It accepts a wide character string argument for *format* and produces wide character output. The argument *buf* specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream. The maximum number of wide characters to store, including a terminating null wide character, is specified by *count*.

**Returns:** 

The snprintf function returns the number of characters that would have been written had *count* been sufficiently large, not counting the terminating null character, or a negative value if an encoding error occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than *count*. The snwprintf function returns the number of wide characters that would have been written had *count* been sufficiently large, not counting the terminating null wide character, or a negative value if an encoding error occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than *count*. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>

/* Format output into a buffer after determining its size */

void main( void )
{
    int    bufsize;
    char    *buffer;

    bufsize = snprintf( NULL, 0, "%3d %P", 42, 42 );
    buffer = malloc( bufsize + 1 );
    snprintf( buffer, bufsize + 1, "%3d %P", 42, 42 );
    free( buffer );
}
```

**Classification:** ISO C

# snprintf, snwprintf

# snwprintf is WATCOM

Systems: snprintf - All, Linux, RDOS, Netware

snwprintf - All, Linux

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and snprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither s nor format shall be a null pointer. The n argument shall neither equal zero nor be greater than RSIZE\_MAX. The number of characters (including the trailing null) required for the result to be written to the array pointed to by s shall not be greater than n. The n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by format. Any argument to format supported to a s-supported to a s-supported to be a null pointer. No encoding error shall occur.

If there is a runtime-constraint violation, then if s is not a null pointer and n is greater than zero and less than RSIZE\_MAX, then the snprintf\_s function sets s[0] to the null character.

# **Description:**

The snprintf\_s function is equivalent to the snprintf function except for the explicit runtime-constraints listed above.

The  $snprintf_s$  function, unlike  $sprintf_s$ , will truncate the result to fit within the array pointed to by s.

The snwprintf\_s function is a wide character version of snprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

#### **Returns:**

The  $snprintf_s$  function returns the number of characters that would have been written had n been sufficiently large, not counting the terminating null character, or a negative value if a runtime-constraint violation occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than n.

The snwprintf\_s function returns the number of wide characters that would have been written had n been sufficiently large, not counting the terminating wide null character, or a negative value if a runtime-constraint violation occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than n.

#### See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
           #include <stdio.h>
           #include <stdlib.h>
           /* Format output into a buffer after determining its size */
           void main( void )
                     bufsize;
               int
               char *buffer;
               bufsize = snprintf( NULL, 0, "%3d %P", 42, 42 ) + 1;
               buffer = malloc( bufsize );
               snprintf_s( buffer, bufsize, "%3d %P", 42, 42 );
               free( buffer );
           }
Classification: TR 24731
Systems:
           snprintf_s - All, Linux, RDOS, Netware
           snwprintf_s - All, Linux
```

#### **Description:**

The \_sopen function opens a file at the operating system level for shared access. The name of the file to be opened is given by *filename*. The file will be accessed according to the access mode specified by *access*. When the file is to be created, the optional argument must be given which establishes the future access permissions for the file. Additionally, the sharing mode of the file is given by the *share* argument. The optional argument is the file permissions to be used when O\_CREAT flag is on in the *access* mode.

The \_sopen function is identical to \_sopen. Use \_sopen for ANSI naming conventions.

The \_wsopen function is identical to \_sopen except that it accepts a wide character string argument.

The access mode is established by a combination of the bits defined in the <fcntl.h> header file. The following bits may be set:

Mode	Meaning
O_RDONLY	permit the file to be only read.
O_WRONLY	permit the file to be only written.
O_RDWR	permit the file to be both read and written.
O_APPEND	causes each record that is written to be written at the end of the file.
O_CREAT	has no effect when the file indicated by <i>filename</i> already exists; otherwise, the file is created;
O_TRUNC	causes the file to be truncated to contain no data when the file exists; has no effect when the file does not exist.
O_BINARY	causes the file to be opened in binary mode which means that data will be transmitted to and from the file unchanged.
O_TEXT	causes the file to be opened in text mode which means that carriage-return characters are written before any linefeed character that is written and causes carriage-return characters to be removed when encountered during reads.
O_NOINHERIT	indicates that this file is not to be inherited by a child process.

**O\_EXCL** indicates that this file is to be opened for exclusive access. If the file exists and O\_CREAT was also specified then the open will fail (i.e., use O\_EXCL to ensure that the file does not already exist).

When neither O\_TEXT nor O\_BINARY are specified, the default value in the global variable \_fmode is used to set the file translation mode. When the program begins execution, this variable has a value of O\_TEXT.

O\_CREAT must be specified when the file does not exist and it is to be written.

When the file is to be created (O\_CREAT is specified), an additional argument must be passed which contains the file permissions to be used for the new file. The access permissions for the file or directory are specified as a combination of bits (defined in the <sys/stat.h> header file).

The following bits define permissions for the owner.

Permission	Meaning
S_IRWXU	Read, write, execute/search
S_IRUSR	Read permission
S_IWUSR	Write permission
S_IXUSR	Execute/search permission

The following bits define permissions for the group.

Permission	Meaning
S_IRWXG	Read, write, execute/search
S_IRGRP	Read permission
S_IWGRP	Write permission
S_IXGRP	Execute/search permission

The following bits define permissions for others.

Permission	Meaning
S_IRWXO	Read, write, execute/search
S_IROTH	Read permission
S_IWOTH	Write permission
S_IXOTH	Execute/search permission

The following bits define miscellaneous permissions used by other implementations.

Permission	Meaning
S_IREAD	is equivalent to S_IRUSR (read permission)
S_IWRITE	is equivalent to S_IWUSR (write permission)
S_IEXEC	is equivalent to S_IXUSR (execute/search permission)

All files are readable with DOS; however, it is a good idea to set S\_IREAD when read permission is intended for the file.

The \_sopen function applies the current file permission mask to the specified permissions (see the umask function).

The shared access for the file, *share*, is established by a combination of bits defined in the <share.h> header file. The following values may be set:

Value	Meaning
SH_COMPAT	Set compatibility mode.
SH_DENYRW	Prevent read or write access to the file.
SH_DENYWR	Prevent write access of the file.
SH_DENYRD	Prevent read access to the file.
SH_DENYNO	Permit both read and write access to the file.

You should consult the technical documentation for the DOS system that you are using for more detailed information about these sharing modes.

The sopen function is deprecated, use \_sopen instead.

**Returns:** 

If successful, \_sopen returns a handle for the file. When an error occurs while opening the file, -1 is returned. When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

	Constant	Meaning
	EACCES	Access denied because <i>path</i> specifies a directory or a volume ID, or sharing mode denied due to a conflicting open.
	<b>EMFILE</b>	No more handles available (too many open files)
	ENOENT	Path or file not found
See Also:	_chsize, close, creat, dup, dup2, _eof, exec, fdopen, _filelength, fileno, fstat, _grow_handles, isatty, lseek, open, read, _setmode, stat, _tell, write, umask	
Example:	<pre>#include <sys stat.h=""> #include <sys types.h=""> #include <fcntl.h> #include <share.h></share.h></fcntl.h></sys></sys></pre>	
	<pre>void main( voi {    int handle</pre>	

```
/* open a file for output
               /* replace existing file if it exists
               handle = _sopen( "file",
                           O_WRONLY | O_CREAT | O_TRUNC,
                           SH_DENYWR,
                           S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
               /* read a file which is assumed to exist
               handle = _sopen( "file", O_RDONLY, SH_DENYWR );
               /* append to the end of an existing file */
               /* write a new file if file does not exist */
               handle = _sopen( "file",
                           O_WRONLY | O_CREAT | O_APPEND,
                           SH_DENYWR,
                           S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
           }
Classification: WATCOM
Systems:
          _sopen - All, Linux, RDOS, Netware
          _wsopen - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux
          sopen - All, Linux, RDOS, Netware
```

```
void sound (unsigned frequency);
Description:
           The sound function turns on the PC's speaker at the specified frequency. The frequency is in Hertz
           (cycles per second). The speaker can be turned off by calling the nosound function after an
           appropriate amount of time.
Returns:
           The sound function has no return value.
See Also:
           delay, nosound
Example:
           #include <i86.h>
           /*
                The numbers in this table are the timer divisors
               necessary to produce the pitch indicated in the
                lowest octave that is supported by the "sound"
                function.
               To raise the pitch by N octaves, simply divide the
               number in the table by 2**N since a pitch which is
               an octave above another has double the frequency of
                the original pitch.
                The frequency obtained by these numbers is given by
                1193180 / X where X is the number obtained in the
                table.
           unsigned short Notes[] = {
                                 /* C b
                    19327 ,
                                    /* C
                    18242 ,
                                                        */
                                    /* C #
                    17218 ,
                                              (Db)
                                    /* D
                    16252 ,
                    15340 ,
                                    /* D #
                                              (Eb)
                    14479 ,
                                    /* E
                                              (Fb)
                    13666 ,
                                    /* F
                                              (E#)
                    12899 ,
                                    /* F #
                                              ( G b )
                                                        */
                    12175 ,
                                    /* G
                                                        */
                    11492 ,
                                    /* G #
                                              (Ab)
                    10847 ,
                                    /* A
                                                        */
                    10238 ,
                                    /* A #
                                              (Bb)
                                                        */
                    9664 ,
                                    /* B
                                              (Cb)
                                                        */
                    9121 ,
                                    /* B #
           };
```

#include <i86.h>

Classification: Intel

**Systems:** DOS, Windows, Win386

```
Synopsis:
         #include cess.h>
         int spawnl( mode, path, arg0, arg1..., argn, NULL);
         int spawnle( mode, path, arg0, arg1..., argn, NULL, envp);
         int spawnlp( mode, file, arg0, arg1..., argn, NULL );
         int spawnlpe( mode, file, arg0, arg1..., argn, NULL, envp);
         int spawnv( mode, path, argv);
         int spawnve ( mode, path, argv, envp );
         int spawnvp( mode, file, argv );
         int spawnvpe( mode, file, argv, envp );
         int _spawnl( mode, path, arg0, arg1..., argn, NULL);
         int _spawnle( mode, path, arg0, arg1..., argn, NULL, envp);
         int _spawnlp( mode, file, arg0, arg1..., argn, NULL );
         int _spawnlpe( mode, file, arg0, arg1..., argn, NULL, envp);
                       mode, path, argv);
         int _spawnv(
         int _spawnve( mode, path, argv, envp );
         int _spawnvp( mode, file, argv );
         int _spawnvpe( mode, file, argv, envp );
                                       /* mode for parent
           int
                     mode;
                                      /* file name incl. path */
           const char *path;
                                      /* file name
           const char *file;
           const char *arg0, ..., *argn; /* arguments
           int _wspawnl( mode, path, arg0, arg1..., argn, NULL );
         int _wspawnle( mode, path, arg0, arg1..., argn, NULL, envp);
         int _wspawnlp( mode, file, arg0, arg1..., argn, NULL );
         int _wspawnlpe( mode, file, arg0, arg1..., argn, NULL, envp);
         int _wspawnv( mode, path, argv);
         int _wspawnve( mode, path, argv, envp );
         int _wspawnvp( mode, file, argv );
         int _wspawnvpe( mode, file, argv, envp );
           int
                        mode;
                                         /* mode for parent
           const wchar_t *path;
                                         /* file name incl. path */
                                         /* file name
           const wchar_t *file;
           const wchar_t *arg0, ..., *argn; /* arguments
                                                                */
           */
                                         /* environment strings */
           const wchar_t *const envp[];
```

**Description:** 

The **spawn...** functions create and execute a new child process, named by *pgm*. The value of *mode* determines how the program is loaded and how the invoking program will behave after the invoked program is initiated:

Mode	Meaning
P_WAIT	The invoked program is loaded into available memory, is executed, and then the original program resumes execution. This option is supported under DOS, OS/2, Win32 and QNX.
P_NOWAIT	Causes the current program to execute concurrently with the new child process. This option is supported under OS/2, Win32 and QNX.
P_NOWAITO	Causes the current program to execute concurrently with the new child process. This option is supported under OS/2, Win32 and QNX. The wait and cwait functions cannot be used to obtain the exit code.

**P OVERLAY** The invoked program replaces the original program in memory and is

executed. No return is made to the original program. This option is supported under DOS (16-bit only), OS/2, Win32, and QNX. This is equivalent to

calling the appropriate exec... function.

**P\_DETACH** Launches the child process in the background without access to the keyboard

or console. This option is supported under only Windows NT.

The program is located by using the following logic in sequence:

1. An attempt is made to locate the program in the current working directory if no directory specification precedes the program name; otherwise, an attempt is made in the specified directory.

- 2. If no file extension is given, an attempt is made to find the program name, in the directory indicated in the first point, with .COM concatenated to the end of the program name.
- 3. If no file extension is given, an attempt is made to find the program name, in the directory indicated in the first point, with .EXE concatenated to the end of the program name.
- 4. When no directory specification is given as part of the program name, the spawnlp, spawnlpe, spawnvp, and spawnvpe functions will repeat the preceding three steps for each of the directories specified by the PATH environment variable. The command

```
path c:\myapps;d:\lib\applns
```

indicates that the two directories

```
c:\myapps
d:\lib\applns
```

are to be searched. The DOS PATH command (without any directory specification) will cause the current path definition to be displayed.

An error is detected when the program cannot be found.

Arguments are passed to the child process by supplying one or more pointers to character strings as arguments in the **spawn...** call. These character strings are concatenated with spaces inserted to separate the arguments to form one argument string for the child process. The length of this concatenated string must not exceed 128 bytes for DOS systems.

The arguments may be passed as a list of arguments (spawn1, spawn1e, spawn1p and spawn1pe) or as a vector of pointers (spawnv, spawnve, spawnvp, and spawnvpe). At least one argument, arg0 or argv[0], must be passed to the child process. By convention, this first argument is a pointer to the name of the program.

If the arguments are passed as a list, there must be a NULL pointer to mark the end of the argument list. Similarly, if a pointer to an argument vector is passed, the argument vector must be terminated by a NULL pointer.

The environment for the invoked program is inherited from the parent process when you use the spawnl, spawnlp, spawnv and spawnvp functions. The spawnle, spawnlpe, spawnve and spawnvpe functions allow a different environment to be passed to the child process through the *envp* argument. The argument *envp* is a pointer to an array of character pointers, each of which points to a

string defining an environment variable. The array is terminated with a NULL pointer. Each pointer locates a character string of the form

```
variable=value
```

that is used to define an environment variable. If the value of *envp* is NULL, then the child process inherits the environment of the parent process.

The environment is the collection of environment variables whose values that have been defined with the DOS SET command or by the successful execution of the putenv function. A program may read these values with the getenv function.

The following example invokes "myprog" as if myprog ARG1 ARG2 had been entered as a command to DOS.

The program will be found if one of "myprog.", "myprog.com", or "myprog.exe" is found in the current working directory.

The following example includes a new environment for "myprog".

The environment for the invoked program will consist of the three environment variables SOURCE, TARGET and lines.

The following example is another variation on the first example.

```
char *arg_list[] = { "myprog", "ARG1", "ARG2", NULL };
spawnv( P_WAIT, "myprog", arg_list );
```

The \_wspawn... functions are similar to their counterparts but operate on wide character strings.

**Returns:** When the value of *mode* is:

Meaning

P\_WAIT then the return value from spawn... is the exit status of the child process.

P\_NOWAIT then the return value from spawn... is the process ID (or process handle under Win32) of the child process. To obtain the exit code for a process spawned with P\_NOWAIT, you must call the wait (under OS/2 or QNX) or cwait (under OS/2 or Win32) function specifying the process ID/handle. If the child

process terminated normally, then the low order byte of the returned status

word will be set to 0, and the high order byte will contain the low order byte of the return code that the child process passed to the DOSEXIT function.

**P\_NOWAITO** then the return value from **spawn...** is the process ID of the child process. The

exit code cannot be obtained for a process spawned with P\_NOWAITO.

**P\_DETACH** then the return value from **spawn...** is zero (0) if successful.

When an error is detected while invoking the indicated program, spawn... returns -1 and errno is set to indicate the error.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

Constant	Meaning
E2BIG	The argument list exceeds 128 bytes, or the space required for the environment information exceeds 32K.
EINVAL	The <i>mode</i> argument is invalid.
ENOENT	Path or file not found
ENOMEM	Not enough memory is available to execute the child process.

**See Also:** abort, atexit, cwait, exec..., exit, \_Exit, \_exit, getcmd, getenv, main, putenv, system, wait

#### **Example:**

```
#include <stdio.h>
#include <stdlib.h>
#include cess.h>
#include <errno.h>
#include <string.h>
void main()
   int
          process_id;
#if defined(__OS2__) | defined(__NT__)
          status, rc;
   int
#endif
   process_id = spawnl( P_NOWAIT, "child.exe",
                         "child", "5", NULL );
    if( process_id == -1 ) {
       printf( "spawn failed - %s\n", strerror( errno ) );
       exit( EXIT_FAILURE );
   printf( "Process id = %d\n", process_id );
```

```
rc = cwait( &status, process_id, WAIT_CHILD );
               if(rc == -1) {
                   printf( "wait failed - %s\n", strerror( errno ) );
               } else {
                   printf( "wait succeeded - %x\n", status );
                   switch( status & 0xff ) {
                   case 0:
                       printf( "Normal termination exit code = %d\n",
                                status >> 8 );
                       break;
                   case 1:
                       printf( "Hard-error abort\n" );
                       break;
                   case 2:
                       printf( "Trap operation\n" );
                       break;
                   case 3:
                       printf( "SIGTERM signal not intercepted\n" );
                   default:
                       printf( "Bogus return status\n" );
           #endif
               printf( "spawn completed\n" );
           /*
           [child.c]
           #include <stdio.h>
           #include <stdlib.h>
           #include <dos.h>
           void main( int argc, char *argv[] )
           {
               int delay;
               if( argc <= 1 )
                   exit( EXIT_FAILURE );
               delay = atoi( argv[1] );
               printf( "I am a child going to sleep "
                       "for %d seconds\n", delay );
               sleep( delay );
               printf( "I am a child awakening\n" );
               exit( 123 );
           }
*/
Classification: WATCOM
           spawnl - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
           spawnle - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
           spawnlp - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware
           spawnlpe - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
           spawnv - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
           spawnve - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
```

#if defined(\_\_OS2\_\_) | defined(\_\_NT\_\_)

**Systems:** 

```
spawnvp - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware
spawnvpe - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_spawnl - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
\_spawnle - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_spawnlp - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware
_spawnlpe - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_spawnv - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_spawnve - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_spawnvp - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS, Netware
_spawnvpe - DOS, Win32, OS/2 1.x(all), OS/2-32, Linux, RDOS
_wspawnl - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnle - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnlp - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnlpe - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnv - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnve - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnvp - DOS, Win32, OS/2 1.x(all), OS/2-32
_wspawnvpe - DOS, Win32, OS/2 1.x(all), OS/2-32
```

#### Synopsis: #include <stdlib.h>

# **Description:**

The \_splitpath function splits up a full pathname into four components consisting of a drive letter, directory path, file name and file name extension. The argument *path* points to a buffer containing the full pathname to be split up.

The \_wsplitpath function is a wide character version of \_splitpath that operates with wide character strings.

The maximum size required for each buffer is specified by the manifest constants \_MAX\_PATH, \_MAX\_DRIVE (or \_MAX\_VOLUME for Netware applications), \_MAX\_DIR, \_MAX\_FNAME, and \_MAX\_EXT which are defined in <stdlib.h>.

drive

The *drive* argument points to a buffer that will be filled in with the drive letter (e.g., A, B, C, etc.) followed by a colon if a drive is specified in the full pathname (filled in by \_splitpath).

For Netware applications, the *drive* argument points to a buffer that will be filled in with the volume identifier (e.g., \\NAME\_SPACE) if a volume is specified in the full pathname (filled in by \_splitpath).

dir

The *dir* argument points to a buffer that will be filled in with the pathname including the trailing slash. Either forward slashes (/) or backslashes (\) may be used.

fname

The *fname* argument points to a buffer that will be filled in with the base name of the file without any extension (suffix) if a file name is specified in the full pathname (filled in by \_splitpath).

ext

The *ext* argument points to a buffer that will be filled in with the filename extension (suffix) including the leading period if an extension is specified in the full pathname (filled in by \_splitpath).

The arguments *drive*, *dir*, *fname* and *ext* will not be filled in if they are NULL pointers.

For each component of the full pathname that is not present, its corresponding buffer will be set to an empty string.

**Returns:** The \_splitpath function returns no value.

See Also:

\_fullpath, \_makepath, \_splitpath2

#include <stdio.h>

**Example:** 

```
#include <stdlib.h>
           void main()
              {
                char full_path[ _MAX_PATH ];
                char drive[ _MAX_DRIVE ];
                char dir[ _MAX_DIR ];
                char fname[ _MAX_FNAME ];
                char ext[ _MAX_EXT ];
               _makepath(full_path, "c", "watcomc\\h\\", "stdio", "h");
               printf( "Full path is: %s\n\n", full_path );
               _splitpath( full_path, drive, dir, fname, ext );
               printf( "Components after _splitpath\n" );
               printf( "drive: %s\n", drive );
               printf( "dir: %s\n", dir );
               printf( "fname: %s\n", fname );
               printf( "ext: %s\n", ext );
           produces the following:
           Full path is: c:watcomc\h\stdio.h
           Components after _splitpath
           drive: c:
           dir: watcomc\h\
           fname: stdio
           ext: .h
           Note the use of two adjacent backslash characters (\) within character-string constants to signify a single
           backslash.
Classification: WATCOM
Systems:
           _splitpath - All, Linux, RDOS, Netware
```

\_wsplitpath - All, Linux

Synopsis: #include <stdlib.h>

**Description:** 

The \_splitpath2 function splits up a full pathname into four components consisting of a drive letter, directory path, file name and file name extension.

*inp* The argument *inp* points to a buffer containing the full pathname to be split up.

outp The argument outp points to a buffer that will contain all the components of the path, each separated by a null character. The maximum size required for this buffer is specified

by the manifest constant \_MAX\_PATH2 which is defined in <stdlib.h>.

*drive* The *drive* argument is the location that is to contain the pointer to the drive letter (e.g., A,

B, C, etc.) followed by a colon if a drive is specified in the full pathname (filled in by \_splitpath2).

For Netware applications, the *drive* argument points to a buffer that will be filled in with the volume identifier (e.g., \\NAME\_SPACE) if a volume is specified in the full

pathname (filled in by \_splitpath2).

dir The dir argument is the location that is to contain the pointer to the directory path including the trailing slash if a directory path is specified in the full pathname (filled in by

\_splitpath2). Either forward slashes (/) or backslashes (\) may be used.

**fname** The *fname* argument is the location that is to contain the pointer to the base name of the

file without any extension (suffix) if a file name is specified in the full pathname (filled in

by \_splitpath2).

ext The ext argument is the location that is to contain the pointer to the filename extension

(suffix) including the leading period if an extension is specified in the full pathname

(filled in by \_splitpath2).

The arguments *drive*, *dir*, *fname* and *ext* will not be filled in if they are NULL pointers.

For each component of the full pathname that is not present, its corresponding pointer will be set to point at a NULL string ('\0').

This function reduces the amount of memory space required when compared to the function.

The \_wsplitpath2 function is a wide character version of \_splitpath2 that operates with wide character strings.

```
Returns:
           The _splitpath2 function returns no value.
See Also:
            _fullpath, _makepath, _splitpath
Example:
            #include <stdio.h>
            #include <stdlib.h>
            void main()
              {
                char full_path[ _MAX_PATH ];
                char tmp_path[ _MAX_PATH2 ];
                char *drive;
                char *dir;
                char *fname;
                char *ext;
                _makepath(full_path, "c", "watcomc\\h", "stdio", "h");
                printf( "Full path is: %s\n\n", full_path );
                _splitpath2( full_path, tmp_path,
                              &drive, &dir, &fname, &ext);
                printf( "Components after _splitpath2\n" );
                printf( "drive: %s\n", drive );
                printf( "dir: %s\n", dir );
                printf( "fname: %s\n", fname );
                printf( "ext: %s\n", ext );
           produces the following:
           Full path is: c:watcomc\h\stdio.h
           Components after _splitpath2
            drive: c:
           dir: watcomc\h\
            fname: stdio
           Note the use of two adjacent backslash characters (\) within character-string constants to signify a single
           backslash.
Classification: WATCOM
Systems:
           _splitpath2 - All, Linux, RDOS, Netware
           _wsplitpath2 - All, Linux
```

Safer C:

The Safer C Library extension provides the sprintf\_s function which is a safer alternative to sprintf.

**Description:** 

The sprintf function is equivalent to the fprintf function, except that the argument *buf* specifies a character array into which the generated output is placed, rather than to a file. A null character is placed at the end of the generated character string. The *format* string is described under the description of the printf function.

The swprintf function is a wide character version of sprintf. It accepts a wide character string argument for *format* and produces wide character output. The argument buf specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream. The maximum number of wide characters to write, including a terminating null wide character, is specified by n.

**Returns:** 

The sprintf function returns the number of characters written into the array, not counting the terminating null character. An error can occur while converting a value for output. The swprintf function returns the number of wide characters written into the array, not counting the terminating null wide character, or a negative value if n or more wide characters were requested to be generated. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also:

\_bprintf, cprintf, fprintf, printf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vswprintf, vswprintf

**Example:** 

#include <stdio.h>

```
/* Create temporary file names using a counter */
char namebuf[13];
int TempCount = 0;

char *make_temp_name( void )
{
    sprintf( namebuf, "zz%.6o.tmp", TempCount++ );
    return( namebuf );
}

void main( void )
{
    FILE *tf1, *tf2;
```

```
tf1 = fopen( make_temp_name(), "w" );
    tf2 = fopen( make_temp_name(), "w" );
    fputs( "temp file 1", tf1 );
    fputs( "temp file 2", tf2 );
    fclose( tf1 );
    fclose( tf2 );
}

Classification: ISO C
    swprintf is ISO C95

Systems:    sprintf - All, Linux, RDOS, Netware
    swprintf - All, Linux
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and sprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *s* nor *format* shall be a null pointer. The *n* argument shall neither equal zero nor be greater than RSIZE\_MAX. The number of characters (including the trailing null) required for the result to be written to the array pointed to by *s* shall not be greater than *n*. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by *format*. Any argument to sprintf\_s corresponding to a %s specifier shall not be a null pointer. No encoding error shall occur.

If there is a runtime-constraint violation, then if s is not a null pointer and n is greater than zero and less than RSIZE\_MAX, then the sprintf\_s function sets s[0] to the null character.

# **Description:**

The sprintf\_s function is equivalent to the sprintf function except for the explicit runtime-constraints listed above.

The sprintf\_s function, unlike snprintf\_s, treats a result too big for the array pointed to by *s* as a runtime-constraint violation.

The swprintf\_s function is a wide character version of sprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

# **Returns:**

If no runtime-constraint violation occurred, the <code>sprintf\_s</code> function returns the number of characters written in the array, not counting the terminating null character. If an encoding error occurred, <code>sprintf\_s</code> returns a negative value. If any other runtime-constraint violation occurred, <code>sprintf\_s</code> returns zero.

If no runtime-constraint violation occurred, the swprintf\_s function returns the number of wide characters written in the array, not counting the terminating null wide character. If an encoding error occurred or if *n* or more wide characters are requested to be written, swprintf\_s returns a negative value. If any other runtime-constraint violation occurred, swprintf\_s returns zero.

#### See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>

/* Create temporary file names using a counter */
char namebuf[13];
int TempCount = 0;
```

```
char *make_temp_name( void )
                sprintf_s( namebuf, sizeof( namebuf ),
                             "zz%.6o.tmp", TempCount++);
                return( namebuf );
            }
            void main( void )
                FILE *tf1, *tf2;
                tf1 = fopen( make_temp_name(), "w" );
                tf2 = fopen( make_temp_name(), "w" );
                fputs( "temp file 1", tf1 );
fputs( "temp file 2", tf2 );
                fclose( tf1 );
                fclose( tf2 );
Classification: TR 24731
Systems:
            sprintf_s - All, Linux, RDOS, Netware
            swprintf_s - All, Linux
```

Synopsis: #include <math.h>

double sqrt( double x);

**Description:** The sqrt function computes the non-negative square root of x. A domain error occurs if the argument

is negative.

**Returns:** The sqrt function returns the value of the square root. When the argument is outside the permissible

range, the matherr function is called. Unless the default matherr function is replaced, it will set the global variable errno to EDOM, and print a "DOMAIN error" diagnostic message using the stderr

stream.

See Also: exp, log, pow, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", sqrt(.5) );
    }
```

produces the following:

0.707107

**Classification:** ISO C

**Systems:** Math

Synopsis: #include <stdlib.h>
 void srand( unsigned int seed );

**Description:** The srand function uses the argument *seed* to start a new sequence of pseudo-random integers to be

returned by subsequent calls to rand. A particular sequence of pseudo-random integers can be repeated by calling srand with the same *seed* value. The default sequence of pseudo-random integers

is selected with a seed value of 1.

**Returns:** The srand function returns no value.

See Also: rand

Example: #include <stdio.h>
#include <stdlib.h>

void main()
{
 int i;

 srand( 982 );
 for( i = 1; i < 10; ++i ) {
 printf( "%d\n", rand() );
 }

 srand( 982 ); /\* start sequence over again \*/
 for( i = 1; i < 10; ++i ) {
 printf( "%d\n", rand() );
 }
}</pre>

Classification: ISO C

Systems: All, Linux, RDOS, Netware

**Synopsis:** #include <stdio.h> int sscanf (const char \*in\_string, const char \*format, ...); #include <wchar.h> int swscanf (const wchar\_t \*in\_string, const wchar\_t \*format, ...); Safer C: The Safer C Library extension provides the sscanf\_s function which is a safer alternative to sscanf. **Description:** The sscanf function scans input from the character string in\_string under control of the argument format. Following the format string is the list of addresses of items to receive values. The *format* string is described under the description of the scanf function. The swscanf function is identical to sscanf except that it accepts a wide character string argument for *format* and the input string *in\_string* consists of wide characters. **Returns:** The sscanf function returns EOF if the end of the input string was reached before any input conversion. Otherwise, the number of input arguments for which values were successfully scanned and stored is returned. See Also: cscanf, fscanf, vcscanf, vfscanf, vscanf, vscanf, fwscanf, wscanf, wscanf, swscanf, vfwscanf, vwscanf, vswscanf **Example:** #include <stdio.h> /\* Scan a date in the form "Saturday April 18 1987" \*/ void main ( void ) int day, year; char weekday[10], month[10];

printf( "%s %s %d %d\n",

weekday, month, &day, &year );

weekday, month, day, year );

produces the following:

Friday August 14 1987

Classification: ISO C90

}

swscanf is ISO C95

Systems: sscanf - All, Linux, RDOS, Netware swscanf - All, Linux

sscanf, swscanf			

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and sscanf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *s* not *format* shall be a null pointer. Any argument indirected through in order to store converted input shall not be a null pointer.

If there is a runtime-constraint violation, the <code>sscanf\_s</code> function does not attempt to perform further input, and it is unspecified to what extent <code>sscanf\_s</code> performed input before discovering the runtime-constraint violation.

## **Description:**

The sscanf\_s function is equivalent to fscanf\_s, except that input is obtained from a string (specified by the argument s) rather than from a stream. Reaching the end of the string is equivalent to encountering end-of-file for the fscanf\_s function. If copying takes place between objects that overlap, the objects take on unspecified values.

The swscanf\_s function is identical to sscanf\_s except that it accepts wide character string arguments for s and format.

## **Returns:**

The sscanf\_s function returns EOF if an input failure occurred before any conversion or if there was a runtime-constraint violation. Otherwise, the sscanf\_s function returns the number of input items successfully assigned, which can be fewer than provided for, or even zero.

## See Also:

cscanf, fscanf, scanf, vcscanf, vfscanf, vscanf, vscanf, fwscanf, wscanf, vswscanf, vswscanf, vswscanf

#### **Example:**

Friday August 13 2004

produces the following:

# sscanf\_s, swscanf\_s

**Classification:** TR 24731

Systems: sscanf\_s - All, Linux, RDOS, Netware

swscanf\_s - All, Linux

```
Synopsis: #include <malloc.h>
    size_t stackavail( void );
    size_t _stackavail( void );
```

**Description:** The stackavail function returns the number of bytes currently available in the stack. This value is usually used to determine an appropriate amount to allocate using alloca.

The \_stackavail function is identical to stackavail. Use \_stackavail for ANSI naming conventions.

**Returns:** The stackavail function returns the number of bytes currently available in the stack.

**See Also:** alloca, calloc Functions, malloc Functions

```
Example:
```

```
#include <stdio.h>
#include <string.h>
#include <malloc.h>
#include <fcntl.h>
#include <io.h>
long char_count(FILE *fp )
     char
            *buffer;
     size_t bufsiz;
     long
             count;
     /* allocate half of stack for temp buffer */
     bufsiz = stackavail() >> 1;
     buffer = (char *) alloca( bufsiz );
     setvbuf( fp, buffer, _IOFBF, bufsiz );
     count = 0L;
     while (fgetc (fp ) != EOF ) ++count;
     fclose(fp);
     return ( count );
}
void main( void )
    FILE
            *fp;
    fp = fopen( "file", "rb" );
    if( fp != NULL ) {
        _setmode( fileno( fp ), O_BINARY );
        printf( "File contains %lu characters\n",
                char_count( fp ) );
        fclose( fp );
    }
}
```

## **Classification:** WATCOM

\_stackavail conforms to ANSI naming conventions

Systems: stackavail - All, Linux, RDOS, Netware \_stackavail - All, Linux, RDOS, Netware

stackavail, _stackavail			

Synopsis: #include <sys/stat.h>

```
int stat( const char *path, struct stat *buf );
int _stat( const char *path, struct _stat *buf );
int _stati64( const char *path, struct _stati64 *buf );
int _wstat( const wchar_t *path, struct _stat *buf );
int _wstati64( const wchar_t *path, struct _stati64 *buf );
int lstat( const char *path, struct stat *buf );
```

**Description:** 

The stat functions obtain information about the file or directory referenced in *path*. This information is placed in the structure located at the address indicated by *buf*.

The file <sys/stat.h> contains definitions for the structure stat.

st\_originatingNameSpace (unsigned char) the originating name space

The structure \_stati64 differs from stat in the following way:

Field	Type/Meaning
st_dev	(dev_t) the disk drive the file resides on
st_ino	(ino_t) this inode's number (not used for DOS)
st_mode	(unsigned short) file mode
st_nlink	(short) number of hard links
st_uid	(unsigned long) user-id (always 'root' for DOS)
st_gid	(short) group-id (always 'root' for DOS)
st_rdev	(dev_t) this should be the device type but it is the same as st_dev for the time being
st_size	(off_t) total file size
st_atime	(time_t) this should be the file "last accessed" time if the file system supports it
st_mtime	(time_t) the file "last modified" time
st_ctime	(time_t) this should be the file "last status change" time if the file system supports it
	The following fields are Netware only:
st_btime	(time_t) the file "last archived" time
st_attr	(unsigned long) the file's attributes
st_archivedID	(unsigned long) the user/object ID that last archived file
st_updatedID	(unsigned long) the user/object ID that last updated file
st_inheritedRig	htsMask (unsigned short) the inherited rights mask

st\_size (\_\_int64) total file size (as a 64-bit value)

At least the following macros are defined in the <sys/stat.h> header file.

Macro	Meaning
S_ISFIFO(m)	Test for FIFO.
S_ISCHR(m)	Test for character special file.
$S_{ISDIR}(m)$	Test for directory file.
S_ISBLK(m)	Test for block special file.
S_ISREG(m)	Test for regular file.

The value *m* supplied to the macros is the value of the st\_mode field of a stat structure. The macro evaluates to a non-zero value if the test is true and zero if the test is false.

The following bits are encoded within the st\_mode field of a stat structure.

Mask	Owner Permissions
S_IRWXU	Read, write, search (if a directory), or execute (otherwise)
S_IRUSR	Read permission bit
S_IWUSR	Write permission bit
S_IXUSR	Search/execute permission bit
S_IREAD	== S_IRUSR (for Microsoft compatibility)
S_IWRITE	== S_IWUSR (for Microsoft compatibility)
S_IEXEC	== S_IXUSR (for Microsoft compatibility)

S\_IRWXU is the bitwise inclusive OR of S\_IRUSR, S\_IWUSR, and S\_IXUSR.

Mask	Group Permissions (same as owner's on DOS, OS/2 or Windows)
S_IRWXG S_IRGRP S_IWGRP S_IXGRP	Read, write, search (if a directory), or execute (otherwise) Read permission bit Write permission bit Search/execute permission bit

 $S_{IRWXG}$  is the bitwise inclusive OR of  $S_{IRGRP}$ ,  $S_{IWGRP}$ , and  $S_{IXGRP}$ .

Mask	Other Permissions (same as owner's on DOS, OS/2 or Windows)
S_IRWXO	Read, write, search (if a directory), or execute (otherwise)
S_IROTH	Read permission bit
S_IWOTH	Write permission bit
S_IXOTH	Search/execute permission bit

S\_IRWXO is the bitwise inclusive OR of S\_IROTH, S\_IWOTH, and S\_IXOTH.

Mask	Meaning
S_ISUID	(Not supported by DOS, OS/2 or Windows) Set user ID on execution. The
	process's effective user ID shall be set to that of the owner of the file when the file
	is run as a program. On a regular file, this bit should be cleared on any write.
S_ISGID	(Not supported by DOS, OS/2 or Windows) Set group ID on execution. Set
	effective group ID on the process to the file's group when the file is run as a
	program. On a regular file, this bit should be cleared on any write.
	en e

The \_stat function is identical to stat. Use \_stat for ANSI naming conventions.

The \_stati64, \_wstat, and \_wstati64 functions differ from stat in the type of structure that they are asked to fill in. The \_wstat and \_wstati64 functions deal with wide character strings. The differences in the structures are described above. The lstat function is identical to stat on non-UNIX platforms.

**Returns:** 

All forms of the stat function return zero when the information is successfully obtained. Otherwise, -1 is returned.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

**EACCES** Search permission is denied for a component of *path*.

fstat

**Example:** 

See Also:

```
#include <stdio.h>
#include <sys/stat.h>

void main()
{
    struct stat buf;

    if( stat( "file", &buf ) != -1 ) {
        printf( "File size = %d\n", buf.st_size );
    }
}
```

Classification: POSIX 1003.1

\_stat conforms to ANSI naming conventions \_stati64 is WATCOM

lstat is POSIX

**Systems:** 

```
stat - All, Linux, RDOS, Netware
_stat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_stati64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
_wstat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
_wstati64 - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
lstat - All, Linux, RDOS, Netware
```

stat, _stat, _stati64, _	_wstat, _wstati64, Istat	

Synopsis: #include <float.h>
unsigned int \_status87( void );

**Description:** The \_status87 function returns the floating-point status word which is used to record the status of

8087/80287/80387/80486 floating-point operations.

**Returns:** The \_status87 function returns the floating-point status word which is used to record the status of

8087/80287/80387/80486 floating-point operations. The description of this status is found in the

<float.h> header file.

See Also: \_\_clear87, \_control87, \_controlfp, \_finite, \_fpreset

Example: #include <stdio.h>
#include <float.h>

Classification: Intel

**Systems:** Math

Synopsis: #include <strings.h>
 int strcasecmp( const char \*s1, const char \*s2 );

**Description:** The function compares, without case sensitivity, the string pointed to by s1 to the string pointed to by

s2. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the

comparison.

The  ${\tt strcasecmp}$  function is identical to the  ${\tt \_stricmp}$  function.

**Returns:** The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed

to by s1 is, ignoring case, less than, equal to, or greater than the string pointed to by s2.

See Also: strcmp, \_stricmp, strncmp, \_strnicmp, strncasecmp

Example: #include <stdio.h>

```
#include <strings.h>
int main( void )
{
    printf( "%d\n", strcasecmp( "AbCDEF", "abcdef" ) );
    printf( "%d\n", strcasecmp( "abcdef", "ABC" ) );
    printf( "%d\n", strcasecmp( "abc", "ABCdef" ) );
    printf( "%d\n", strcasecmp( "Abcdef", "mnopqr" ) );
    printf( "%d\n", strcasecmp( "Mnopqr", "abcdef" ) );
    return( 0 );
}
```

produces the following:

0 100 -100 -12 12

Classification: POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

**Safer C:** The Safer C Library extension provides the strcat\_s function which is a safer alternative to strcat.

**Description:** The strcat function appends a copy of the string pointed to by *src* (including the terminating null character) to the end of the string pointed to by *dst*. The first character of *src* overwrites the null character at the end of *dst*.

The \_fstrcat function is a data model independent form of the strcat function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wescat function is a wide character version of streat that operates with wide character strings.

The strcat function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The value of *dst* is returned.

See Also: strncat, strcat\_s, strncat\_s

## Example:

```
#include <stdio.h>
#include <string.h>

void main()
{
    char buffer[80];

    strcpy( buffer, "Hello " );
    strcat( buffer, "world" );
    printf( "%s\n", buffer );
}
```

produces the following:

Hello world

**Classification:** ISO C

```
Systems: st
```

```
strcat - All, Linux, RDOS, Netware
_fstrcat - All, Linux, RDOS
wcscat - All, Linux
_mbscat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbscat - DOS, Windows, OS/2 1.x(all)
```

strcat, _	_fstrcat, wcscat,	_mbscat, _f	mbscat		

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and strcat\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Let m denote the value  $s1max - strnlen\_s(s1, s1max)$  upon entry to strcat\_s. Neither s1 nor s2 shall be a null pointer. s1max shall not be greater than RSIZE\_MAX. s1max shall not equal zero. m shall not equal zero. m shall be greater than  $strnlen\_s(s2, m)$ . Copying shall not take place between objects that overlap.

If there is a runtime-constraint violation, then if s1 is not a null pointer and s1max is greater than zero and not greater than RSIZE\_MAX, then strcat\_s sets s1[0] to the null character.

## **Description:**

The strcat\_s function appends a copy of the string pointed to by s2 (including the terminating null character) to the end of the string pointed to by s1. The initial character from s2 overwrites the null character at the end of s1. All elements following the terminating null character (if any) written by strcat\_s in the array of s1max characters pointed to by s1 take unspecified values when strcat\_s returns.

The wcscat\_s function is a wide character version of strcat\_s that operates with wide character strings.

**Returns:** 

The strcat\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

strcat, strncat, strncat\_s

## Example:

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <string.h>

void main( void )
{
    char buffer[80];

    strcpy_s( buffer, sizeof( buffer ), "Hello " );
    strcat_s( buffer, sizeof( buffer ), "world" );
    printf( "%s\n", buffer );
}
```

Hello world

produces the following:

Classification: TR 24731

## strcat\_s, wcscat\_s

strcat\_s - All, Linux, RDOS, Netware
wcscat\_s - All, Linux **Systems:** 

```
#include <string.h>
char *strchr( const char *s, int c );
char __far *_fstrchr( const char __far *s, int c );
#include <wchar.h>
wchar_t *wcschr( const wchar_t *s, wint_t c );
```

## **Description:**

The strchr function locates the first occurrence of c (converted to a char) in the string pointed to by s. The terminating null character is considered to be part of the string.

The \_fstrchr function is a data model independent form of the strchr function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The weschr function is a wide character version of strchr that operates with wide character strings.

The strchr function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

#### **Returns:**

The strchr function returns a pointer to the located character, or NULL if the character does not occur in the string.

See Also:

memchr, strcspn, strrchr, strspn, strstr, strtok

## **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    char buffer[80];
    char *where;

    strcpy( buffer, "video x-rays" );
    where = strchr( buffer, 'x' );
    if( where == NULL ) {
        printf( "'x' not found\n" );
    }
}
```

**Classification:** ISO C

#### **Systems:**

```
strchr - All, Linux, RDOS, Netware
_fstrchr - All, Linux, RDOS
wcschr - All, Linux
_mbschr - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbschr - DOS, Windows, OS/2 1.x(all)
```

**Description:** The strcmp function compares the string pointed to by s1 to the string pointed to by s2.

The \_fstrcmp function is a data model independent form of the strcmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The wesemp function is a wide character version of stremp that operates with wide character strings.

The strcmp function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The strcmp function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by sI is less than, equal to, or greater than the string pointed to by s2.

See Also: \_\_stricmp, strncmp, \_strnicmp, strcasecmp, strncasecmp

```
Example: #include <stdio.h>
#include <string.h>
```

```
void main()
{
    printf( "%d\n", strcmp( "abcdef", "abcdef" ) );
    printf( "%d\n", strcmp( "abcdef", "abc" ) );
    printf( "%d\n", strcmp( "abc", "abcdef" ) );
    printf( "%d\n", strcmp( "abcdef", "mnopqr" ) );
    printf( "%d\n", strcmp( "mnopqr", "abcdef" ) );
}
```

produces the following:

0 1 -1 -1 1

Classification: ISO C

```
Systems: strcmp - All, Linux, RDOS, Netware
```

```
_fstrcmp - All, Linux, RDOS
wcscmp - All, Linux
_mbscmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbscmp - DOS, Windows, OS/2 1.x(all)
```

	 _fmbscmp		

```
** deprecated **
#include <string.h>
int strcmpi( const char *s1, const char *s2 );
int wcscmpi( const wchar_t *s1, const wchar_t *s2 );
```

#### **Description:**

The function compares, without case sensitivity, the string pointed to by s1 to the string pointed to by s2. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The wcscmpi function is a wide character version of strcmpi that operates with wide character strings.

The strcmpi function is deprecated, use \_stricmp instead. The wcscmpi function is deprecated, use \_wcsicmp instead.

#### **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2.

See Also: strcmp, \_stricmp, strncmp, \_strnicmp, strcasecmp, strncasecmp

## **Example:**

```
#include <string.h>

void main()
{
    printf( "%d\n", _strcmpi( "AbCDEF", "abcdef" ) );
    printf( "%d\n", _strcmpi( "abcdef", "ABC" ) );
    printf( "%d\n", _strcmpi( "abc", "ABCdef" ) );
    printf( "%d\n", _strcmpi( "Abcdef", "mnopqr" ) );
    printf( "%d\n", _strcmpi( "Mnopqr", "abcdef" ) );
}
```

produces the following:

#include <stdio.h>

0 100 -100 -12 12

**Classification:** WATCOM

## **Systems:**

```
strcmpi - All, Linux, RDOS, Netware
wcscmpi - All, Linux
```

```
Synopsis: #include <string.h>
    int strcoll( const char *s1, const char *s2 );
    #include <wchar.h>
```

int wcscoll( const wchar\_t \*s1, const wchar\_t \*s2 );

**Description:** The strcoll function compares the string pointed to by s1 to the string pointed to by s2. The comparison uses the collating sequence selected by the setlocale function. The function will be

equivalent to the  ${\tt strcmp}$  function when the collating sequence is selected from the  ${\tt "C"}$  locale.

The wcscoll function is a wide character version of strcoll that operates with wide character strings.

The strcoll function is a multi-byte character version of that operates with multi-byte character strings.

**Returns:** The strcoll function returns an integer less than, equal to, or greater than zero, indicating that the

string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2, according to the

collating sequence selected.

See Also: setlocale, strcmp, strncmp

```
Example: #include <stdio.h>
#include <string.h>
```

```
char buffer[80] = "world";

void main()
{
   if( strcoll( buffer, "Hello" ) < 0 ) {
      printf( "Less than\n" );
   }
}</pre>
```

**Classification:** ISO C

```
Systems: strcoll - All, Linux, RDOS, Netware
```

```
wcscoll - All, Linux
```

\_mbscoll - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

```
Synopsis: #include <string.h>
```

**Safer C:** The Safer C Library extension provides the strcpy\_s function which is a safer alternative to strcpy.

**Description:** The strcpy function copies the string pointed to by *src* (including the terminating null character) into the array pointed to by *dst*. Copying of overlapping objects is not guaranteed to work properly. See the description for the memmove function to copy objects that overlap.

The \_fstrcpy function is a data model independent form of the strcpy function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wcscpy function is a wide character version of strcpy that operates with wide character strings.

The strcpy function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The value of *dst* is returned.

See Also: strdup, strncpy, strcpy\_s, strncpy\_s

#### **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    auto char buffer[80];

    strcpy( buffer, "Hello " );
    strcat( buffer, "world" );
    printf( "%s\n", buffer );
}
```

produces the following:

Hello world

#### **Classification:** ISO C

```
Systems: st
```

```
strcpy - All, Linux, RDOS, Netware
_fstrcpy - All, Linux, RDOS
wcscpy - All, Linux
_mbscpy - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbscpy - DOS, Windows, OS/2 1.x(all)
```


#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and strcpy\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither s1 nor s2 shall be a null pointer. s1max shall not be greater than RSIZE\_MAX. s1max shall not equal zero. s1max shall be greater than  $strnlen\_s(s2, s1max)$ . Copying shall not take place between objects that overlap.

If there is a runtime-constraint violation, then if s1 is not a null pointer and s1max is greater than zero and not greater than RSIZE\_MAX, then strcpy\_s sets s1[0] to the null character.

## **Description:**

The strcpy\_s function copies the string pointed to by s2 (including the terminating null character) into the array pointed to by s1. All elements following the terminating null character (if any) written by strcpy\_s in the array of s1max characters pointed to by s1 take unspecified values when strcpy\_s returns.

The wcscpy\_s function is a wide character version of strcpy\_s that operates with wide character strings.

#### **Returns:**

The strcpy\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

strcpy, strdup, strncpy, strncpy\_s

## **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <string.h>

void main( void )
{
    auto char buffer[80];

    strcpy_s( buffer, sizeof( buffer ), "Hello " );
    strcat_s( buffer, sizeof( buffer ), "world" );
    printf( "%s\n", buffer );
}
```

produces the following:

Hello world

Classification: TR 24731

Systems: strcpy\_s - All, Linux, RDOS, Netware

wcscpy\_s - All, Linux

#### **Description:**

The strcspn function computes the length, in bytes, of the initial segment of the string pointed to by *s* which consists entirely of characters *not* from the string pointed to by *charset*. The terminating null character is not considered part of *s*.

The \_fstrcspn function is a data model independent form of the strcspn function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The wcscspn function is a wide character version of strcspn that operates with wide character strings.

The strcspn function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The length, in bytes, of the initial segment is returned.

See Also: strspn

## **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%d\n", strcspn( "abcbcadef", "cba" ) );
    printf( "%d\n", strcspn( "xxxbcadef", "cba" ) );
    printf( "%d\n", strcspn( "123456789", "cba" ) );
}
```

produces the following:

0 3 9

**Classification:** ISO C

```
Systems:
```

```
strcspn - All, Linux, RDOS, Netware
_fstrcspn - All, Linux, RDOS
wcscspn - All, Linux
_mbscspn - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbscspn - DOS, Windows, OS/2 1.x(all)
```

on, _fstrcspn, wcscspn, _mbscspn, _fmbscspn				

**Description:** The \_strdate function copies the current date to the buffer pointed to by *datestr*. The date is

formatted as "MM/DD/YY" where "MM" is two digits representing the month, where "DD" is two digits representing the day, and where "YY" is two digits representing the year. The buffer must be at

least 9 bytes long.

The \_wstrdate function is a wide character version of \_strdate that operates with wide character strings.

**Returns:** The \_strdate function returns a pointer to the resulting text string *datestr*.

See Also: asctime Functions, ctime Functions, gmtime, localtime, mktime, \_strtime, time,

tzset

```
#include <stdio.h>
#include <time.h>

void main()
{
    char datebuff[9];

    printf( "%s\n", _strdate( datebuff ) );
```

**Classification:** WATCOM

```
Systems: _strdate - All, Linux, RDOS _wstrdate - All, Linux
```

```
#include <string.h>
char *strdup( const char *src );
char *_strdup( const char *src );
char __far *_fstrdup( const char __far *src );
#include <wchar.h>
wchar_t *wcsdup( const wchar_t *src );
wchar_t *_wcsdup( const wchar_t *src );
```

#### **Description:**

The strdup function creates a duplicate copy of the string pointed to by *src* and returns a pointer to the new copy. For strdup the memory for the new string is obtained by using the malloc function and can be freed using the free function. For \_fstrdup, the memory for the new string is obtained by using the \_fmalloc function and can be freed using the \_ffree function.

The \_strdup function is identical to strdup. Use \_strdup for ANSI naming conventions.

The \_fstrdup function is a data model independent form of the strdup function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wesdup function is a wide character version of strdup that operates with wide character strings.

The \_wcsdup function is a wide character version of strdup that operates with wide character strings.

The strdup function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

## **Returns:**

The strdup function returns the pointer to the new copy of the string if successful, otherwise it returns NULL.

See Also:

free, malloc, strcpy, strncpy

#### **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
   char *dup;

   dup = strdup( "Make a copy" );
   printf( "%s\n", dup );
}
```

#### **Classification:** WATCOM

\_strdup conforms to ANSI naming conventions

## **Systems:**

```
strdup - All, Linux, RDOS, Netware
_strdup - All, Linux, RDOS, Netware
_fstrdup - All, Linux, RDOS
wcsdup - All, Linux, RDOS
_wcsdup - All, Linux, RDOS
_mbsdup - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

\_fmbsdup - DOS, Windows, OS/2 1.x(all)

```
Synopsis:
             #include <string.h>
             char *strerror( int errnum );
             wchar_t *_wcserror( int errnum );
Safer C:
             The Safer C Library extension provides the strerror_s function which is a safer alternative to
             strerror.
Description:
             The strerror function maps the error number contained in errnum to an error message.
             The _wcserror function is a wide character version of strerror except that it produces a wide
             character string.
Returns:
             The strerror function returns a pointer to the error message. The array containing the error string
             should not be modified by the program. This array may be overwritten by a subsequent call to the
             strerror function.
See Also:
             clearerr, feof, ferror, perror, strerror_s, strerrorlen_s
Example:
             #include <stdio.h>
             #include <string.h>
             #include <errno.h>
             void main()
                  FILE *fp;
                  fp = fopen( "file.nam", "r" );
                  if( fp == NULL ) {
                       printf( "Unable to open file: %s\n",
                                   strerror( errno ) );
                  }
```

Classification: ISO C

Systems: strerror - All, Linux, RDOS, Netware

\_wcserror - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,

Linux

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and strerror\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

s shall not be a null pointer. maxsize shall not be greater than RSIZE\_MAX. maxsize shall not equal zero.

If there is a runtime-constraint violation, then the array (if any) pointed to by s is not modified.

#### **Description:**

The strerror\_s function maps the number in *errnum* to a locale-specific message string. Typically, the values for *errnum* come from errno, but strerror\_s shall map any value of type int to a message. If the length of the desired string is less than *maxsize*, then the string is copied to the array pointed to by s. Otherwise, if *maxsize* is greater than zero, then *maxsize-1* characters are copied from the string to the array pointed to by s and then s[maxsize-1] is set to the null character. Then, if maxsize is greater than 3, then s[maxsize-2], s[maxsize-3], and s[maxsize-4] are set to the character period (.).

The \_wcserror\_s function is a wide character version of strerror\_s that operates with wide character strings.

## **Returns:**

The strerror\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

clearerr, feof, ferror, perror, strerror, strerrorlen\_s

## **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <string.h>
#include <errno.h>

void main( void )
{
    FILE *fp;
    char emsg[ 100 ];

    fp = fopen( "file.nam", "r" );
    if( fp == NULL ) {
        strerror_s( emsg, sizeof( emsg ), errno );
        printf( "Unable to open file: %s\n", emsg );
    }
}
```

Classification: TR 24731

Systems: strerror\_s - All, Linux, RDOS, Netware

\_wcserror\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux

```
#define __STDC_WANT_LIB_EXT1__ 1
Synopsis:
            #include <string.h>
            size_t strerrorlen_s( errno_t errnum );
            #include <wchar.h>
            size_t _wcserrorlen_s( errno errnum );
Constraints:
            None.
Description:
            The strerrorlen_s function calculates the length of the (untruncated) locale-specific message
            string that the strerror_s function maps to errnum.
            The _wcserrorlen_s function is a wide character version of strerrorlen_s that operates with
            wide character strings.
Returns:
            The strerrorlen_s function returns the number of characters (not including the null character) in
            the full message string.
See Also:
            strerror, strerror_s
Example:
            #define __STDC_WANT_LIB_EXT1__ 1
            #include <stdio.h>
            #include <string.h>
            #include <errno.h>
            void main( void )
                 FILE
                          *fp;
                 char
                          emsg[ 100 ];
                 size_t emsglen;
                 fp = fopen( "file.nam", "r" );
                 if( fp == NULL ) {
                      emsglen = strerrorlen_s( errno );
                      printf( "Length of errormessage: %d\n", emsglen );
```

strerror\_s( emsg, sizeof( emsg ), errno );
printf( "Unable to open file: %s\n", emsg );

Classification: TR 24731

}

Systems: strerrorlen\_s - All, Linux, RDOS, Netware

\_wcserrorlen\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,

Linux

}

```
#include <time.h>
size_t strftime( char *s,
                         size_t maxsize,
                         const char *format,
                         const struct tm *timeptr );
#include <wchar.h>
size_t wcsftime( wchar_t *s,
                         size_t maxsize,
                         const wchar_t *format,
                         const struct tm *timeptr );
#include <time.h>
size_t _wstrftime_ms( wchar_t *s,
                                 size_t maxsize,
                                 const char *format,
                                 const struct tm *timeptr );
struct tm {
  int tm_sec; /* seconds after the minute -- [0,61] */
  int tm_min; /* minutes after the hour -- [0,59] */
  int tm_hour; /* hours after midnight -- [0,23] */
int tm_mday; /* day of the month -- [1,31] */
int tm_mon; /* months since January -- [0,11] */
int tm_year; /* years since 1900 */
int tm_wday; /* days since Sunday -- [0,6] */
int tm_yday; /* days since January 1 -- [0,365]*/
int tm_indet: /* Daylight Savings Time flag
  int tm_isdst; /* Daylight Savings Time flag
```

## **Description:**

The strftime function formats the time in the argument *timeptr* into the array pointed to by the argument *s* according to the *format* argument.

The wcsftime function is a wide character version of strftime that operates with wide character strings.

The \_wstrftime\_ms function is identical to wcsftime except that the *format* is not a wide character string.

The *format* string consists of zero or more directives and ordinary characters. A directive consists of a '%' character followed by a character that determines the substitution that is to take place. All ordinary characters are copied unchanged into the array. No more than *maxsize* characters are placed in the array. The format directives %D, %h, %n, %r, %t, and %T are from POSIX.

Directive	Meaning	
%a	locale's abbreviated weekday name	
%A	locale's full weekday name	
%b	locale's abbreviated month name	
%B	locale's full month name	
%c	locale's appropriate date and time representation	

is replaced by the year devided by 100 and truncated to an integer (0-99)
day of the month as a decimal number (1-31)
date in the format mm/dd/yy (POSIX)
day of the month as a decimal number (1-31), a single digit is preceded by a blank
is equivalent to '%Y-%m-%d' (the ISO 8601 date format)
is replaced by the last 2 digits of the week-based year as a decimal number (0-99)
is replaced by the week-based year as a decimal number (e.g. 2006)
locale's abbreviated month name (POSIX)
hour (24-hour clock) as a decimal number (0-23)
hour (12-hour clock) as a decimal number (1-12)
day of the year as a decimal number (1-366)
month as a decimal number (1-12)
minute as a decimal number (0-59)
newline character (POSIX)
locale's equivalent of either AM or PM
12-hour clock time (1-12) using the AM/PM notation in the format HH:MM:SS (AM PM) (POSIX)
second as a decimal number (0-59)
tab character (POSIX)
24-hour clock time in the format HH:MM:SS (POSIX)
is replaced by the ISO 8601 weekday as a decimal number (1-7), where Monday is 1
week number of the year as a decimal number (0-52) where Sunday is the first day of the week
is replaced by the ISO 8601 week number as a decimal number (1-53)
weekday as a decimal number (0-6) where 0 is Sunday
week number of the year as a decimal number (0-52) where Monday is the first day of the week
locale's appropriate date representation

%X	locale's appropriate time representation
%y	year without century as a decimal number (0-99)
%Y	year with century as a decimal number
%z	offset from UTC in the ISO 8601 format '-0430' (meaning 4 hours 30 minutes behind UTC, west of Greenwich), or by no characters, if no timezone is determinable
% <b>Z</b>	timezone name, or by no characters if no timezone exists
%%	character %

When the %Z or %z directive is specified, the tzset function is called.

% g, %G, %V give values according to the ISO 8601 week-based year. In this system, weeks begin on a monday and week 1 of the year is the week that includes January 4th, which is also the week that includes the first Thursday of the year, and is also the first week that contains at least four days in the year. If the first Monday of January is the 2nd, 3rd, or 4th, the preceding days are part of the last week of the preceding year; thus, for Saturday 2nd January 1999, %G is replaced by 1998 and %V is replaced by 53. If december 29th, 30th, or 31st is a Monday, it and any following days are part of week 1 of the following year. Thus, for Tuesday 30th December 1997, %G is replaced by 1998 and %V is replaced by 01.

The format modifiers E and O are ignored. (eg. %EY is the same as %Y)

## **Returns:**

If the number of characters to be placed into the array is less than *maxsize*, the strftime function returns the number of characters placed into the array pointed to by *s* not including the terminating null character. Otherwise, zero is returned. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also:

setlocale, asctime Functions, asctime\_s, clock, ctime Functions, ctime\_s, difftime, gmtime, gmtime\_s, localtime, localtime\_s, mktime, time, tzset

## **Example:**

produces the following:

Today is Friday December 25, 1987

Classification: ISO C, POSIX

wcsftime is ISO C95

strftime - All, Linux, RDOS, Netware
wcsftime - All, Linux **Systems:** 

\_wstrftime\_ms - All, Linux

## **Description:**

The function compares, without case sensitivity, the string pointed to by s1 to the string pointed to by s2. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_fstricmp function is a data model independent form of the \_stricmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The \_wcsicmp function is a wide character version of \_stricmp that operates with wide character strings.

The \_stricmp function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The stricmp function is deprecated, use \_stricmp instead.

#### **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2.

See Also:

strcmp, strncmp, \_strnicmp, strcasecmp, strncasecmp

# **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%d\n", _stricmp( "AbCDEF", "abcdef" ) );
    printf( "%d\n", _stricmp( "abcdef", "ABC" ) );
    printf( "%d\n", _stricmp( "abc", "ABCdef" ) );
    printf( "%d\n", _stricmp( "Abcdef", "mnopqr" ) );
    printf( "%d\n", _stricmp( "Mnopqr", "abcdef" ) );
}
```

produces the following:

0 100 -100 -12 12

```
_stricmp - All, Linux, RDOS, Netware
_fstricmp - All, Linux, RDOS
_wcsicmp - All, Linux
Systems:
```

\_mbsicmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

\_fmbsicmp - DOS, Windows, OS/2 1.x(all) stricmp - All, Linux, RDOS, Netware

```
Synopsis: #include <string.h>
    int _stricoll( const char *s1, const char *s2 );
    #include <wchar.h>
    int _wcsicoll( const wchar_t *s1, const wchar_t *s2 );
```

#### **Description:**

The function performs a comparison without case sensitivity of the string pointed to by s1 to the string pointed to by s2. The comparison uses the current code page which can be selected by the \_setmbcp function. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_wcsicoll function is a wide character version of \_stricoll that operates with wide character strings.

The \_stricoll function is a multi-byte character version of that operates with multi-byte character strings.

#### **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2, according to the collating sequence selected.

See Also: \_setmbcp, strcoll, \_stricmp, strncmp, \_strncoll, \_strnicmp, \_strnicoll

# **Example:**

```
#include <stdio.h>
#include <string.h>

char buffer[80] = "world";

void main()
{
   int test;

   test = _stricoll( buffer, "world2" );
   if( test < 0 ) {
      printf( "Less than\n" );
   } else if( test == 0 ) {
      printf( "Equal\n" );
   } else {
      printf( "Greater than\n" );
   }
}</pre>
```

```
Systems:
```

```
_stricoll - All, Linux, RDOS, Netware
_wcsicoll - All, Linux
_mbsicoll - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

_stricoll, _wcsicoll, _mbsicoll

```
Synopsis:
           #include <string.h>
           size_t strlcat( char *dst, const char *src, size_t n );
           size_t *wcslcat( wchar_t *dst,
                             const wchar_t *src,
                             size_t n );
```

**Description:** 

The strlcat function appends characters of the string pointed to by src to the end of the string in a buffer pointed to by dst that can hold up to n characters. The first character of src overwrites the null character at the end of dst. A terminating null character is always appended to the result, unless ncharacters of dst are scanned and no null character is found.

The wcslcat function is a wide character version of strlcat that operates with wide character strings.

**Returns:** 

The strlcat function returns the total length of string it tried to create, that is the number of characters in both src and dst strings, not counting the terminating null characters. If n characters of dst were scanned without finding a null character, *n* is returned.

See Also: strlcpy, strncat, strcat

**Example:** 

```
#include <stdio.h>
#include <string.h>
char buffer[80];
void main( void )
    strcpy( buffer, "Hello " );
    strlcat( buffer, "world", 12 );
    printf( "%s\n", buffer );
    strlcat( buffer, "*********, 16 );
    printf( "%s\n", buffer );
}
produces the following:
```

```
Hello world
Hello world****
```

**Classification:** WATCOM

**Systems:** strlcat - All, Linux, RDOS, Netware

wcslcat - All, Linux

## **Description:**

The strlcpy function copies no more than n characters from the string pointed to by src into the array pointed to by dst. Copying of overlapping objects is not guaranteed to work properly. See the memmove function if you wish to copy objects that overlap.

If the string pointed to by src is longer than n characters, then only n - 1 characters will be copied and the result will be null terminated.

The wcslcpy function is a wide character version of strlcpy that operates with wide character strings.

#### **Returns:**

The strlcpy function returns the number of characters in the *src* string, not including the terminating null character.

See Also:

strlcat, strncpy, strcpy

#include <stdio.h>

# **Example:**

produces the following:

15:'Buffer ov'

# **Classification:** WATCOM

**Systems:** 

```
strlcpy - All, Linux, RDOS, Netware
wcslcpy - All, Linux
```

**Library Functions and Macros 1213** 

```
Synopsis: #include <string.h>
    size_t strlen( const char *s );
    size_t _fstrlen( const char __far *s );
    #include <wchar.h>
    size_t wcslen( const wchar_t *s );
```

**Safer C:** The Safer C Library extension provides the strnlen\_s function which is a safer alternative to strlen.

**Description:** The strlen function computes the length of the string pointed to by s.

The \_fstrlen function is a data model independent form of the strlen function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The wcslen function is a wide character version of strlen that operates with wide character strings.

The strlen function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The strlen function returns the number of characters that precede the terminating null character.

See Also: strnlen\_s

```
Example:
```

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%d\n", strlen( "Howdy" ) );
    printf( "%d\n", strlen( "Hello world\n" ) );
    printf( "%d\n", strlen( "" ) );
}
```

produces the following:

5 12 0

Classification: ISO C

```
Systems:
```

```
strlen - All, Linux, RDOS, Netware
_fstrlen - All, Linux, RDOS
wcslen - All, Linux
_mbslen - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbslen - DOS, Windows, OS/2 1.x(all)
```

strlen, _fstrlen, wcslen, _mbslen, _fmbslen
 ,_ ,_ ,_ ,_

**Constraints:** None.

**Description:** The strnlen\_s function calculates the length of the string pointed to by s.

The wcsnlen\_s function is a wide character version of strnlen\_s that operates with wide character strings.

**Returns:** If s is a null pointer, then the strnlen\_s function returns zero. Otherwise, the strnlen\_s function

returns the number of characters that precede the terminating null character. If there is no null character in the first *maxsize* characters of *s* then strnlen\_s returns *maxsize*. At most the first *maxsize* 

characters of s shall be accessed by strnlen\_s

See Also: strlen

Example: #define \_\_STDC\_WANT\_LIB\_EXT1\_\_ 1
#include <stdio.h>

```
#include <string.h>
void main( void )
{
   char   buffer[ 30 ] = "Hello world.";
   size_t len;

len = strnlen_s( buffer, sizeof( buffer ) );
   printf( "Length of text: %d\n", emsglen );
```

printf( "Text: %s\n", buffer );

Classification: TR 24731

Systems: strnlen\_s - All, RDOS, Netware

wcsnlen\_s - All, Linux

```
#include <string.h>
char *_strlwr( char *s1 );
char __far *_fstrlwr( char __far *s1 );
#include <wchar.h>
wchar_t *_wcslwr( wchar_t *s1 );

** deprecated **
char *strlwr( char *s1 );
```

#### **Description:**

The \_strlwr function replaces the string *s1* with lowercase characters by invoking the tolower function for each character in the string.

The \_fstrlwr function is a data model independent form of the \_strlwr function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The \_wcslwr function is a wide character version of \_strlwr that operates with wide character strings.

The \_strlwr function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The strlwr function is deprecated, use \_strlwr instead.

**Returns:** 

The address of the original string *s1* is returned.

See Also:

\_strupr

#### **Example:**

```
#include <stdio.h>
#include <string.h>

char source[] = { "A mixed-case STRING" };

void main()
    {
        printf( "%s\n", source );
        printf( "%s\n", _strlwr( source ) );
        printf( "%s\n", source );
    }
}
```

produces the following:

```
A mixed-case STRING
a mixed-case string
a mixed-case string
```

```
Systems:
```

```
_strlwr - All, Linux, RDOS, Netware
_fstrlwr - All, Linux, RDOS
_wcslwr - All, Linux
_mbslwr - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

\_fmbslwr - DOS, Windows, OS/2 1.x(all)
strlwr - All, Linux, RDOS, Netware

**Description:** The function compares, without case sensitivity, the string pointed to by s1 to the string pointed to by

s2, for at most len characters. All uppercase characters from s1 and s2 are mapped to lowercase for the

purposes of doing the comparison.

The strncasecmp function is identical to the \_strnicmp function.

**Returns:** The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed

to by sI is, ignoring case, less than, equal to, or greater than the string pointed to by s2.

See Also: strcmp, \_stricmp, strncmp, \_strnicmp, strcasecmp

#include <stdio.h>
#include <strings.h>

int main( void )
{
 printf( "%d\n", strncasecmp( "abcdef", "ABCXXX", 10 ) );
 printf( "%d\n", strncasecmp( "abcdef", "ABCXXX", 6 ) );
 printf( "%d\n", strncasecmp( "abcdef", "ABCXXX", 3 ) );
 printf( "%d\n", strncasecmp( "abcdef", "ABCXXX", 0 ) );
 return( 0 );
}

produces the following:

-20 -20 0 0

Classification: POSIX 1003.1

**Systems:** All, RDOS, Netware

## 

size\_t n );

**Safer C:** The Safer C Library extension provides the strncat\_s function which is a safer alternative to strncat.

**Description:** The strncat function appends not more than *n* characters of the string pointed to by *src* to the end of the string pointed to by *dst*. The first character of *src* overwrites the null character at the end of *dst*. A terminating null character is always appended to the result.

The \_fstrncat function is a data model independent form of the strncat function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wcsncat function is a wide character version of strncat that operates with wide character strings.

The strncat function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The strncat function returns the value of *dst*.

See Also: strcat, strlcat, strncat\_s, strcat\_s

#include <stdio.h>
#include <string.h>

char buffer[80];

void main( void )
{
 strcpy( buffer, "Hello " );
 strncat( buffer, "world", 8 );
 printf( "%s\n", buffer );
 strncat( buffer, "\*\*\*\*\*\*\*\*\*\*\*, 4 );
 printf( "%s\n", buffer );
}

produces the following:

Hello world
Hello world\*\*\*\*

**Classification:** ISO C

# Systems: strncat - All, Linux, RDOS, Netware

\_fstrncat - All, Linux, RDOS

wcsncat - All, Linux

\_mbsncat - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

\_fmbsncat - DOS, Windows, OS/2 1.x(all)

```
#define ___STDC_WANT_LIB_EXT1___
#include <string.h>
errno_t strncat_s( char * restrict s1,
                   rsize_t s1max,
                   const char * restrict s2,
                   rsize_t n )
#include <wchar.h>
errno_t wcsncat_s( wchar_t * restrict s1,
                   rsize_t s1max,
                   const wchar_t * restrict s2,
                   rsize_t n )
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and strncat\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Let m denote the value sImax - strnlen s(s1, sImax) upon entry to strncat s

Neither s1 nor s2 shall be a null pointer. Neither s1max nor n shall be greater than RSIZE MAX. sImax shall not equal zero. m shall not equal zero. If n is not less than m, then m shall be greater than *strnlen\_s*(*s*2, *m*). Copying shall not take place between objects that overlap.

If there is a runtime-constraint violation, then if s1 is not a null pointer and s1max is greater than zero and not greater than RSIZE\_MAX, then strncat\_s sets s1[0] to the null character.

## **Description:**

The strncat\_s function appends not more than *n* successive characters (characters that follow a null character are not copied) from the array pointed to by s2 to the end of the string pointed to by s1. The initial character from s2 overwrites the null character at the end of s1. If no null character was copied from s2,then s1[s1max-m+n] is set to a null character. All elements following the terminating null character (if any) written by strncat\_s in the array of sImax characters pointed to by sI take unspecified values when strncat\_s returns.

The wcsncat\_s function is a wide character version of strncat\_s that operates with wide character strings.

# **Returns:**

The strncat\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

# See Also:

strncat, strcat, strlcat, strcat\_s

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <string.h>
char buffer[80];
void main( void )
    strcpy( buffer, "Hello " );
    strncat_s( buffer, sizeof( buffer ), "world", 8 );
   printf( %s\n'', buffer );
    strncat( buffer, "*********, 4 );
   printf( %s\n, buffer );
}
```

produces the following:

Hello world
Hello world\*\*\*\*

Classification: TR 24731

Systems: strncat\_s - All, Linux, RDOS, Netware

wcsncat\_s - All, Linux

## **Description:**

The strncmp compares not more than n characters from the string pointed to by s1 to the string pointed to by s2.

The \_fstrncmp function is a data model independent form of the strncmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The wcsncmp function is a wide character version of strncmp that operates with wide character strings.

The strncmp function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

## **Returns:**

The strncmp function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2.

See Also:

strcmp, \_stricmp, \_strnicmp, strcasecmp

#### **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%d\n", strncmp( "abcdef", "abcDEF", 10 ) );
    printf( "%d\n", strncmp( "abcdef", "abcDEF", 6 ) );
    printf( "%d\n", strncmp( "abcdef", "abcDEF", 3 ) );
    printf( "%d\n", strncmp( "abcdef", "abcDEF", 0 ) );
}
```

produces the following:

**Classification:** ISO C

**Systems:** 

```
strncmp - All, Linux, RDOS, Netware
_fstrncmp - All, Linux, RDOS
```

```
wcsncmp - All, Linux
_mbsncmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbsncmp - DOS, Windows, OS/2 1.x(all)
```

## 

#include <stdio.h>

**Description:** These functions compare the first *count* characters of the string pointed to by s1 to the string pointed to by s2. The comparison uses the current code page which can be selected by the \_setmbcp function.

size\_t count );

The \_wcsncoll function is a wide character version of \_strncoll that operates with wide character strings.

The \_strncoll function is a multi-byte character version of that operates with multi-byte character strings.

**Returns:** 

These functions return an integer less than, equal to, or greater than zero, indicating that the string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2, according to the collating sequence selected.

See Also: \_setmbcp, strcoll, \_stricmp, \_stricoll, strncmp, \_strnicmp, \_strnicoll

**Example:** 

```
#include <string.h>
char buffer[80] = "world";

void main()
{
   int test;

   test = _strncoll( buffer, "world2", 5 );
   if( test < 0 ) {
      printf( "Less than\n" );
   } else if( test == 0 ) {
      printf( "Equal\n" );
   } else {
      printf( "Greater than\n" );
   }
}</pre>
```

```
Systems: _strncoll - All, Linux, RDOS, Netware _wcsncoll - All, Linux _mbsncoll - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

_strncoll, _wcsncoll, _mbsncoll

#### Safer C:

The Safer C Library extension provides the strncpy\_s function which is a safer alternative to strncpy.

#### **Description:**

The strncpy function copies no more than n characters from the string pointed to by src into the array pointed to by dst. Copying of overlapping objects is not guaranteed to work properly. See the memmove function if you wish to copy objects that overlap.

If the string pointed to by src is shorter than n characters, null characters are appended to the copy in the array pointed to by dst, until n characters in all have been written. If the string pointed to by src is longer than n characters, then the result will not be terminated by a null character.

The \_fstrncpy function is a data model independent form of the strncpy function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wcsncpy function is a wide character version of strncpy that operates with wide character strings.

The strncpy function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The strncpy function returns the value of *dst*.

See Also: strlcpy, strcpy, strdup, strncpy\_s, strcpy\_s

## **Example:**

```
#include <stdio.h>
#include <string.h>

void main( void )
{
    char buffer[15];

    printf( "%s\n", strncpy( buffer, "abcdefg", 10 ) );
    printf( "%s\n", strncpy( buffer, "1234567", 6 ) );
    printf( "%s\n", strncpy( buffer, "abcdefg", 3 ) );
    printf( "%s\n", strncpy( buffer, "abcdefg", 3 ) );
    printf( "%s\n", strncpy( buffer, "******", 0 ) );
}
```

produces the following:

```
abcdefg
123456g
abc456g
abc456g
```

**Classification:** ISO C

Systems: strncpy - All, Linux, RDOS, Netware

\_fstrncpy - All, Linux, RDOS

wcsncpy - All, Linux

\_mbsncpy - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

\_fmbsncpy - DOS, Windows, OS/2 1.x(all)

```
#define __STDC_WANT_LIB_EXT1__
#include <string.h>
errno_t strncpy_s( char * restrict s1,
                   rsize_t s1max,
                   const char * restrict s2,
                   rsize_t n );
#include <wchar.h>
errno_t wcsncpy_s( wchar_t * restrict s1,
                   rsize_t s1max,
                   const wchar_t * restrict s2,
                   rsize_t n );
```

Constraints: If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and strncpy\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither s1 nor s2 shall be a null pointer. Neither s1max nor n shall be greater than RSIZE\_MAX. s1max shall not equal zero. If n is not less than s1max, then s1max shall be greater than strnlen\_s(s2, s1max).

Copying shall not take place between objects that overlap.

If there is a runtime-constraint violation, then if s1 is not a null pointer and s1max is greater than zero and not greater than RSIZE\_MAX, then strncpy\_s sets s1[0] to the null character.

## **Description:**

The strncpy\_s function copies not more than n successive characters (characters that follow a null character are not copied) from the array pointed to by s2 to the array pointed to by s1. If no null character was copied from s2, then s1/n is set to a null character.

All elements following the terminating null character (if any) written by strncpy\_s in the array of slmax characters pointed to by sl take unspecified values when strncpy\_s returns.

The wcsncpy\_s function is a wide character version of strncpy\_s that operates with wide character strings.

# **Returns:**

The strncpy\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

### See Also:

strncpy, strlcpy, strcpy, strdup, strcpy\_s

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <string.h>
void main( void )
    char buffer[15];
```

```
strncpy_s( buffer, sizeof( buffer ), "abcdefg", 10 );
               printf( "%s\n", buffer );
               strncpy_s( buffer, sizeof( buffer ), "1234567", 6 );
               printf( %s\n, buffer );
               strncpy_s( buffer, sizeof( buffer ), "abcdefg", 3 );
               printf( "%s\n", buffer );
               strncpy_s( buffer, sizeof( buffer ), "******", 0 );
               printf( "%s\n", buffer );
           }
           produces the following:
           abcdefg
           123456
           abc
           (nothing)
Classification: TR 24731
Systems:
           strncpy_s - All, Linux, RDOS, Netware
           wcsncpy_s - All, Linux
```

#### **Description:**

The function compares, without case sensitivity, the string pointed to by s1 to the string pointed to by s2, for at most *len* characters. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_fstrnicmp function is a data model independent form of the \_strnicmp function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The \_wcsnicmp function is a wide character version of \_strnicmp that operates with wide character strings.

The \_strnicmp function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The strnicmp function is deprecated, use \_strnicmp instead.

## **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by sI is less than, equal to, or greater than the string pointed to by s2.

See Also:

strcmp, \_stricmp, strncmp, strcasecmp, strncasecmp

# **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%d\n", _strnicmp( "abcdef", "ABCXXX", 10 ) );
    printf( "%d\n", _strnicmp( "abcdef", "ABCXXX", 6 ) );
    printf( "%d\n", _strnicmp( "abcdef", "ABCXXX", 3 ) );
    printf( "%d\n", _strnicmp( "abcdef", "ABCXXX", 0 ) );
}
```

produces the following:

```
-20
-20
0
0
```

```
Systems:

_strnicmp - All, Linux, RDOS, Netware
_fstrnicmp - All, Linux, RDOS
_wcsnicmp - All, Linux
_mbsnicmp - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbsnicmp - DOS, Windows, OS/2 1.x(all)
strnicmp - All, Linux, RDOS, Netware
```

#include <stdio.h>

## **Synopsis:**

#### **Description:**

The function performs a comparison without case sensitivity of the first *count* characters of the string pointed to by s1 to the string pointed to by s2. The comparison uses the current code page which can be selected by the \_setmbcp function. All uppercase characters from s1 and s2 are mapped to lowercase for the purposes of doing the comparison.

The \_wcsnicoll function is a wide character version of \_strnicoll that operates with wide character strings.

The \_strnicoll function is a multi-byte character version of that operates with multi-byte character strings.

#### **Returns:**

The function returns an integer less than, equal to, or greater than zero, indicating that the string pointed to by s1 is less than, equal to, or greater than the string pointed to by s2, according to the collating sequence selected.

See Also: \_setmbcp, strcoll, \_stricmp, \_stricoll, strncmp, \_strncoll, \_strnicmp

## **Example:**

```
#include <string.h>
char buffer[80] = "world";

void main()
{
   int test;

   test = _strnicoll( buffer, "World2", 5 );
   if( test < 0 ) {
      printf( "Less than\n" );
   } else if( test == 0 ) {
      printf( "Equal\n" );
   } else {
      printf( "Greater than\n" );
   }
}</pre>
```

```
Systems:
```

```
_strnicoll - All, Linux, RDOS, Netware
_wcsnicoll - All, Linux
_mbsnicoll - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
RDOS
```

_strnicoll, _wcsnicoll, _mbsnicoll

# **Description:**

The \_strnset function fills the string *s* with the value of the argument *fill*, converted to be a character value. When the value of *count* is greater than the length of the string, the entire string is filled. Otherwise, that number of characters at the start of the string are set to the fill character.

The \_fstrnset function is a data model independent form of the \_strnset function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The \_wcsnset function is a wide character version of \_strnset that operates with wide character strings. For \_wcsnset, the value of *count* is the number of wide characters to fill. This is half the number of bytes.

The \_strnset function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

For , the value of *count* is the number of multibyte characters to fill. If the number of bytes to be filled is odd and *fill* is a double-byte character, the partial byte at the end is filled with an ASCII space character.

The strnset function is deprecated, use \_strnset instead.

**Returns:** 

The address of the original string *s* is returned.

See Also:

\_strset

## **Example:**

```
#include <stdio.h>
#include <string.h>

char source[] = { "A sample STRING" };

void main()
    {
        printf( "%s\n", source );
        printf( "%s\n", _strnset( source, '=', 100 ) );
        printf( "%s\n", _strnset( source, '*', 7 ) );
    }
}
```

produces the following:

**Classification:** WATCOM

Systems: \_strnset - All, Linux, RDOS, Netware

\_fstrnset - All, Linux, RDOS

\_wcsnset - All, Linux

\_mbsnset - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

\_fmbsnset - DOS, Windows, OS/2 1.x(all) strnset - All, Linux, RDOS, Netware

wcsnset - All, Linux

## 

**Description:** 

The strpbrk function locates the first occurrence in the string pointed to by *s* of any character from the string pointed to by *charset*.

The \_fstrpbrk function is a data model independent form of the strpbrk function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wcspbrk function is a wide character version of strpbrk that operates with wide character strings.

The strpbrk function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** 

The strpbrk function returns a pointer to the located character, or NULL if no character from *charset* occurs in s.

**See Also:** strchr, strrchr, strtok

#include <stdio.h>

**Example:** 

```
#include <string.h>
void main()
{
    char *p = "Find all vowels";

    while( p != NULL ) {
        printf( "%s\n", p );
        p = strpbrk( p+1, "aeiouAEIOU" );
    }
}
```

produces the following:

```
Find all vowels
ind all vowels
all vowels
owels
els
```

Classification: ISO C

**Systems:** 

```
strpbrk - All, Linux, RDOS, Netware
_fstrpbrk - All, Linux, RDOS
wcspbrk - All, Linux
```

\_mbspbrk - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS \_fmbspbrk - DOS, Windows, OS/2 1.x(all)

#### 

char \_\_far \*\_fstrrchr( const char \_\_far \*s, int c );
#include <wchar.h>
wchar\_t \*wcsrchr( const wchar\_t \*s, wint\_t c );

**Description:** 

The strrchr function locates the last occurrence of c (converted to a char) in the string pointed to by s. The terminating null character is considered to be part of the string.

The \_fstrrchr function is a data model independent form of the strrchr function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wcsrchr function is a wide character version of strrchr that operates with wide character strings.

The strrchr function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** 

The strrchr function returns a pointer to the located character, or a NULL pointer if the character does not occur in the string.

See Also: strchr, strpbrk

**Example:** 

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%s\n", strrchr( "abcdeaaklmn", 'a' ) );
    if( strrchr( "abcdeaaklmn", 'x' ) == NULL )
        printf( "NULL\n" );
}
```

produces the following:

aklmn NULL

Classification: ISO C

```
strrchr - All, Linux, RDOS, Netware
_fstrrchr - All, Linux, RDOS
wcsrchr - All, Linux
_mbsrchr - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbsrchr - DOS, Windows, OS/2 1.x(all)
```

etrr	chr fetrrehr	weerchr m	bsrchr, _fmbsi
501			

# Synopsis: #incl char

```
#include <string.h>
char *_strrev( char *s1 );
char __far *_fstrrev( char __far *s1 );
#include <wchar.h>
wchar_t *_wcsrev( wchar_t *s1 );

** deprecated **
char *strrev( char *s1 );
```

**Description:** 

The \_strrev function replaces the string s1 with a string whose characters are in the reverse order.

The \_strrev function is identical to \_strrev. Use \_strrev for ANSI naming conventions.

The \_fstrrev function is a data model independent form of the \_strrev function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The \_wcsrev function is a wide character version of \_strrev that operates with wide character strings.

The \_strrev function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The strrev function is deprecated, use \_strrev instead.

**Returns:** 

The address of the original string *s1* is returned.

**Example:** 

produces the following:

#include <stdio.h>

```
A sample STRING
GNIRTS elpmas A
A sample STRING
```

**Classification:** WATCOM

```
Systems:
```

```
_strrev - All, Linux, RDOS, Netware
_fstrrev - All, Linux, RDOS
_wcsrev - All, Linux
_mbsrev - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbsrev - DOS, Windows, OS/2 1.x(all)
```

strrev - All, Linux, RDOS, Netware

# 

char \*strset( char \*s1, int fill );

**Description:** The \_strset function fills the string pointed to by *s1* with the character *fill*. The terminating null character in the original string remains unchanged.

The \_fstrset function is a data model independent form of the \_strset function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The \_wcsset function is a wide character version of \_strset that operates with wide character strings.

The \_strset function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The strset function is deprecated, use \_strset instead.

**Returns:** The address of the original string *s1* is returned.

#include <stdio.h>

```
See Also: _strnset
```

# **Example:**

```
#include <string.h>
char source[] = { "A sample STRING" };

void main()
{
    printf( "%s\n", source );
    printf( "%s\n", _strset( source, '=' ) );
    printf( "%s\n", _strset( source, '*' ) );
}
```

produces the following:

# **Classification:** WATCOM

```
Systems: _strset - All, Linux, RDOS, Netware _fstrset - All, Linux, RDOS
```

```
_wcsset - All, Linux
_mbsset - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

\_fmbsset - DOS, Windows, OS/2 1.x(all)
strset - All, Linux, RDOS, Netware

#### **Description:**

The strspn function computes the length, in bytes, of the initial segment of the string pointed to by *s* which consists of characters from the string pointed to by *charset*. The terminating null character is not considered to be part of *charset*.

The \_fstrspn function is a data model independent form of the strspn function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The wcsspn function is a wide character version of strspn that operates with wide character strings.

The strspn function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The length, in bytes, of the initial segment is returned.

See Also: strcspn, strspnp

# **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%d\n", strspn( "out to lunch", "aeiou" ) );
    printf( "%d\n", strspn( "out to lunch", "xyz" ) );
}
```

produces the following:

2

#### **Classification:** ISO C

```
strspn - All, Linux, RDOS, Netware
_fstrspn - All, Linux, RDOS
wcsspn - All, Linux
_mbsspn - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbsspn - DOS, Windows, OS/2 1.x(all)
```

strspn, _fstrspn, wcsspn, _mbsspn, _fmbs	spi

**Systems:** 

```
Synopsis:
             #include <string.h>
             char *strspnp( const char *s,
                                const char *charset );
             char __far *_fstrspnp( const char __far *s,
                                          const char __far *charset );
Description:
             The strspnp function returns a pointer to the first character in s that does not belong to the set of
             characters in charset. The terminating null character is not considered to be part of charset.
             The _fstrspnp function is a data model independent form of the strspnp function. It accepts far
             pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.
Returns:
             These functions return NULL if s consists entirely of characters from charset.
See Also:
             strcspn, strspn
Example:
             #include <stdio.h>
             #include <string.h>
             void main()
                  printf( "%s\n", strspnp( "out to lunch", "aeiou" ) );
                  printf( "%s\n", strspnp( "out to lunch", "xyz" ) );
             produces the following:
             t to lunch
             out to lunch
Classification: WATCOM
```

strspnp - All, Linux, RDOS, Netware

\_fstrspnp - All, Linux, RDOS

#### **Description:**

The strstr function locates the first occurrence in the string pointed to by *s* of the sequence of characters (excluding the terminating null character) in the string pointed to by *substr*.

The \_fstrstr function is a data model independent form of the strstr function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wesstr function is a wide character version of strstr that operates with wide character strings.

The strstr function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

**Returns:** The strstr function returns a pointer to the located string, or NULL if the string is not found.

See Also: strcspn

# **Example:**

```
#include <stdio.h>
#include <string.h>

void main()
{
    printf( "%s\n", strstr("This is an example", "is") );
}
```

produces the following:

is is an example

#### **Classification:** ISO C

\_fstrstr is WATCOM wcsstr is ISO C95 \_mbsstr is WATCOM \_fmbsstr is WATCOM

```
strstr - All, Linux, RDOS, Netware
_fstrstr - All, Linux, RDOS
wcsstr - All, Linux
_mbsstr - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
_fmbsstr - DOS, Windows, OS/2 1.x(all)
```

**Description:** The \_strtime function copies the current time to the buffer pointed to by *timestr*. The time is

formatted as "HH:MM:SS" where "HH" is two digits representing the hour in 24-hour notation, where "MM" is two digits representing the minutes past the hour, and where "SS" is two digits representing

seconds. The buffer must be at least 9 bytes long.

The \_wstrtime function is a wide character version of \_strtime that operates with wide character

strings.

**Returns:** The \_strtime function returns a pointer to the resulting text string *timestr*.

See Also: asctime Functions, ctime Functions, gmtime, localtime, mktime, \_strdate, time,

tzset

```
Example: #include <stdio.h>
#include <time.h>
```

```
void main()
{
   char timebuff[9];

  printf( "%s\n", _strtime( timebuff ) );
}
```

**Classification:** WATCOM

```
Systems: _strtime - All, Linux, RDOS _wstrtime - All, Linux
```

Synopsis: #include <stdlib.h>

```
double strtod( const char *ptr, char **endptr );
#include <wchar.h>
double wcstod( const wchar_t *ptr, wchar_t **endptr );
```

#### **Description:**

The strtod function converts the string pointed to by *ptr* to double representation. First, it decompose the input string into three parts: an initial, possibly empty, sequence of white-space characters (as specified by the isspace function), a subject sequence resembling a floating-point constant or representing an infinity or NaN; and a final string of one or more unrecognized characters, including the terminating null character of the input string. Then, it attempts to convert the subject sequence to a floating-point number, and return the result.

The expected form of the subject sequence is an optional plus or minus sign, then one of the following:

- a decimal floating-point number
- a hexadecimal floating-point number
- INF or INFINITY, ignoring case
- NAN, ignoring case, optionally followed by a sequence of digits and nondigits (upper- or lowercase characters or underscore) enclosed in parentheses.

The subject sequence is defined as the longest initial subsequence of the input string, starting with the first non-whitespace character, that is of the expected form. The subject sequence contains no characters if the input string is not of the expected form.

A decimal floating-point number recognized by strtod (after optional sign was processed) is a string containing:

- a sequence of digits containing an optional decimal point,
- an optional 'e' or 'E' followed by an optionally signed sequence of digits.

A hexadecimal floating-point number recognized by strtod (after optional sign was processed) is a string containing:

- a 0X prefix, ignoring case,
- a sequence of hexadecimal digits containing an optional decimal point,
- an optional 'p' or 'P' followed by an optionally signed sequence of decimal digits.

The subject sequence is defined as the longest initial subsequence of the input string, starting with the first non-white-space character, that is of the expected form. The subject sequence contains no characters if the input string is not of the expected form.

If the subject sequence contains NAN, a NaN (with appropriate sign) will be returned; the optional digit-nondigit sequence is ignored. If the subject sequence contains INF, the value of infinity (with appropriate sign) will be returned. This case can be distinguished from overflow by checking errno.

For a hexadecimal floating-point number, the optional exponent is binary (that is, denotes a power of two), not decimal.

A pointer to the final string (following the subject sequence) will be stored in the object to which *endptr* points if *endptr* is not NULL. By comparing the "end" pointer with *ptr*, it can be determined how much of the string, if any, was scanned by the strtod function.

The wested function is a wide character version of strted that operates with wide character strings.

**Returns:** 

The strtod function returns the converted value, if any. If no conversion could be performed, zero is returned. If the correct value would cause overflow, plus or minus HUGE\_VAL is returned according to the sign, and errno is set to ERANGE. If the correct value would cause underflow, then zero is returned, and errno is set to ERANGE. Zero is returned when the input string cannot be converted. In this case, errno is not set. When an error has occurred, errno contains a value indicating the type of error that has been detected.

pi = strtod( "3.141592653589793", NULL );

printf( "pi=%17.15f\n",pi );

See Also: atof

Example: #include <stdio.h>
 #include <stdlib.h>

void main( void )
{
 double pi;

Classification: ISO C90

Systems: strtod - Math wcstod - Math

#### Safer C:

The Safer C Library extension provides the strtok\_s function which is a safer alternative to strtok.

#### **Description:**

The strtok function is used to break the string pointed to by sI into a sequence of tokens, each of which is delimited by a character from the string pointed to by s2. The first call to strtok will return a pointer to the first token in the string pointed to by sI. Subsequent calls to strtok must pass a NULL pointer as the first argument, in order to get the next token in the string. The set of delimiters used in each of these calls to strtok can be different from one call to the next.

The first call in the sequence searches sI for the first character that is not contained in the current delimiter string s2. If no such character is found, then there are no tokens in sI and the strtok function returns a NULL pointer. If such a character is found, it is the start of the first token.

The strtok function then searches from there for a character that is contained in the current delimiter string. If no such character is found, the current token extends to the end of the string pointed to by s1. If such a character is found, it is overwritten by a null character, which terminates the current token. The strtok function saves a pointer to the following character, from which the next search for a token will start when the first argument is a NULL pointer.

Because strtok may modify the original string, that string should be duplicated if the string is to be re-used.

The reentrant form of this function, strtok\_r, also requires a pointer to a string pointer to be passed. This pointer is used internally by the function for subsequent calls to perform tokenizing without relying on internal state within the function.

The \_fstrtok function is a data model independent form of the strtok function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The wcstok function is a wide character version of strtok that operates with wide character strings. The third argument *ptr* points to a caller-provided wchar\_t pointer into which the wcstok function stores information necessary for it to continue scanning the same wide string.

On the first call in the sequence of calls to wcstok, sI points to a wide string. In subsequent calls for the same string, sI must be NULL. If sI is NULL, the value pointed to by ptr matches that set by the previous call to wcstok for the same wide string. Otherwise, the value of ptr is ignored. The list of delimiters pointed to by s2 may be different from one call to the next. The tokenization of sI is similar to that for the strtok function.

The strtok function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

```
Returns:
           The strtok function returns a pointer to the first character of a token or NULL if there is no token
            found.
See Also:
            strcspn, strpbrk, strtok_s
Example:
            #include <stdio.h>
            #include <string.h>
            void main()
                char *p;
                char *buffer;
                char *delims = { " ., " };
                buffer = strdup( "Find words, all of them." );
                printf( "%s\n", buffer );
                p = strtok( buffer, delims );
                while( p != NULL ) {
                  printf( "word: %s\n", p );
                  p = strtok( NULL, delims );
                printf( "%s\n", buffer );
            produces the following:
           Find words, all of them.
           word: Find
           word: words
           word: all
           word: of
           word: them
           Find
Classification: ISO C
           strtok_r is WATCOM
           fstrtok is WATCOM
           _fstrtok_r is WATCOM
            westok is ISO C95
           _mbstok is WATCOM
           _mbstok_r is WATCOM
           _fmbstok is WATCOM
           _fmbstok_r is WATCOM
Systems:
            strtok - All, Linux, RDOS, Netware
            strtok_r - All, Linux, RDOS, Netware
           _fstrtok - All, Linux, RDOS
           _fstrtok_r - All, Linux, RDOS
           wcstok - All, Linux
           _mbstok - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
           _{\rm mbstok\_r} - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
           _fmbstok - DOS, Windows, OS/2 1.x(all)
           _fmbstok_r - DOS, Windows, OS/2 1.x(all)
```

strtok, strtok_r,	_fstrtok, _fstrtc	ok_r, wcstok, _m	bstok, _mbstok_r,	_fmbstok, _fmbstok	_ <b>r</b>

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and strtok\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

None of sImax, s2, or ptr shall be a null pointer. If sI is a null pointer, then \*ptr shall not be a null pointer. The value of \*sImax shall not be greater than RSIZE\_MAX. The end of the token found shall occur within the first \*sImax characters of sI for the first call, and shall occur within the first \*sImax characters of where searching resumes on subsequent calls. If there is a runtime-constraint violation, the strtok\_s function does not indirect through the sI or s2 pointers, and does not store a value in the object pointed to by ptr.

#### **Description:**

A sequence of calls to the strtok\_s function breaks the string pointed to by s1 into a sequence of tokens, each of which is delimited by a character from the string pointed to by s2. The fourth argument points to a caller-provided char pointer into which the strtok\_s function stores information necessary for it to continue scanning the same string. The first call in a sequence has a non-null first argument and sImax points to an object whose value is the number of elements in the character array pointed to by the first argument. The first call stores an initial value in the object pointed to by ptr and updates the value pointed to by sImax to reflect the number of elements that remain in relation to ptr. Subsequent calls in the sequence have a null first argument and the objects pointed to by slmax and ptr are required to have the values stored by the previous call in the sequence, which are then updated. The separator string pointed to by s2 may be different from call to call. The first call in the sequence searches the string pointed to by s1 for the first character that is not contained in the current separator string pointed to by s2. If no such character is found, then there are no tokens in the string pointed to by s1 and the strtok\_s function returns a null pointer. If such a character is found, it is the start of the first token. The strtok\_s function then searches from there for the first character in s1 that is contained in the current separator string. If no such character is found, the current token extends to the end of the string pointed to by s1, and subsequent searches in the same string for a token return a null pointer. If such a character is found, it is overwritten by a null character, which terminates the current token. In all cases, the strtok\_s function stores sufficient information in the pointer pointed to by ptr so that subsequent calls, with a null pointer for s1 and the unmodified pointer value for ptr, shall start searching just past the element overwritten by a null character (if any).

The wcstok\_s function is a wide character version of strtok\_s that operates with wide character strings.

**Returns:** 

The strtok\_s function returns a pointer to the first character of a token, or a null pointer if there is no token or there is a runtime-constraint violation.

See Also:

strtok, strcspn, strpbrk

```
Example:
           #define __STDC_WANT_LIB_EXT1__ 1
           #include <stdio.h>
           #include <string.h>
           void main( void )
               char
                       *p;
                      *buffer;
               char
               char *delims = { " .," };
               size_t buflen;
               char
                      *ptr;
               buffer = strdup( "Find words, all of them." );
               printf( "%s\n", buffer );
               buflen = strlen( buffer );
               p = strtok_s( buffer, &buflen, delims, &ptr );
               while( p != NULL ) {
                 printf( "word: %s\n", p );
                 p = strtok_s( NULL, &buflen, delims, &ptr );
               printf( "%s\n", buffer );
           }
           produces the following:
           Find words, all of them.
           word: Find
           word: words
           word: all
           word: of
           word: them
           Find
Classification: TR 24731
Systems:
           strtok_s - All, Linux, RDOS, Netware
           wcstok_s - All, Linux
```

#### **Description:**

The strtol function converts the string pointed to by *ptr* to an object of type long int. The strtol function recognizes a string containing:

• optional white space,

#include <stdlib.h>

- an optional plus or minus sign,
- a sequence of digits and letters.

The conversion ends at the first unrecognized character. A pointer to that character will be stored in the object to which *endptr* points if *endptr* is not NULL.

If base is zero, the first characters after the optional sign determine the base used for the conversion. If the first characters are "0x" or "0X" the digits are treated as hexadecimal. If the first character is '0', the digits are treated as octal. Otherwise the digits are treated as decimal.

If *base* is not zero, it must have a value between 2 and 36. The letters a-z and A-Z represent the values 10 through 35. Only those letters whose designated values are less than *base* are permitted. If the value of *base* is 16, the characters "0x" or "0X" may optionally precede the sequence of letters and digits.

The west-ol function is a wide character version of strtol that operates with wide character strings.

#### **Returns:**

The strtol function returns the converted value. If the correct value would cause overflow, LONG\_MAX or LONG\_MIN is returned according to the sign, and errno is set to ERANGE. If *base* is out of range, zero is returned and errno is set to EDOM.

#### See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtoll, strtoul, strtoull, strtoimax, strtoumax, ultoa, ultoa, utoa

## **Example:**

```
void main()
{
    long int v;
    v = strtol( "12345678", NULL, 10 );
}
```

# Classification: ISO C

```
strtol - All, Linux, RDOS, Netware wcstol - All, Linux, RDOS
```

strtol, wcstol			

#### **Description:**

The strtoll function converts the string pointed to by *ptr* to an object of type long long int. The strtoll function recognizes a string containing:

- optional white space,
- an optional plus or minus sign,
- a sequence of digits and letters.

The conversion ends at the first unrecognized character. A pointer to that character will be stored in the object to which *endptr* points if *endptr* is not NULL.

If base is zero, the first characters after the optional sign determine the base used for the conversion. If the first characters are "0x" or "0X" the digits are treated as hexadecimal. If the first character is '0', the digits are treated as octal. Otherwise the digits are treated as decimal.

If *base* is not zero, it must have a value between 2 and 36. The letters a-z and A-Z represent the values 10 through 35. Only those letters whose designated values are less than *base* are permitted. If the value of *base* is 16, the characters "0x" or "0X" may optionally precede the sequence of letters and digits.

The west-oll function is a wide character version of strtoll that operates with wide character strings.

#### **Returns:**

The strtoll function returns the converted value. If the correct value would cause overflow, LLONG\_MAX or LLONG\_MIN is returned according to the sign, and errno is set to ERANGE. If *base* is out of range, zero is returned and errno is set to EDOM.

## See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoul, strtoull, strtoimax, strtoumax, ultoa, ultoa, utoa

# **Example:**

```
#include <stdlib.h>
void main()
{
    long long int v;

    v = strtol( "12345678909876", NULL, 10 );
}
```

# Classification: ISO C

```
strtoll - All, Linux, RDOS, Netware
wcstoll - All, Linux, RDOS
```

strtoll, wcstoll			

#### Synopsis: #include <inttypes.h>

**Description:** 

The strtoimax function converts the string pointed to by *ptr* to an object of type intmax\_t. The strtoimax function recognizes a string containing:

- optional white space,
- an optional plus or minus sign,
- a sequence of digits and letters.

The conversion ends at the first unrecognized character. A pointer to that character will be stored in the object to which *endptr* points if *endptr* is not NULL.

If *base* is zero, the first characters after the optional sign determine the base used for the conversion. If the first characters are "0x" or "0X" the digits are treated as hexadecimal. If the first character is '0', the digits are treated as octal. Otherwise the digits are treated as decimal.

If *base* is not zero, it must have a value between 2 and 36. The letters a-z and A-Z represent the values 10 through 35. Only those letters whose designated values are less than *base* are permitted. If the value of *base* is 16, the characters "0x" or "0X" may optionally precede the sequence of letters and digits.

The wcstoimax function is a wide character version of strtoimax that operates with wide character strings.

#### **Returns:**

The strtoimax function returns the converted value. If the correct value would cause overflow, INTMAX\_MAX or INTMAX\_MIN is returned according to the sign, and errno is set to ERANGE. If *base* is out of range, zero is returned and errno is set to EDOM.

#### See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull, strtoumax, ultoa, ultoa, utoa

## **Example:**

```
#include <inttypes.h>
#include <stdlib.h>

void main()
{
   intmax_t v;
   v = strtoimax( "12345678909876", NULL, 10 );
}
```

# Classification: ISO C

```
strtoimax - All, Linux, RDOS, Netware wcstoimax - All, Linux, RDOS
```

strtoimax, wcstoimax			

## **Description:**

The strtoul function converts the string pointed to by *ptr* to an unsigned long. The function recognizes a string containing optional white space, an optional sign (+ or -), followed by a sequence of digits and letters. The conversion ends at the first unrecognized character. A pointer to that character will be stored in the object *endptr* points to if *endptr* is not NULL.

If *base* is zero, the first characters determine the base used for the conversion. If the first characters are "0x" or "0X" the digits are treated as hexadecimal. If the first character is '0', the digits are treated as octal. Otherwise the digits are treated as decimal.

If *base* is not zero, it must have a value of between 2 and 36. The letters a-z and A-Z represent the values 10 through 35. Only those letters whose designated values are less than *base* are permitted. If the value of *base* is 16, the characters "0x" or "0X" may optionally precede the sequence of letters and digits.

If there is a leading minus sign in the string, the value is negated.

The west-oul function is a wide character version of strtoul that operates with wide character strings.

## **Returns:**

The strtoul function returns the converted value. If the correct value would cause overflow, ULONG\_MAX is returned and errno is set to ERANGE. If *base* is out of range, zero is returned and errno is set to EDOM.

#### See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoull, strtoimax, strtoumax, ultoa, ultoa, utoa

# **Example:**

```
void main()
{
    unsigned long int v;

    v = strtoul( "12345678", NULL, 10 );
}
```

#include <stdlib.h>

# **Classification:** ISO C

```
strtoul - All, Linux, RDOS, Netware wcstoul - All, Linux, RDOS
```


#### **Description:**

The strtoull function converts the string pointed to by *ptr* to an unsigned long long. The function recognizes a string containing optional white space, an optional sign (+ or -), followed by a sequence of digits and letters. The conversion ends at the first unrecognized character. A pointer to that character will be stored in the object *endptr* points to if *endptr* is not NULL.

If *base* is zero, the first characters determine the base used for the conversion. If the first characters are "0x" or "0X" the digits are treated as hexadecimal. If the first character is '0', the digits are treated as octal. Otherwise the digits are treated as decimal.

If *base* is not zero, it must have a value of between 2 and 36. The letters a-z and A-Z represent the values 10 through 35. Only those letters whose designated values are less than *base* are permitted. If the value of *base* is 16, the characters "0x" or "0X" may optionally precede the sequence of letters and digits.

If there is a leading minus sign in the string, the value is negated.

The west-oull function is a wide character version of strtoull that operates with wide character strings.

## **Returns:**

The strtoull function returns the converted value. If the correct value would cause overflow, ULLONG\_MAX is returned and errno is set to ERANGE. If *base* is out of range, zero is returned and errno is set to EDOM.

#### See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoimax, strtoumax, ultoa, ultoa, utoa

# **Example:**

```
void main()
{
    unsigned long long int v;

    v = strtoul( "12345678909876", NULL, 10 );
}
```

# **Classification:** ISO C

# **Systems:**

```
strtoull - All, Linux, RDOS, Netware
wcstoull - All, Linux, RDOS
```

#include <stdlib.h>


#### **Description:**

The strtoumax function converts the string pointed to by ptr to an uintmax\_t. The function recognizes a string containing optional white space, an optional sign (+ or -), followed by a sequence of digits and letters. The conversion ends at the first unrecognized character. A pointer to that character will be stored in the object endptr points to if endptr is not NULL.

If *base* is zero, the first characters determine the base used for the conversion. If the first characters are "0x" or "0X" the digits are treated as hexadecimal. If the first character is '0', the digits are treated as octal. Otherwise the digits are treated as decimal.

If *base* is not zero, it must have a value of between 2 and 36. The letters a-z and A-Z represent the values 10 through 35. Only those letters whose designated values are less than *base* are permitted. If the value of *base* is 16, the characters "0x" or "0X" may optionally precede the sequence of letters and digits.

If there is a leading minus sign in the string, the value is negated.

The wostoumax function is a wide character version of strtoumax that operates with wide character strings.

## **Returns:**

The strtoumax function returns the converted value. If the correct value would cause overflow, UINTMAX\_MAX is returned and errno is set to ERANGE. If *base* is out of range, zero is returned and errno is set to EDOM.

#### See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull, strtoimax, ultoa, ultoa, utoa

#### **Example:**

```
#include <inttypes.h>
#include <stdlib.h>

void main()
{
    uintmax_t v;
    v = strtoumax( "12345678909876", NULL, 10 );
}
```

# Classification: ISO C

```
strtoumax - All, Linux, RDOS, Netware wcstoumax - All, Linux, RDOS
```

strtoumax, wcstoui	max			

```
#include <string.h>
char *_strupr( char *s );
char __far *_fstrupr( char __far *s );
#include <wchar.h>
wchar_t *_wcsupr( wchar_t *s );

** deprecated **
char *strupr( char *s );
```

#### **Description:**

The \_strupr function replaces the string *s* with uppercase characters by invoking the toupper function for each character in the string.

The \_fstrupr function is a data model independent form of the \_strupr function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The \_wcsupr function is a wide character version of \_strupr that operates with wide character strings.

The \_strupr function is a multi-byte character version of that operates with multi-byte character strings.

The function is a data model independent form of the function. It accepts far pointer arguments and returns a far pointer. It is most useful in mixed memory model applications.

The strupr function is deprecated, use \_strupr instead.

**Returns:** 

The address of the original string *s* is returned.

See Also:

\_strlwr

# **Example:**

```
#include <string.h>
char source[] = { "A mixed-case STRING" };

void main()
    {
      printf( "%s\n", source );
      printf( "%s\n", _strupr( source ) );
      printf( "%s\n", source );
}
```

produces the following:

#include <stdio.h>

```
A mixed-case STRING
A MIXED-CASE STRING
A MIXED-CASE STRING
```

# **Classification:** WATCOM

```
Systems:
```

```
_strupr - All, Linux, RDOS, Netware
_fstrupr - All, Linux, RDOS
_wcsupr - All, Linux
_mbsupr - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
```

\_fmbsupr - DOS, Windows, OS/2 1.x(all) strupr - All, Linux, RDOS, Netware

**Description:** 

The strxfrm function transforms, for no more than n characters, the string pointed to by src to the buffer pointed to by dst. The transformation uses the collating sequence selected by the setlocale function so that two transformed strings will compare identically (using the strncmp function) to a comparison of the original two strings using the strcoll function. The function will be equivalent to the strncpy function (except there is no padding of the dst argument with null characters when the argument src is shorter than n characters) when the collating sequence is selected from the "C" locale.

The wcsxfrm function is a wide character version of strxfrm that operates with wide character strings. For wcsxfrm, after the string transformation, a call to wcscmp with the two transformed strings yields results identical to those of a call to wcscoll applied to the original two strings. wcsxfrm and strxfrm behave identically otherwise.

**Returns:** 

The strxfrm function returns the length of the transformed string. If this length is more than n, the contents of the array pointed to by dst are indeterminate.

**See Also:** setlocale, strcoll

#include <stdio.h>

**Example:** 

```
#include <string.h>
#include <locale.h>

char src[] = { "A sample STRING" };
char dst[20];

void main()
    {
        size_t len;

        setlocale( LC_ALL, "C" );
        printf( "%s\n", src );
        len = strxfrm( dst, src, 20 );
        printf( "%s (%u)\n", dst, len );
    }
}
```

produces the following:

```
A sample STRING A sample STRING (15)
```

Classification: ISO C

Systems: strxfrm - All, Linux, RDOS, Netware wcsxfrm - All, Linux

Synopsis: #include <stdlib.h>
 void swab( char \*src, char \*dest, int num );

**Description:** The swab function copies *num* bytes (which should be even) from *src* to *dest* swapping every pair of

characters. This is useful for preparing binary data to be transferred to another machine that has a

different byte ordering.

**Returns:** The swab function has no return value.

Example: #include <stdio.h>
#include <string.h>

#include <stdlib.h>

char \*msg = "hTsim seasegi swspaep.d";
#define NBYTES 24

void main()
{
 auto char buffer[80];

 printf( "%s\n", msg );
 memset( buffer, '\0', 80 );
 swab( msg, buffer, NBYTES );
 printf( "%s\n", buffer );
}

produces the following:

hTsim seasegi swspaep.d This message is swapped.

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

Synopsis: #include <unistd.h>

long sysconf( int name );

**Description:** The sysconf function retrieves a current system configuration parameter depending on the value of

system information from the kernel via the *name* passed. This implementation currently supports the

following inputs:

Member	Meaning
_SC_ARG_MAX	The maximum number of arguments supported by execv and related arguments
_SC_CHILD_MAX	The maximum number of per-user child processes
_SC_CLK_TCK	The number of clock ticks per second
_SC_NGROUPS_MAX	The maximum number of groups to which a user may be a member
_SC_OPEN_MAX	The maximum number of file that may be opened by a user
_SC_JOB_CONTROL	If job control is supported, the value of 1 is returned
_SC_SAVED_IDS	If saved identifiers are supported, the value of 1 is returned
_SC_VERSION	The release year and month of the POSIX.1 standard attempting to be supported, in the format YYYYMM
_SC_STREAM_MAX	The maximum number of per-process streams supported
_SC_TZNAME_MAX	The maximum length of a time zone name
_SC_PAGE_SIZE	The size, in bytes, of one page of memory
_SC_PAGESIZE	The size, in bytes, of one page of memory
_SC_NPROCESSORS_CO	<b>VF</b> The number of processors currently configured on the system
_SC_NPROCESSORS_ON	LN The number of processors currently online and functioning on the system
_SC_PHYS_PAGES	The total number of physical pages of memory for the system
_SC_AVPHYS_PAGES	The available number of physical pages of memory for the system
_SC_REALTIME_SIGNAL	S If real-time signals are supported, the value of 1 is returned
_SC_SOMAXCONN	For the socket function, retrieve the largest supported backlog of listen requests

In this implementation, \_SC\_PAGE\_SIZE and \_SC\_PAGESIZE have the same value, and a request to \_SC\_NPROCESSORS\_CONF or \_SC\_NPROCESSORS\_ONLN will return the same value. Some inputs, specifically \_SC\_OPEN\_MAX and \_SC\_CHILD\_MAX, are configurable via calls to setrlimit and may change between subsequent sysconf calls.

**Returns:** If successful, the function will return zero. If the call fails, the return value is -1, and errno will be set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

*EINVAL* The value of *name* is unsupported on this implementation

Classification: POSIX 1003.1

**Synopsis:** #include <sys/sysinfo.h> int sysinfo( struct sysinfo \*info ); struct sysinfo { unsigned long uptime; unsigned long loads[3]; unsigned long totalram; unsigned long freeram; unsigned long sharedram; unsigned long bufferram; unsigned long totalswap; unsigned long freeswap; unsigned short procs; unsigned short pad; unsigned long totalhigh; unsigned long freehigh; unsigned mem\_unit;

char

};

**Description:** 

The sysinfo function retrieves system information from the kernel via the *info* structure. The members of the structure are defined below:

\_\_reserved[];

M . .....

Member	Meaning
uptime	The number of seconds since the system booted
loads	The 1 minute, 5 minute, and 15 minute load averages
totalram	The total usable amount of system memory in bytes
freeram	The amount of memory currently unused and unallocated
sharedram	The amount of memory currently being shared
bufferram	The amount of memory allocated to buffering
totalswap	The amount of swap space available in bytes
freeswap	The amount of unused swap space
procs	The amount of processes currently running
pad	Padding for alignment; can be ignored
totalhigh	Total amount of "high" memory
mem_unit	The memory unit size in bytes

**Returns:** 

If successful, the function will return zero. If the call fails, the return value is -1, and  $\,$ errno will be set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

# **Constant Meaning**

**EINVAL** The value of *info* is NULL

**EFAULT** The value of *info* is invalid

**Classification:** WATCOM

Synopsis: #include <stdlib.h>

```
int system( const char *command );
int _wsystem( const wchar_t *command );
```

**Description:** 

If the value of *command* is NULL, then the system function determines whether or not a command processor is present ("COMMAND.COM" in DOS and Windows 95/98 or "CMD.EXE" in OS/2 and Windows NT/2000).

Otherwise, the system function invokes a copy of the command processor, and passes the string *command* to it for processing. This function uses spawnl to load a copy of the command processor identified by the COMSPEC environment variable.

This means that any command that can be entered to DOS can be executed, including programs, DOS commands and batch files. The exec... and spawn... functions can only cause programs to be executed.

The \_wsystem function is a wide character version of system that operates with wide character strings.

**Returns:** 

If the value of *command* is NULL, then the system function returns zero if the command processor is not present, a non-zero value if the command processor is present. Note that Microsoft Windows 3.x does not support a command shell and so the system function always returns zero when *command* is NULL.

Otherwise, the system function returns the result of invoking a copy of the command processor. A non-zero value is returned if the command processor could not be loaded; otherwise, zero is returned. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also:

abort, atexit, \_bgetcmd, exec..., exit, \_Exit, \_exit, getcmd, getenv, main, putenv, spawn..., \_wsystem

**Example:** 

```
#include <stdlib.h>
#include <stdlib.h>

void main()
{
   int rc;

   rc = system( "dir" );
   if( rc != 0 ) {
      printf( "shell could not be run\n" );
   }
}
```

Classification: ISO C, POSIX 1003.2

**Systems:** 

```
system - All, Linux, RDOS, Netware
_wsystem - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

	system, _wsystem

**Description:** The tan function computes the tangent of x (measured in radians). A large magnitude argument may

yield a result with little or no significance.

**Returns:** The tan function returns the tangent value. When an error has occurred, errno contains a value

indicating the type of error that has been detected.

See Also: atan, atan2, cos, sin, tanh

Example: #include <stdio.h>
#include <math.h>

```
void main()
     {
      printf( "%f\n", tan(.5) );
    }
```

produces the following:

0.546302

Classification: ISO C

**Systems:** Math

( 20 20 20 20 7 7

**Description:** The tanh function computes the hyperbolic tangent of x.

When the x argument is large, partial or total loss of significance may occur. The matherr function

will be invoked in this case.

**Returns:** The tanh function returns the hyperbolic tangent value. When an error has occurred, errno contains

a value indicating the type of error that has been detected.

See Also: cosh, sinh, matherr

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", tanh(.5) );
    }
```

produces the following:

0.462117

Classification: ISO C

**Systems:** Math

# **Synopsis:**

```
#include <io.h>
off_t _tell( int handle );
__int64 _telli64( int handle );

** deprecated **
off_t tell( int handle );
```

## **Description:**

The \_tell function reports the current file position at the operating system level. The *handle* value is the file handle returned by a successful execution of the open function.

The returned value may be used in conjunction with the lseek function to reset the current file position.

The \_telli64 function is similar to the \_tell function but returns a 64-bit file position. This value may be used in conjunction with the \_lseeki64 function to reset the current file position.

The tell function is deprecated, use \_tell instead.

#### **Returns:**

If an error occurs in \_tell (-1L) is returned.

If an error occurs in \_telli64, (-1I64) is returned.

When an error has occurred, errno contains a value indicating the type of error that has been detected.

Otherwise, the current file position is returned in a system-dependent manner. A value of 0 indicates the start of the file.

#### See Also:

\_chsize, close, creat, dup, dup2, \_eof, exec..., fdopen, \_filelength, fileno, fstat, \_grow\_handles, isatty, lseek, open, read, \_setmode, \_sopen, stat, write, umask

## **Example:**

```
if( handle !=-1 ) {
                    /* print file position */
                   printf( "%ld\n", _tell( handle ) );
                    /* write the text */
                   size_written = write( handle, buffer,
                                           sizeof( buffer ) );
                   /* print file position */
                   printf( "%ld\n", _tell( handle ) );
                    /* close the file */
                   close( handle );
               }
           }
           produces the following:
           28
Classification: WATCOM
           _tell - All, Linux, RDOS, Netware
Systems:
           _telli64 - All, Linux
           tell - All, Linux, RDOS, Netware
```

Synopsis: #include <stdio.h>

```
char *_tempnam( const char *dir, const char *prefix );
wchar_t *_wtempnam( const wchar_t *dir, const wchar_t *prefix );
```

**Description:** 

\_tempnam creates a temporary filename for use in another directory. This filename is different from that of any existing file. The *prefix* argument is the prefix to the filename. \_tempnam uses malloc to allocate space for the filename; the program is responsible for freeing this space when it is no longer needed. \_tempnam looks for the file with the given name in the following directories, listed in order of precedence.

## **Directory Used Conditions**

**Directory specified by TMP** The TMP environment variable must be set and the directory specified by TMP must exist.

*dir (function argument)* The TMP environment variable must not be set or the directory specified by TMP does not exist.

\_*P\_tmpdir* (\_*wP\_tmpdir*) *in STDIO.H* The *dir* argument is NULL or *dir* is the name of a nonexistent directory. The \_wP\_tmpdir string is used by \_wtempnam.

Current working directory \_tempnam uses the current working directory when \_P\_tmpdir does not exist. \_wtempnam uses the current working directory when \_wP\_tmpdir does not exist.

\_tempnam automatically handles multi-byte character string arguments as appropriate, recognizing multi-byte character sequences according to the OEM code page obtained from the operating system.

The \_wtempnam function is a wide character version of \_tempnam. It accepts a wide character string argument for *format* and produces wide character output. The \_wtempnam function does not handle multi-byte character strings.

The function generates unique filenames for up to TMP\_MAX calls.

**Returns:** 

The \_tempnam function returns a pointer to the name generated, unless it is impossible to create this name or the name is not unique. If the name cannot be created or if a file with that name already exists, \_tempnam returns NULL.

See Also:

fopen, freopen, mkstemp, \_mktemp, tmpfile, tmpnam

**Example:** 

```
#include <stdlib.h>
             Environment variable TMP=C:\WINDOWS\TEMP
           void main()
             {
               char *filename;
               FILE *fp;
               filename = _tempnam( "D:\\TEMP", "_T" );
               if( filename == NULL )
                   printf( "Can't obtain temp file name\n" );
               else {
                   printf( "Temp file name is %s\n", filename );
                   fp = fopen( filename, "w+b" );
                    /* · */
                    /* · */
/* · */
                   fclose( fp );
                   remove( filename );
                   free( filename );
             }
           produces the following:
           Temp file name is C:\WINDOWS\TEMP\_T1
Classification: WATCOM
Systems:
           _tempnam - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
           _wtempnam - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

#include <stdio.h>

**Description:** The tgamma function returns the value of the Gamma function of x.

**Returns:** If successful, the return value is the value of the Gamma function computed for x. the function returns

NAN. If the argument is positive infinity, the function returns positive infinity.

See Also: lgamma, lgamma\_r

Example: #include <stdio.h>
#include <math.h>

```
void main()
     {
        printf( "%f\n", tgamma( 4.0 ) );
     }
```

produces the following:

6.00000

Classification: ISO C99

**Systems:** Math

```
Synopsis: #include <time.h>
    time_t time( time_t *tloc );
```

**Description:** The time function determines the current calendar time and encodes it into the type time\_t.

The time represents the time since January 1, 1970 Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time (GMT)).

The time set on the computer with the DOS time command and the DOS date command reflects the local time. The environment variable TZ is used to establish the time zone to which this local time applies. See the section *The TZ Environment Variable* for a discussion of how to set the time zone.

**Returns:** The time function returns the current calendar time. If *tloc* is not NULL, the current calendar time is also stored in the object pointed to by *tloc*.

**See Also:** asctime Functions, asctime\_s, clock, ctime Functions, ctime\_s, difftime, gmtime, gmtime\_s, localtime, localtime\_s, mktime, strftime, tzset

#include <stdio.h>
#include <time.h>

void main()
{
 time\_t time\_of\_day;

 time\_of\_day = time( NULL );
 printf( "It is now: %s", ctime( &time\_of\_day ) );
}

produces the following:

It is now: Fri Dec 25 15:58:42 1987

Classification: ISO C, POSIX 1003.1

**Systems:** All, Linux, RDOS, Netware

Synopsis: #include <time.h>

**Description:** 

The timer\_create function creates a new timer using the clock specified by *clockid* as supported by the underlying operating system. The *evp* argument can be NULL or may specify a handler for when an event of interest occurs. This implementation currently only supports responding using

SIGEV\_SIGNAL implementations. The pointer timerid will contain the unique, per-process timer id if

the call is successful.

**Returns:** If successful, the function will return zero, and the *timerid* argument will contain the timer id. If the call

fails, the return value is -1, and errno will be set appropriately.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of timerid is NULL or an invalid clockid is specified

EAGAIN The system was unable to allocate resources for a new timer

See Also: timer\_gettime, timer\_settime, timer\_delete, timer\_getoverrun

Classification: POSIX 1003.1

Synopsis: #include <time.h>

int timer\_delete(timer\_t timerid );

**Description:** The timer\_delete function disarms, if necessary, and deletes the timer *timerid* immediately.

Returns: If successful, the function will return zero. If the call fails, the return value is -1, and errno will be set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of timerid is NULL or invalid

See Also: timer\_create, timer\_settime, timer\_gettime

Classification: POSIX 1003.1

```
Synopsis:
           #include <time.h>
           int timer_gettime(timer_t timerid,
                             struct itimerspec *value );
           struct timespec {
               time_t tv_sec;
               long tv_nsec;
           };
           struct itimerspec {
               struct timespec it_interval;
               struct timespec it_value;
                               notify_type;
               int
                               timer_type;
               int
               long
                               data;
           };
```

**Description:** The timer\_gettime function retrieves time remaining in the timer *timerid* until expiration.

Returns: If successful, the function will return zero. If the call fails, the return value is -1, and errno will be set

appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of timerid is NULL or invalid

See Also: timer\_create, timer\_settime, timer\_delete, timer\_getoverrun

Classification: POSIX 1003.1

**Synopsis:** 

```
#include <time.h>
int timer_settime(timer_t timerid, int flags,
                  struct itimerspec *new_value,
                  struct itimerspec *old_value );
struct timespec {
   time_t tv_sec;
    long tv_nsec;
};
struct itimerspec {
    struct timespec it_interval;
    struct timespec it_value;
    int
                   notify_type;
    int
                    timer_type;
    long
                    data;
};
```

**Description:** 

The timer\_settime function arms or resets the timer timerid using the interval and value specified in *new\_value* pointer. The previous interval and value is returned in the *oldvalue* pointer.

The structure pointed to by the "it\_value" member of new\_value specifies the time in the future when the timer will expire, and effectively arms the timer. If the it\_value member of new\_value specifies a time of zero, the timer is disarmed. The structure pointed to by the "it\_interval" member of new\_value specifies the interval after the initial timer expiration when the timer would repeat expiration. If the it\_interval member's components are set to zero, the timer will expire at the time specified by the "it value" member of *new value* and the timer will not automatically rearm.

The "it\_value" member of new\_value is regarded, by default, as a time relative to the system clock at the time of the function call. If flags incorporates the TIMER ABSTIME constant, the time in "it\_value" is regarded as an absolute system time as opposed to a time relative to calling this function.

**Returns:** 

If successful, the function will return zero. If the call fails, the return value is -1, and errno will be set appropriately.

**Errors:** 

When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**EINVAL** The value of *timerid* is NULL or invalid

See Also:

timer\_create, timer\_gettime, timer\_delete, timer\_getoverrun

Classification: POSIX 1003.1

**Systems:** 

Linux

timer_settime			

Synopsis: #include <time.h>

int timer\_getoverrun( timer\_t timerid );

**Description:** The timer\_getoverrun function returns the number of intervals for the given *timerid* since

expiration.

**Returns:** If successful, the function will return the number of elapsed intervals since the latest timer expiration. If

the call fails, the return value is -1, and errno will be set appropriately.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

EINVAL The value of timerid is NULL or invalid

See Also: timer\_create, timer\_settime, timer\_delete

Classification: POSIX 1003.1

Synopsis: #include <stdio.h>
 FILE \*tmpfile( void );

**Safer C:** The Safer C Library extension provides the tmpfile\_s function which is a safer alternative to

tmpfile.

**Description:** The tmpfile function creates a temporary binary file that will automatically be removed when it is

closed or at program termination. The file is opened for update. For all systems except NetWare, the temporary file is located in the path specified by one of the following environment variables, if one is defined. Otherwise, the current working directory is used. They are listed in the order examined: TMP,

TEMP, TMPDIR, and TEMPDIR.

**Returns:** The tmpfile function returns a pointer to the stream of the file that it created. If the file cannot be

created, the tmpfile function returns NULL. When an error has occurred, errno contains a value

indicating the type of error that has been detected.

See Also: fopen, fopen\_s, freopen, freopen\_s, mkstemp, \_mktemp, \_tempnam, tmpfile\_s,

tmpnam, tmpnam\_s

Example: #include <stdio.h>

```
static FILE *TempFile;

void main()
{
    TempFile = tmpfile();
    /* . */
    /* . */
    /* . */
    fclose( TempFile );
}
```

Classification: ISO C

**Systems:** All, Linux, RDOS, Netware

Synopsis: #define \_\_STDC\_WANT\_LIB\_EXT1\_\_ 1
 #include <stdio.h>
 errno\_t tmpfile\_s( FILE \* restrict \* restrict streamptr);

**Constraints:** 

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and tmpfile\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

*streamptr* shall not be a null pointer. If there is a runtime-constraint violation, tmpfile\_s does not attempt to create a file.

**Description:** 

The tmpfile\_s function creates a temporary binary file that is different from any other existing file and that will automatically be removed when it is closed or at program termination. If the program terminates abnormally, whether an open temporary file is removed is implementation-defined. The file is opened for update with "wb+" mode with the meaning that mode has in the fopen\_s function (including the mode's effect on exclusive access and file permissions). If the file was created successfully, then the pointer to FILE pointed to by *streamptr* will be set to the pointer to the object controlling the opened file. Otherwise, the pointer to FILE pointed to by *streamptr* will be set to a null pointer. For all systems except NetWare, the temporary file is located in the path specified by one of the following environment variables, if one is defined. Otherwise, the current working directory is used. They are listed in the order examined: TMP, TEMP, TMPDIR, and TEMPDIR.

**Returns:** The tmpfile\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

fopen, fopen\_s, freopen, freopen\_s, mkstemp, \_mktemp, \_tempnam, tmpfile,
tmpnam, tmpnam\_s

**Example:** 

See Also:

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>

void main()
{
    errno_t rc;
    FILE *TempFile;

    rc = tmpfile_s( &TempFile );
    if( rc == 0 ) {
        /* . */
        /* . */
        fclose( TempFile );
    }
}
```

**Classification:** TR 24731

**Systems:** All, RDOS, Netware

tmpfile_s			

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
errno_t tmpnam_s( char * s, rsize_t maxsize );
#include <wchar.h>
errno_t _wtmpnam_s( wchar_t * s, rsize_t maxsize );
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and tmpnam\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

s shall not be a null pointer. maxsize shall be less than or equal to RSIZE\_MAX. maxsize shall be greater than the length of the generated file name string.

## **Description:**

The tmpnam\_s function generates a string that is a valid file name and that is not the same as the name of an existing file. The function is potentially capable of generating TMP\_MAX\_S different strings, but any or all of them may already be in use by existing files and thus not be suitable return values. The lengths of these strings shall be less than the value of the L\_tmpnam\_s macro. The tmpnam\_s function generates a different string each time it is called.

The \_wtmpnam\_s function is a wide character version of tmpnam\_s. It accepts a wide character string argument for *format* and produces wide character output.

#### **Returns:**

If no suitable string can be generated, or if there is a runtime-constraint violation, the  $tmpnam_s$  function writes a null character to s[0] (only if s is not null and maxsize is greater than zero) and returns a non-zero value. Otherwise, the  $tmpnam_s$  function writes the string in the array pointed to by s and returns zero.

See Also:

fopen, fopen\_s, freopen, freopen\_s, mkstemp, \_mktemp, \_tempnam, tmpfile, tmpfile\_s, tmpnam

### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
void main()
    char
            filename[ L_tmpnam_s ];
   FILE
            *fp;
   errno_t rc;
    rc = tmpnam(filename, sizeof(filename));
    if(rc == 0) {
        fp = fopen(filename, "w+b");
        /* . */
        /* . */
        /* . */
        fclose(fp);
        remove(filename);
    }
}
```

Classification: TR 24731

\_wtmpnam\_s is WATCOM

Systems: tmpnam\_s - All, Linux, RDOS, Netware

\_wtmpnam\_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

**Safer C:** The Safer C Library extension provides the tmpnam\_s function which is a safer alternative to tmpnam.

**Description:** The tmpnam function generates a unique string for use as a valid file name.

The \_wtmpnam function is a wide character version of tmpnam. It accepts a wide character string argument for *format* and produces wide character output. An internal static buffer is used to construct the filename. Subsequent calls to tmpnam reuse the internal buffer.

The function generates unique filenames for up to TMP\_MAX calls.

**Returns:** 

If the argument *buffer* is a NULL pointer, tmpnam returns a pointer to an internal buffer containing the temporary file name. If the argument *buffer* is not a NULL pointer, tmpnam copies the temporary file name from the internal buffer to the specified buffer and returns a pointer to the specified buffer. It is assumed that the specified buffer is an array of at least L\_tmpnam characters.

If the argument *buffer* is a NULL pointer, you may wish to duplicate the resulting string since subsequent calls to tmpnam reuse the internal buffer.

```
char *name1, *name2;

name1 = strdup( tmpnam( NULL ) );
name2 = strdup( tmpnam( NULL ) );

See Also: fopen, fopen_s, freopen, freopen_s, mkstemp, _mktemp, _tempnam, tmpfile, tmpfile_s, tmpnam_s

Example: #include <stdio.h>
```

void main()
{
 char filename[ L\_tmpnam ];
 FILE \*fp;

 tmpnam( filename );
 fp = fopen( filename, "w+b" );
 /\* . \*/
 /\* . \*/
 /\* . \*/
 fclose( fp );
 remove( filename );
}

**Classification:** ISO C

```
Systems: tmpnam - All, Linux, RDOS, Netware
_wtmpnam - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32
```

tmpnam, _wtmpnam		

**Synopsis:** 

```
#include <ctype.h>
int tolower( int c );
int _tolower( int c );
#include <wctype.h>
wint_t towlower( wint_t c );
```

**Description:** 

The tolower function converts c to a lowercase letter if c represents an uppercase letter.

The  $\_$ tolower function is a version of tolower to be used only when c is known to be uppercase.

The towlower function is a wide character version of tolower that operates with wide character strings.

**Returns:** 

The tolower function returns the corresponding lowercase letter when the argument is an uppercase letter; otherwise, the original character is returned. The towlower function returns the corresponding wide character lowercase letter when the argument is a wide character uppercase letter; otherwise, the original wide character is returned.

The result of \_tolower is undefined if *c* is not an uppercase letter.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans, \_strlwr, \_strupr, toupper

**Example:** 

```
#include <ctype.h>
char chars[] = {
    'A',
    151,
    '$',
    'Z'
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "%c ", tolower( chars[ i ] ) );
    printf( "\n" );
}
produces the following:
```

#include <stdio.h>

a 5 \$ z

**Classification:** ISO C

\_tolower is WATCOM

# tolower, \_tolower, towlower

# towlower is ISO C95

Systems: tolower - All, Linux, RDOS, Netware

\_tolower - All, Linux, RDOS, Netware towlower - All, Linux, RDOS, Netware

\_\_\_\_\_

**Synopsis:** 

```
#include <ctype.h>
int toupper( int c );
int _toupper( int c );
#include <wctype.h>
wint_t towupper( wint_t c );
```

**Description:** 

The toupper function converts c to a uppercase letter if c represents a lowercase letter.

The  $\_$ toupper function is a version of toupper to be used only when c is known to be lowercase.

The towupper function is a wide character version of toupper that operates with wide character strings.

**Returns:** 

The toupper function returns the corresponding uppercase letter when the argument is a lowercase letter; otherwise, the original character is returned. The towupper function returns the corresponding wide character uppercase letter when the argument is a wide character lowercase letter; otherwise, the original wide character is returned.

The result of  $\_$ toupper is undefined if c is not a lowercase letter.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, wctrans, towctrans, \_strlwr, \_strupr, tolower

**Example:** 

```
#include <ctype.h>
char chars[] = {
    ′a′,
    ′5′,
    '$',
    'z'
};
#define SIZE sizeof( chars ) / sizeof( char )
void main()
    int
          i;
    for( i = 0; i < SIZE; i++ ) {
        printf( "%c ", toupper( chars[ i ] ) );
    printf( "\n" );
}
produces the following:
```

**Classification:** ISO C

A 5 \$ Z

\_toupper is WATCOM

#include <stdio.h>

# toupper, \_toupper, towupper

towupper is ISO C95

Systems: toupper - All, Linux, RDOS, Netware

\_toupper - All, Linux, RDOS, Netware towupper - All, Linux, RDOS, Netware

\_\_\_\_\_

```
Synopsis: #include <wctype.h>
    wint_t towctrans( wint_t wc, wctrans_t desc );
```

**Description:** The towetrans function maps the wide character *wc* using the mapping described by *desc*. Valid values of *desc* are defined by the use of the wetrans function.

The two expressions listed below behave the same as a call to the wide character case mapping function shown.

Expression Equivalent

towctrans(wc, wctrans("tolower")) towlower(wc)

towctrans(wc, wctrans("toupper")) towupper(wc)

**Returns:** The towetrans function returns the mapped value of wc using the mapping described by desc.

See Also: isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctrans

#include <stdio.h>
#include <wctype.h>

char \*translations[2] = {
 "tolower",
 "toupper"
};

void main( void )
{
 int i;
 wint\_t wc = 'A';
 wint\_t twc;

for( i = 0; i < 2; i++ ) {
 twc = towctrans( wc, wctrans( translations[i] ) );
 printf( "%s(%lc): %lc\n", translations[i], wc, twc );
 }
}</pre>

produces the following:

tolower(A): a
toupper(A): A

Classification: ISO C95

**Systems:** All, Linux, RDOS, Netware

towctrans			
lowctrairs			

Synopsis: #include <math.h>

double trunc( double x );

**Description:** The trunc function truncates the argument *x* to the appropriate integer. The function is equivalent to

floor for positive numbers and ceil for negative numbers.

**Returns:** The value of *x* without any fractional values.

See Also: nearbyint, rint, round, floor, ceil

Example: #include <stdio.h>
#include <math.h>

```
void main()
    {
      printf( "%f\n", round( 1.5 ) );
}
```

produces the following:

1.000000

Classification: ISO C99

**Systems:** Math

Synopsis: #include <unistd.h>

char \*ttyname( int fd );

int ttyname\_r( int fd, char \*buf, size\_t buflen );

**Description:** The POSIX-compliant ttyname function retrieves the name of a TTY as specified by the fd file

descriptor, returning a static pointer to the name. Subsequent calls may change the contents of the string pointed to by the original call to ttyname, and the memory to which the return value points

should not be freed.

The ttyname\_r function performs the same function as ttyname, but the name of the TTY is returned in the *buf* argument. The argument *buflen* should specify the size of the *buf* argument. The ttyname\_r function is an Open Watcom extension commonly implemented in other standard

libraries.

**Returns:** Upon success, the ttyname function returns a pointer to statically allocated memory containing the

name of the TTY. Upon failure, the returned pointer will be NULL and errno will be set

appropriately.

Upon success, the ttyname\_r function will return zero, and the *buf* argument will contain the name of the TTY. Upon failure, the ttyname\_r function will return the error code and set erroe as well.

**Errors:** When an error has occurred, errno contains a value indicating the type of error that has been detected.

**Constant Meaning** 

**ENOTTY** The value of fd does not refer to a TTY

**EACCES** The user does not have permission to query the file descriptor

**EBADFD** The file descriptor fd is invalid

**ERANGE** The buf is not large enough to hold the result, or the file descriptor name exceeds

POSIX\_PATH\_MAX

See Also: isatty

Classification: POSIX 1003.1

Systems: ttyname - Linux

ttyname\_r - Linux

Synopsis: #include <time.h>
 void tzset( void );

### **Description:**

The tzset function sets the global variables daylight, timezone and tzname according to the value of the TZ environment variable. The section *The TZ Environment Variable* describes how to set this variable.

Under Win32, tzset also uses operating system supplied time zone information. The TZ environment variable can be used to override this information.

The global variables have the following values after tzset is executed:

**daylight** Zero indicates that daylight saving time is not supported in the locale; a non-zero

value indicates that daylight saving time is supported in the locale. This variable is cleared/set after a call to the tzset function depending on whether a daylight

saving time abbreviation is specified in the TZ environment variable.

timezone Contains the number of seconds that the local time zone is earlier than

Coordinated Universal Time (UTC) (formerly known as Greenwich Mean Time

(GMT)).

tzname Two-element array pointing to strings giving the abbreviations for the name of the

time zone when standard and daylight saving time are in effect.

The time set on the computer with the DOS time command and the DOS date command reflects the local time. The environment variable TZ is used to establish the time zone to which this local time applies. See the section *The TZ Environment Variable* for a discussion of how to set the time zone.

**Returns:** The tzset function does not return a value.

See Also: ctime Functions, localtime, mktime, strftime

## **Example:**

```
void main()
{
    print_zone();
    setenv( "TZ", "PST8PDT", 1 );
    tzset();
    print_zone();
}

produces the following:

TZ: default EST5EDT
    daylight: 1
    timezone: 18000
    time zone names: EST EDT

TZ: PST8PDT
    daylight: 1
    timezone: 28800
    time zone names: PST PDT
```

Classification: POSIX 1003.1

Systems: All, Linux, RDOS, Netware

**Description:** 

The ulltoa function converts the unsigned binary integer *value* into the equivalent string in base *radix* notation storing the result in the character array pointed to by *buffer*. A null character is appended to the result. The size of *buffer* must be at least 65 bytes when converting values in base 2. The value of *radix* must satisfy the condition:

```
2 <= radix <= 36
```

The \_ulltoa function is identical to ulltoa. Use \_ulltoa for ANSI naming conventions.

The \_ulltow function is a wide character version of ulltoa except that it produces a wide character string.

**Returns:** The ulltoa function returns the pointer to the result.

See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull, strtoimax, strtoimax, ultoa, utoa

**Example:** 

produces the following:

```
2 1001001100011101101101001001101
 4 1021203231221031
 6 322243004113
 8 11143555115
10 1234098765
12 2a5369639
14 b9c8863b
```

16 498eda4d

**Classification:** WATCOM

\_ulltoa conforms to ANSI naming conventions

**Systems:** ulltoa - All, Linux, RDOS, Netware

\_ulltoa - All, Linux, RDOS, Netware \_ulltow - All, Linux, RDOS

**Description:** 

The ultoa function converts the unsigned binary integer *value* into the equivalent string in base *radix* notation storing the result in the character array pointed to by *buffer*. A null character is appended to the result. The size of *buffer* must be at least 33 bytes when converting values in base 2. The value of *radix* must satisfy the condition:

```
2 <= radix <= 36
```

The \_ultoa function is identical to ultoa. Use \_ultoa for ANSI naming conventions.

The \_ultow function is a wide character version of ultoa except that it produces a wide character string.

**Returns:** The ultoa function returns the pointer to the result.

See Also:

atoi, atol, atoll, itoa, ltoa, lltoa, scanf, strtol, strtoll, strtoul, strtoull, strtoimax, strtoumax, ulltoa, utoa

**Example:** 

produces the following:

```
2 11000111011101
 4 3013131
 6 135033
 8 30735
10 12765
12 7479
14 491b
16 31dd
```

**Classification:** WATCOM

\_ultoa conforms to ANSI naming conventions

**Systems:** ultoa - All, Linux, RDOS, Netware

\_ultoa - All, Linux, RDOS, Netware \_ultow - All, Linux, RDOS

```
#include <sys/types.h>
#include <sys/stat.h>
#include <fcntl.h>
#include <io.h>
mode_t umask( mode_t cmask );
mode_t _umask( mode_t cmask );
```

## **Description:**

The umask function sets the process's file mode creation mask to *cmask*. The process's file mode creation mask is used during creat, open or \_sopen to turn off permission bits in the *permission* argument supplied. In other words, if a bit in the mask is on, then the corresponding bit in the file's requested permission value is disallowed.

The \_umask function is identical to umask. Use \_umask for ANSI naming conventions.

The argument *cmask* is a constant expression involving the constants described below. The access permissions for the file or directory are specified as a combination of bits (defined in the <sys/stat.h> header file).

The following bits define permissions for the owner.

Permission	Meaning		
S_IRWXU	Read, write, execute/search		
S_IRUSR	Read permission		
S_IWUSR	Write permission		
S_IXUSR	Execute/search permission		

The following bits define permissions for the group.

Permission	Meaning		
S_IRWXG	Read, write, execute/search		
S_IRGRP	Read permission		
S_IWGRP	Write permission		
S_IXGRP	Execute/search permission		

The following bits define permissions for others.

Permission	Meaning		
S_IRWXO	Read, write, execute/search		
S_IROTH	Read permission		
S_IWOTH	Write permission		
S_IXOTH	Execute/search permission		

The following bits define miscellaneous permissions used by other implementations.

Permission	Meaning
S_IREAD	is equivalent to S_IRUSR (read permission)
S_IWRITE	is equivalent to S_IWUSR (write permission)

**S\_IEXEC** is equivalent to **S\_IXUSR** (execute/search permission)

For example, if S\_IRUSR is specified, then reading is not allowed (i.e., the file is write only). If S\_IWUSR is specified, then writing is not allowed (i.e., the file is read only).

**Returns:** The umask function returns the previous value of *cmask*.

See Also: chmod, creat, mkdir, open, \_sopen

Classification: POSIX 1003.1

}

\_umask conforms to ANSI naming conventions

Systems: umask - All, Linux, RDOS, Netware

\_umask - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

```
#include <stdio.h>
int ungetc( int c, FILE *fp );
#include <stdio.h>
#include <wchar.h>
wint_t ungetwc( wint_t c, FILE *fp );
```

**Description:** 

The ungetc function pushes the character specified by c back onto the input stream pointed to by fp. This character will be returned by the next read on the stream. The pushed-back character will be discarded if a call is made to the fflush function or to a file positioning function (fseek, fsetpos or rewind) before the next read operation is performed.

Only one character (the most recent one) of pushback is remembered.

The ungetc function clears the end-of-file indicator, unless the value of c is EOF.

The ungetwo function is identical to ungeto except that it pushes the wide character specified by c back onto the input stream pointed to by fp.

The ungetwo function clears the end-of-file indicator, unless the value of c is WEOF.

**Returns:** The ungetc function returns the character pushed back.

See Also: fgetc, fgetchar, fgets, fopen, getc, getchar, gets

**Example:** 

```
#include <stdio.h>
#include <ctype.h>
void main()
  {
   FILE *fp;
   int c;
   long value;
    fp = fopen( "file", "r" );
   value = 0;
    c = fqetc(fp);
   while( isdigit(c) ) {
        value = value*10 + c - '0';
        c = fgetc(fp);
   ungetc( c, fp ); /* put last character back */
   printf( "Value=%ld\n", value );
    fclose( fp );
```

Classification: ISO C

**Systems:** 

```
ungetc - All, Linux, RDOS, Netware
ungetwc - All, Linux
```


Synopsis: #include <conio.h>
 int ungetch( int c );

**Description:** The ungetch function pushes the character specified by *c* back onto the input stream for the console.

This character will be returned by the next read from the console (with getch or getche functions)

and will be detected by the function kbhit. Only the last character returned in this way is

remembered.

The ungetch function clears the end-of-file indicator, unless the value of c is EOF.

**Returns:** The ungetch function returns the character pushed back.

See Also: getch, getche, kbhit, putch

Example: #include <stdio.h>

#include <ctype.h>
#include <conio.h>

void main()
{
 int c;

long value;
value = 0;
c = getche();

while( isdigit( c ) ) {
 value = value\*10 + c - '0';
 c = getche();

ungetch( c );
printf( "Value=%ld\n", value );
}

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

```
Synopsis: #include <io.h>
    int unlink( const char *path );
    int _unlink( const char *path );
    int _wunlink( const wchar_t *path );
```

**Description:** The unlink function deletes the file whose name is the string pointed to by *path*. This function is equivalent to the remove function.

The \_unlink function is identical to unlink. Use \_unlink for ANSI naming conventions.

The \_wunlink function is a wide character version of unlink that operates with wide character strings.

**Returns:** The unlink function returns zero if the operation succeeds, non-zero if it fails.

See Also: chdir, chmod, close, getcwd, mkdir, open, remove, rename, rmdir, stat

Classification: POSIX 1003.1

\_unlink conforms to ANSI naming conventions

Systems: unlink - All, Linux, RDOS, Netware
\_unlink - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
\_wunlink - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

**Description:** The unlock function unlocks *nbytes* amount of previously locked data in the file designated by *handle* starting at byte *offset* in the file. This allows other processes to lock this region of the file.

Multiple regions of a file can be locked, but no overlapping regions are allowed. You cannot unlock multiple regions in the same call, even if the regions are contiguous. All locked regions of a file should be unlocked before closing a file or exiting the program.

With DOS, locking is supported by version 3.0 or later. Note that SHARE.COM or SHARE.EXE must be installed.

**Returns:** The unlock function returns zero if successful, and -1 when an error occurs. When an error has occurred, errno contains a value indicating the type of error that has been detected.

See Also: lock, locking, open, \_sopen

Example: #include <stdio.h>

```
#include <fcntl.h>
#include <io.h>
void main()
  {
    int handle;
   char buffer[20];
   handle = open( "file", O_RDWR | O_TEXT );
    if (handle !=-1) {
      if( lock( handle, OL, 20L ) ) {
        printf( "Lock failed\n" );
      } else {
        read( handle, buffer, 20 );
        /* update the buffer here */
        lseek( handle, OL, SEEK_SET );
        write( handle, buffer, 20 );
        unlock( handle, OL, 20L);
      close( handle );
  }
```

**Classification:** WATCOM

**Systems:** All, RDOS, Netware

unlock			

Synopsis: #include <graph.h>
 void \_FAR \_unregisterfonts( void );

**Description:** The \_unregisterfonts function frees the memory previously allocated by the

\_registerfonts function. The currently selected font is also unloaded.

Attempting to use the \_setfont function after calling \_unregisterfonts will result in an error.

**Returns:** The \_unregisterfonts function does not return a value.

See Also: \_\_registerfonts, \_\_setfont, \_\_getfontinfo, \_\_outgtext, \_\_getgtextextent,

\_setgtextvector, \_getgtextvector

Example: #include <conio.h>
#include <stdio.h>

#include <graph.h>
main()

int i, n;

char buf[ 10 ];

\_setvideomode( \_VRES16COLOR );
n = \_registerfonts( "\*.fon" );
for( i = 0; i < n; ++i ) {
 sprintf( buf, "n%d", i );
 \_setfont( buf );
 \_moveto( 100, 100 );
 \_outgtext( "WATCOM Graphics" );
 getch();</pre>

getch();
 \_clearscreen( \_GCLEARSCREEN );
}
\_unregisterfonts();
 \_setvideomode( \_DEFAULTMODE );
}

Classification: PC Graphics

Systems: DOS

```
Synopsis: #include <stdlib.h>
   int unsetenv( const char *name );
   int _wunsetenv( const wchar_t *name );
```

**Description:** The environment list consists of a number of environment names, each of which has a value associated

with it.

The unsetenv delete all items with name name from the environment list.

The \_wunsetenv function is a wide character version of unsetenv that operates with wide character strings.

**Returns:** The unsetenv function returns zero upon successful completion. Otherwise, it will return -1 value

and set errno to indicate the error.

Errors: When an error has occurred, errno contains a value indicating the type of error that has been detected.

EINVAL The name argument points to an empty string, or points to a string containing an

'=' character.

See Also: exec..., \_wexec..., clearenv, getenv, getenv\_s, putenv, \_searchenv, setenv,

\_wgetenv, \_wputenv, \_wsearchenv, \_wsetenv, \_wunsetenv, spawn..., \_wspawn..., system, \_wsystem

Example: #include <stdio.h>

#include <stdlib.h>
int main( void )
 {
 if( unsetenv( "INCLUDE" ) == 0 )
 printf( "INCLUDE environment variable deleted\n" );
}

Classification: POSIX 1003.1

\_wunsetenv is WATCOM

Systems: unsetenv - All, Linux, RDOS

\_wunsetenv - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

the owner of the file

**Synopsis:** 

```
#include <sys/utime.h>
int utime ( const char *path,
          const struct utimbuf *times );
int _utime( const char *path,
          const struct utimbuf *times );
int _wutime( const wchar_t *path,
            const struct utimbuf *times );
struct utimbuf {
   time_t actime;
                      /* access time
   time_t modtime;
                       /* modification time */
};
```

**Description:** 

The utime function records the access and modification times for the file identified by path.

The \_utime function is identical to utime. Use \_utime for ANSI naming conventions.

If the times argument is NULL, the access and modification times of the file or directory are set to the current time. Write access to this file must be permitted for the time to be recorded.

If the times argument is not NULL, it is interpreted as a pointer to a utimbuf structure and the access and modification times of the file or directory are set to the values contained in the designated structure. The access and modification times are taken from the actime and modtime fields in this structure.

The \_wutime function is identical to utime except that path points to a wide character string.

**Returns:** 

The utime function returns zero when the time was successfully recorded. A value of -1 indicates an error occurred.

**Errors:** 

**Example:** 

When an error has occurred, erroc contains a value indicating the type of error that has been detected.

Constant	Meaning
EACCES	Search permission is denied for a component of <i>path</i> or the <i>times</i> argument is NULL and the effective user ID of the process does not match the owner of the and write access is denied.
EINVAL	The date is before 1980 (DOS only).
<b>EMFILE</b>	There are too many open files.
ENOENT	The specified path does not exist or path is an empty string.
#include <stdi #include <sys <="" td=""><td></td></sys></stdi 	
void main( int	argc, char *argv[] )

if( (utime( argv[1], NULL ) != 0) && (argc > 1) ) { printf( "Unable to set time for %s\n", argv[1] );

Classification: POSIX 1003.1

}

\_utime conforms to ANSI naming conventions

Systems: utime - All, Linux, RDOS, Netware

\_utime - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

\_wutime - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32

**Description:** 

The utoa function converts the unsigned binary integer *value* into the equivalent string in base *radix* notation storing the result in the character array pointed to by *buffer*. A null character is appended to the result. The size of *buffer* must be at least (8 \* sizeof(int) + 1) bytes when converting values in base 2. That makes the size 17 bytes on 16-bit machines, and 33 bytes on 32-bit machines. The value of *radix* must satisfy the condition:

```
2 <= radix <= 36
```

The \_utoa function is identical to utoa. Use \_utoa for ANSI naming conventions.

The utoa function is a wide character version of <ret> that operates with wide character strings.

**Returns:** The utoa function returns the pointer to the result.

See Also: atoi, atol, itoa, ltoa, lltoa, sscanf, strtol, strtoll, strtoul, strtoull, strtoimax, strtoimax, ultoa, ultoa

**Example:** 

produces the following:

```
2 11000111011101
4 3013131
6 135033
8 30735
10 12765
12 7479
14 491b
16 31dd
```

**Classification:** WATCOM

\_utoa conforms to ANSI naming conventions

Systems: utoa - All, Linux, RDOS, Netware
\_utoa - All, Linux, RDOS, Netware

\_utow - All, Linux, RDOS

Synopsis: #include <stdarg.h>
 type va\_arg( va\_list param, type );

**Description:** 

va\_arg is a macro that can be used to obtain the next argument in a list of variable arguments. It must be used with the associated macros va\_start and va\_end. A sequence such as

```
void example( char *dst, ... )
{
   va_list curr_arg;
   int next_arg;

  va_start( curr_arg, dst );
   next_arg = va_arg( curr_arg, int );
   .
  .
  .
  .
  .
}
```

causes next\_arg to be assigned the value of the next variable argument. The argument *type* (which is int in the example) is the type of the argument originally passed to the function.

The macro va\_start must be executed first in order to properly initialize the variable curr\_arg and the macro va\_end should be executed after all arguments have been obtained.

The data item curr\_arg is of type va\_list which contains the information to permit successive acquisitions of the arguments.

**Returns:** 

The macro returns the value of the next variable argument, according to type passed as the second parameter.

See Also:

va\_end, va\_start, vfprintf, vprintf, vsprintf

**Example:** 

```
printf( "\n%s -- %s\n", msg, types );
               va_start( argument, types );
               while( *types_ptr != '\0' ) {
                   if (*types_ptr == 'i') {
                       arg_int = va_arg( argument, int );
                       printf( "integer: %d\n", arg_int );
                   } else if (*types_ptr == 's') {
                       arg_string = va_arg( argument, char * );
                       printf( "string: %s\n", arg_string );
                   ++types_ptr;
               va_end( argument );
           }
           void main( void )
               printf( "VA...TEST\n" );
               test_fn( "PARAMETERS: 1, \"abc\", 546",
                        "isi", 1, "abc", 546);
               test_fn( "PARAMETERS: \"def\", 789",
                         "si", "def", 789);
           }
           produces the following:
           VA...TEST
           PARAMETERS: 1, "abc", 546 -- isi
           integer: 1
           string: abc
           integer: 546
           PARAMETERS: "def", 789 -- si
           string: def
           integer: 789
Classification: ISO C90
```

types\_ptr = types;

**MACRO** 

**Systems:** 

Synopsis: #include <stdarg.h>
 void va\_end( va\_list param );

**Description:** va\_end is a macro used to complete the acquisition of arguments from a list of variable arguments. It must be used with the associated macros va\_start and va\_arg. See the description for va\_arg

for complete documentation on these macros.

**Returns:** The macro does not return a value.

See Also: va\_arg, va\_start, vfprintf, vprintf, vsprintf

Example: #include <stdio.h>
#include <stdarg.h>

#include <time.h>

#define ESCAPE 27

time\_t

```
void tprintf( int row, int col, char *fmt, ...)
{
   auto va_list ap;
   char *p1, *p2;

   va_start( ap, fmt );
   p1 = va_arg( ap, char * );
   p2 = va_arg( ap, char * );
   printf( "%c[%2.2d;%2.2dH", ESCAPE, row, col );
   printf( fmt, p1, p2 );
   va_end( ap );
}

void main()
{
   struct tm time_of_day;
```

ltime;

\_localtime( &ltime, &time\_of\_day ); tprintf( 12, 1, "Date and time is:  $s\n''$ ,

\_asctime( &time\_of\_day, buf ) );

auto char buf[26];

time( &ltime );

Classification: ISO C

**Systems:** MACRO

}

va_end			

Synopsis: #include <stdarg.h>
 void va\_start( va\_list param, previous );

**Description:** va\_start is a macro used to start the acquisition of arguments from a list of variable arguments. The

param argument is used by the va\_arg macro to locate the current acquired argument. The previous argument is the argument that immediately precedes the "..." notation in the original function definition. It must be used with the associated macros va\_arg and va\_end. See the description of

va\_arg for complete documentation on these macros.

**Returns:** The macro does not return a value.

See Also: va\_arg, va\_end, vfprintf, vprintf, vsprintf

Example: #include <stdio.h>

}

}

#include <stdarg.h>
#include <time.h>

#define ESCAPE 27

auto va\_list ap;
char \*p1, \*p2;

va\_start( ap, fmt );
p1 = va\_arg( ap, char \* );
p2 = va\_arg( ap, char \* );
printf( "%c[%2.2d;%2.2dH", ESCAPE, row, col );
printf( fmt, p1, p2 );
va\_end( ap );

void tprintf( int row, int col, char \*fmt, ... )

void main()
{
 struct tm time\_of\_day;
 time\_t ltime;
 auto char buf[26];

Classification: ISO C

Systems: MACRO

va_start			

# Synopsis: #include <stdio.h>

#### **Description:**

The \_vbprintf function formats data under control of the *format* control string and writes the result to *buf*. The argument *bufsize* specifies the size of the character array *buf* into which the generated output is placed. The *format* string is described under the description of the printf function. The \_vbprintf function is equivalent to the \_bprintf function, with the variable argument list replaced with *arg*, which has been initialized by the va\_start macro.

The \_vbwprintf function is a wide character version of \_vbprintf. It accepts a wide character string argument for *format* and produces wide character output.

**Returns:** 

The \_vbprintf function returns the number of characters written, or a negative value if an output error occurred.

See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, va\_arg, va\_end, va\_start, vcprintf, vfprintf, vprintf, vsprintf

**Example:** 

The following shows the use of \_vbprintf in a general error message routine.

```
#include <stdio.h>
#include <stdarq.h>
#include <string.h>
char msgbuf[80];
char *fmtmsg( char *format, ... )
  {
    va_list arglist;
    va_start( arglist, format );
    strcpy( msgbuf, "Error: " );
    _vbprintf( &msgbuf[7], 73, format, arglist );
    va_end( arglist );
    return( msgbuf );
  }
void main()
  {
    char *msg;
   msg = fmtmsg( "%s %d %s", "Failed", 100, "times" );
    printf( %s\n, msg );
```

**Classification: WATCOM** 

Systems:

\_vbprintf - All, Linux, RDOS, Netware
\_vbwprintf - All, Linux

_vbprintf, _vbwprintf			

Synopsis: #include <conio.h>
 #include <stdarg.h>
 int vcprintf( const char \*format, va\_list arg );

**Description:** The vcprintf function writes output directly to the console under control of the argument *format*. The putch function is used to output characters to the console. The *format* string is described under the description of the printf function. The vcprintf function is equivalent to the cprintf function, with the variable argument list replaced with *arg*, which has been initialized by the

va\_start macro.

**Returns:** The vcprintf function returns the number of characters written, or a negative value if an output error

occurred. When an error has occurred, errno contains a value indicating the type of error that has

been detected.

See Also: \_bprintf, cprintf, fprintf, printf, sprintf, va\_arg, va\_end, va\_start,

\_vbprintf, vfprintf, vprintf, vsprintf

Example: #include <conio.h>

#include <stdarg.h>
#include <time.h>

#define ESCAPE 27

void tprintf( int row, int col, char \*format, ... )
{
 auto va\_list arglist;

cprintf( "%c[%2.2d;%2.2dH", ESCAPE, row, col );
va\_start( arglist, format );
vcprintf( format, arglist );
va\_end( arglist );
}

struct tm time\_of\_day;
time\_t ltime;
auto char buf[26];

time( &ltime );
\_localtime( &ltime, &time\_of\_day );

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

void main()

vcprintf			

Synopsis: #include <conio.h>
 #include <stdarg.h>
 int vcscanf( const char \*format, va\_list args )

**Description:** The vcscanf function scans input from the console under control of the argument *format*. The vcscanf function uses the function getche to read characters from the console. The *format* string is described under the description of the scanf function.

The vcscanf function is equivalent to the cscanf function, with a variable argument list replaced with arg, which has been initialized using the va\_start macro.

**Returns:** The vcscanf function returns EOF when the scanning is terminated by reaching the end of the input stream. Otherwise, the number of input arguments for which values were successfully scanned and stored is returned. When a file input error occurs, the errno global variable may be set.

See Also: cscanf, fscanf, scanf, sscanf, va\_arg, va\_end, va\_start, vfscanf, vscanf, vsscanf, fwscanf, wscanf, vfwscanf, vwscanf, vswscanf

**Example:** #include <conio.h> #include <stdarg.h> void cfind( char \*format, ... ) { va\_list arglist; va\_start( arglist, format ); vcscanf( format, arglist ); va\_end( arglist ); } void main() { int day, year; char weekday[10], month[10]; cfind( "%s %s %d %d", weekday, month, &day, &year ); cprintf( "\n%s, %s %d, %d\n", weekday, month, day, year ); }

**Classification:** WATCOM

**Systems:** All, Linux, RDOS, Netware

**Safer C:** The Safer C Library extension provides the vfprintf\_s function which is a safer alternative to vfprintf.

**Description:** The vfprintf function writes output to the file pointed to by fp under control of the argument format. The format string is described under the description of the printf function. The vfprintf function is equivalent to the fprintf function, with the variable argument list replaced with arg, which has been initialized by the va\_start macro.

The vfwprintf function is a wide character version of vfprintf. It accepts a wide character string argument for *format* and produces wide character output.

**Returns:** The vfprintf function returns the number of characters written, or a negative value if an output error occurred. The vfwprintf function returns the number of wide characters written, or a negative value if an output error occurred. When an error has occurred, error contains a value indicating the type of error that has been detected.

See Also: \_\_bprintf, cprintf, fprintf, printf, sprintf, va\_arg, va\_end, va\_start, \_\_vbprintf, vcprintf, vprintf, vsprintf

#include <stdio.h>
#include <stdarg.h>

FILE \*LogFile;

/\* a general error routine \*/

void errmsg( char \*format, ... )
{
 va\_list arglist;

fprintf( stderr, "Error: " );
va\_start( arglist, format );

va\_end( arglist );

```
if( LogFile != NULL ) {
    fprintf( LogFile, "Error: " );
    va_start( arglist, format );
    vfprintf( LogFile, format, arglist );
    va_end( arglist );
}
```

vfprintf( stderr, format, arglist );

}

```
void main( void )
{
    LogFile = fopen( "error.log", "w" );
    errmsg( "%s %d %s", "Failed", 100, "times" );
}

Classification: ISO C
    vfwprintf is ISO C95

Systems:    vfprintf - All, Linux, RDOS, Netware
    vfwprintf - All, Linux
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vfprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *stream* nor *format* shall be a null pointer. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by *format*. Any argument to vfprintf\_s corresponding to a %s specifier shall not be a null pointer.

If there is a runtime-constraint violation, the vfprintf\_s function does not attempt to produce further output, and it is unspecified to what extent vfprintf\_s produced output before discovering the runtime-constraint violation.

# **Description:**

The vfprintf\_s function is equivalent to the vprintf function except for the explicit runtime-constraints listed above.

The vfwprintf\_s function is a wide character version of vfprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

#### **Returns:**

The vfprintf\_s function returns the number of characters written, or a negative value if an output error or runtime-constraint violation occurred.

The vfwprintf\_s function returns the number of wide characters written, or a negative value if an output error or runtime-constraint violation occurred.

# See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdarg.h>

FILE *LogFile;

/* a general error routine */

void errmsg( char *format, ... )
{
    va_list arglist;
```

```
fprintf_s( stderr, "Error: " );
               va_start( arglist, format );
               vfprintf_s( stderr, format, arglist );
               va_end( arglist );
               if( LogFile != NULL ) {
                   fprintf_s( LogFile, "Error: " );
                   va_start( arglist, format );
                   vfprintf_s( LogFile, format, arglist );
                   va_end( arglist );
               }
           }
           void main( void )
               errmsg( "%s %d %s", "Failed", 100, "times" );
           produces the following:
           Error: Failed 100 times
Classification: TR 24731
Systems:
           vfprintf_s - All, Linux, RDOS, Netware
           vfwprintf_s - All, Linux
```

Safer C: The Safer C Library extension provides the vfscanf\_s function which is a safer alternative to vfscanf.

va\_list arg );

**Description:** The vfscanf function scans input from the file designated by *fp* under control of the argument *format*. The *format* string is described under the description of the scanf function.

The vfscanf function is equivalent to the fscanf function, with a variable argument list replaced with *arg*, which has been initialized using the va\_start macro.

The vfwscanf function is a wide character version of vfscanf. It accepts a wide character string argument for *format* and produces wide character output.

**Returns:** The vfscanf function returns EOF if an input failure occurred before any conversion. Otherwise, the number of input arguments for which values were successfully scanned and stored is returned. When a file input error occurs, the errno global variable may be set.

See Also: cscanf, fscanf, scanf, sscanf, va\_arg, va\_end, va\_start, vcscanf, vscanf, vsscanf, fwscanf, wscanf, vfwscanf, vwscanf, vswscanf

#include <stdio.h>
#include <stdarg.h>

void ffind( FILE \*fp, char \*format, ...)
{
 va\_list arglist;

 va\_start( arglist, format );
 vfscanf( fp, format, arglist );
 va\_end( arglist );
}

void main( void )
{
 int day, year;

char weekday[10], month[10];

"%s %s %d %d",

printf( "\n%s, %s %d, %d\n",

weekday, month, &day, &year );

weekday, month, day, year );

ffind( stdin,

Classification: ISO C99

}

vfscanf - All, Linux, RDOS, Netware vfwscanf - All, Linux **Systems:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdarg.h>
#include <stdio.h>
int vfscanf_s( FILE * restrict stream,
        const char * restrict format, va_list arg );
#include <stdarg.h>
#include <stdio.h>
#include <wchar.h>
int vfwscanf_s(FILE * restrict stream,
       const wchar_t * restrict format, va_list arg );
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vfscanf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither stream nor format shall be a null pointer. Any argument indirected through in order to store converted input shall not be a null pointer.

If there is a runtime-constraint violation, the vfscanf\_s function does not attempt to perform further input, and it is unspecified to what extent vfscanf\_s performed input before discovering the runtime-constraint violation.

#### **Description:**

The vfscanf\_s function is equivalent to fscanf\_s, with the variable argument list replaced by arg, which shall have been initialized by the va\_start macro (and possibly subsequent va\_arg calls). The vfscanf\_s function does not invoke the va\_end macro.

The vfwscanf\_s function is identical to vfscanf\_s except that it accepts a wide character string argument for format.

# **Returns:**

The vfscanf\_s function returns EOF if an input failure occurred before any conversion or if there was a runtime-constraint violation. Otherwise, the vfscanf\_s function returns the number of input items successfully assigned, which can be fewer than provided for, or even zero.

When a file input error occurs, the errno global variable may be set.

#### See Also:

cscanf, fscanf, scanf, sscanf, va\_arg, va\_end, va\_start, vcscanf, vfscanf, vscanf, vsscanf, fwscanf, wscanf, vfwscanf, vwscanf, vswscanf

# **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdarg.h>
void ffind( FILE *fp, char *format, ...)
    va_list arglist;
   va_start( arglist, format );
   vfscanf_s( fp, format, arglist );
   va_end( arglist );
```

Systems: vfscanf\_s - All, Linux, RDOS, Netware vfwscanf\_s - All, Linux

```
Synopsis:
             #include <stdarq.h>
             #include <stdio.h>
             int vprintf( const char *format, va_list arg );
             #include <stdarg.h>
             #include <wchar.h>
             int vwprintf( const wchar_t *format, va_list arg );
Safer C:
             The Safer C Library extension provides the vprintf_s function which is a safer alternative to
             vprintf.
Description:
             The vprintf function writes output to the file stdout under control of the argument format. The
             format string is described under the description of the printf function. The vprintf function is
             equivalent to the printf function, with the variable argument list replaced with arg, which has been
             initialized by the va_start macro.
             The vwprintf function is a wide character version of vprintf. It accepts a wide character string
             argument for format and produces wide character output.
Returns:
             The vprintf function returns the number of characters written, or a negative value if an output error
             occurred. The vwprintf function returns the number of wide characters written, or a negative value
             if an output error occurred. When an error has occurred, errno contains a value indicating the type of
             error that has been detected.
See Also:
             _bprintf, cprintf, fprintf, printf, sprintf, va_arg, va_end, va_start,
             _vbprintf, vcprintf, vfprintf, vsprintf
Example:
             The following shows the use of vprintf in a general error message routine.
              #include <stdio.h>
             #include <stdarg.h>
             void errmsg( char *format, ... )
                   va_list arglist;
                  printf( "Error: " );
                  va_start( arglist, format );
                  vprintf( format, arglist );
                  va_end( arglist );
             }
             void main( void )
                  errmsg( "%s %d %s", "Failed", 100, "times" );
             produces the following:
             Error: Failed 100 times
Classification: ISO C
```

# 1350 Library Functions and Macros

**Systems:** 

vwprintf is ISO C95

vwprintf - All, Linux

vprintf - All, Linux, RDOS, Netware

vprintf, vwprin		

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdarg.h>
#include <stdio.h>
int vprintf_s( const char * restrict format, va_list arg );
#include <stdarg.h>
#include <wchar.h>
int vwprintf_s( const wchar_t * restrict format, va_list prg );
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

The *format* argument shall not be a null pointer. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by *format*. Any argument to vprintf\_s corresponding to a %s specifier shall not be a null pointer.

If there is a runtime-constraint violation, the <code>vprintf\_s</code> function does not attempt to produce further output, and it is unspecified to what extent <code>vprintf\_s</code> produced output before discovering the runtime-constraint violation.

# **Description:**

The vprintf\_s function is equivalent to the vprintf function except for the explicit runtime-constraints listed above.

The vwprintf\_s function is a wide character version of vprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

#### **Returns:**

The vprintf\_s function returns the number of characters written, or a negative value if an output error or runtime-constraint violation occurred.

The vwprintf\_s function returns the number of wide characters written, or a negative value if an output error or runtime-constraint violation occurred.

#### See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdarg.h>

void errmsg( char *format, ... )
{
    va_list arglist;

    printf_s( "Error: " );
    va_start( arglist, format );
    vprintf_s( format, arglist );
    va_end( arglist );
}

void main( void )
{
    errmsg( "%s %d %s", "Failed", 100, "times" );
}
```

produces the following:

Error: Failed 100 times

**Classification:** TR 24731

Systems: vprintf\_s - All, Linux, RDOS, Netware

vwprintf\_s - All, Linux

```
Synopsis:
             #include <stdarq.h>
             #include <stdio.h>
             int vscanf( const char *format, va_list arg );
             #include <stdarg.h>
             #include <wchar.h>
             int vwscanf( const wchar_t *format, va_list arg );
Safer C:
             The Safer C Library extension provides the vscanf_s function which is a safer alternative to
             vscanf.
            The vscanf function scans input from the file designated by stdin under control of the argument
Description:
             format. The format string is described under the description of the scanf function.
             The vscanf function is equivalent to the scanf function, with a variable argument list replaced with
             arg, which has been initialized using the va_start macro.
             The vwscanf function is identical to vscanf except that it accepts a wide character string argument
             for format.
Returns:
             The vscanf function returns EOF if an input failure occurred before any conversion. values were
             successfully scanned and stored is returned.
See Also:
             cscanf, fscanf, scanf, sscanf, va_arg, va_end, va_start, vcscanf, vfscanf,
             vsscanf, fwscanf, wscanf, swscanf, vfwscanf, vwscanf, vswscanf
Example:
             #include <stdio.h>
             #include <stdarg.h>
             void find( char *format, ... )
                  va_list arglist;
                  va_start( arglist, format );
                  vscanf( format, arglist );
                  va_end( arglist );
             }
             void main( void )
                  int day, year;
                  char weekday[10], month[10];
                  find( "%s %s %d %d",
                            weekday, month, &day, &year );
                  printf( "\n%s, %s %d, %d\n",
                            weekday, month, day, year );
             }
```

# Classification: ISO C99

Systems: vscanf - All, Linux, RDOS, Netware vwscanf - All, Linux

		vscanf, vwscanf

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdarg.h>
#include <stdio.h>
int vscanf_s( const char * restrict format, va_list arg );
#include <stdarg.h>
#include <wchar.h>
int vwscanf_s( const wchar_t * restrict format, va_list arg );
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vscanf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> The argument format shall not be a null pointer. Any argument indirected through in order to store converted input shall not be a null pointer.

If there is a runtime-constraint violation, the vscanf\_s function does not attempt to perform further input, and it is unspecified to what extent vscanf\_s performed input before discovering the runtime-constraint violation.

## **Description:**

The vscanf\_s function is equivalent to scanf\_s, with the variable argument list replaced by arg, which shall have been initialized by the va\_start macro (and possibly subsequent va\_arg calls). The vscanf\_s function does not invoke the va\_end macro.

The vwscanf\_s function is identical to vscanf\_s except that it accepts a wide character string argument for format.

#### **Returns:**

The vscanf\_s function returns EOF if an input failure occurred before any conversion or if there was a runtime-constraint violation. Otherwise, the vscanf\_s function returns the number of input items successfully assigned, which can be fewer than provided for, or even zero.

When a file input error occurs, the errno global variable may be set.

#### See Also:

cscanf, fscanf, scanf, sscanf, va\_arg, va\_end, va\_start, vcscanf, vfscanf, vscanf, vsscanf, fwscanf, wscanf, swscanf, vfwscanf, vwscanf, vswscanf

#### **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdarq.h>
void find( char *format, ... )
    va_list arglist;
    va_start( arglist, format );
    vscanf_s( format, arglist );
    va_end( arglist );
void main( void )
    int day, year;
    char weekday[10], month[10];
```

**Description:** 

The \_vsnprintf function formats data under control of the *format* control string and stores the result in *buf*. The maximum number of characters to store is specified by *count*. A null character is placed at the end of the generated character string if fewer than *count* characters were stored. The *format* string is described under the description of the printf function. The \_vsnprintf function is equivalent to the \_snprintf function, with the variable argument list replaced with *arg*, which has been initialized by the va\_start macro.

The \_vsnwprintf function is a wide character version of \_vsnprintf. It accepts a wide character string argument for *format* and produces wide character output. The argument *buf* specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream. The maximum number of wide characters to write is specified by *count*. A null wide character is placed at the end of the generated wide character string if fewer than *count* wide characters were stored.

**Returns:** 

The \_vsnprintf function returns the number of characters written into the array, not counting the terminating null character, or a negative value if more than *count* characters were requested to be generated. An error can occur while converting a value for output. The \_vsnwprintf function returns the number of wide characters written into the array, not counting the terminating null wide character, or a negative value if more than *count* wide characters were requested to be generated. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also:

```
_bprintf, cprintf, fprintf, printf, sprintf, va_arg, va_end, va_start, _vbprintf, vcprintf, vfprintf, vprintf
```

**Example:** 

The following shows the use of \_vsnprintf in a general error message routine.

```
#include <stdio.h>
#include <stdarg.h>
#include <string.h>

char msgbuf[80];

char *fmtmsg( char *format, ...)
{
   va_list arglist;

   va_start( arglist, format );
   strcpy( msgbuf, "Error: " );
   _vsnprintf( &msgbuf[7], 80-7, format, arglist );
   va_end( arglist );
   return( msgbuf );
}
```

```
void main()
{
    char *msg;

    msg = fmtmsg( "%s %d %s", "Failed", 100, "times" );
    printf( "%s\n", msg );
}
```

**Classification:** WATCOM

Systems: \_vsnprintf - All, Linux, RDOS, Netware \_vsnwprintf - All, Linux

\_\_\_\_\_

Safer C:

The Safer C Library extension provides the vsnprintf\_s function which is a safer alternative to vsnprintf.

**Description:** 

The vsnprintf function formats data under control of the *format* control string and stores the result in *buf*. The maximum number of characters to store, including a terminating null character, is specified by *count*. The *format* string is described under the description of the printf function. The vsnprintf function is equivalent to the \_snprintf function, with the variable argument list replaced with *arg*, which has been initialized by the va\_start macro.

The vsnwprintf function is a wide character version of vsnprintf. It accepts a wide character string argument for *format* and produces wide character output. The argument *buf* specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream. The maximum number of wide characters to write, including a terminating null wide character, is specified by *count*.

**Returns:** 

The vsnprintf function returns the number of characters that would have been written had *count* been sufficiently large, not counting the terminating null character, or a negative value if an encoding error occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than *count*. The vsnwprintf function returns the number of wide characters that would have been written had *count* been sufficiently large, not counting the terminating null wide character, or a negative value if an encoding error occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than *count*. When an error has occurred, erroc contains a value indicating the type of error that has been detected.

See Also:

```
_bprintf, cprintf, fprintf, printf, sprintf, va_arg, va_end, va_start, _vbprintf, vcprintf, vfprintf, vprintf
```

**Example:** 

The following shows the use of vsnprintf in a general error message routine.

```
#include <stdio.h>
           #include <stdlib.h>
           #include <stdarg.h>
           #include <string.h>
           char *fmtmsg( char *format, ... )
                       *msgbuf;
               char
               int
                       len;
               va_list arglist;
               va_start( arglist, format );
               len = vsnprintf( NULL, 0, format, arglist );
               va_end( arglist );
               len = len + 1 + 7;
               msgbuf = malloc( len );
               strcpy( msgbuf, "Error: " );
               va_start( arglist, format );
               vsnprintf( &msgbuf[7], len, format, arglist );
               va_end( arglist );
               return( msgbuf );
           }
           void main( void )
               char *msg;
               msg = fmtmsg( "%s %d %s", "Failed", 100, "times" );
               printf( "%s\n", msg );
               free( msg );
Classification: ISO C
Systems:
           vsnprintf - All, Linux, RDOS, Netware
           vsnwprintf - All, Linux
```

#### Constraints:

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vsnprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *s* nor *format* shall be a null pointer. The *n* argument shall neither equal zero nor be greater than RSIZE\_MAX. The number of characters (including the trailing null) required for the result to be written to the array pointed to by *s* shall not be greater than *n*. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by *format*. Any argument to vsnprintf\_s corresponding to a %s specifier shall not be a null pointer. No encoding error shall occur.

If there is a runtime-constraint violation, then if s is not a null pointer and n is greater than zero and less than RSIZE\_MAX, then the vsnprintf\_s function sets s[0] to the null character.

### **Description:**

The vsnprintf\_s function is equivalent to the vsnprintf function except for the explicit runtime-constraints listed above.

The vsnprintf\_s function, unlike vsprintf\_s, will truncate the result to fit within the array pointed to by *s*.

The vsnwprintf\_s function is a wide character version of vsnprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

# **Returns:**

The  $vsnprintf_s$  function returns the number of characters that would have been written had n been sufficiently large, not counting the terminating null character, or a negative value if a runtime-constraint violation occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than n.

The  $vsnprintf_s$  function returns the number of wide characters that would have been written had n been sufficiently large, not counting the terminating wide null character, or a negative value if a runtime-constraint violation occurred. Thus, the null-terminated output has been completely written if and only if the returned value is nonnegative and less than n.

# See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

#### **Example:**

The following shows the use of vsnprintf\_s in a general error message routine.

```
#define ___STDC_WANT_LIB_EXT1__ 1
           #include <stdio.h>
           #include <stdlib.h>
           #include <stdarg.h>
           #include <string.h>
           char *fmtmsg( char *format, ... )
                       *msgbuf;
               char
               int
                       len;
               va_list arglist;
               va_start( arglist, format );
               len = vsnprintf( NULL, 0, format, arglist );
               va_end( arglist );
               len = len + 1 + 7;
               msgbuf = malloc( len );
               strcpy( msgbuf, "Error: " );
               va_start( arglist, format );
               vsnprintf_s( &msgbuf[7], len, format, arglist );
               va_end( arglist );
               return( msgbuf );
           }
           void main( void )
               char *msg;
               msg = fmtmsg( "%s %d %s", "Failed", 100, "times" );
               printf_s( "%s\n", msg );
               free( msg );
           }
Classification: TR 24731
Systems:
           vsnprintf_s - All, Linux, RDOS, Netware
           vsnwprintf_s - All, Linux
```

Safer C:

The Safer C Library extension provides the vsprintf\_s function which is a safer alternative to vsprintf.

**Description:** 

The vsprintf function formats data under control of the *format* control string and writes the result to *buf*. The *format* string is described under the description of the printf function. The vsprintf function is equivalent to the sprintf function, with the variable argument list replaced with *arg*, which has been initialized by the va\_start macro.

The vswprintf function is a wide character version of vsprintf. It accepts a wide character string argument for *format* and produces wide character output. The argument *buf* specifies an array of wide characters into which the generated output is to be written, rather than converted to multibyte characters and written to a stream. The maximum number of wide characters to write, including a terminating null wide character, is specified by *count*.

**Returns:** 

The vsprintf function returns the number of characters written, or a negative value if an output error occurred. The vswprintf function returns the number of wide characters written into the array, not counting the terminating null wide character, or a negative value if *count* or more wide characters were requested to be generated.

See Also:

```
_bprintf, cprintf, fprintf, printf, sprintf, va_arg, va_end, va_start, _vbprintf, vcprintf, vfprintf, vprintf
```

**Example:** 

The following shows the use of vsprintf in a general error message routine.

```
#include <stdio.h>
#include <stdarg.h>
#include <string.h>

char msgbuf[80];

char *fmtmsg( char *format, ...)
{
   va_list arglist;

   va_start( arglist, format );
   strcpy( msgbuf, "Error: " );
   vsprintf( &msgbuf[7], format, arglist );
   va_end( arglist );
   return( msgbuf );
}
```

#### **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vsprintf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither s nor *format* shall be a null pointer. The n argument shall neither equal zero nor be greater than RSIZE\_MAX. The number of characters (including the trailing null) required for the result to be written to the array pointed to by s shall not be greater than n. The %n specifier (modified or not by flags, field width, or precision) shall not appear in the string pointed to by *format*. Any argument to vsprintf\_s corresponding to a %s specifier shall not be a null pointer. No encoding error shall occur.

If there is a runtime-constraint violation, then if s is not a null pointer and n is greater than zero and less than RSIZE\_MAX, then the vsprintf\_s function sets s[0] to the null character.

### **Description:**

The vsprintf\_s function is equivalent to the vsprintf function except for the explicit runtime-constraints listed above.

The vsprintf\_s function, unlike vsnprintf\_s, treats a result too big for the array pointed to by s as a runtime-constraint violation.

The vswprintf\_s function is a wide character version of vsprintf\_s. It accepts a wide character string argument for *format* and produces wide character output.

# **Returns:**

If no runtime-constraint violation occurred, the vsprintf\_s function returns the number of characters written in the array, not counting the terminating null character. If an encoding error occurred, vsprintf\_s returns a negative value. If any other runtime-constraint violation occurred, vsprintf\_s returns zero.

If no runtime-constraint violation occurred, the vswprintf\_s function returns the number of wide characters written in the array, not counting the terminating null wide character. If an encoding error occurred or if *n* or more wide characters are requested to be written, vswprintf\_s returns a negative value. If any other runtime-constraint violation occurred, vswprintf\_s returns zero.

# See Also:

\_bprintf, cprintf, fprintf, printf, sprintf, \_vbprintf, vcprintf, vfprintf, vprintf, vsprintf, \_bwprintf, fwprintf, swprintf, \_vbwprintf, vfwprintf, vwprintf, vswprintf

#### **Example:**

The following shows the use of vsprintf\_s in a general error message routine.

```
#define ___STDC_WANT_LIB_EXT1__ 1
           #include <stdio.h>
           #include <stdarg.h>
           #include <string.h>
           char msgbuf[80];
           char *fmtmsg( char *format, ... )
               va_list arglist;
               va_start( arglist, format );
               strcpy_s( msgbuf, sizeof( buffer ), "Error: " );
               vsprintf_s( &msgbuf[7], sizeof( msgbuf ) - 7,
                            format, arglist );
               va_end( arglist );
               return( msgbuf );
           }
           void main( void )
               char *msg;
               msg = fmtmsg( "%s %d %s", "Failed", 100, "times" );
               printf( "%s\n", msg );
Classification: TR 24731
Systems:
           vsprintf_s - All, Linux, RDOS, Netware
           vswprintf_s - All, Linux
```

Synopsis: #in

Safer C:

The Safer C Library extension provides the vsscanf\_s function which is a safer alternative to vsscanf.

**Description:** 

The vsscanf function scans input from the string designated by *s* under control of the argument *format*. The *format* string is described under the description of the scanf function.

The vsscanf function is equivalent to the sscanf function, with a variable argument list replaced with *arg*, which has been initialized using the va\_start macro.

The vswscanf function is identical to vsscanf except that it accepts a wide character string argument for *format*.

**Returns:** 

The vsscanf function returns EOF if the end of the input string was reached before any conversion. Otherwise, the number of input arguments for which values were successfully scanned and stored is returned.

See Also:

cscanf, fscanf, scanf, sscanf, va\_arg, va\_end, va\_start, vcscanf, vfscanf, vscanf, fwscanf, wscanf, vwscanf, vwscanf, vswscanf

**Example:** 

```
#include <stdio.h>
#include <stdarg.h>
void sfind( char *string, char *format, ... )
    va_list arglist;
    va_start( arglist, format );
    vsscanf( string, format, arglist );
    va_end( arglist );
}
void main( void )
    int day, year;
    char weekday[10], month[10];
    sfind( "Saturday April 18 1987",
            "%s %s %d %d",
            weekday, month, &day, &year );
    printf( "\n%s, %s %d, %d\n",
            weekday, month, day, year );
}
```

Classification: ISO C99

vsscanf - All, Linux, RDOS, Netware
vswscanf - All, Linux **Systems:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdarg.h>
#include <stdio.h>
int vsscanf_s( const char * restrict str,
               const char * restrict format,
               va_list arg );
#include <stdarq.h>
#include <wchar.h>
int vswscanf_s( const wchar_t * restrict str,
                const wchar_t * restrict format,
                va_list arg );
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and vsscanf\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither str not format shall be a null pointer. Any argument indirected through in order to store converted input shall not be a null pointer.

If there is a runtime-constraint violation, the vsscanf\_s function does not attempt to perform further input, and it is unspecified to what extent vsscanf\_s performed input before discovering the runtime-constraint violation.

#### **Description:**

The vsscanf\_s function is equivalent to sscanf\_s, with the variable argument list replaced by arg, which shall have been initialized by the va\_start macro (and possibly subsequent va\_arg calls). The vsscanf\_s function does not invoke the va\_end macro.

The vswscanf\_s function is identical to vsscanf\_s except that it accepts wide character string arguments for str and format.

#### **Returns:**

The vsscanf\_s function returns EOF if an input failure occurred before any conversion or if there was a runtime-constraint violation. Otherwise, the vsscanf\_s function returns the number of input items successfully assigned, which can be fewer than provided for, or even zero.

When a file input error occurs, the errno global variable may be set.

# See Also:

cscanf, fscanf, scanf, sscanf, va\_arg, va\_end, va\_start, vcscanf, vfscanf, vscanf, vsscanf, fwscanf, wscanf, vfwscanf, vwscanf, vswscanf

# **Example:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <stdarg.h>
void sfind( char *string, char *format, ... )
    va_list arglist;
    va_start( arglist, format );
    vsscanf_s( string, format, arglist );
    va_end( arglist );
}
```

```
void main( void )
               int day, year;
               char weekday[10], month[10];
               sfind( "Friday August 0013 2004",
                        "%s %s %d %d",
                         weekday, sizeof( weekday ),
                         month, sizeof( month ),
                         &day, &year );
               printf_s( "\n%s, %s %d, %d\n",
                        weekday, month, day, year );
           }
           produces the following:
           Friday, August 13, 2004
Classification: TR 24731
Systems:
           vsscanf_s - All, Linux, RDOS, Netware
           vswscanf_s - All, Linux
```

Synopsis: #include process.h>
int wait( int \*status );

**Description:** 

The wait function suspends the calling process until any of the caller's immediate child processes terminate.

Under Win32, there is no parent-child relationship amongst processes so the wait function cannot and does not wait for child processes to terminate. To wait for any process, you must specify its process ID. For this reason, the cwait function should be used (one of its arguments is a process ID).

If *status* is not NULL, it points to a word that will be filled in with the termination status word and return code of the terminated child process.

If the child process terminated normally, then the low order byte of the status word will be set to 0, and the high order byte will contain the low order byte of the return code that the child process passed to the DOSEXIT function. The DOSEXIT function is called whenever main returns, or exit, or \_Exit or \_exit are explicitly called.

If the child process did not terminate normally, then the high order byte of the status word will be set to 0, and the low order byte will contain one of the following values:

Value	Meaning
1	Hard-error abort
2	Trap operation
3	SIGTERM signal not intercepted

Note:

This implementation of the status value follows the OS/2 model and differs from the Microsoft implementation. Under Microsoft, the return code is returned in the low order byte and it is not possible to determine whether a return code of 1, 2, or 3 imply that the process terminated normally. For portability to Microsoft compilers, you should ensure that the application that is waited on does not return one of these values. The following shows how to handle the status value in a portable manner.

```
cwait( &status, process_id, WAIT_CHILD );
#if defined(__WATCOMC__)
switch( status & 0xff ) {
case 0:
   printf( "Normal termination exit code = %d\n", status >> 8 );
   break;
case 1:
    printf( "Hard-error abort\n" );
   break;
case 2:
   printf( "Trap operation\n" );
   break;
case 3:
   printf( "SIGTERM signal not intercepted\n" );
   break;
default:
   printf( "Bogus return status\n" );
#else if defined(_MSC_VER)
switch( status & 0xff ) {
case 1:
   printf( "Possible Hard-error abort\n" );
   break;
case 2:
   printf( "Possible Trap operation\n" );
   break;
case 3:
   printf( "Possible SIGTERM signal not intercepted\n" );
   break;
default:
   printf( "Normal termination exit code = %d\n", status );
#endif
```

**Returns:** 

The wait function returns the child's process ID if the child process terminated normally. Otherwise, wait returns -1 and sets errno to one of the following values:

# Constant Meaning

**ECHILD** No child processes exist for the calling process.

**EINTR** The child process terminated abnormally.

```
See Also: cwait, exit, _Exit, _exit, spawn...
```

wait( &status );

**Classification:** WATCOM

}

**Systems:** Win32, OS/2 1.x(all), OS/2-32, Linux

Synopsis: #include <wchar.h>

```
size_t wcrtomb( char *s, wchar_t wc, mbstate_t *ps );
size_t _fwcrtomb( char __far *s, wchar_t wc, mbstate_t __far *ps );
```

Safer C:

The Safer C Library extension provides the wcrtomb\_s function which is a safer alternative to wcrtomb.

**Description:** 

If s is a null pointer, the wortomb function determines the number of bytes necessary to enter the initial shift state (zero if encodings are not state-dependent or if the initial conversion state is described). The resulting state described will be the initial conversion state.

If s is not a null pointer, the wortomb function determines the number of bytes needed to represent the multibyte character that corresponds to the wide character given by wc (including any shift sequences), and stores the resulting bytes in the array whose first element is pointed to by s. At most MB\_CUR\_MAX bytes will be stored. If wc is a null wide character, the resulting state described will be the initial conversion state.

The \_fwcrtomb function is a data model independent form of the wcrtomb function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The restartable multibyte/wide character conversion functions differ from the corresponding internal-state multibyte character functions ( mblen, mbtowc, and wctomb) in that they have an extra argument, ps, of type pointer to mbstate\_t that points to an object that can completely describe the current conversion state of the associated multibyte character sequence. If ps is a null pointer, each function uses its own internal mbstate\_t object instead. You are guaranteed that no other function in the library calls these functions with a null pointer for ps, thereby ensuring the stability of the state.

Also unlike their corresponding functions, the return value does not represent whether the encoding is state-dependent.

If the encoding is state-dependent, on entry each function takes the described conversion state (either internal or pointed to by ps) as current. The conversion state described by the pointed-to object is altered as needed to track the shift state of the associated multibyte character sequence. For encodings without state dependency, the pointer to the mbstate\_t argument is ignored.

**Returns:** 

If *s* is a null pointer, the wcrtomb function returns the number of bytes necessary to enter the initial shift state. The value returned will not be greater than that of the MB\_CUR\_MAX macro.

If s is not a null pointer, the wortomb function returns the number of bytes stored in the array object (including any shift sequences) when wc is a valid wide character; otherwise (when wc is not a valid wide character), an encoding error occurs: the wortomb function stores the value of the macro EILSEQ in errno and returns (size\_t)-1; but the conversion state is unspecified.

See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs, wcstombs\_s, wctob, wctomb, wctomb\_s

```
Example:
           #include <stdio.h>
           #include <wchar.h>
           #include <mbctype.h>
           #include <errno.h>
           const wchar_t wc[] = {
               0 \times 0020,
               0x002e,
               0 \times 0031,
               0 \times 0041,
               0x3000,
                           /* double-byte space */
                           /* double-byte A */
               0xff21,
                           /* double-byte Hiragana */
               0x3048,
               0x30a3,
                            /* double-byte Katakana */
               0xff61,
                           /* single-byte Katakana punctuation */
               0xff66,
                           /* single-byte Katakana alphabetic */
                           /* single-byte Katakana alphabetic */
               0xff9f,
                           /* double-byte Kanji */
               0x720d,
               0x0000
           };
           #define SIZE sizeof( wc ) / sizeof( wchar_t )
           void main()
           {
               int
                            i, j, k;
               char
                            s[2];
               _setmbcp( 932 );
               i = wcrtomb( NULL, 0, NULL );
               printf( "Number of bytes to enter "
                        "initial shift state = %d\n", i );
               j = 1;
               for( i = 0; i < SIZE; i++ ) {
                    j = wcrtomb(s, wc[i], NULL);
                   printf( "%d bytes in character ", j );
                   if( errno == EILSEQ ) {
                     printf( " - illegal wide character\n" );
                    } else {
                      if (j == 0) {
                          k = 0;
                      } else if ( j == 1 ) {
                          k = s[0];
                      } else if( j == 2 ) {
                          k = s[0] << 8 \mid s[1];
                      printf( "(%#6.4x->%#6.4x)\n", wc[i], k );
                    }
               }
           }
```

produces the following:

```
Number of bytes to enter initial shift state = 0

1 bytes in character (0x0020->0x0020)

1 bytes in character (0x002e->0x002e)

1 bytes in character (0x0031->0x0031)

1 bytes in character (0x0041->0x0041)

2 bytes in character (0x3000->0x8140)

2 bytes in character (0xff21->0x8260)

2 bytes in character (0x3048->0x82a6)

2 bytes in character (0x30a3->0x8342)

1 bytes in character (0xff61->0x00a1)

1 bytes in character (0xff66->0x00a6)

1 bytes in character (0xf720d->0x00df)

2 bytes in character (0x720d->0xe0a1)

1 bytes in character (0x000->0x0069)

SISO C
```

# Classification: ISO C

Systems: wcrtomb - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, Linux,

RDOS

\_fwcrtomb - DOS, Windows, OS/2 1.x(all)

# **Constraints:**

If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and wortomb\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

Neither *retval* nor *ps* shall be a null pointer. If *s* is not a null pointer, then *smax* shall not equal zero and shall not be greater than RSIZE\_MAX. If *s* is not a null pointer, then *smax* shall be not be less than the number of bytes to be stored in the array pointed to by *s*. If *s* is a null pointer, then *smax* shall equal zero.

If there is a runtime-constraint violation, then wcrtomb\_s does the following. If s is not a null pointer and smax is greater than zero and not greater than RSIZE\_MAX, then wcrtomb\_s sets s[0] to the null character. If retval is not a null pointer, then the wcrtomb\_s sets \*retval to (size\_t)-1.

# **Description:**

If s is a null pointer, the wcrtomb\_s function is equivalent to the call wcrtomb\_s(&retval, buf, size of buf, L'\0', ps) where retval and buf are internal variables of the appropriate types, and the size of buf is greater than MB\_CUR\_MAX.

If s is not a null pointer, the wcrtomb\_s function determines the number of bytes needed to represent the multibyte character that corresponds to the wide character given by wc (including any shift sequences), and stores the multibyte character representation in the array whose first element is pointed to by s. At most MB\_CUR\_MAX bytes are stored. If wc is a null wide character, a null byte is stored, preceded by any shift sequence needed to restore the initial shift state; the resulting state described is the initial conversion state.

If wc does not correspond to a valid multibyte character, an encoding error occurs: the wcrtomb\_s function stores the value (size\_t)-1 into \*retval\* and the conversion state is unspecified. Otherwise, the wcrtomb\_s function stores into \*retval\* the number of bytes (including any shift sequences) stored in the array pointed to by s.

The \_fwcrtomb\_s function is a data model independent form of the wcrtomb\_s function that accepts far pointer arguments. It is most useful in mixed memory model applications.

#### **Returns:**

The wcrtomb\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

# See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcsrtombs, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

```
#define __STDC_WANT_LIB_EXT1__ 1
Example:
           #include <stdio.h>
           #include <wchar.h>
           #include <mbctype.h>
           #include <errno.h>
           const wchar_t wc[] = {
               0x0020,
               0x002e,
               0x0031,
               0x0041,
               0x3000,
                           /* double-byte space */
                           /* double-byte A */
               0xff21,
               0x3048,
                           /* double-byte Hiragana */
               0x30a3,
                           /* double-byte Katakana */
               0xff61,
                           /* single-byte Katakana punctuation */
               0xff66,
                           /* single-byte Katakana alphabetic */
               0xff9f,
                           /* single-byte Katakana alphabetic */
                           /* double-byte Kanji */
               0x720d,
               0x0000
           };
           #define SIZE sizeof( wc ) / sizeof( wchar_t )
           int main()
           {
                            i, j, k;
               int
               char
                            s[2];
               errno_t
                            rc;
               size_t
                            retval;
               mbstate_t
                           state;
               _setmbcp( 932 );
               j = 1;
               for( i = 0; i < SIZE; i++ ) {
                    rc = wcrtomb_s( &retval, s, 2, wc[i], &state );
                   if( rc != 0 ) {
                     printf( " - illegal wide character\n" );
                    } else {
                     printf( "%d bytes in character ", retval );
                     if ( retval == 0 ) {
                         k = 0;
                      } else if ( retval == 1 ) {
                          k = s[0];
                      } else if( retval == 2 ) {
                         k = s[0] << 8 \mid s[1];
                     printf( "(\#6.4x->\#6.4x)\n", wc[i], k );
                    }
               return( 0 );
           }
           produces the following:
```

**Systems:** 

```
1 bytes in character (0x0020->0x0020)
           1 bytes in character (0x002e->0x002e)
           1 bytes in character (0x0031->0x0031)
           1 bytes in character (0x0041->0x0041)
           2 bytes in character (0x3000->0x8140)
           2 bytes in character (0xff21->0x8260)
           2 bytes in character (0x3048->0x82a6)
           2 bytes in character (0x30a3->0x8342)
           1 bytes in character (0xff61->0x00a1)
           1 bytes in character (0xff66->0x00a6)
           1 bytes in character (0xff9f->0x00df)
           2 bytes in character (0x720d->0xe0a1)
           1 bytes in character ( 0000 -> 0 \times 0069)
Classification: TR 24731
           _fwcrtomb_s is s WATCOM
           wcrtomb_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
           Linux, RDOS
           _fwcrtomb_s - DOS, Windows, OS/2 1.x(all)
```

Safer C:

The Safer C Library extension provides the wcsrtombs\_s function which is a safer alternative to wcsrtombs.

**Description:** 

The wesrtombs function converts a sequence of wide characters from the array indirectly pointed to by *src* into a sequence of corresponding multibyte characters that begins in the shift state described by *ps*, which, if *dst* is not a null pointer, are then stored into the array pointed to by *dst*. Conversion continues up to and including a terminating null wide character, but the terminating null character (byte) will not be stored. Conversion will stop earlier in two cases: when a code is reached that does not correspond to a valid multibyte character, or (if *dst* is not a null pointer) when the next multibyte character would exceed the limit of *len* total bytes to be stored into the array pointed to by *dst*. Each conversion takes place as if by a call to the wertomb function.

If dst is not a null pointer, the pointer object pointed to by src will be assigned either a null pointer (if conversion stopped due to reaching a terminating null wide character) or the address just past the last wide character converted. If conversion stopped due to reaching a terminating null wide character and if dst is not a null pointer, the resulting state described will be the initial conversion state.

The \_fwcsrtombs function is a data model independent form of the wcsrtombs function that accepts far pointer arguments. It is most useful in mixed memory model applications.

The restartable multibyte/wide string conversion functions differ from the corresponding internal-state multibyte string functions ( mbstowcs and wcstombs) in that they have an extra argument, ps, of type pointer to mbstate\_t that points to an object that can completely describe the current conversion state of the associated multibyte character sequence. If ps is a null pointer, each function uses its own internal mbstate\_t object instead. You are guaranteed that no other function in the library calls these functions with a null pointer for ps, thereby ensuring the stability of the state.

Also unlike their corresponding functions, the conversion source argument, *src*, has a pointer-to-pointer type. When the function is storing conversion results (that is, when *dst* is not a null pointer), the pointer object pointed to by this argument will be updated to reflect the amount of the source processed by that invocation.

If the encoding is state-dependent, on entry each function takes the described conversion state (either internal or pointed to by *ps*) as current and then, if the destination pointer, *dst*, is not a null pointer, the conversion state described by the pointed-to object is altered as needed to track the shift state of the associated multibyte character sequence. For encodings without state dependency, the pointer to the mbstate\_t argument is ignored.

**Returns:** 

If the first code is not a valid wide character, an encoding error occurs: the westtombs function stores the value of the macro EILSEQ in erro and returns (size\_t)-1; but the conversion state is unspecified. Otherwise, it returns the number of bytes in the resulting multibyte characters sequence, which is the same as the number of array elements modified when dst is not a null pointer.

See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc,

mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs\_s, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

# **Example:**

```
#include <stdio.h>
#include <wchar.h>
#include <mbctype.h>
#include <errno.h>
const wchar_t wc[] = {
    0x0020,
    0x002e,
    0x0031,
    0 \times 0041,
    0x3000,
               /* double-byte space */
               /* double-byte A */
    0xff21,
                /* double-byte Hiragana */
    0x3048,
                /* double-byte Katakana */
    0x30a3,
                /* single-byte Katakana punctuation */
    0xff61,
    0xff66,
                /* single-byte Katakana alphabetic */
    0xff9f,
               /* single-byte Katakana alphabetic */
    0x720d,
               /* double-byte Kanji */
    0x0000
};
void main()
{
    int
                     i;
    size_t
                     elements;
    const wchar_t
                     *src;
    char
                    mb[50];
    mbstate_t
                   pstate;
    _setmbcp( 932 );
    src = wc;
    elements = wcsrtombs( mb, &src, 50, &pstate );
    if( errno == EILSEQ ) {
        printf( "Error in wide character string\n" );
    } else {
        for( i = 0; i < elements; i++ ) {</pre>
            printf( "0x%2.2x\n", mb[i] );
    }
}
```

produces the following:

```
0x20
           0x2e
           0x31
           0x41
           0x81
           0x40
           0x82
           0x60
           0x82
           0xa6
           0x83
           0x42
           0xa1
           0xa6
           0xdf
           0xe0
           0xa1
Classification: ISO C
           wcsrtombs - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
```

\_fwcsrtombs - DOS, Windows, OS/2 1.x(all)

**Systems:** 

Linux, RDOS

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1_
errno_t wcsrtombs_s( size_t * restrict retval,
                     char * restrict dst,
                     rsize_t dstmax,
                     const wchar_t ** restrict src,
                     rsize_t len,
                     mbstate_t * restrict ps);
errno_t _fwcsrtombs_s( size_t __far * restrict retval,
                       char __far * restrict dst,
                       rsize_t dstmax,
                       const wchar_t __far * __far * restrict src,
                       rsize_t len,
                       mbstate_t __far * restrict ps);
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and wcsrtombs\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> None of retval, src, \*src, or ps shall be null pointers. If dst is not a null pointer, then neither len nor dstmax shall be greater than RSIZE\_MAX. If dst is a null pointer, then dstmax shall equal zero. If dst is not a null pointer, then dstmax shall not equal zero. If dst is not a null pointer and len is not less than dstmax, then the conversion shall have been stopped (see below) because a terminating null wide character was reached or because an encoding error occurred.

> If there is a runtime-constraint violation, then wcsrtombs\_s does the following. If retval is not a null pointer, then the wcsrtombs\_s sets \*retval to (size\_t) -1. If dst is not a null pointer and dstmax is greater than zero and less than RSIZE\_MAX, then wcsrtombs\_s sets dst[0] to the null character.

#### **Description:**

The wcsrtombs\_s function converts a sequence of wide characters from the array indirectly pointed to by src into a sequence of corresponding multibyte characters that begins in the conversion state described by the object pointed to by ps. If dst is not a null pointer, the converted characters are then stored into the array pointed to by dst. Conversion continues up to and including a terminating null wide character, which is also stored.

Conversion stops earlier in two cases:

- when a wide character is reached that does not correspond to a valid multibyte character;
- (if dst is not a null pointer) when the next multibyte character would exceed the limit of n total bytes to be stored into the array pointed to by dst. If the wide character being converted is the null wide character, then n is the lesser of len or dstmax. Otherwise, n is the lesser of len or dstmax-1.

If the conversion stops without converting a null wide character and dst is not a null pointer, then a null character is stored into the array pointed to by dst immediately following any multibyte characters already stored. Each conversion takes place as if by a call to the wortomb function.

If dst is not a null pointer, the pointer object pointed to by src is assigned either a null pointer (if conversion stopped due to reaching a terminating null wide character) or the address just past the last wide character converted (if any). If conversion stopped due to reaching a terminating null wide character, the resulting state described is the initial conversion state.

Regardless of whether dst is or is not a null pointer, if the input conversion encounters a wide character that does not correspond to a valid multibyte character, an encoding error occurs: the wcsrtombs\_s

function stores the value  $(size_t)-1$  into \*retval and the conversion state is unspecified. Otherwise, the wcsrtombs\_s function stores into \*retval the number of bytes in the resulting multibyte character sequence, not including the terminating null character (if any).

All elements following the terminating null character (if any) written by wcsrtombs\_s in the array of dstmax elements pointed to by dst take unspecified values when wcsrtombs\_s returns.

If copying takes place between objects that overlap, the objects take on unspecified values.

The \_fwcsrtombs\_s function is a data model independent form of the wcsrtombs\_s function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** 

The wcsrtombs\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also:

\_mbccmp, \_mbccpy, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbtowc, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcstombs\_s, wcstombs\_s, wctob, wctomb, wctomb\_s

**Example:** 

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdio.h>
#include <wchar.h>
#include <mbctype.h>
#include <errno.h>
const wchar_t wc[] = {
    0x0020,
    0x002e,
    0x0031,
    0x0041,
                /* double-byte space */
    0x3000,
                /* double-byte A */
    0xff21,
                /* double-byte Hiragana */
    0x3048,
                /* double-byte Katakana */
    0x30a3,
    0xff61,
                /* single-byte Katakana punctuation */
              /* single-byte Katakana punctuation *
/* single-byte Katakana alphabetic */
/* single-byte Katakana alphabetic */
/* double-byte Kanji */
    0xff66,
                /* single-byte Katakana alphabetic */
    0xff9f,
    0x720d,
                /* double-byte Kanji */
    0x0000
};
int main()
                    i;
    int
    size_t
                     retval;
    const wchar_t
                     *src;
                    mb[50];
    char
    mbstate_t
                    pstate;
    errno_t
                     rc;
    _setmbcp( 932 );
    src = wc;
    rc = wcsrtombs_s( &retval, mb, 50, &src, sizeof(wc), &pstate );
    if( rc != 0 ) {
        printf( "Error in wide character string\n" );
    } else {
         for( i = 0; i < retval; i++ ) {
             printf( "0x%2.2x\n", mb[i] );
    }
    return( rc );
}
```

produces the following:

```
0x20
           0x2e
           0x31
           0x41
           0x81
           0x40
           0x82
           0x60
           0x82
           0xa6
           0x83
           0x42
           0xa1
           0xa6
           0xdf
           0xe0
           0xa1
Classification: TR 24731
           _fwcsrtombs_s is WATCOM
Systems:
           wcsrtombs_s - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32,
           Linux, RDOS
           _fwcsrtombs_s - DOS, Windows, OS/2 1.x(all)
```

Safer C: The Safer C Library extension provides the wcstombs\_s function which is a safer alternative to wcstombs.

**Description:** The westombs function converts a sequence of wide character codes from the array pointed to by *pwcs* into a sequence of multibyte characters and stores them in the array pointed to by *s*. The westombs function stops if a multibyte character would exceed the limit of *n* total bytes, or if the null character is stored. At most *n* bytes of the array pointed to by *s* will be modified.

The \_fwcstombs function is a data model independent form of the wcstombs function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** If an invalid multibyte character is encountered, the wcstombs function returns (size\_t)-1. Otherwise, the wcstombs function returns the number of array elements modified, not including the terminating zero code if present.

See Also: wcstombs\_s, mblen, mbtowc, mbstowcs, mbstowcs\_s, wctomb, wctomb\_s

**Example:** #include <stdio.h> #include <stdlib.h> wchar\_t wbuffer[] = {  $0 \times 0073$ , 0x0074,  $0 \times 0072$ , 0x0069, 0x006e, 0x0067, 0x0000 } **;** void main() { mbsbuffer[50]; char int i, len;

len = wcstombs( mbsbuffer, wbuffer, 50 );

printf( "/%4.4x", wbuffer[i] );

printf( "%s(%d)\n", mbsbuffer, len );

for( i = 0; i < len; i++ )

mbsbuffer[len] =  $' \setminus 0';$ 

produces the following:

if ( len !=-1 )

printf( "\n" );

}

/0073/0074/0072/0069/006e/0067 string(6)

Classification: ISO C

Systems: wcstombs - All, Linux, RDOS, Netware

\_fwcstombs - DOS, Windows, OS/2 1.x(all)

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdlib.h>
errno_t wcstombs_s( size_t * restrict retval,
                   char * restrict dst,
                    rsize_t dstmax,
                    const wchar_t * restrict src,
                    rsize_t len);
errno_t _fwcstombs_s( size_t __far * restrict retval,
                      char __far * restrict dst,
                      rsize_t dstmax,
                      const wchar_t __far * restrict src,
                      rsize_t len);
```

Constraints: If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and wcstombs\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Neither retval nor src shall be a null pointer. If dst is not a null pointer, then neither len nor dstmax shall be greater than RSIZE\_MAX. If dst is a null pointer, then dstmax shall equal zero. If dst is not a null pointer, then dstmax shall not equal zero. If dst is not a null pointer and len is not less than dstmax, then the conversion shall have been stopped (see below) because a terminating null wide character was reached or because an encoding error occurred.

> If there is a runtime-constraint violation, then westombs\_s does the following. If retval is not a null pointer, then the wcstombs\_s sets \*retval to (size\_t)-1. If dst is not a null pointer and dstmax is greater than zero and less than RSIZE\_MAX, then wcstombs\_s sets dst[0] to the null character.

#### **Description:**

The wcstombs\_s function converts a sequence of wide characters from the array pointed to by src into a sequence of corresponding multibyte characters that begins in the initial shift state. If dst is not a null pointer, the converted characters are then stored into the array pointed to by dst. Conversion continues up to and including a terminating null wide character, which is also stored.

Conversion stops earlier in two cases:

when a wide character is reached that does not correspond to a valid multibyte character; (if dst is not a null pointer) when the next multibyte character would exceed the limit of n total bytes to be stored into the array pointed to by dst. If the wide character being converted is the null wide character, then n is the lesser of len or dstmax. Otherwise, n is the lesser of len or dstmax-1.

If the conversion stops without converting a null wide character and dst is not a null pointer, then a null character is stored into the array pointed to by dst immediately following any multibyte characters already stored. Each conversion takes place as if by a call to the wortomb function.

Regardless of whether dst is or is not a null pointer, if the input conversion encounters a wide character that does not correspond to a valid multibyte character, an encoding error occurs: the wcstombs\_s function stores the value (size\_t)-1 into \*retval. Otherwise, the wcstombs\_s function stores into \*retval the number of bytes in the resulting multibyte character sequence, not including the terminating null character (if any).

All elements following the terminating null character (if any) written by wcstombs\_s in the array of dstmax elements pointed to by dst take unspecified values when wcstombs\_s returns.

If copying takes place between objects that overlap, the objects take on unspecified values.

The \_fwcstombs\_s function is a data model independent form of the wcstombs\_s function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** The wcstombs\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

See Also: wcstombs, mblen, mbtowc, mbstowcs, mbstowcs\_s, wctomb, wctomb\_s

```
Example:
            #define __STDC_WANT_LIB_EXT1__ 1
            #include <stdio.h>
            #include <stdlib.h>
            wchar_t wbuffer[] = {
                0x0073,
                0 \times 0074,
                0x0072,
                0x0069,
                 0x006e,
                0x0067,
                0x0073,
                0x0074,
                0x0072,
                0 \times 0069,
                0x006e,
                0 \times 0067,
                0x0000
              };
            int main()
                         mbsbuffer[50];
                char
                int
                         i;
                size_t retval;
                errno_t rc;
                rc = wcstombs_s( &retval, mbsbuffer, 50, wbuffer, sizeof( wbuffer
             ) );
                if(rc == 0) {
                     for( i = 0; i < retval; i++ )</pre>
                         printf( "/%4.4x", wbuffer[i] );
                     printf( "\n" );
                     mbsbuffer[retval] = ' \setminus 0';
                     printf( "%s(%d)\n", mbsbuffer, retval );
                return( rc );
            produces the following:
            /0073/0074/0072/0069/006e/0067
            string(6)
```

#### Classification: TR 24731

\_fwcstombs\_s is WATCOM

Systems: wcstombs\_s - All, Linux, RDOS, Netware

\_fwcstombs\_s - DOS, Windows, OS/2 1.x(all)

```
Synopsis: #include <wchar.h>
    int wctob( wint_t wc );
```

**Description:** The wotob function determines whether *wc* corresponds to a member of the extended character set whose multibyte character representation is as a single-byte character when in the initial shift state.

**Returns:** The wotob function returns EOF if wc does not correspond to a multibyte character with length one; otherwise, it returns the single-byte character representation.

See Also: \_mbccmp, \_mbcicmp, \_mbcjistojms, \_mbcjmstojis, \_mbclen, \_mbctohira, \_mbctokata, \_mbctolower, \_mbctombb, \_mbctoupper, mblen, mbrlen, mbrtowc, mbsrtowcs, mbsrtowcs\_s, mbstowcs, mbstowcs\_s, mbstowcs\_s, mbstowcs, mbsinit, btowc, wcrtomb, wcrtomb\_s, wcsrtombs, wcsrtombs\_s, wcstombs, wcstombs\_s, wctomb, wctomb\_s

Example: #include <stdio.h>
#include <wchar.h>
#include <mbctype.h>

```
const wint_t wc[] = {
    0 \times 0020,
    0x002e,
    0x0031,
    0x0041,
    0x3000,
               /* double-byte space */
               /* double-byte A */
    0xff21,
    0x3048,
               /* double-byte Hiragana */
               /* double-byte Katakana */
    0x30a3,
               /* single-byte Katakana punctuation */
    0xff61,
               /* single-byte Katakana alphabetic */
    0xff66,
                /* single-byte Katakana alphabetic */
    0xff9f,
    0x720d,
                /* double-byte Kanji */
    0x0000
};
#define SIZE sizeof( wc ) / sizeof( wchar_t )
void main()
                i, j;
    int
    _setmbcp( 932 );
    for( i = 0; i < SIZE; i++ ) {
      j = wctob(wc[i]);
      if(j == EOF) {
        printf( "%#6.4x EOF\n", wc[i] );
      } else {
        printf( \%#6.4x->%#6.4x\n", wc[i], j);
    }
}
```

produces the following:

0x0020->0x0020 0x002e->0x002e 0x0031->0x0031 0x0041->0x0041 0x3000 EOF 0xff21 EOF 0x3048 EOF 0x30a3 EOF 0xff61->0x00a1 0xff66->0x00a6 0xff9f->0x00df 0x720d EOF 0000->0x0000

Classification: ISO C

Systems: DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS

**Synopsis:** 

```
#include <stdlib.h>
int wctomb( char *s, wchar_t wc );
#include <mbstring.h>
int _fwctomb( char __far *s, wchar_t wc );
```

Safer C:

The Safer C Library extension provides the wctomb\_s function which is a safer alternative to wctomb.

**Description:** 

The wotomb function determines the number of bytes required to represent the multibyte character corresponding to the wide character contained in wc. If s is not a NULL pointer, the multibyte character representation is stored in the array pointed to by s. At most MB\_CUR\_MAX characters will be stored.

The \_fwctomb function is a data model independent form of the wctomb function that accepts far pointer arguments. It is most useful in mixed memory model applications.

**Returns:** 

If s is a NULL pointer, the wetomb function returns zero if multibyte character encodings are not state dependent, and non-zero otherwise. If s is not a NULL pointer, the wotomb function returns:

#### Value Meaning

-1 if the value of wc does not correspond to a valid multibyte character

the number of bytes that comprise the multibyte character corresponding to the value of wc. len

See Also: wctomb\_s, mblen, mbstowcs, mbstowcs\_s, mbtowc, wcstombs, wcstombs\_s

**Example:** 

```
#include <stdio.h>
#include <stdlib.h>
wchar_t wchar = \{0x0073\};
char
     mbbuffer[2];
void main()
 {
    int len;
    printf( "Character encodings are %sstate dependent\n",
             ( wctomb( NULL, 0 ) )
            ? "" : "not " );
    len = wctomb( mbbuffer, wchar );
    mbbuffer[len] = ' \setminus 0';
    printf( %s(%d) \n, mbbuffer, len );
  }
```

produces the following:

Character encodings are not state dependent

**Classification:** ISO C

**Systems:** wctomb - All, Linux, RDOS, Netware

\_fwctomb - DOS, Windows, OS/2 1.x(all)

wctomb, _fwctomb			

#### **Synopsis:**

```
#define __STDC_WANT_LIB_EXT1__ 1
#include <stdlib.h>
errno_t wctomb_s( int * restrict status,
                  char * restrict s,
                  rsize_t smax,
                  wchar_t wc);
errno_t _fwctomb_s( int __far * restrict status,
                  char __far * restrict s,
                  rsize_t smax,
                  wchar_t wc);
```

**Constraints:** If any of the following runtime-constraints is violated, the currently active runtime-constraint handler will be invoked and wctomb\_s will return a non-zero value to indicate an error, or the runtime-constraint handler aborts the program.

> Let n denote the number of bytes needed to represent the multibyte character corresponding to the wide character given by wc (including any shift sequences).

If s is not a null pointer, then smax shall not be less than n, and smax shall not be greater than RSIZE\_MAX. If s is a null pointer, then smax shall equal zero.

If there is a runtime-constraint violation, wctomb\_s does not modify the int pointed to by status, and if s is not a null pointer, no more than smax elements in the array pointed to by s will be accessed.

#### **Description:**

The wctomb\_s function determines n and stores the multibyte character representation of wc in the array whose first element is pointed to by s (if s is not a null pointer). The number of characters stored never exceeds MB\_CUR\_MAX or smax. If wc is a null wide character, a null byte is stored, preceded by any shift sequence needed to restore the initial shift state, and the function is left in the initial conversion state.

The implementation shall behave as if no library function calls the wctomb\_s function.

If s is a null pointer, the wctomb\_s function stores into the int pointed to by status a nonzero or zero value, if multibyte character encodings, respectively, do or do not have state-dependent encodings.

If s is not a null pointer, the wctomb\_s function stores into the int pointed to by status either n or -1 if wc, respectively, does or does not correspond to a valid multibyte character.

In no case will the int pointed to by *status* be set to a value greater than the MB\_CUR\_MAX macro.

The \_fwctomb\_s function is a data model independent form of the wctomb\_s function that accepts far pointer arguments. It is most useful in mixed memory model applications.

#### **Returns:**

The wctomb\_s function returns zero if there was no runtime-constraint violation. Otherwise, a non-zero value is returned.

#### See Also:

wctomb, mblen, mbstowcs, mbstowcs\_s, mbtowc, wcstombs, wcstombs\_s

```
#define __STDC_WANT_LIB_EXT1__ 1
Example:
           #include <stdio.h>
           #include <stdlib.h>
           wchar_t wchar = \{0x0073\};
           char mbbuffer[3];
           int main()
               int
                        len;
               int
                      status;
               errno_t rc;
               rc = wctomb_s( &status, NULL, 0, wchar );
               printf( "Character encodings are %sstate dependent\n",
                        ( status ) ? "" : "not " );
               rc = wctomb_s( &len, mbbuffer, 2, wchar );
               if( rc != 0) {
                    printf( "Character encoding error\n");
               } else {
                   mbbuffer[len] = ' \setminus 0';
                    printf( "%s(%d)\n", mbbuffer, len );
               return( rc );
           }
           produces the following:
           Character encodings are not state dependent
           s(1)
Classification: TR 24731
           _fwctomb_s is WATCOM
Systems:
           wctomb_s - All, Linux, RDOS, Netware
           _fwctomb_s - DOS, Windows, OS/2 1.x(all)
```

Synopsis: #include <wctype.h>
 wctrans\_t wctrans( const char \*property );

**Description:** 

The wctrans function constructs a value with type wctrans\_t that describes a mapping between wide characters identified by the string argument *property*. The constructed value is affected by the LC\_CTYPE category of the current locale; the constructed value becomes indeterminate if the category's setting is changed.

The two strings listed below are valid in all locales as *property* arguments to the wctrans function.

Constant Meaning

#include <stdio.h>

tolower uppercase characters are mapped to lowercase

toupper lowercase characters are mapped to uppercase

**Returns:** 

If *property* identifies a valid class of wide characters according to the LC\_CTYPE category of the current locale, the wctrans function returns a non-zero value that is valid as the second argument to the towctrans function; otherwise, it returns zero.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint, iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype, wctype, towctrans

**Example:** 

```
#include <wctype.h>
char *translations[2] = {
    "tolower",
    "toupper"
};

void main( void )
{
    int     i;
    wint_t    wc = 'A';
    wint_t    twc;

    for( i = 0; i < 2; i++ ) {
        twc = towctrans( wc, wctrans( translations[i] ) );
        printf( "%s(%lc): %lc\n", translations[i], wc, twc );
    }
}</pre>
```

produces the following:

tolower(A): a
toupper(A): A

Classification: ISO C95

**Systems:** All, Linux, RDOS, Netware

wctrans			
			-

Synopsis: #include <wctype.h>

wctype\_t wctype( const char \*property );

**Description:** 

The wctype function constructs a value with type wctype\_t that describes a class of wide characters identified by the string argument, *property*. The constructed value is affected by the LC\_CTYPE category of the current locale; the constructed value becomes indeterminate if the category's setting is changed.

The twelve strings listed below are valid in all locales as *property* arguments to the wctype function.

Constant	Meaning
alnum	any wide character for which one of iswalpha or iswdigit is true
alpha	any wide character for which iswupper or iswlower is true, that is, for any wide character that is one of an implementation-defined set for which none of iswcntrl, iswdigit, iswpunct, or iswspace is true
blank	any wide character corresponding to a standard blank character (space or horizontal tab) or is one of an implementation-defined set of wide characters for which iswblank is true
cntrl	any control wide character
digit	any wide character corresponding to a decimal-digit character
graph	any printable wide character except a space wide character
lower	any wide character corresponding to a lowercase letter, or one of an implementation-defined set of wide characters for which none of iswcntrl, iswdigit, iswpunct, or iswspace is true
print	any printable wide character including a space wide character
punct	any printable wide character that is not a space wide character or a wide character for which iswalnum is true
space	any wide character corresponding to a standard white-space character or is one of an implementation-defined set of wide characters for which <code>iswalnum</code> is false
upper	any wide character corresponding to a uppercase letter, or if c is one of an implementation-defined set of wide characters for which none of iswcntrl, iswdigit, iswpunct, or iswspace is true
xdigit	any wide character corresponding to a hexadecimal digit character
If <i>property</i> identi	ifies a valid class of wide characters according to the LC_CTYPE category of the

**Returns:** 

If *property* identifies a valid class of wide characters according to the LC\_CTYPE category of the current locale, the wctype function returns a non-zero value that is valid as the second argument to the iswctype function; otherwise, it returns zero.

See Also:

isalnum, isalpha, isblank, iscntrl, isdigit, isgraph, islower, isprint, ispunct, isspace, isupper, isxdigit, tolower, toupper, isleadbyte, iswalnum, iswalpha, iswblank, iswcntrl, iswdigit, iswgraph, iswlower, iswprint,

```
iswpunct, iswspace, iswupper, iswxdigit, towlower, towupper, iswctype,
            wctrans, towctrans
Example:
            #include <stdio.h>
            #include <wchar.h>
            char *types[] = {
                "alnum",
                "blank",
                "alpha",
                "cntrl",
                "digit",
                "graph",
                "lower",
                "print",
                "punct",
                "space",
                "upper",
                "xdigit"
            } ;
            void main( void )
                int
                         i;
                wint_t wc = 'A';
                for( i = 0; i < 12; i++ )
                     if( iswctype( wc, wctype( types[i] ) ) )
                         printf( "%s\n", types[i] );
            }
            produces the following:
            alnum
            alpha
            graph
           print
           upper
            xdigit
Classification: ISO C95
Systems:
            All, Linux, RDOS
```

**Description:** The \_wrapon function is used to control the display of text when the text output reaches the right side

of the text window. This is text displayed with the \_outtext and \_outmem functions. The wrap

argument can take one of the following values:

**\_GWRAPON** causes lines to wrap at the window border

**\_GWRAPOFF** causes lines to be truncated at the window border

**Returns:** The \_wrapon function returns the previous setting for wrapping.

for( $i = 4; i \le 6; ++i$ ) {

\_setvideomode( \_DEFAULTMODE );

\_outtext( buf );

\_settextposition(2 \* i, 1);

sprintf( buf, "Very very long line %d", i );

See Also: \_outtext, \_outmem, \_settextwindow

#include <stdio.h>

getch();

Example: #include <conio.h>
#include <graph.h>

main()
{
 int i;
 char buf[ 80 ];

 \_setvideomode( \_TEXTC80 );
 \_settextwindow( 5, 20, 20, 30 );
 \_wrapon( \_GWRAPOFF );
 for( i = 1; i <= 3; ++i ) {
 \_settextposition( 2 \* i, 1 );
 sprintf( buf, "Very very long line %d", i );
 \_outtext( buf );
 }
 \_wrapon( \_GWRAPON );</pre>

Classification: PC Graphics

Systems: DOS

_wrapon			

#### **Synopsis:**

#### **Description:**

The write function writes data at the operating system level. The number of bytes transmitted is given by *len* and the data to be transmitted is located at the address specified by *buffer*.

The writev function performs the same action as write, but gathers the output data from the iovent buffers specified by the members of the iov array: iov[0], iov[1], ..., iov[iovent-1].

The \_write function is identical to write. Use \_write for ANSI naming conventions.

The *handle* value is returned by the open function. The access mode must have included either O\_WRONLY or O\_RDWR when the open function was invoked.

The data is written to the file at the end when the file was opened with O\_APPEND included as part of the access mode; otherwise, it is written at the current file position for the file in question. This file position can be determined with the \_tell function and can be set with the lseek function.

When O\_BINARY is included in the access mode, the data is transmitted unchanged. When O\_TEXT is included in the access mode, the data is transmitted with extra carriage return characters inserted before each linefeed character encountered in the original data.

A file can be truncated under DOS and OS/2 2.0 by specifying 0 as the *len* argument. **Note**, however, that this doesn't work under OS/2 2.1, Windows NT/2000, and other operating systems. To truncate a file in a portable manner, use the \_chsize function.

#### **Returns:**

The write function returns the number of bytes (does not include any extra carriage-return characters transmitted) of data transmitted to the file. When there is no error, this is the number given by the *len* argument. In the case of an error, such as there being no space available to contain the file data, the return value will be less than the number of bytes transmitted. A value of -1 may be returned in the case of some output errors. When an error has occurred, errno contains a value indicating the type of error that has been detected.

#### See Also:

\_chsize, close, creat, dup, dup2, \_eof, exec..., fdopen, \_filelength, fileno, fstat, \_grow\_handles, isatty, lseek, open, read, \_setmode, \_sopen, stat, \_tell, umask

#### **Example:**

```
/* open a file for output
                 /* replace existing file if it exists */
                handle = open( "file",

O_WRONLY | O_CREAT | O_TRUNC | O_TEXT,

S_IRUSR | S_IWUSR | S_IRGRP | S_IWGRP );
                 if (handle !=-1) {
                     /* write the text
                     size_written = write( handle, buffer,
                                              sizeof( buffer ) );
                      /* test for error
                     if( size_written != sizeof( buffer ) ) {
                          printf( "Error writing file\n" );
                      }
                     /* close the file
                                                                 */
                     close( handle );
Classification: POSIX 1003.1
            _write conforms to ANSI naming conventions
            writev is WATCOM
Systems:
            write - All, Linux, RDOS, Netware
            _write - DOS, Windows, Win386, Win32, OS/2 1.x(all), OS/2-32, RDOS
            writev - Linux, Netware
```

# 5 Re-entrant Functions

The following functions in the C library are re-entrant:

abs bsearch_s	atoi div	atol fabs	bsearch _fmbsrtowcs_s
_fmbstowcs_s	_fmemccpy	_fmemchr	_fmemcmp
_fmemcpy	_fmemicmp	_fmemmove	_fmemset
_fstrcat	_fstrchr	_fstrcmp	_fstrcpy
_fstrcspn	_fstricmp	_fstrlen	_fstrlwr
_fstrncat	_fstrncmp	_fstrncpy	_fstrnicmp
_fstrnset	_fstrpbrk	_fstrrchr	_fstrrev
_fstrset	_fstrspn	_fstrstr	_fstrupr
_fwcrtombs_s	_fwcsrtombs_s	_fwcstombs_s	_fwctomb_s
isalnum	isalpha	isascii	isblank
iscntrl	isdigit	isgraph	islower
isprint	ispunct	isspace	isupper
isxdigit	itoa	labs	ldiv
lfind	longjmp	_lrotl	_lrotr
lsearch	ltoa	_makepath	mblen
mbsrtowcs_s	mbstowcs	mbstowcs_s	mbtowc
memccpy	memchr	memcmp	memcpy
memcpy_s	_memicmp	memmove	memmove_s
memset	movedata	qsort	qsort_s
_rotl	_rotr	segread	setjmp
_splitpath	strcat	strcat_s	strchr
strcmp	strcoll	strcpy	strcpy_s
strcspn	strerror_s	strerrorlen_s	_stricmp
strlen	_strlwr	strncat	strncat_s
strncmp	strncpy	strncpy_s	_strnicmp
strnlen_s	_strnset	strpbrk	strrchr
_strrev	_strset	strspn	strstr
strtok_s	_strupr	swab	tolower
toupper	ultoa	utoa	wcrtombs_s
wcscat_s	wcscpy_s	_wcserror_s	_wcserrorlen_s
wcsncat_s	wcsncat_s	wcsncpy_s	wcsnlen_s
wcsrtombs_s	wcstok_s	wcstombs	wcstombs_s
wctomb	wctomb_s	wmemcpy_s	wmemmove_s

# **Appendices**

# A. Implementation-Defined Behavior of the C Library

This appendix describes the behavior of the 16-bit and 32-bit Open Watcom C libraries when the ISO/ANSI C Language standard describes the behavior as *implementation-defined*. The term describing each behavior is taken directly from the ISO/ANSI C Language standard. The numbers in parentheses at the end of each term refers to the section of the standard that discusses the behavior.

### A.1 NULL Macro

The null pointer constant to which the macro NULL expands (7.1.6).

The macro NULL expands to 0 in small data models and to 0L in large data models.

# A.2 Diagnostic Printed by the assert Function

The diagnostic printed by and the termination behavior of the assert function (7.2).

The assert function prints a diagnostic message to stderr and calls the abort routine if the expression is false. The diagnostic message has the following form:

Assertion failed: [expression], file [name], line [number]

# A.3 Character Testing

The sets of characters tested for by the isalnum, isalpha, iscntrl, islower, isprint, and isupper functions (7.3.1).

Function	Characters Tested For		
isalnum	Characters 0-9, A-Z, a-z		
isalpha	Characters A-Z, a-z		
iscntrl	ASCII 0x00-0x1f, 0x7f		
islower	Characters a-z		
isprint	ASCII 0x20-0x7e		
isupper	Characters A-Z		

### A.4 Domain Errors

The values returned by the mathematics functions on domain errors (7.5.1).

When a domain error occurs, the listed values are returned by the following functions:

Function	Value returned
acos	0.0
acosh	- HUGE_VAL
asin	0.0
atan2	0.0
atanh	- HUGE_VAL
log	- HUGE_VAL
log10	- HUGE_VAL
log2	- HUGE_VAL
pow(neg,frac)	0.0
pow(0.0,0.0)	1.0
pow(0.0,neg)	- HUGE_VAL
sqrt	0.0
y <b>0</b>	- HUGE_VAL
y1	- HUGE_VAL
yn	- HUGE_VAL

# A.5 Underflow of Floating-Point Values

Whether the mathematics functions set the integer expression errno to the value of the macro ERANGE on underflow range errors (7.5.1).

The integer expression errno is not set to ERANGE on underflow range errors in the mathematics functions.

### A.6 The fmod Function

Whether a domain error occurs or zero is returned when the fmod function has a second argument of zero (7.5.6.4).

Zero is returned when the second argument to fmod is zero.

### A.7 The signal Function

The set of signals for the signal function (7.7.1.1).

See the description of the signal function presented earlier in this book.

The semantics for each signal recognized by the signal function (7.7.1.1).

See the description of the signal function presented earlier in this book.

The default handling and the handling at program startup for each signal recognized by the signal function (7.7.1.1).

See the description of the signal function presented earlier in this book.

### A.8 Default Signals

If the equivalent of  $signal(sig, SIG_DFL)$  is not executed prior to the call of a signal handler, the blocking of the signal that is performed (7.7.1.1).

```
The equivalent of signal (sig, SIG_DFL);
```

is executed prior to the call of a signal handler.

# A.9 The SIGILL Signal

Whether the default handling is reset if the SIGILL signal is received by a handler specified to the signal function (7.7.1.1).

```
The equivalent of signal ( SIGILL, SIG_DFL );
```

is executed prior to the call of the signal handler.

# A.10 Terminating Newline Characters

Whether the last line of a text stream requires a terminating new-line character (7.9.2).

The last line of a text stream does not require a terminating new-line character.

### A.11 Space Characters

Whether space characters that are written out to a text stream immediately before a new-line character appear when read in (7.9.2).

All characters written out to a text stream will appear when read in.

#### A.12 Null Characters

The number of null characters that may be appended to data written to a binary stream (7.9.2).

No null characters are appended to data written to a binary stream.

### A.13 File Position in Append Mode

Whether the file position indicator of an append mode stream is initially positioned at the beginning or end of the file (7.9.3).

When a file is open in append mode, the file position indicator initially points to the end of the file.

#### A.14 Truncation of Text Files

Whether a write on a text stream causes the associated file to be truncated beyond that point (7.9.3).

Writing to a text stream does not truncate the file beyond that point.

# A.15 File Buffering

The characteristics of file buffering (7.9.3).

Disk files accessed through the standard I/O functions are fully buffered. The default buffer size is 512 bytes for 16-bit systems, and 4096 bytes for 32-bit systems.

# A.16 Zero-Length Files

Whether a zero-length file actually exists (7.9.3).

A file with length zero can exist.

### A.17 File Names

The rules of composing valid file names (7.9.3).

A valid file specification consists of an optional drive letter (which is always followed by a colon), a series of optional directory names separated by backslashes, and a file name.

FAT File System: Directory names and file names can contain up to eight characters followed optionally by a period and a three letter extension. The complete path (including drive, directories and file name) cannot exceed 143 characters. Case is ignored (lowercase letters are converted to uppercase letters).

*HPFS File System:* Directory names and file names can contain up to 254 characters in the OS/2 High Performance File System (HPFS). However, the complete path (including drive, directories and file name)

cannot exceed 259 characters. The period is a valid file name character and can appear in a file name or directory name as many times as required; HPFS file names do not require file extensions as in the FAT file system. The HPFS preserves case in file names only in directory listings but ignores case in file searches and other system operations (i.e, a directory cannot have more than one file whose names differ only in case).

### A.18 File Access Limits

Whether the same file can be open multiple times (7.9.3).

It is possible to open a file multiple times.

# A.19 Deleting Open Files

The effect of the remove function on an open file (7.9.4.1).

The remove function deletes a file, even if the file is open.

### A.20 Renaming with a Name that Exists

The effect if a file with the new name exists prior to a call to the rename function (7.9.4.2).

The rename function will fail if you attempt to rename a file using a name that exists.

### A.21 Printing Pointer Values

The output for %p conversion in the fprintf function (7.9.6.1).

Two types of pointers are supported: near pointers (%hp), and far pointers (%lp). The output for %p depends on the memory model being used.

In 16-bit mode, the fprintf function produces hexadecimal values of the form XXXX for 16-bit near pointers, and XXXX:XXXX (segment and offset separated by a colon) for 32-bit far pointers.

In 32-bit mode, the fprintf function produces hexadecimal values of the form XXXXXXXX for 32-bit near pointers, and XXXX:XXXXXXXX (segment and offset separated by a colon) for 48-bit far pointers.

### A.22 Reading Pointer Values

The input for \*p conversion in the fscanf function (7.9.6.2).

The fscanf function converts hexadecimal values into the correct address when the %p format specifier is used.

# A.23 Reading Ranges

The interpretation of a – character that is neither the first nor the last character in the scanlist for %[ conversion in the fscanf function (7.9.6.2).

The "-" character indicates a character range. The character prior to the "-" is the first character in the range. The character following the "-" is the last character in the range.

### A.24 File Position Errors

The value to which the macro errno is set by the fgetpos or ftell function on failure (7.9.9.1, 7.9.9.4).

When the function fgetpos or ftell fails, they set errno to EBADF if the file number is bad. The constants are defined in the <errno.h> header file.

# A.25 Messages Generated by the perror Function

The messages generated by the perror function (7.9.10.4).

The perror function generates the following messages.

Error	Message
0	"Error 0"
1	"No such file or directory"
2	"Argument list too big"
3	"Exec format error"
4	"Bad file number"
5	"Not enough memory"
6	"Permission denied"
7	"File exists"
8	"Cross-device link"
9	"Invalid argument"
10	"File table overflow"
11	"Too many open files"
12	"No space left on device"
13	"Argument too large"
14	"Result too large"
15	"Resource deadlock would occur"

### A.26 Allocating Zero Memory

The behavior of the calloc, malloc, or realloc function if the size requested is zero (7.10.3).

The value returned will be NULL. No actual memory is allocated.

#### A.27 The abort Function

The behavior of the abort function with regard to open and temporary files (7.10.4.1).

The abort function does not close any files that are open or temporary, nor does it flush any output buffers.

### A.28 The atexit Function

The status returned by the exit function if the value of the argument is other than zero, EXIT\_SUCCESS, or EXIT\_FAILURE (7.10.4.3).

The exit function returns the value of its argument to the operating system regardless of its value.

### A.29 Environment Names

The set of environment names and the method for altering the environment list used by the getenv function (7.10.4.4).

The set of environment names is unlimited. Environment variables can be set from the DOS command line using the SET command. A program can modify its environment variables with the puterv function. Such modifications last only until the program terminates.

# A.30 The system Function

The contents and mode of execution of the string by the system function (7.10.4.5).

The system function executes an internal DOS, Windows, or OS/2 command, or an EXE, COM, BAT or CMD file from within a C program rather than from the command line. The system function examines the COMSPEC environment variable to find the command interpreter and passes the argument string to the command interpreter.

### A.31 The strerror Function

The contents of the error message strings returned by the strerror function (7.11.6.2).

The strerror function generates the following messages.

Error	Message
0	"Error 0"
1	"No such file or directory"
2	"Argument list too big"
3	"Exec format error"

4	"Bad file number"
5	"Not enough memory"
6	"Permission denied"
7	"File exists"
8	"Cross-device link"
9	"Invalid argument"
10	"File table overflow"
11	"Too many open files"
12	"No space left on device"
13	"Argument too large"
14	"Result too large"
15	"Resource deadlock would occur"

### A.32 The Time Zone

The local time zone and Daylight Saving Time (7.12.1).

The default time zone is "Eastern Standard Time" (EST), and the corresponding daylight saving time zone is "Eastern Daylight Saving Time" (EDT).

### A.33 The clock Function

The era for the clock function (7.12.2.1).

The clock function's era begins with a value of 0 when the program starts to execute.

	acosh 67, 1412
0	actime 1327
8	AF_INET 417-418, 420, 427
	AF_INET6 417, 427
	alloca 68
2006 International	AM_STR 888
8086 Interrupts	_amblksiz 35, 1034
_chain_intr 130	_ANALOGCOLOR 467
_dos_getvect 211	_ANALOGMONO 467
_dos_setvect 228	_arc <b>69</b> , 48, 385, 396, 966
int386 516	
int386x 517	_arc_w 69
int86 519	_arc_wxy <b>69</b>
int86x 520	_argc 35
intr 526	_argv 35
intrf 528	asctime <b>72</b> , 72, 169
	asctime Functions <b>70</b>
	_asctime <b>72</b> , 72
	asctime_s <b>74</b> , 72
A	asin 77, 1412
<i>n</i>	asinh 78
	assert <b>79</b> , 31, 1411
	assert.h 31
_A_ARCH 198, 206, 222	atan <b>80</b>
_A_HIDDEN 191, 193, 197-198, 206, 222	atan2 <b>81</b> , 1412
_A_NORMAL 191, 193, 197-198, 206, 222	atanh <b>82</b> , 1412
_A_RDONLY 191, 193, 197-198, 206, 222	atexit <b>83</b> , 264, 266, 895
_A_SUBDIR 198, 206, 222	atof <b>84</b>
	atoi 85
_A_SYSTEM 191, 193, 197-198, 206, 222	
_A_VOLID 197-198, 206, 222	atol <b>86</b>
ABDAY_1 889	atoll 87
ABDAY_2 889	_atouni 88
ABDAY_3 889	
ABDAY_4 889	
ABDAY_5 889	
ABDAY_6 889	<i>B</i>
ABDAY_7 889	
ABMON_1 890	
ABMON_10 891	
ABMON_11 891	_BASE 1106
ABMON_12 891	basename 89
ABMON_2 890	_bcalloc <b>125</b> , 14, 103, 125
ABMON_3 890	bcmp <b>97</b>
ABMON_4 891	bcopy 98
ABMON_5 891	bdos <b>91</b> , 56
ABMON_6 891	_beginthread <b>92</b> , 253
	_beginthreadex <b>92</b> , 92-93, 253
ABMON_7 891	Bessel Functions <b>95</b> , 16-17
ABMON_8 891	_bexpand <b>270</b> , 103, 270
ABMON_9 891	_bfree <b>351</b> , 14, 351
abort <b>61</b> , 1134, 1411, 1417	_bfreeseg 99
abort_handler_s 62	_bgetcmd 101
abs <b>63</b>	_bheapchk <b>491</b> , 491
access 64	-
_access 64	_bheapmin <b>496</b> , 496
acos <b>66.</b> 1412	_bheapseg <b>103</b> , 99

acos 66, 1412

_bheapset <b>498</b> , 498	_CENTER 1106
_bheapshrink <b>500</b> , 500	CGA 1123
_bheapwalk <b>502</b> , 502	_CGA 466
binary files 36	cgets 129
BINMODE.OBJ 36, 328, 332	_chain_intr 130
BIOS classification 58	CHAR_MAX 642
BIOS Functions 26	Character Manipulation Functions 5-6
_bios_disk 105	isalnum 530
_bios_equiplist 107	isalpha 531
_bios_keybrd 108	isascii 532
_bios_memsize 110	isascii 532
_bios_printer 111	isblank 535
bios_serialcom 112	isentrl 537
_bios_timeofday 114	iscsym 539
bios.h 31	iscsym 539
_bios_disk 105	iscsymf 541
_bios_equiplist 107	_iscsymf 541
_bios_keybrd 108	isdigit 543
_bios_memsize 110	isgraph 546
_bios_printer 111	isleadbyte 549
_bios_serialcom 112	islower 551
_bios_timeofday 114	isprint 615
_bmalloc <b>677</b> , 14, 103, 677	ispunct 617
_bmsize <b>878</b> , 878	isspace 619
bool 33	isupper 621
	iswalnum 530
_BOTTOM 1106	
_bprintf 115, 1337	iswalpha 531
BREAK 1135	iswascii 532
break Functions 115	iswblank 535
break_off <b>116</b> , 116	iswentrl 537
break_on 116, 116	iswcsym 539
_brealloc <b>1014</b> , 14, 103, 1014-1015	iswcsymf 541
brk 117	iswetype 623
bsearch 118	iswdigit 543
bsearch_s <b>120</b> , 118	iswgraph 546
btom 745	iswlower 551
btowc 122	iswprint 615
bufferram 1278	iswpunct 617
BUFSIZ 1071	iswspace 619
_bwprintf 115	iswupper 621
bzero 123	iswxdigit 625
	isxdigit 625
	_mbctohira 702
	_mbctokata 704
<b>C</b>	_mbctolower 698
	_mbctoupper 700
	tolower 1303
ashs 124	_tolower 1303
cabs 124	toupper 1305
calloc 125, 14, 125, 351, 878, 1416	_toupper 1305
calloc Functions 124	towlower 1303
_CAP 1106	towupper 1305
cbrt 127	wctype 1401
ceil <b>128</b> , 1309	chdir 132

_chdir 132	_fmbsnbcmp 735
_chdrive 134	_fmbsnbicmp 739
chkctype 683	_fmemcmp 776
chmod 135	_fmemicmp 782
_chmod 135	_fstrcmp 1187
chsize 137	_fstricmp 1208
_chsize <b>137</b> , 137, 664, 1405	_fstrncmp 1224
classes of functions 46	_fstrnicmp 1232
_clear87 <b>139</b>	_mbsnbcmp 735
cleareny 140	_mbsnbicmp 739
clearerr 141	memcmp 776
_clearscreen <b>142</b> , 1053	memicmp 782
clock <b>143</b> , 1418	_memicmp 782
clock_getres 145	strcasecmp 1180
clock_gettime 146	strcmp 1187
clock_nanosleep 147	strcmpi 1189
clock_settime 148	strcoll 1190
CLOCKS_PER_SEC 143	stricmp 1208
clone <b>149</b>	_stricmp 1208
CLONE_CHILD_CLEARTID 149	_stricoll 1210
CLONE_CHILD_SETTID 150	strncasecmp 1219
CLONE_FILES 149	strncmp 1224
CLONE_FS 149	_strncoll 1226
CLONE_IO 150	strnicmp 1232
CLONE_NEWIPC 150	_strnicmp 1232
CLONE_NEWNET 150	_strnicoll 1234
CLONE_NEWNS 149	strxfrm 1273
CLONE_NEWPID 150	wcscmp 1187
CLONE_NEWUSER 150	wcscmpi 1189
CLONE_NEWUTS 150	wescoll 1190
CLONE_PARENT 149	_wcsicmp 1208
CLONE_PARENT_SETTID 149	_wcsicoll 1210
CLONE_PTRACE 149	wesnemp 1224
CLONE_SETTLS 149	_wcsncoll 1226
CLONE_SIGHAND 149	_wcsnicmp 1232
CLONE_SYSVSEM 149	_wcsnicoll 1234
CLONE_THREAD 149	wmemcmp 776
CLONE_UNTRACED 150	complex 33
CLONE_VFORK 149	COMSPEC 140, 1280, 1417
CLONE_VM 149	CON 54
close <b>151</b> , 433, 906	Concatenation Functions
_close 151	_fmbsnbcat 733
closedir <b>152</b> , 901-902, 1008	_fstrcat 1181
_cmdname 154	_fstrncat 1220
CODESET 888	_mbsnbcat 733
_COLOR 467	strcat 1181
_COM_INIT 112	strcat_s 1183
COM_RECEIVE 112	strlcat 1212
_COM_SEND 112	strncat 1220
_COM_STATUS 112	strncat_s 1222
_commit 155	wescat 1181
COMMODE.OBJ 329, 332	wcscat_s 1183
Comparison Functions	wesleat 1212
bcmp 97	wesneat 1220
_	

wcsncat_s 1222	towupper 1305
conio.h 31	ulltoa 1313
Console I/O 26, 31	ulltoa 1313
cgets 129	_ulltow 1313
cprintf 163	ultoa 1315
cputs 164	_ultoa 1315
cscanf 168	_ultow 1315
getche 392	utoa 1329
kbhit 629	_utoa 1329
_kbhit 629	wested 1252
putch 989	westoimax 1263
stdin 18	westell 1259
stdout 18	westell 1261
ungetch 1321	weston 1267 westoul 1265
veprintf 1339	westoul 1265 westoull 1267
vescanf 1341	westoum 1267 westoumax 1269
const 57	westouriax 1209 wetrans 1399
control87 <b>156</b>	_weevt 242
_controlfp 158	wfcvt 275
Conversion Functions 13	_wgcvt 381
atof 84	wstrdate 1197
atoi 85	_wstrtime 1251
atol 86	_wstrinie 1231 _wtof 84
atol 87	_wtoi 85
ecvt 242	<del>_</del>
	_wtol 86
_ecvt 242	_wtoll 87
fevt 275	coordinate systems 47
_fcvt 275	Coordinated Universal Time 39-40, 42
gevt 381	Copying Functions
_gcvt 381	bcopy 98
itoa 627	_fmbsnbcpy 737
_itoa 627	_fmemcpy 778
_itow 627	_fmemmove 785
lltoa 667	_fstrcpy 1191
_lltoa 667	_fstrdup 1198
_lltow 667	C-4 1000
<del>-</del>	_fstrncpy 1228
ltoa 669	_mbsnbcpy 737
ltoa 669 _ltoa 669	_mbsnbcpy 737 memcpy 778
ltoa 669 _ltoa 669 _ltow 669	_mbsnbcpy 737 memcpy 778 memcpy_s 780
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267 strtoumax 1269	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213 strncpy 1228
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267 strtoumax 1269 tolower 1303	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213 strncpy 1228 strncpy_s 1230
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267 strtoumax 1269 tolower 1303 _tolower 1303	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213 strncpy 1228 strncpy_s 1230 wcscpy 1191
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267 strtoumax 1269 tolower 1303 _tolower 1305	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213 strncpy 1228 strncpy_s 1230 wcscpy_s 1191 wcscpy_s 1193
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267 strtoumax 1269 tolower 1303 _tolower 1305 _toupper 1305	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213 strncpy 1228 strncpy_s 1230 wcscpy 1191 wcscpy_s 1193 wcsdup 1198
ltoa 669 _ltoa 669 _ltow 669 _strdate 1197 _strtime 1251 strtod 1252 strtoimax 1263 strtol 1259 strtoll 1261 strtoul 1265 strtoull 1267 strtoumax 1269 tolower 1303 _tolower 1305	_mbsnbcpy 737 memcpy 778 memcpy_s 780 memmove 785 memmove_s 787 movedata 808 strcpy 1191 strcpy_s 1193 strdup 1198 _strdup 1198 strlcpy 1213 strncpy 1228 strncpy_s 1230 wcscpy_s 1191 wcscpy_s 1193

wesnepy 1228	errno.h 32
wcsncpy_s 1230	fcntl.h 32
wmemcpy 778	fenv.h 32
wmemcpy_s 780	float.h 32
wmemmove 785	fltused_ 35
wmemmove_s 787	_fmode 35
copysign 160	fnmatch.h 32
cos <b>161</b>	graph.h 32
cosh 162	i86.h 32
cprintf <b>163</b> , 1339	inttypes.h 32
CPUID 789	io.h 32
cputs 164	limits.h 32
creat <b>165</b> , 36, 151, 278, 664, 1317	locale.h 32
_creat <b>165</b>	malloc.h 32
CREATE_SUSPENDED 93	math.h 33
cscanf <b>168</b> , 1341	MaxThreads 36
ctime <b>169</b> , 41, 72	minreal 36
ctime Functions 168	mmintrin.h 33
_ctime 169, 41, 169	optarg 36
ctime_s <b>171</b> , 169	opterr 36
ctype.h 31	optind 36
• •	<u>*</u>
currency_symbol 641-642	optopt 36 _osbuild 37
current directory 132	<del>-</del>
current drive 132	_osmajor 37
current working directory 132	_osminor 37
cwait <b>173</b> , 1153, 1155, 1372	_osmode 37
_cwait 173	_osver 37
	process.h 33
	_psp 37
	search.h 33
D	setjmp.h 33
	share.h 33
	signal.h 33
d_attr 901, 1008	_stacksize_37
d_date 901, 1008	stdarg.h 33
D_FMT 888	stdaux 37
D_T_FMT 888	stdbool.h 33
d_time 901, 1008	stddef.h 33
data	stderr 38
_amblksiz 35	stdin 38
_argc 35	stdint.h 33
<u> </u>	stdio.h 33
_argv 35	stdlib.h 34
assert.h 31 bios.h 31	stdout 38
	stdprn 38
conio.h 31	string.h 34
ctype.h 31	sys/locking.h 34
daylight 35	sys/stat.h 34
direct.h 31	sys/timeb.h 34
dos.h 31	sys/types.h 34
_doserrno 35	sys/utime.h 35
env.h 32	sys_errlist 38
environ 35	sys_nerr 38
errno 35	_threadid 38

time.h 34	_wopendir 901
timezone 38	_wpopen 977
tzname 38	_wreaddir 1008
varargs.h 34	_wrewinddir 1027
wargc 38	_wrmdir 1030
wargv 38	dirent 901, 1008
wchar.h 34	dirname 180
wctype.h 34	_disable <b>181</b> , 246
_wenviron 39	_DISK_FORMAT 105
win_alloc_flags 39	_DISK_READ 105
win_realloc_flags 39	_DISK_RESET 105
win_reanoc_nags 37 _winmajor 39	_DISK_STATUS 105
_winminor 39	_DISK_VERIFY 105
_winver 39	
	_DISK_WRITE 105
DAY_1 888	diskfree_t 203, 402
DAY_2 888	diskinfo_t 105
DAY_3 888	_displayeursor 183
DAY_4 888	div <b>184</b>
DAY_5 889	div_t 184
DAY_6 889	_dmsbintoieee 185
DAY_7 889	DOMAIN 679, 1092
daylight 35, 40, 1311	DOS
default drive 132	Program Segment Prefix 37
Default Windowing Functions 26	PSP 37
DEFAULTMODE 1123	DOS classification 58
delay 176	DOS command
devices 53	CHDIR (CD) 54
_dieeetomsbin 177	date 39, 169, 476, 645, 1289, 1311
difftime 179	PATH 260, 1154
DIR 31	SET 40, 260, 406, 408, 992, 1078, 1155
direct.h 31	time 39, 169, 476, 645, 1289, 1311
directory 53	DOS commands 56
Directory Functions 24	DOS considerations 53
_bgetcmd 101	DOS devices 53
chdir 132	DOS directory 53
_chdir 132	DOS file 55
closedir 152	DOS Functions 27
getcmd 394	_chdrive 134
getcwd 397	chsize 137
_getdcwd 399	_chsize 137
mkdir 794	delay 176
_mkdir 794	_dos_allocmem 187
opendir 901	_dos_close 189
popen 975	_dos_creat 191
_popen 977	_dos_creatnew 193
readdir 1008	_dos_findclose 197
rewinddir 1027	_dos_findfirst 197
rmdir 1030	_dos_findnext 197
_rmdir 1030	_dos_freemem 200
wchdir 132	_dos_getdate 202
_wclosedir 152	•
	_dos_getdiskfree 203
_wgetcwd 397	_dos_getdrive_205
_wgetdcwd 399 wmkdir 794	_dos_getfileattr 206
WHIKAIT /94	gos genume zux

_dos_gettime 210	_isatty 534
_dos_open 214	lock 649
_dos_read 216	locking 651
_dos_setblock 217	_locking 651
_dos_setdate 219	lseek 664
_dos_setdrive 221	_lseek 664
_dos_setfileattr 222	_lseeki64 664
_dos_setftime 224	open 897
_dos_settime 226	_open 897
_dos_write 230	read 1006
_findclose 309	_read 1006
_findfirst 310	readlink 1012
_findfirsti64 310	readv 1006
_findnext 313	setmode 1095
_getdiskfree 402	_setmode 1095
_getdrive 404	sopen 1147
nosound 893	_sopen 1147
sleep 1140	_tell 1284
sound 1151	_telli64 1284
swab 1275	umask 1317
_wdos_findclose 197	_umask 1317
_wdos_findfirst 197	unlock 1323
_wdos_findnext 197	utime 1327
_wfindfirst 310	_utime 1327
_wfindfirsti64 310	_wcreat 165
_wfindnext 313	_wopen 897
_wfindnexti64 313	write 1405
DOS I/O Functions 24	_write 1405
close 151	writev 1405
_close 151	_wsopen 1147
creat 165	_wutime 1327
_creat 165	DOS Interrupts 56
_dos_close 189	bdos 91
_dos_creat 191	intdos 522
_dos_creatnew 193	intdosx 524
_dos_open 214	DOS LFN aware Functions 30
_dos_read 216	DOS path 53
_dos_write 230	dos.h 31
dup 231	_dos_allocmem <b>187</b> , 200, 217
dup2 233	_dos_close <b>189</b>
_dup2 233	_dos_commit <b>190</b>
_dup 231	_dos_creat 191
eof 255	_dos_creatnew 193
_eof 255	_dos_find Functions 196
_fdopen 278	_dos_find 198
filelength 305	dos_findclose <b>197</b> , 198
_filelength 305	dos_findfirst <b>197</b> , 197-198
_filelengthi64 305	_dos_findnext <b>197</b> , 198
fileno 308	_dos_freemem 200
fstat 369	_dos_getdate 202
_fstat 369	_dos_getdiskfree 203
_fstati64 369	_dos_getdrive <b>205</b> , 221
_grow_handles 480	_dos_getfileattr <b>206</b>
isatty 534	_dos_getftime 208
10accj 551	

_dos_gettime 210	_EGA 466
_dos_getvect 211	EILSEQ 297-298, 345, 388, 391, 715, 719, 754, 1375,
_dos_keep 213	1381
_dos_open 214	EINTR 147, 175, 917-918, 1373
_dos_read <b>216</b>	EINVAL 93, 145-148, 175, 203, 214, 226, 311, 373,
_dos_setblock 217	397, 402, 651, 665, 803-804, 806, 838, 880,
_dos_setdate 219	882, 884, 975, 977, 1012, 1046-1048,
_dos_setdrive <b>221</b> , 132	1050-1051, 1061-1065, 1135, 1156, 1277, 1279,
_dos_setfileattr 222	1290-1293, 1295, 1326-1327
_dos_setftime 224	EIO 373
_dos_settime 226	_ellipse <b>244</b> , 48, 411
_dos_setvect 228	_ellipse_w 244
_dos_write 230	_ellipse_wxy 244
dosdate_t 32, 202, 219	ELOOP 1012
_doserrno 35	EMFILE 166, 193, 214, 231, 233, 261, 899, 969,
_DOSERROR 32	1149, 1327
DOSEXIT 173, 1156, 1372	_enable <b>246</b> , 181
dosexterr 195	ENAMETOOLONG 1012
dostime_t 32, 210, 226	endhostent 248
dup <b>231</b> , 151, 278, 664	endnetent <b>249</b> , 1097
dup2 <b>233</b> , 151, 278, 433, 664, 905	endprotoent <b>250</b> , 1103
_dup2 <b>233</b>	endpwent 251
_dup 231	endservent <b>252</b> , 1105
_dwDeleteOnClose 235	_endthread <b>253</b> , 93
_dwSetAboutDlg 236	_endthreadex <b>253</b> , 93, 253
_dwSetAppTitle 237	ENFILE 969
_dwSetConTitle 238	_ENHANCED 467
_dwShutDown 239	ENODEV 399, 806
_dwYield 241	ENOENT 64, 132, 136, 166, 193, 214, 261, 309, 311,
	314, 377, 794, 899, 902, 1012, 1149, 1156,
	1327
	ENOMEM 93, 140, 217, 261, 377, 397, 399, 803-804,
E	806, 838, 880, 882, 993, 1079, 1156
	ENOSPC 137, 969
	ENOSYS 373, 1012, 1062
	ENOTDIR 1012
E2BIG 261, 1156	ENOTSUP 147, 838
EACCES 64, 136-137, 166, 193, 214, 261, 651, 794,	ENOTTY 1310
806, 838, 899, 902, 1012, 1149, 1177, 1310,	env.h 32
1327	environ 35, 140, 1078
EAGAIN 93, 803-804, 838, 1064, 1290	environment 406, 408, 992, 1078, 1326
EBADF 137, 151-152, 231, 233, 255, 371, 373, 433,	environment variable
651, 665, 1009, 1416	tmpfile 1296
EBADFD 1310	tmpfile_s 1297
EBUSY 880, 1060	EOF <b>255</b> , 122, 168, 274, 295, 297-298, 345-346, 348,
ECHILD 175, 917-918, 1373	359, 361, 388, 390-392, 474, 988, 990, 997-998,
ecvt <b>242</b> , 275	1037, 1043, 1169, 1171, 1319, 1321, 1341,
_ecvt 242	1346, 1348, 1354, 1356, 1368, 1370, 1393
EDEADLOCK 651	_eof <b>255</b> , 255
EDOM 66-67, 77, 81-82, 96, 653-654, 656, 979, 1167,	EOVERFLOW 806
1259, 1261, 1263, 1265, 1267, 1269	EPERM 148, 803-804, 806, 1045, 1049
EEXIST 193, 794	ERANGE 162, 267, 377, 397, 399, 1139, 1253, 1259,
EFAULT 1045, 1049-1051, 1279	1261, 1263, 1265, 1267, 1269, 1310, 1412
EGA 1123	ERESCOLOR 1123

ERESNOCOLOR 1123	_execl <b>259</b>
erf <b>257</b>	execle <b>259</b> , 260
erfc <b>258</b>	_execle 259
EROFS 969	execlp <b>259</b> , 259-260
errno 32, 35, 57, 64, 66-67, 77, 81-82, 84, 93, 96, 115,	_execlp 259
117, 132, 136-137, 140, 145-148, 150-152, 155,	execlpe <b>259</b> , 259-260
162, 164, 166, 168, 174, 187, 189-191, 193,	_execlpe <b>259</b>
198, 200, 203, 206, 208, 214, 216-217, 219,	execv <b>259</b> , 260
222, 224, 226, 230-231, 233, 255, 260, 267,	_execv <b>259</b>
273, 278, 295, 297-298, 300-301, 305, 308-309,	execve <b>259</b> , 260
311, 314, 319, 329, 341, 345-346, 348-349, 354,	_execve 259
359, 361, 363, 365, 367, 371, 373, 375, 377,	execvp <b>259</b> , 259-260
380, 388, 391, 397, 399, 402, 433, 451, 480,	_execvp <b>259</b>
506, 522, 524, 534, 649, 651, 653-654, 656,	execvpe <b>259</b> , 259-260
665, 679, 715, 719, 754, 794, 799, 803-805,	_execvpe 259
838, 880, 882, 884, 898, 902, 917-919, 969,	exit <b>266</b> , 93, 173, 671, 1134, 1372, 1417
975, 977, 979-980, 988, 990, 993, 997, 1006,	_exit <b>264</b> , <b>264</b> , 93, 173, 1372
1009, 1012, 1024-1025, 1030, 1034, 1043,	EXIT_FAILURE 61, 1417
1045-1051, 1060-1065, 1078-1079, 1092, 1095,	EXIT_SUCCESS 1417
1135, 1139, 1141, 1143, 1149, 1156, 1163,	exp <b>267</b>
1167, 1177, 1206, 1252-1253, 1259, 1261,	exp2 <b>268</b>
1263, 1265, 1267, 1269, 1277-1278, 1280,	_expand Functions <b>269</b>
1282-1284, 1290-1293, 1295-1296, 1310, 1323,	_expand <b>270</b> , 270
1326-1327, 1339, 1341-1342, 1346, 1348, 1350,	expm1 <b>269</b>
1356, 1358, 1360, 1370, 1373, 1375, 1381,	extern 32
1405, 1412, 1416	
errno.h 32	
CI11O.11 J2	
errno_t 1066	F
errno_t 1066 Error Handling 32, 35	F
errno_t 1066 Error Handling 32, 35 _clear87 139	F
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141	
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156	<b>F</b> _OK 64
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158	F_OK 64 fabs <b>272</b>
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158 dosexterr 195	F_OK 64 fabs <b>272</b> false 33
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158 dosexterr 195 feof 287	F_OK 64 fabs <b>272</b>
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158 dosexterr 195 feof 287 ferror 289	F_OK 64 fabs <b>272</b> false 33
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158 dosexterr 195 feof 287 ferror 289 _fpreset 340	F_OK 64 fabs <b>272</b> false 33 _fcalloc <b>125</b> , 14, 125
errno_t 1066 Error Handling 32, 35clear87 139clearerr 141control87 156controlfp 158dosexterr 195feof 287ferror 289fpreset 340matherr 679	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273
errno_t 1066 Error Handling 32, 35clear87 139 clearerr 141control87 156controlfp 158 dosexterr 195 feof 287 ferror 289fpreset 340 matherr 679 perror 919	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242
errno_t 1066 Error Handling 32, 35clear87 139 clearerr 141control87 156controlfp 158 dosexterr 195 feof 287 ferror 289fpreset 340 matherr 679 perror 919 raise 1003	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275
errno_t 1066 Error Handling 32, 35clear87 139 clearerr 141control87 156controlfp 158 dosexterr 195 feof 287 ferror 289fpreset 340 matherr 679 perror 919 raise 1003set_matherr 1092	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158 dosexterr 195 feof 287 ferror 289 _fpreset 340 matherr 679 perror 919 raise 1003 _set_matherr 1092 signal 1134	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275
errno_t 1066 Error Handling 32, 35 _clear87 139 clearerr 141 _control87 156 _controlfp 158 dosexterr 195 feof 287 ferror 289 _fpreset 340 matherr 679 perror 919 raise 1003 _set_matherr 1092 signal 1134 _status87 1179	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277
errno_t 1066 Error Handling 32, 35clear87 139 clearerr 141control87 156controlfp 158 dosexterr 195 feof 287 ferror 289fpreset 340 matherr 679 perror 919 raise 1003setmatherr 1092 signal 1134status87 1179 stderr 18	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274
errno_t 1066 Error Handling 32, 35clear87 139 clearerr 141control87 156controlfp 158 dosexterr 195 feof 287 ferror 289fpreset 340 matherr 679 perror 919 raise 1003set_matherr 1092 signal 1134status87 1179 stderr 18 strerror 1200	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329
errno_t 1066 Error Handling 32, 35    _clear87 139    clearerr 141    _control87 156    _controlfp 158    dosexterr 195    feof 287    ferror 289    _fpreset 340    matherr 679    perror 919    raise 1003    _set_matherr 1092    signal 1134    _status87 1179    stderr 18    strerror 1200    strerror_s 1201	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284
errno_t 1066 Error Handling 32, 35   _clear87 139   clearerr 141   _control87 156   _controlfp 158   dosexterr 195   feof 287   ferror 289   _fpreset 340   matherr 679   perror 919   raise 1003   _set_matherr 1092   signal 1134   _status87 1179   stderr 18   strerror 1200   strerror_s 1201   _wcserror 1200	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284 FE_DENORMAL 284
errno_t 1066 Error Handling 32, 35   _clear87 139   clearerr 141   _control87 156   _controlfp 158   dosexterr 195   feof 287   ferror 289   _fpreset 340   matherr 679   perror 919   raise 1003   _set_matherr 1092   signal 1134   _status87 1179   stderr 18   strerror 1200   strerror_s 1201   _wcserror_s 1201	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284 FE_DENORMAL 284 FE_DFL_ENV 290
errno_t 1066 Error Handling 32, 35   _clear87 139   clearerr 141   _control87 156   _controlfp 158   dosexterr 195   feof 287   ferror 289   _fpreset 340   matherr 679   perror 919   raise 1003   _set_matherr 1092   signal 1134   _status87 1179   stderr 18   strerror 1200   strerror_s 1201   _wcserror_s 1201   _wcserror_s 1201   _wperror 919	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284 FE_DENORMAL 284 FE_DFL_ENV 290 FE_DIVBYZERO 284 FE_DOWNWARD 292 FE_INEXACT 284
errno_t 1066 Error Handling 32, 35    _clear87 139    clearerr 141    _control87 156    _controlfp 158    dosexterr 195    feof 287    ferror 289    _fpreset 340    matherr 679    perror 919    raise 1003    _set_matherr 1092    signal 1134    _status87 1179    stderr 18    strerror 1200    strerror_s 1201    _wcserror_s 1201    _wcserror_919 ESRCH 1045, 1048-1051	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284 FE_DENORMAL 284 FE_DFL_ENV 290 FE_DIVBYZERO 284 FE_DOWNWARD 292 FE_INEXACT 284 FE_INVALID 284
errno_t 1066 Error Handling 32, 35   _clear87 139   clearerr 141   _control87 156   _controlfp 158   dosexterr 195   feof 287   ferror 289   _fpreset 340   matherr 679   perror 919   raise 1003   _set_matherr 1092   signal 1134   _status87 1179   stderr 18   strerror 1200   strerror_s 1201   _wcserror_s 1201   _wcserror_919 ESRCH 1045, 1048-1051   exception 33	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284 FE_DENORMAL 284 FE_DFL_ENV 290 FE_DIVBYZERO 284 FE_DOWNWARD 292 FE_INEXACT 284
errno_t 1066 Error Handling 32, 35    _clear87 139    clearerr 141    _control87 156    _controlfp 158    dosexterr 195    feof 287    ferror 289    _fpreset 340    matherr 679    perror 919    raise 1003    _set_matherr 1092    signal 1134    _status87 1179    stderr 18    strerror 1200    strerror_s 1201    _wcserror_s 1201    _wcserror_919 ESRCH 1045, 1048-1051	F_OK 64 fabs 272 false 33 _fcalloc 125, 14, 125 fclose 273 fcloseall 274 fcntl.h 32 fcvt 275, 242 _fcvt 275 fdim 277 fdopen 278, 274 _fdopen 278, 329 FE_ALL_EXCEPT 284 FE_DENORMAL 284 FE_DFL_ENV 290 FE_DIVBYZERO 284 FE_DOWNWARD 292 FE_INEXACT 284 FE_INVALID 284

EE LINDEDELOW 204	1006
FE_UNDERFLOW 284	_tempnam_1286
FE_UPWARD 292	tmpnam 1301
feclearexcept 280	tmpnam_s 1299
fedisableexcept 281	unlink 1322
fedisableexcept 281	_unlink 1322
feenableexcept 282	_waccess 64
feenableexcept 282	_wchmod 135
fegetenv <b>283</b> , 290	_wmktemp 799
fegetexceptflag <b>284</b> , 280-282, 288, 291, 293	_wremove 1024
fegetround <b>285</b> , 886, 1029	_wrename 1025
feholdexcept <b>286</b> , 290	_wstat 1175
fenv.h 32	_wstati64 1175
feof <b>287</b> , 349	_wtempnam 1286
feraiseexcept 288	_wtmpnam 1301
ferror <b>289</b> , 349, 474, 998	_wtmpnam_s 1299
fesetenv <b>290</b> , 290	_wunlink 1322
fesetexceptflag 291	FILE 79
fesetround <b>292</b> , 285	filelength 305
fetestexcept 293	_filelength <b>305</b> , 305
feupdateenv 294	_filelengthi64 305
_fexpand <b>270</b> , 270	Filename Parsing Functions
fflush <b>295</b> , 319, 328-329, 332, 367, 1319	_fullpath 377
_ffree <b>351</b> , 14, 351, 1198	_makepath 675
ffs <b>296</b>	_splitpath2 1161
fgetc <b>297</b> , 298, 388	_wfullpath 377
fgetchar 298	_wmakepath 675
_fgetchar 298	_wsplitpath2 1161
fgetpos <b>300</b> , 365, 1416	_wsplitpath 1159
fgets <b>301</b> , 451	FILENAME_MAX 307
fgetwc 297	fileno <b>308</b> , 19
_fgetwchar 298	FILES= 480
fgetws 301	find_t 32, 197
_fheapchk <b>491</b> , 491	_findclose <b>309</b> , 311
	_finddata_t 310, 313
_fheapmin <b>496</b> , 496	_finddatai64_t 310, 313
_fheapset <b>498</b> , 498	_findfirst <b>310</b> , 309, 313
_fheapshrink <b>500</b> , 500	_findfirsti64 <b>310</b> , 313
_fheapwalk <b>502</b> , 502	_findnext 313, 311
_fieeetomsbin 303	_findnexti64 313
FILE 18, 34	_finite 315, 985
file open limits 480	
File Operations 25	fixed-point 982, 1039 float.h 32
access 64	
	Floating Point Environment 32
_access 64	feclearexcept 280
chmod 135	fedisableexcept 281
_chmod 135	feenableexcept 282
_commit 155	fegetenv 283
lstat 1175	fegetexceptflag 284
mkstemp 797	fegetround 285
_mktemp 799	feholdexcept 286
remove 1024	feraiseexcept 288
rename 1025	fesetenv 290
stat 1175	fesetexceptflag 291
stat 1175	fesetround 202

0	0.1
fetestexcept 293	_fmbsstr 1249
feupdateenv 294	_fmbstok 1254
_floodfill 316, 411	_fmbstok_r 1254
_floodfill_w 316	_fmbstowes 762
floor <b>318</b> , 1309	_fmbstowcs_s 764
fltused_ 35	_fmbsupr 1271
flushall 319	_fmbterm 766
_flushall <b>319</b> , 319, 328, 332	_fmbtowc 768
fma 320	_fmbvtop 770
_fmalloc 677, 14, 494, 677, 1198	_fmemccpy 773
fmax 321	_fmemchr 774
_fmbccmp 686	_fmemcmp 776
_fmbccpy 688	_fmemcpy 778
_fmbclen_690	_fmemicmp 782
_fmbclen 696	_fmemmove 785
_fmbgetcode 708	_fmemset <b>791</b>
_fmblen 710	fmin 322
_fmbputchar 713	fmod <b>323</b> , 1412
_fmbrlen 715	_fmode 35-36, 328, 332, 366, 897, 905, 977, 1148
_fmbrtowc 718	_fmsbintoieee 324
_fmbsbtype 722	_fmsize <b>878</b> , 878
_fmbscat 1181	FNM_CASEFOLD 326
_fmbschr 1185	FNM_IGNORECASE 326
_fmbscmp 1187	FNM_LEADING_DIR 326
_fmbscpy 1191	FNM_NOESCAPE 326
_fmbscspn 1195 _fmbsdec 725	FNM_PATHNAME 326 FNM_PERIOD 326
_fmbsdup 1198	fnmatch <b>326</b> , 32
_fmbsicmp 1208	fnmatch.h 32
_fmbsinc 727	fopen <b>328</b> , 36, 274, 278, 354, 363
_fmbslen 1214	fopen_s <b>331</b> , 328
_fmbslwr 1217	fp 354
_fmbshbcat 733	FP_INFINITE 338
_fmbsnbcmp 735	FP_NAN 338
_fmbsnbcnt 743	FP_NORMAL 338
_fmbsnbcpy 737	FP_OFF <b>334</b> , 32, 796
_fmbsnbicmp 739	FP_SEG <b>336</b> , 32, 796
_fmbsnbset <b>741</b>	FP_SUBNORMAL 338
_fmbsncat 1220	FP_ZERO 338
_fmbsnccnt 743	fpclassify 338
_fmbsncmp 1224	_fpreset 340
_fmbsncpy 1228	fprintf <b>341</b> , 343, 919, 1141, 1143, 1163, 1342, 1415
fmbsnextc 749	fprintf_s <b>343</b> , 341
_fmbsnicmp 1232	fputc <b>345</b> , 988
fmbsninc 751	fputchar 346
_fmbsnset 1236	_fputchar <b>346</b>
_fmbspbrk 1238	fputs 348
_fmbsrchr 1240	fputwc 345
_fmbsrev 1242	_fputwchar 346
_fmbsrtowcs <b>754</b>	fputws 348
_fmbsrtowcs_s 757	fread <b>349</b>
_fmbsset 1244	_frealloc <b>1014</b> , 14, 1014
_fmbsspn 1246	free <b>351</b> , 14, 125, 351, 377, 397, 399, 1014, 1198
_fmbsspnp <b>760</b>	free Functions 349

_freect 353	fwprintf_s 343
freeram 1278	fwrite <b>380</b>
freeswap 1278	fwscanf 359
freopen <b>354</b> , 18, 20, 274, 363	fwscanf_s 361
freopen_s <b>356</b> , 354	
frexp 358	
fscanf <b>359</b> , 361, 1346, 1415-1416	G
fscanf_s <b>361</b> , 359, 1043, 1171, 1348	4
fseek <b>363</b> , 329, 332, 367, 375, 1319	
fsetpos <b>365</b> , 300, 329, 332, 367, 1319	
_fsopen 366	_GAND 439, 995, 1101
fstat <b>369</b> , 32, 34	_GBORDER 244, 967, 973, 1016
_fstat 369	_GCLEARSCREEN 142
_fstati64 <b>369</b> , 371	_GCURSOROFF 183
_fstrcat 1181	_GCURSORON 183
_fstrchr 1185	gevt 381
_fstrcmp 1187	_gcvt 381
_fstrcpy 1191	_get_osfhandle <b>433</b> , 905
_fstrcspn 1195	_getactivepage 383
_fstrdup 1198	_getactivepage 385
_fstricmp 1208	_getbkcolor 387
_fstrlen 1214	
_fstrlwr 1217	getc 388, 391
_fstrncat 1220	getch <b>390</b> , 392, 629, 1321
_fstrncmp 1224	getchar <b>391</b>
_fstrncpy 1228	getche <b>392</b> , 168, 390, 629, 1321, 1341
_fstrnicmp 1232	_getcliprgn 393
_fstrnset 1236	getcmd <b>394</b> , 671
_fstrpbrk 1238	_getcolor 395
_fstrrchr 1240	_getcurrentposition 396
_fstrrev 1242	_getcurrentposition_w 396
_fstrset 1244	getcwd 397
_fstrspn 1246	_getdcwd 399
_fstrspnp 1248	getdelim <b>401</b> _getdiskfree <b>402</b>
_fstrstr 1249	_getdrive 404
_fstrtok 1254	
_fstrtok_r 1254	getegid <b>405</b>
_fstrupr 1271	getenv <b>406</b> , 40, 260, 992, 1078, 1155, 1417
fsync 373	getenv_s <b>408</b> , 406
ftell <b>375</b> , 363, 1416	geteuid 410
ftime <b>376</b> , 34	_getfillmask 411 _getfontinfo 412
_fullpath 377	
function 1134	getgid 414
function classification 3	_getgtextextent 415 _getgtextvector 416
_fwcrtomb 1375	gethostbyaddr 417
_fwcrtomb_s 1378	gethostbyaddi 417 gethostbyname 418
_fwcsrtombs 1381	gethostent <b>420</b> , 1085
_fwcsrtombs_s 1384	
_fwcstombs 1388	_getimage_vy_422
_fwcstombs_s 1390	_getimage_w 422
_fwctomb 1395	_getimage_wxy 422
_fwctomb_s 1397	getline 424
fwide 379	_getlinestyle 425
fwprintf 341	getlogcoord 470

_getmbcp 426	graphics adapters 45
getnetbyaddr 427	graphics functions 45
getnetbyname 428	graphics header files 52
getnetent <b>429</b> , 1097	graphics library 45
getopt <b>430</b> , 36-37	GRCLIPPED 482
getpgrp 435	Greenwich Mean Time 39
_getphyscoord 436	GRERROR 482
getpid 437	GRFONTFILENOTFOUND 482
_getpid 437	GRINSUFFICIENTMEMORY 482
_getpixel 438	GRINVALIDFONTFILE 482
_getpixel_w 438	GRINVALIDPARAMETER 482
_getplotaction 439	GRMODENOTSUPPORTED 482
getppid 441	GRNOOUTPUT 482
getprotobyname 442	GRNOTINPROPERMODE 482
getprotobynumber 443	GROK 482
getprotoent 444, 1103	grouping 642
getpwent 445	_grow_handles 480
getpwnam 447	_grstatus 482
getpwuid 449	_grtext <b>484</b> , 458, 461, 484, 909, 911, 916, 1072, 1074,
gets <b>451</b> , 301	1106, 1112, 1114
gets_s <b>452</b>	_grtext_w 484
getservbyname 453	_GSCROLLDOWN 1053
getservbyport 454	_GSCROLLUP 1053
getservent <b>455</b> , 1105	_GVIEWPORT 142
_gettextcolor 456	_GWINDOW 142
_gettextcursor 457	_GWRAPOFF 1403
_gettextextent 458	_GWRAPON 1403
_gettextposition 460, 1119	_GXOR 439, 995, 1101
_gettextsettings <b>461</b> , 1072	
_gettextwindow 463	
gettid 464	
getuid 465	<b>H</b>
GetVersionEx 37, 39	
_getvideoconfig 466, 46, 383, 472, 1020, 1068, 1130	
_getviewcoord 470	1 11 11 4 417 410
_getviewcoord_w 470	h_addr_list 417-418
_getviewcoord_wxy 470	h_aliases 417
_getvisualpage 472	h_name 417-418
_getw <b>474</b>	_HALF 1106
getwc 388, 391	halloc <b>486</b> , 494, 505
getwchar 391	hantozen 682
_getwindowcoord 475	_harderr 487
_getws 451	_hardresume <b>487</b> , 488
_GFILLINTERIOR 244, 967, 973, 1016	_hardretn <b>487</b> , 488
GMT 39	hardware port 513-515, 913-915
gmtime 476	_hdopen 490
gmtime Functions 475	Heap Functions 15
_gmtime <b>476</b> , 476	_bheaprin_406
gmtime_s 478, 476	_bheapmin 496
_GOR 439, 995, 1101	_bheapset 498
_GPRESET 995	_bheapshrink 500
_GPSET 439, 995, 1101	_bheapwalk 502
graph.h 32	_fheapragu 404
graphic page 46	_fheapgrow 494

_fheapmin 496	tanh 1283
_fheapset 498	hypot <b>506</b>
_fheapshrink 500	• •
_fheapwalk 502	
_heapchk 491	
_heapenable 493	1
_heapgrow 494	
_heapmin 496	
heapset 498	
_heapshrink 500	i86.h 32
_heapwalk 502	IA MMX 33
_nheapchk 491	IA MMX functions 28
_nheapgrow 494	ignore_handler_s 507
_nheapmin 496	ilogb <b>508</b>
_nheapset 498	_imagesize <b>509</b> , 422
_nheapshrink 500	_imagesize_w 509
_nheapwalk 502	_imagesize_wxy 509
_HEAPBADBEGIN 491, 498, 502	imaxabs 511
HEAPBADNODE 491, 498, 502	imaxdiv 512
HEAPBADPTR 502	imaxdiv_t 512
heapchk Functions 490	INCLUDE 993, 1079
heapchk <b>491</b> , 491, 498, 502	infinity 315, 985
_HEAPEMPTY 491, 498, 502	inp <b>513</b>
heapenable <b>493</b>	inpd <b>514</b>
HEAPEND 502	inpw <b>515</b>
heapgrow Functions 493	int 1098, 1331
heapgrow 494	int386 <b>516</b> , 56
	int386x <b>517</b> , 56
heapinfo 502	int64 983, 1040
heapmin Functions 494	int86 <b>519</b> , 56
_heapmin <b>496</b> , 496, 500	int86x <b>520</b> , 56, 526, 528
_HEAPOK 491, 498, 502	intdos <b>522</b> , 56
heapset Functions <b>496</b>	intdosx <b>524</b> , 56
heapset <b>498</b> , 491, 498, 502	Intel classification 58
heapshrink Functions 499	Intel-Specific Functions 27
heapshrink <b>500</b> , 496, 500	Interrupt Functions
heapwalk Functions 500	_disable 181
_heapwalk <b>502</b> , 491, 498, 502	_enable 246
HERCHUES 466	INTMAX_MAX 1263
_HERCULES 466	INTMAX_MIN 1263
nfree 505	intmax_t 983, 1039
HGC 1123	INTPACK 32
nInstance 671	intr <b>526</b> , 56
nPrevInstance 671	intrf <b>528</b> , 56
HRES16COLOR 1123	inttypes.h 32
HRESBW 1123	io.h 32
HUGE_VAL 1253	IOFBF 1121
Hyperbolic Functions	_IOLBF 1121
acos 66	_IONBF 1121
acosh 67	isalnum <b>530</b> , 553, 1411
asinh 78	isalpha <b>531</b> , 530, 555, 1411
atan 80	isascii <b>532</b>
atanh 82	isascii 532
cosh 162	isatty <b>534</b>
sinh 1139	isuity SST

isatty 534 isblank 535 iscntrl 537, 1411 iscsym 539 \_\_iscsym **539** iscsymf 541 iscsymf 541 isdigit 543, 530 isfinite 545 isgraph 546, 557, 615 isinf **548** isleadbyte 549 islower 551, 531, 1411 ismbbalnum 553 \_ismbbalpha 555 \_ismbbgraph 557 \_ismbbkalnum **559**, 553 \_ismbbkalpha **563**, 555 \_ismbbkana 561 \_ismbbkprint **565**, 557 \_ismbbkpunct **567** \_ismbblead 569 \_ismbbprint 571 \_ismbbpunct 573 \_ismbbtrail 575 \_ismbcalnum 577 \_ismbcalpha 579, 577 \_ismbccntrl 581 \_ismbcdigit **583**, 577 \_ismbcgraph **585**, 601 \_ismbchira 587 ismbckata 589 ismbcl0 591 \_ismbcl1 **593** \_ismbcl2 595 \_ismbclegal 597 \_ismbclower 599 \_ismbcprint 601, 585 ismbepunct 603 \_ismbcspace 605 \_ismbcsymbol 607 \_ismbcupper 609 ismbexdigit 611 isnan **613** isnormal 614 ISO C classification 57 ISO C90 classification 57 ISO C95 classification 57 ISO C99 classification 57 isprint 615, 546, 1411 ispunct 617 isspace 619 isupper 621, 531, 1411 iswalnum 530, 535, 617, 619, 1401

iswalpha 531, 530, 1401 iswascii 532 iswblank **535**, 1401 iswentrl 537, 531, 551, 621, 1401 \_\_iswcsym 539 \_\_iswcsymf 541 iswctype **623**, 1401 iswdigit 543, 530-531, 551, 621, 1401 iswgraph 546 iswlower 551, 531, 1401 iswprint 615 iswpunct 617, 531, 551, 621, 1401 iswspace 619, 531, 551, 621, 1401 iswupper **621**, 531, 1401 iswxdigit 625 isxdigit 625 itoa 627 \_itoa 627 \_itow **627** 



j0 **96**, 16, 96 j1 **96**, 16, 96 jistojms 692 jmp\_buf 658, 1086 jmstojis 694 jn **96**, 16, 96 jtohira 702 jtokata 704 jtolower 698 jtoupper 700



kbhit **629**, 390, 392, 1321 \_kbhit **629** \_KEYBRD\_READ 108 \_KEYBRD\_READY 108 \_KEYBRD\_SHIFTSTATUS 108

	locking <b>651</b> , 34
	_locking 651
L	log <b>653</b> , 655, 1412
	log10 <b>654</b> , 1412
	log1p <b>655</b>
I tmmnom 1201	log2 <b>656</b> , 1412
L_tmpnam 1301	logb <b>657</b>
L_tmpnam_s 1299	long double 983, 1040
labs 630	long long 983
LC_ALL 1090	LONG_MAX 1259
LC_COLLATE 1090	LONG_MIN 1259
LC_CTYPE 1090, 1399, 1401	longimp <b>658</b> , 33, 1003, 1086, 1134
LC_MONETARY 1090	lpszCmdLine 671
LC_NUMERIC 1090	_lrotl 660
LC_TIME 1090	_lrotr <b>661</b>
ldexp 631	lsearch <b>662</b> , 33
ldiv <b>632</b>	lseek <b>664</b> , 1006, 1284, 1405
ldiv_t 632	lseek 664
_LEFT 1106	_lseeki64 <b>664</b> , 1284
lfind <b>633</b> , 33	
lgamma 635	lstat <b>1175</b> , 1012, 1177 ltoa <b>669</b>
lgamma_r <b>636</b> , 635	
limits	_lton 669
file open 480	_ltow <b>669</b>
limits.h 32	
LINE 79	
_lineto <b>637</b> , 48, 396, 809	M
_lineto_w 637	IVI
_LK_LOCK, LK_LOCK 651	
_LK_LOCK 651	
_LK_NBLCK, LK_NBLCK 651	m64 33
_LK_NBLCK 651	m_empty <b>789</b>
_LK_NBRLCK, LK_NBRLCK 651	_m_from_int <b>792</b>
_LK_RLCK, LK_RLCK 651	_m_packssdw 810
_LK_UNLCK, LK_UNLCK 651	_m_packsswb 812
llabs <b>639</b>	_m_packuswb 814
lldiv <b>640</b>	_m_paddb <b>816</b>
lldiv_t 640	_m_paddd 817
LLONG_MAX 1261	_m_paddsb <b>818</b>
LLONG_MIN 1261	_m_paddsw <b>820</b>
lltoa <b>667</b>	_m_paddusb <b>821</b>
_lltoa <b>667</b>	*
lltow <b>667</b>	_m_paddux 824
loads 1278	_m_paddw 824
Locale Functions	_m_pand 825
localecony 641	_m_pandn <b>826</b>
setlocale 1090	_m_pcmpeqb 827
_wsetlocale 1090	_m_pcmpeqd 828
locale.h 32	_m_pcmpeqw <b>829</b>
localecony 641	_m_pcmpgtb 830
localtime <b>645</b> , 41	_m_pcmpgtd 831
localtime Functions 643	_m_pcmpgtw 832
localtime 645, 41, 645	_m_pmaddwd 833
localtime_s <b>647</b> , 645	_m_pmulhw 835
lock 649	_m_pmullw <b>836</b>
1001. 017	

_m_por <b>837</b>	atanh 82
_m_pslld <b>840</b>	Bessel Functions 96
_m_pslldi <b>841</b>	cabs 124
_m_psllq <b>842</b>	cbrt 127
_m_psllqi <b>843</b>	ceil 128
_m_psllw <b>844</b>	copysign 160
_m_psllwi 845	cos 161
_m_psrad <b>846</b>	cosh 162
_m_psradi <b>847</b>	_dieeetomsbin 177
_m_psraw <b>848</b>	_dmsbintoieee 185
_m_psrawi <b>849</b>	erf 257
_m_psrld <b>850</b>	erfc 258
_m_psrldi <b>851</b>	exp 267
_m_psrlq <b>852</b>	exp2 268
	expm1 269
rn_psrlw <b>854</b>	fabs 272
_m_psrlwi 855	fdim 277
_m_psubb <b>856</b>	fieeetomsbin 303
_m_psubd 857	finite 315
_m_psubsb 858	floor 318
_m_psubsw 860	fma 320
_m_psubusb <b>861</b>	fmax 321
_m_psubusw 863	fmin 322
_m_psubw <b>864</b>	fmod 323
_m_punpckhbw <b>865</b>	fmsbintoieee 324
_m_punpckhdq <b>867</b>	frexp 358
_m_punpckhwd <b>869</b>	hypot 506
_m_punpcklbw 871	ilogb 508
_m_punpckldq 873	j0 96
_m_punpcklwd 875	j1 96
_m_pxor 877	jn 96
_m_to_int 881	ldexp 631
main <b>671</b> , 35, 173, 430, 1372	lgamma 635
main program 671	lgamma_r 636
_makepath 675	log 653
malloc <b>677</b> , 14, 92, 351, 353, 377, 397, 399, 494, 677,	log10 654
878, 1198, 1286, 1416	log1p 655
malloc Functions 676	log2 656
malloc.h 32	logb 657
MAP_ANONYMOUS 805	matherr 679
MAP_FIXED 805	modf 807
MAP_LOCKED 805	nan 885
MAP NORESERVE 805	nearbyint 886
MAP_POPULATE 805	nextafter 887
MAP_PRIVATE 805, 838	pow 979
MAP_SHARED 805	remainder 1019
math.h 33	rint 1029
Mathematical Functions 15, 33	round 1033
acos 66	scalbn 1036
acosh 67	_set_matherr 1092
asin 77	sin 1138
asinh 78	sinh 1139
atan 80	sqrt 1167
atan2 81	tan 1282

tanh 1283	_mbsicoll 1210
tgamma 1288	_mbsinc <b>727</b>
trunc 1309	mbsinit <b>730</b> , 730
y0 96	_mbslen 1214
y1 96	_mbslwr <b>1217</b> , 13
yn 96	_mbsnbcat 733
matherr <b>679</b> , 33, 66-67, 77, 81-82, 96, 124, 162, 267,	_mbsnbcmp 735
506, 653-654, 656, 979, 1092, 1139, 1167, 1283	_mbsnbcnt 743
max <b>681</b>	_mbsnbcpy 737
_MAX_DIR 675, 1159	_mbsnbicmp <b>739</b>
_MAX_DRIVE 675, 1159	_mbsnbset <b>741</b>
_MAX_EXT 675, 1159	_mbsncat <b>1220</b>
_MAX_FNAME 675, 1159	_mbsnccnt 743
MAX_PATH2 1161	_mbsncmp <b>1224</b> , 735
MAX_PATH 377, 675, 1159	_mbsncoll 1226
MAX_VOLUME 1159	_mbsncpy <b>1228</b>
MAXCOLORMODE 1123	mbsnextc 749
MAXRESMODE 1123	_mbsnicmp <b>1232</b> , 739
MaxThreads 36	_mbsnicoll 1234
MB_CUR_MAX 715, 718, 768, 1375, 1378, 1395,	_mbsninc 751
1397	mbsnset <b>1236</b> , 741
_mbbtombc 682	_mbspbrk 1238
_mbbtype 683	_mbsrchr 1240
_MBC_ILLEGAL 683, 722	_mbsrev 1242
_MBC_LEAD 683, 722	mbsrtowcs 754
_MBC_SINGLE 683, 722	mbsrtowcs_s <b>757</b> , 754
_MBC_TRAIL 683, 722	_mbsset 1244
_mbccmp 686	_mbsspn 1246
_mbccpy 688	_mbsspnp <b>760</b>
_mbcicmp 690	_mbsstr 1249
_mbcjistojms 692	mbstate_t 34, 715, 718, 730, 754, 1375, 1381
_mbcjinstojiis 694	_mbstok 1254
mbclen <b>696</b>	_mbstok_r 1254
_MBCS 725, 727, 747, 749, 751, 760	mbstowcs <b>762</b> , 754, 1381
_mbctohira <b>702</b>	mbstowes 762, 754, 1361 mbstowes_s 764, 762
_mbctokata 704	_mbsupr <b>1271</b> , 13
_mbctolower 698, 13	_mbterm <b>766</b>
_mbctonbb <b>706</b>	mbtowc <b>768</b> , 715, 718, 1375
_mbctoupper <b>700</b> , 13	
_mbgetcode 708	_mbvtop <b>770</b> MCGA 1123
mblen <b>710</b> , 715, 718, 1375	MCGA 1123 _MCGA 466
_mbputchar 713	MCL_CURRENT 804
mbrlen 715	<del>-</del>
	MCL_FUTURE 804, 883
mbrtowc <b>718</b> , 754, 757, 764	MDPA 1123
_mbsbtype 722	_MDPA 466
_mbscat 1181	mem_unit 1278
_mbschr 1185	_memavl 772
_mbscmp 1187	memccpy 773
_mbscoll 1190	_memccpy 773
_mbscpy 1191	memchr 774
_mbscspn 1195	memcmp <b>776</b> , 97
_mbsdec 725	memcpy <b>778</b> , 785
_mbsdup 1198	memcpy_s <b>780</b> , 778
mbsicmp 1208	memicmp 782

_memicmp <b>782</b> , 782	_nheapset 498
_memmax <b>784</b> , 772	_nheapshrink 500
memmove <b>785</b> , 98, 778, 1191, 1213, 1228	_nheapwalk 502
memmove_s <b>787</b> , 780, 785	_nmalloc 677
Memory Allocation 14	_nmsize 878
alloca 68	_nrealloc 1014
_bcalloc 125	realloc 1014
_bexpand 270	sbrk 1034
_bfree 351	stackavail 1173
_bfreeseg 99	_stackavail 1173
_bheapchk 491	Memory Manipulation Functions 8
_bheapmin 496	memset <b>791</b> , 123
_bheapseg 103	min <b>793</b>
_bheapset 498	minreal 36
_bheapshrink 500	Miscellaneous Functions 29
_bheapwalk 502	MK_FP <b>796</b> , 32
_bmalloc 677	mkdir <b>794</b>
_bmsize 878	_mkdir <b>794</b>
_brealloc 1014	mkstemp 797
brk 117	_mktemp <b>799</b>
calloc 125	mktime <b>801</b> , 41
_expand 270	mlock 803
_fcalloc 125	mlockall <b>804</b> , 883
_fexpand 270	mm_release 149
_ffree 351	mmap <b>805</b>
_fheapchk 491	mmintrin.h 33
_fheapgrow 494	MMX 33
_fheapmin 496	MMX detection 789
_fheapset 498	MMX functions 28
_fheapshrink 500	modf <b>807</b>
_fheapwalk 502	modtime 1327
_fmalloc 677	MON_1 889
_fmsize 878	MON_10 890
_frealloc 1014	MON_11 890
free 351	MON_12 890
_freect 353	MON_2 889
halloc 486	MON_3 890
_heapchk 491	MON_4 890
_heapgrow 494	MON_5 890
_heapmin 496	MON_6 890
_heapset 498	MON_7 890
_heapshrink 500	MON_8 890
_heapwalk 502	MON_9 890
hfree 505	mon_grouping 642
malloc 677	_MONO 467
_memavl 772	movedata 808
_memmax 784	_moveto <b>809</b> , 396, 460, 909, 1116
_msize 878	_moveto_w <b>809</b>
_ncalloc 125	mprotect 838
_nexpand 270	MRES16COLOR 1123
_nfree 351	MRES256COLOR 1123
_nheapchk 491	MRES4COLOR 1123
_nheapgrow 494	MRESNOCOLOR 1123
_nheapmin 496	MS_ASYNC 880

MS_INVALIDATE 880	sisinit 730
MS_SYNC 880	wertomb 1375
_msize Functions <b>877</b>	wcrtomb_s 1378
_msize <b>878</b> , 270, 878	wesrtombs 1381
msync <b>880</b>	wcsrtombs_s 1384
mtob 745	westombs 1388
Multibyte Character Functions 6, 10-11	wcstombs_s 1390
_fmbccmp 686	wctob 1393
_fmbccpy 688	wctomb 1395
_fmbcicmp 690	wctomb_s 1397
fmbclen 696	Multimedia Extension 33
_fmblen 710	Multimedia Extension functions 28
_fmbsdec 725	munlock 882
_fmbsinc 727	munlockall 883
_fmbsnbcnt 743	munmap 884
fmbsnccnt 743	1
fmbsnextc 749	
fmbsninc 751	
fmbsrtowes 754	<b>N</b>
_fmbsrtowcs_s 757	''
_fmbsspnp 760	
fmbstowcs 762	
_fmbstowcs_s 764	n_aliases 427-429
fmbterm 766	n_sign_posn 642
_fmbtowc 768	NaN <b>885</b> , 315, 985
_fmbvtop 770	_ncalloc <b>125</b> , 14, 125
fwertomb 1375	nCmdShow 671
_fwertomb_s 1378	NDEBUG 79
fwestombs 1381	nearbyint 886
_fwestombs_s 1384	nExitCode 672
_fwestombs_s 1388	_nexpand <b>270</b> , 270
_fwestombs_s 1390	nextafter 887
_fwctomb 1395	_NFILES 480
_fwctomb_s 1397	_nfree <b>351</b> , 14, 351
_mbccmp 686	_nheapchk <b>491</b> , 491
_mbccpy 688	_nheapgrow <b>494</b> , 353, 494, 772, 784
_mbcicmp 690	_nheapmin <b>496</b> , 496
_mbclen 696	_nheapset <b>498</b> , 498
mblen 710	_nheapshrink <b>500</b> , 500
mbsdec 725	_nheapwalk <b>502</b> , 502
mbsinc 727	_NKEYBRD_READ 108
mbsinit 730	_NKEYBRD_READY 108
mbsnbcnt 743	_NKEYBRD_SHIFTSTATUS 108
mbsnccnt 743	nl_langinfo 888
mbsnextc 749	_nmalloc <b>677</b> , 14, 353, 677
_mbsninc 751	nmsize <b>878</b> , 878
mbsrtowes 754	_NODISPLAY 466
mbsrtowes s 757	NOEXPR 892
_	Non-local Jumps 33
_mbsspnp 760 mbstowcs 762	longjmp 658
	setjmp 1086
mbstowcs_s 764 _mbterm 766	_NORMAL 1106
_moterm 766 mbtowc 768	nosound <b>893</b> , 1151
	_nrealloc <b>1014</b> , 14, 1014
_mbvtop 770	

NULL 93, 751, 1061, 1063-1065, 1310, 1411, 1416 outtext **916**, 49, 456, 460, 484, 909, 911, 916, \_NULLOFF 125, 677, 1015 1076-1077, 1108, 1116, 1119, 1129, 1403 NULLSEG 103, 491, 500 OVERFLOW 679, 1092 0 P O APPEND 897, 905, 1147, 1405 p aliases 442-444 O\_BINARY 36, 897, 905, 1006, 1095, 1147-1148, P\_DETACH 1154, 1156 1405 P NOWAIT 33, 1153, 1155 O\_CREAT 897-898, 905, 1147-1148 P\_NOWAITO 33, 1153, 1156 O\_EXCL 897, 905, 1148 P\_OVERLAY 21, 33, 1154 O NOINHERIT 214, 897, 905, 1147 p\_sign\_posn 642 O\_NONBLOCK 969 P tmpdir 1286 O\_RDONLY 214, 897, 905, 1006, 1147 P\_WAIT 21, 33, 56, 1153, 1155 O\_RDWR 214, 897, 905, 1006, 1147, 1405 pad 1278 O\_TEXT 36, 897, 905, 1006, 1095, 1147-1148, 1405 PATH 53, 140, 259, 1154 O TRUNC 897, 905, 1147 PATH DOWN 1114 \_PATH\_LEFT 1114 O\_WRONLY 214, 897, 905, 1147, 1405 offsetof **894**, 33 PATH\_MAX 397, 399 onexit 895 \_PATH\_RIGHT 1114 \_onexit **895**, 264 \_PATH\_UP 1114 open 897, 32, 36, 151, 278, 308, 664, 1006, 1284, PC Graphics classification 58 1317, 1405 pclose **917**, 975 \_pclose 918, 977 \_open **897** \_open\_osfhandle **905**, 433 \_pentry 502 perror 919, 35, 1416 opendir 901, 152, 902, 1008, 1027 PFU 1098 optarg 36, 430 opterr 36, 430 PFV 1098 optind 36, 430 \_pg\_analyzechart 920 optopt 36, 430 \_pg\_analyzechartms 920 OS/2 classification 58 \_pg\_analyzepie 922 OS/2 Functions \_pg\_analyzescatter 925 \_pg\_analyzescatterms 925 \_beginthread 92 cwait 173 PG BARCHART 937 cwait 173 \_pg\_chart **928**, 920 \_pg\_chartms 928, 920 endthread 253 \_pg\_chartpie 931, 922 wait 1372 os handle 908 \_pg\_chartscatter **934**, 925 osbuild 37 \_pg\_chartscatterms 934, 925 \_osmajor 37 \_PG\_COLUMNCHART 937 osminor 37 \_pg\_defaultchart 937 osmode 37 \_pg\_getchardef 939 \_pg\_getpalette 941 \_osver 37 \_outgtext 909, 415-416, 484, 909, 911, 916, 1018, \_pg\_getstyleset 944 \_pg\_hlabelchart 947 1082, 1084 \_outmem **911**, 49, 456, 460, 484, 909, 911, 916, 1076, \_pg\_initchart **949**, 51 \_PG\_LINECHART 937 1108, 1116, 1119, 1129, 1403 outp 913 PG\_NOPERCENT 937 outpd **914** PG\_PERCENT 937 outpw **915** \_PG\_PIECHART 937

PG_PLAINBARS 937	PRN 54
PG_POINTANDLINE 937	Process Functions 21, 23, 33, 56
PG_POINTONLY 937	abort 61
_pg_resetpalette <b>951</b>	abort_handler_s 62
_resetstyleset 954	atexit 83
_PG_SCATTERCHART 937	_bgetcmd 101
_pg_setchardef 956	cleareny 140
_pg_setpalette 958	execl 259
_pg_setstyleset 961	execl 259
PG_STACKEDBARS 937	execle 259
_pg_vlabelchart <b>964</b>	_execle 259
PharLap TNT Functions	execlp 259
_beginthread 92	_execlp 259
_beginthreadex 92	execlpe 259
physical coordinates 47	_execlpe 259
_pie <b>966</b> , 48, 385, 411	execv 259
_pie_w <b>966</b>	_execv 259
_pie_wxy 966	execve 259
_pipe <b>969</b> , 977	_execve 259
_pipe 905, 977 PLOSS 679, 1092	
	execup 259
PM_STR 888	_execvp 259
_polygon 973, 48, 411	execupe 259
_polygon_w 973	_execvpe 259
_polygon_wxy 973	_Exit 264
popen <b>975</b> , 917	getcmd 394
_popen <b>977</b> , 918	getenv 406
port 512,515,012,015	ignore_handler_s 507
hardware 513-515, 913-915	main 671
Port I/O 26, 31	onexit 895
inp 513	_onexit 895
inpd 514	putenv 992
inpw 515	_putenv 992
outp 913	set_constraint_handler_s 1066
outpd 914	setenv 1078
outpw 915	_setenv 1078
positive_sign 642	spawnl 1153
POSIX 1003.1 classification 58	_spawnl 1153
POSIX 1003.2 classification 58	spawnle 1153
POSIX 1003.4 classification 58	_spawnle 1153
POSIX classification 58	spawnlp 1153
POSIX_PATH_MAX 1310	_spawnlp 1153
PostQuitMessage 672	spawnlpe 1153
pow <b>979</b>	_spawnlpe 1153
pow(0.0,0.0) 1412	spawnv 1153
pow(0.0,neg) 1412	_spawnv 1153
pow(neg,frac) 1412	spawnve 1153
Prime Meridian 40, 42	_spawnve 1153
_PRINTER_INIT 111	spawnvp 1153
_PRINTER_STATUS 111	_spawnvp 1153
_PRINTER_WRITE 111	spawnvpe 1153
printf <b>980</b> , 35, 115, 163, 341, 982-983, 986, 1116,	_spawnvpe 1153
1141, 1143, 1163, 1337, 1339, 1342, 1350,	system 1280
1358, 1360, 1364	unsetenv 1326
printf s <b>986</b> , 980	wexecl 259

_wexecle 259	
_wexeclp 259	R
_wexeclpe 259	"
_wexecv 259	
_wexecve 259	
_wexecvp 259	R OK 64
_wexecvpe 259	RADIXCHAR 891
_wgetenv 406	raise <b>1003</b> , 33, 658, 1135
_wputenv 992	rand <b>1005</b> , 1168
_wsetenv 1078	RAND_MAX 1005
_wspawnl 1153	Random Numbers
_wspawnle 1153	rand 1005
_wspawnlp 1153	srand 1168
_wspawnlpe 1153	read 1006
_wspawnv 1153	_read <b>1006</b>
_wspawnve 1153	readdir <b>1008</b> , 901-902
_wspawnvp 1153	readlink <b>1012</b> , 1012
_wspawnvpe 1153	readv <b>1006</b>
_wsystem 1280	realloc 1014, 14, 351, 878, 1014, 1416
_wunsetenv 1326	realloc Functions 1013
process.h 33	_rectangle <b>1016</b> , 48, 411
procs 1278	_rectangle_w 1016
Program Segment Prefix 37	_rectangle_wxy 1016
PROT_EXEC 805, 838	_registerfonts <b>1018</b> , 50, 1082, 1325
PROT_NONE 805, 838	REGPACK 32
PROT_READ 805, 838	REGS 32
PROT_WRITE 805, 838	rem 184, 512, 632, 640
PSP 37	remainder 1019
_psp 37, 213	_remapallpalette 1020
ptrdiff_t 33, 983, 1040	_remappalette 1022
putc 988	remove <b>1024</b> , 1322, 1415
putch <b>989</b> , 163-164, 1339	rename <b>1025</b> , 1415
putchar <b>990</b> , 346	ResumeThread 93
putenv <b>992</b> , 40, 260, 406, 408, 1078, 1155, 1417	return 671
_putenv 992	rewind <b>1026</b> , 141, 329, 332, 367, 1319
_putimage <b>995</b> , 50, 422	rewinddir 1027
_putimage_w 995	_RIGHT 1106
puts <b>997</b> , 164	rint <b>1029</b>
_putw 998	rmdir <b>1030</b>
putwc 988	_rmdir <b>1030</b>
putwchar 990	Rotate Functions
_putws <b>997</b>	_lrotl 660
	_lrotr 661
	_rotl 1031
	_rotr 1032
<b>Q</b>	_rotl <b>1031</b>
	_rotr 1032
	round 1033
qsort <b>999</b>	RSIZE_MAX 120, 408, 452, 757, 764, 780, 1001
qsort_s <b>1001</b> , 999	1183, 1193, 1201, 1222, 1230, 1257, 1299,
auot 184, 512, 632, 640	1378, 1384, 1390, 1397

	sched_setparam 1050
S	sched_setscheduler 1051
	sched_yield 1052
	_scrolltextwindow 1053
a aliana 452 455	Search Functions
s_aliases 453-455	_fmbsspnp 760
S_IEXEC 135, 166, 370, 898, 1148, 1176, 1318	_fmemchr 774
S_IREAD 135, 166, 370, 898, 1148, 1176, 1317	_fstrchr 1185
S_IRGRP 135, 165, 370, 898, 1148, 1176, 1317	_fstrcspn 1195
S_IROTH 135, 165, 370, 898, 1148, 1176, 1317	_fstrpbrk 1238
S_IRUSR 135, 165, 370, 898, 1148, 1176, 1317-1318	_fstrrchr 1240
S_IRWXG 135, 165, 370, 898, 1148, 1176, 1317	_fstrspn 1246
S_IRWXO 135, 165, 370, 898, 1148, 1176, 1317	_fstrspnp 1248
S_IRWXU 135, 165, 370, 898, 1148, 1176, 1317	_fstrstr 1249
S_ISBLK(m) 370, 1176	_fstrtok 1254
S_ISCHR(m) 370, 1176	lfind 633
S_ISDIR(m) 370, 1176	lsearch 662
S_ISFIFO(m) 370, 1176	
S_ISGID 371, 1177	_mbsspnp 760
S_ISREG(m) 370, 1176	memchr 774
S_ISUID 371, 1177	_searcheny 1055
S_IWGRP 135, 165, 370, 898, 1148, 1176, 1317	strchr 1185
S_IWOTH 135, 165, 370, 898, 1148, 1176, 1317	strcspn 1195
S_IWRITE 135, 166, 370, 898, 1148, 1176, 1317	strpbrk 1238
S_IWUSR 135, 165, 370, 898, 1148, 1176, 1317-1318	strrchr 1240
S_IXGRP 135, 165, 370, 898, 1148, 1176, 1317	strspn 1246
S_IXOTH 135, 165, 370, 898, 1148, 1176, 1317	strspnp 1248
S_IXUSR 135, 165, 370, 898, 1148, 1176, 1317	_strspnp 760
sbrk <b>1034</b> , 494	strstr 1249
_SC_ARG_MAX 1276	strtok 1254
_SC_AVPHYS_PAGES 1276	strtok_s 1257
_SC_CHILD_MAX 1276	weschr 1185
_SC_CLK_TCK 1276	wesespn 1195
_SC_JOB_CONTROL 1276	wcspbrk 1238
_SC_NGROUPS_MAX 1276	wesrchr 1240
_SC_NPROCESSORS_CONF 1276	wcsspn 1246
_SC_NPROCESSORS_ONLN 1276	_wcsspnp 760
_SC_OPEN_MAX 1276	wcsstr 1249
_SC_PAGE_SIZE 1276	westok 1254
_SC_PAGESIZE 1276	wcstok_s 1257
_SC_PHYS_PAGES 1276	wcsxfrm 1273
_SC_REALTIME_SIGNALS 1276	wmemchr 774
_SC_SAVED_IDS 1276	_wsearchenv 1055
_SC_SOMAXCONN 1276	search.h 33
_SC_STREAM_MAX 1276	_searchenv 1055
_SC_TZNAME_MAX 1276	Searching Functions 17
_SC_VERSION 1276	SECURITY_ATTRIBUTES 93
scalbn 1036	SEEK_CUR 363, 664
	SEEK_END 363, 664
scanf <b>1037</b> , 168, 359, 1169, 1341, 1346, 1354, 1368	SEEK_SET 363, 664
scanf_s 1043, 1037, 1356	segread <b>1057</b> , 517, 520, 524
sched_get_priority_max 1046	_selectpalette 1058
sched_get_priority_min 1047	sem_destroy 1060
sched_getparam 1045	sem_getvalue 1061
sched_getscheduler 1048	_8

sched\_rr\_get\_interval 1049

sem_init <b>1062</b>	_setwindow <b>1132</b> , 47, 470, 475
sem_post 1063	SH_COMPAT 214, 367, 1149
sem_trywait 1064	SH_DENYNO 214, 367, 1149
SEM_VALUE_MAX 1062	SH_DENYRD 214, 367, 1149
sem_wait <b>1065</b>	SH_DENYRW 214, 367, 1149
set_constraint_handler_s 1066	SH_DENYWR 214, 367, 1149
_set_matherr 1092	share.h 33
set_new_handler 1098	sharedram 1278
_set_new_handler 1098	sig_atomic_t 1135
_setactivepage 1068	SIG_DFL 1135, 1413
_setbkcolor 1070	SIG_ERR 1135
setbuf 1071	SIG_IGN 1135
_setcharsize <b>1072</b> , 49	SIGABRT 1134
_setcharsize_w 1072	SIGBREAK 1134-1135
_setcharspacing 1074	SIGFPE 1134
_setcharspacing_w 1074	SIGILL 1134, 1413
_setcliprgn <b>1076</b> , 393	SIGINT 1134-1135
_setcolor <b>1077</b> , 48, 1108	signal <b>1134</b> , 33, 1003, 1412-1413
setenv 1078, 40, 406, 408	signal.h 33
_setenv 1078	signbit 1137
_setfillmask 1080, 48	SIGSEGV 1134
_setfont <b>1082</b> , 50, 412, 909, 949, 1018, 1325	SIGTERM 1134
_setgtextvector 1084	SIGUSR1 1134
sethostent <b>1085</b> , 420	SIGUSR2 1134
setjmp <b>1086</b> , 33, 658	SIGUSR3 1134
setjmp.h 33	sin 1138
_setlinestyle 1088, 48	SING 679, 1092
setlocale <b>1090</b> , 32, 1190, 1273	sinh 1139
setlogorg 1128	sisinit 730
_setmbcp <b>1094</b> , 1210, 1226, 1234	size_t 33-34, 361, 983, 1039
setmode 1095	sleep 1140
_setmode <b>1095</b> , 55, 1095	snprintf <b>1143</b> , 1145
setnetent <b>1097</b> , 429	_snprintf <b>1141</b> , 1358, 1360
_setpixel 1100	snprintf_s <b>1145</b> , 1143, 1165
_setpixel_w 1100	snwprintf 1143
_setplotaction 1101, 48	_snwprintf 1141
setprotoent 1103, 444	snwprintf_s 1145
setpwent 1104	sopen 1147
setservent <b>1105</b> , 455	_sopen <b>1147</b> , 32-33, 36, 151, 278, 664, 1149, 1317
_settextalign <b>1106</b> , 49	sound 1151
_settextcolor <b>1108</b> , 49, 911, 916, 1077	spawn 21-22, 33, 56, 174, 496, 500, 1034, 1280
_settextcursor 1110, 457	spawn Functions <b>1152</b>
_settextorient 1112, 49	spawnii 1153, 977, 1154, 1280
_settextpath 1114	_spawni 1153, 777, 1154, 1266
_settextposition <b>1116</b> , 49, 396, 460, 809, 911, 916,	spawnle <b>1153</b> , 1154
1119	_spawnle 1153
_settextrows 1117, 1127	_spawnle 1153 spawnlp 1153, 1154
_settextwindow 1119, 49, 460, 463, 1053, 1076, 1129	_spawnlp 1153, 1154
	- <b>1</b>
setvbuf <b>1121</b> _setvideomode <b>1123</b> , 46, 949, 1127	spawnlpe 1153, 1154
	_spawnlye 1153
_setvideomoderows 1127	spawny 1153, 1154
_setvieworg <b>1128</b> , 47, 436, 470	_spawnv 1153
_setviewport <b>1129</b> , 393, 396, 436, 470, 1132	spawnve <b>1153</b> , 1154
_setvisualpage 1130	_spawnve 1153

spawnvp 1153, 1154	stdlib.h 34
_spawnvp 1153	stdout 18, 36, 38, 274, 308, 346, 480, 980, 990, 997
spawnype <b>1153</b> , 1154	1116, 1350
_spawnvpe 1153	STDOUT_FILENO 308, 969
_splitpath2 1161	stdprn 18, 38, 274, 308, 480
_splitpath 1159	STDPRN_FILENO 308
sprintf <b>1163</b> , 115, 1165, 1364	strcasecmp 1180
sprintf_s <b>1165</b> , 1145, 1163	streat 1181
sqrt <b>1167</b> , 1412	strcat_s <b>1183</b> , 1181, 1183
srand <b>1168</b> , 1005	strchr 1185
SREGS 32	strcmp <b>1187</b> , 1190
sscanf <b>1169</b> , 1368	strempi 1189
sscanf_s <b>1171</b> , 1169, 1370	strcoll <b>1190</b> , 1273
st_archivedID 369, 1175	strcpy <b>1191</b> , 992
st_atime 369, 1175	strcpy_s <b>1193</b> , 1191, 1193
st_attr 369, 1175	strcspn 1195
st_btime 369, 1175	_strdate 1197
st_ctime 369, 1175	_strdec <b>725</b>
st_dev 369, 1175	strdup <b>1198</b> , 992, 1301
st_gid 369, 1175	_strdup 1198
st_inheritedRightsMask 369, 1175	Stream I/O Functions 18, 20
st_ino 369, 1175	_bprintf 115
st_mode 369-370, 1175-1176	_bwprintf 115
st_mtime 369, 1175	clearerr 141
st_nlink 369, 1175	fclose 273
st_originatingNameSpace 369, 1175	fcloseall 274
st_rdev 369, 1175	fdopen 278
st_size 369-370, 1175-1176	feof 287
st_uid 369, 1175	ferror 289
st_updatedID 369, 1175	fflush 295
stackavail 1173	fgetc 297
_stackavail 1173	fgetchar 298
_stackavan 1173 _stacksize 37	_fgetchar 298
	•
stat <b>1175</b> , 34, 369-370, 1175-1176	fgetpos 300
_stat 1175 _stati64 1175, 369, 1175, 1177	fgets 301 fgetwc 297
	_fgetwc 297
_status87 1179	_ 0
stdarg.h 33	fgetws 301 flushall 319
stdaux 18, 37, 274, 308, 480 STDAUX_FILENO 308	_flushall 319
stdbool.h 33	fopen 328
_STDC_CONSTANT_MACROS 33	fopen_s 331
STDC_CONSTANT_MACROS 33 STDC_FORMAT_MACROS 32	fprintf 341
STDC_FORMAT_MACROS 32 STDC_LIMIT_MACROS 33	<u>*</u>
STDC_LIMIT_MACKOS 55 stddef.h 33	fprintf_s 343 fputc 345
stder. 18, 36, 38, 66-67, 77, 79, 81-82, 96, 162, 267,	fputchar 346
274, 308, 430, 480, 653-654, 656, 679, 919,	_fputchar 346
	<u>-</u>
979, 1092, 1139, 1167, 1411 STDERR_FILENO 308	fputs 348
_	fputwoher 346
stdin 18, 36, 38, 274, 298, 308, 391, 451-452, 480,	_fputwchar 346
1037 STDIN EILENO 308 060	fputws 348
STDIN_FILENO 308, 969	fread 349
stdint.h 33	freopen 354
stdio.h 33	freopen_s 356

fscanf 359	vscanf 1354
fscanf_s 361	vscanf_s 1356
fseek 329, 332, 363, 367	vsnprintf_s 1362
fsetpos 365	vsnwprintf_s 1362
_fsopen 366	vsprintf_s 1366
ftell 375	vsscanf_s 1370
fwprintf 341	vswprintf_s 1366
fwprintf_s 343	vswscanf_s 1370
fwrite 380	vwprintf 1350
fwscanf 359	vwprintf_s 1352
fwscanf_s 361	vwscanf 1354
getc 388	vwscanf_s 1356
getchar 391	_wfdopen 278
gets 451	_wfopen 276 _wfopen 328
_getw 474	_wfopen_s 331
getwc 388	_wfreopen 354
getwc 366 getwchar 391	_wfreopen_s 356
	_wfsopen_s 356
_getws 451	<u>*</u>
Multibyte Character Functions 20	Wide Character Functions 20
perror 919	_wperror 919
printf 980	wprintf 980
printf_s 986	wprintf_s 986
putc 988	wscanf 1037
putchar 990	wscanf_s 1043
puts 997	strerror <b>1200</b> , 35, 1417
_putw 998	strerror_s <b>1201</b> , 1200, 1203
putwc 988	strerrorlen_s 1203
putwchar 990	strftime <b>1204</b> , 41, 1090
_putws 997	stricmp 1208
rewind 1026	_stricmp <b>1208</b> , 1180, 1189, 1208
scanf 1037	_stricoll 1210
scanf_s 1043	_strinc <b>727</b>
setbuf 1071	String Functions 8
setvbuf 1121	bcmp 97
snprintf_s 1145	bcopy 98
snwprintf_s 1145	bzero 123
sprintf_s 1165	_cmdname 154
sscanf_s 1171	ffs 296
swprintf_s 1165	_fmbsdec 725
swscanf_s 1171	_fmbsinc 727
tmpfile 1296	_fmbsnbcat 733
tmpfile_s 1297	_fmbsnbcmp 735
ungetc 295, 1319	_fmbsnbcnt 743
ungetwc 1319	_fmbsnbcpy 737
vfprintf 1342	_fmbsnbicmp 739
vfprintf_s 1344	_fmbsnbset 741
vfscanf 1346	_fmbsnccnt 743
vfscanf_s 1348	_fmbsnextc 749
vfwprintf 1342	_fmbsninc 751
vfwprintf_s 1344	_fmbsspnp 760
vfwscanf 1346	_fmemccpy 773
vfwscanf_s 1348	_fmemset 791
vprintf 1350	_fstrcat 1181
vprintf s 1352	fstrchr 1185

fstrcmp 1187 strerror 1200 strerror\_s 1201 \_fstrcpy 1191 fstrcspn 1195 strerrorlen s 1203 \_fstrdup 1198 stricmp 1208 \_fstricmp 1208 \_stricmp 1208 \_fstrlen 1214 \_stricoll 1210 fstrncat 1220 strine 727 \_fstrncmp 1224 strlcat 1212 \_fstrncpy 1228 strlcpy 1213 strlen 1214 \_fstrnicmp 1232 \_fstrnset 1236 strlwr 1217 fstrpbrk 1238 strlwr 1217 \_fstrrchr 1240 strncasecmp 1219 fstrrev 1242 strncat 1220 \_fstrset 1244 strncat\_s 1222 \_fstrspn 1246 strncmp 1224 \_fstrspnp 1248 \_strncnt 743 \_fstrstr 1249 \_strncoll 1226 \_fstrtok 1254 strncpy 1228 \_fstrupr 1271 strncpy\_s 1230 \_mbsdec 725 \_strnextc 749 \_mbsinc 727 strnicmp 1232 \_mbsnbcat 733 \_strnicmp 1232 \_mbsnbcmp 735 \_strnicoll 1234 \_mbsnbcnt 743 \_strninc 751 \_mbsnbcpy 737 strnlen\_s 1216 \_mbsnbicmp 739 strnset 1236 \_mbsnbset 741 \_strnset 1236 \_mbsnccnt 743 strpbrk 1238 \_mbsnextc 749 strrchr 1240 \_mbsninc 751 strrev 1242 \_mbsspnp 760 strrev 1242 memccpy 773 strset 1244 \_memccpy 773 \_strset 1244 memset 791 strspn 1246 snprintf 1143 strspnp 1248 \_snprintf 1141 \_strspnp 760 snwprintf 1143 strstr 1249 snwprintf 1141 strtok 1254 sprintf 1163 strtok\_s 1257 sscanf 1169 strupr 1271 strcasecmp 1180 \_strupr 1271 strcat 1181 strxfrm 1273 strcat s 1183 swprintf 1163 strchr 1185 swscanf 1169 strcmp 1187 \_vbprintf 1337 strcmpi 1189 \_vbwprintf 1337 strcoll 1190 vsnprintf 1360 strcpy 1191 \_vsnprintf 1358 strcpy\_s 1193 vsnwprintf 1360 strcspn 1195 \_vsnwprintf 1358 \_strdec 725 vsprintf 1364 strdup 1198 vsscanf 1368 \_strdup 1198 vswprintf 1364

vswscanf 1368	_strlwr <b>1217</b> , 13, 1217
wescat 1181	strncasecmp 1219
wcscat_s 1183	strncat 1220
weschr 1185	strncat_s <b>1222</b> , 1220
wescmp 1187	strnemp <b>1224</b> , 1273
wesempi 1189	_strncnt 743
wescoll 1190	_strncoll 1226
wesepy 1191	strncpy <b>1228</b> , 1273
wesepy_s 1193	strncpy_s <b>1230</b> , 1228, 1230
wesespn 1195	_strnextc <b>749</b>
_wcsdec 725	strnicmp 1232
wesdup 1198	_strnicmp <b>1232</b> , 1219, 1232
_wcsdup 1198	_strnicoll 1234
_wcserror 1200	_strninc <b>751</b>
_wcserror_s 1201	strnlen_s <b>1216</b> , 1214
_wcserrorlen_s 1203	strnset 1236
_wesicmp 1208	_strnset <b>1236</b> , 1236
_wesicoll 1210	strpbrk <b>1238</b>
_wesine 727	strrchr 1240
wesleat 1212	strrev 1242
weslepy 1213	_strrev <b>1242</b> , 1242
weslep 1213 weslen 1214	strset 1244
_wesler 1217	_strset <b>1244</b> , 1244
wesneat 1220	strspn <b>1246</b>
wesheat 1220 wesheat_s 1222	strspnp 1248
wesnemp 1224	_strspnp <b>760</b>
_wesnerit 743	strstr 1249
_weshell 1226	strtime <b>1251</b>
wesnepy 1228	_strtod 1252
wesnepy_s 1230	strtoimax 1263
_wesnexte 749	strtok 1254
_wesnicate 749 _wesnicmp 1232	strtok_r <b>1254</b> , 1254
_wesnicoll 1234	strtok_s <b>1257</b> , 1254
wesnine 751	strtol <b>1259</b>
weshine 731 weshlen_s 1216	strtoll <b>1261</b>
weshed_s 1216 wesnset 1236	strtoul <b>1265</b>
_wesnset 1236	strtoul <b>1265</b> strtoull <b>1267</b>
wespbrk 1238	strtoumax 1269
wespork 1238 wesrehr 1240	struct 894
western 1240 westerv 1242	struct lconv 641
_wessev 1242 _wesset 1244	struct protoent 442-443
wesser 1244 wesspn 1246	struct protoent 442-443 struct servent 453-454
_wesspnp 760	struct tm 34, 801
wesstr 1249	structure
westok 1254	complex 33
westok 1254 westok_s 1257	exception 33
_wcstor_s 1237 _wcsupr 1271	INTPACK 32
westfrm 1273	
wcsxrm 1273 wmemset 791	m64 33 REGPACK 32
	REGS 32
string.h 34	SREGS 32
stricat 1212	
strlepy 1213 strlen 1214	stat 34
strien 1214 striwr 1217	strupr 1271
Suiwi 141/	_strupr <b>1271</b> , 13, 1271

strxfrm 1273	TEMPDIR 1296-1297
SVGA 1123	_tempnam 1286
_SVGA 466	Terminate and Stay Resident
SVRES16COLOR 1123	_dos_keep 213
SVRES256COLOR 1123	text files 36
SW_HIDE 672	TEXTBW40 1123
SW_MINIMIZE 672	TEXTBW80 1123
SW_RESTORE 672	TEXTC40 1123
SW_SHOW 672	TEXTC80 1123
SW_SHOWMAXIMIZED 672	TEXTMONO 1123
SW_SHOWMINIMIZED 672	tgamma 1288
SW_SHOWMINNOACTIVE 672	THOUSEP 891
SW_SHOWNA 672	_threadid 38, 93
SW_SHOWNOACTIVATE 672	time <b>1289</b> , 169, 645, 801
SW_SHOWNORMAL 672	Time Functions 17, 34
swab 1275	asctime 72
swprintf 1163	_asctime 72
swprintf_s 1165	asctime_s 74
swscanf 1169	clock 143
swscanf_s 1171	ctime 169
sys 34	_ctime 169
sys/locking.h 34	ctime_s 171
sys/stat.h 34	difftime 179
sys/timeb.h 34	ftime 376
sys/types.h 34	gmtime 476
sys/utime.h 35	_gmtime 476
SYS_clone 149	gmtime_s 478
sys_errlist 38	localtime 645
sys_nerr 38	localtime 645
sysconf 1276	localtime_s 647
sysinfo 1278	mktime 801
system <b>1280</b> , 21, 33, 56, 496, 500, 1417	strftime 1204
system 1200, 21, 33, 30, 470, 300, 1417	time 1289
	_wasctime 72
	wasctime 72
T	wasctime_s 74
, ,	wasetime_s 74 wcsftime 1204
	_westime 1204
	wetime 169
T_FMT 888	wetime_s 171
T_FMT_AMPM 888	_wettine_s 171 _wstrftime_ms 1204
tan 1282	time zone 39, 42, 169, 476, 645, 1289, 1311
tanh 1283	time.h 34
_tcsdec 725	_TIME_GETCLOCK 114
_tcsinc 727	_TIME_GETCLOCK 114 _TIME_SETCLOCK 114
_tcsnbcnt 747	time_t 1289
_tcsnccnt 747	time 34
_tcsnextc 749	
_tcsninc 751	timer_create 1290
_tcsspnp 760	timer_delete 1291
tell <b>1284</b>	timer_getoverrun 1295
_tell <b>1284</b> , 664, 1006, 1284, 1405	timer_gettime 1292
_telli64 <b>1284</b>	timer_settime 1293
TEMP 1296-1297	timezone 38, 40, 1311
	TLOSS 679, 1092

tm 34, 476, 645	
tm_hour 801	
tm_isdst 801	U
tm_mday 801	
tm_min 801	
tm_mon 801	
tm_sec 801	UINTMAX_MAX 1269
tm_wday 801	uintmax_t 983, 1039
tm_yday 801	ULLONG_MAX 1267
TMP 1286, 1296-1297	ulltoa 1313
	_ulltoa 1313
TMP_MAX 1286, 1301	_ulltow 1313
TMP_MAX_S 1299	ULONG_MAX 1265
TMPDIR 1296-1297	ultoa 1315
tmpfile <b>1296</b> , 264, 266	_ultoa 1315
tmpfile_s <b>1297</b> , 1296	_ultow 1315
tmpnam 1301	umask <b>1317</b> , 898, 1148
tmpnam_s <b>1299</b> , 1301	_umask 1317
tolower <b>1303</b> , 13, 1217, 1399	undefined references
_tolower 1303	fltused_ 35
_TOP 1106	UNDERFLOW 679, 1092
totalhigh 1278	ungetc 1319, 295, 363
totalram 1278	ungetch 1321
totalswap 1278	ungetwc 1319
toupper <b>1305</b> , 13, 1271, 1399	_UNICODE 725, 727, 747, 749, 751, 760
_toupper 1305	union 894
towctrans 1307, 1399	_UNKNOWN 466
towlower <b>1303</b> , 13	unlink 1322
towupper <b>1305</b> , 13	_unlink 1322
TR 24731 classification 58	unlock <b>1323</b> , 649
Trigonometric Functions 15	_unregisterfonts 1325
acos 66	unsetenv 1326
acosh 67	
asin 77	unsigned 1098
asinh 78	uptime 1278
atan 80	URES256COLOR 1123
atan2 81	UTC 39-40, 42
atanh 82	utimbuf 35, 1327
cos 161	utime 1327, 35
cosh 162	_utime 1327
hypot 506	utoa 1329
sin 1138	_utoa 1329
sinh 1139	_utow 1329
tan 1282	
tanh 1283	
true 33	1/
	<b>V</b>
trunc 1309	
ttyname 1310	
ttyname_r <b>1310</b> , 1310	vo and <b>1321</b> 1222 1225 1240 1256 1270
TZ 39-43, 140, 169, 476, 645, 1289, 1311	va_arg <b>1331</b> , 1333, 1335, 1348, 1356, 1370
tzname 38, 40-41, 1311	va_end <b>1333</b> , 1331, 1335, 1348, 1356, 1370
tzset <b>1311</b> , 35, 38, 40-41, 169, 645, 801, 1206	va_list 1331
	va_start <b>1335</b> , 1331, 1333, 1337, 1339, 1341-1342,
	1346, 1348, 1350, 1354, 1356, 1358, 1360,
	1364, 1368, 1370

varargs.h 34	_waccess 64
variable arguments 18	wait <b>1372</b> , 1153, 1155
va_arg 1331	WAIT CHILD 174
va_end 1333	WAIT_GRANDCHILD 174
va_start 1335	wargc 38
_vbprintf 1337	wargv 38
_vbwprintf 1337	wasctime <b>72</b> , 72
veprintf 1339	wasctime <b>72</b> , 72
vescanf 1341	wasctime_s <b>74</b>
vfprintf 1342	WATCOM classification 58
vfprintf_s <b>1344</b> , 1342	wchar.h 34
vfscanf 1346	wchar_t 34, 983, 1254
vfscanf_s 1348, 1346	_wchdir <b>132</b>
vfwprintf 1342	_wchmod <b>135</b>
vfwprintf_s 1344	_wclosedir <b>152</b> , 902
vfwscanf 1346	_wcreat <b>165</b>
vfwscanf_s 1348	wertomb <b>1375</b> , 1381, 1384
VGA 1123	wertomb_s <b>1378</b> , 1375
VGA 466	wescat <b>1181</b>
view coordinates 47	wcscat_s 1183
void 671, 1098	weschr 1185
vprintf <b>1350</b> , 1344, 1352	wescmp <b>1187</b> , 1273
vprintf_s <b>1352</b> , 1350	wescmpi 1189
VRES16COLOR 1123	wescoll <b>1190</b> , 1273
VRES256COLOR 1123	wescon 1190, 1275 wescpy 1191
VRES2COLOR 1123	wesepy 1151 wesepy_s 1193
vscanf 1354	wesepy_s 1195 wesespn 1195
vscanf_s <b>1356</b> , 1354	_wcsdec <b>725</b>
vsnprintf <b>1360</b> , 1362	_wesdee 725 wesdup 1198
_vsnprintf 1358	_wcsdup 1198
vsnprintf_s <b>1362</b> , 1360, 1366	_wcserror 1200
vsnwprintf <b>1360</b>	_wcserror_s 1201
_vsnwprintf 1358	_weserrorlen_s 1201 _weserrorlen_s 1203
vsnwprintf_s 1362	westime 1204
vsprintf <b>1364</b> , 1366	_wesicmp <b>1204</b>
vsprintf_s <b>1366</b> , 1362, 1364	_wesicall <b>1210</b>
vsscanf <b>1368</b>	_wesiecon 1210 _wesine 727
vsscanf_s <b>1370</b> , 1368	weshee 727 wesleat 1212
vswprintf <b>1364</b>	westear 1212 weslepy 1213
vswprintf_s 1366	weslepy 1213 weslen 1214
vswscanf 1368	wester <b>1217</b> , 13
vswscanf_s 1370	weshed 1217, 13
vwprintf 1350	wesheat 1220 wesheat s 1222
vwprintf_s 1352	wesnemp 1224
vwscanf 1354	_wesnent <b>743</b>
vwscanf s 1356	_wesnell <b>1226</b>
vwscam_s 1550	wesnepy 1228
	wesnepy 1220 wesnepy_s 1230
	_wesnexte <b>749</b>
W	_wesniemp 1232
"	_wesnicoll 1232
	_wesnicon 1234 _wesnine 751
	_weshine 751 weshlen_s 1216
W_OK 64	wesner_s 1216 wesnset 1236
	Weshisel 1230

_wcsnset 1236	_wfindfirsti64 310
wespbrk 1238	_wfindnext 313
wesrchr 1240	_wfindnexti64 313
_wcsrev 1242	_wfopen <b>328</b>
wesrtombs 1381	_wfopen_s 331
wcsrtombs_s 1384, 1381	_wfreopen 354
_wcsset 1244	_wfreopen_s 356
wcsspn 1246	_wfsopen 366
_wcsspnp 760	_wfullpath 377
wesstr 1249	_wgcvt 381
westod 1252	_wgetcwd 397
westoimax 1263	_wgetdcwd 399
westok 1254	_wgetenv 406
wcstok_s 1257	Wide Character Functions 6, 10-1
westol 1259	btowc 122
westoll 1261	_bwprintf 115
westombs 1388, 754, 1381	fgetwc 297
wcstombs_s 1390, 1388	_fgetwchar 298
westoul 1265	fgetws 301
westoull 1267	fputwc 345
westoumax 1269	_fputwchar 346
_wcsupr <b>1271</b> , 13	fputws 348
wcsxfrm 1273	_fwcrtomb 1375
_wctime <b>169</b>	_fwcrtomb_s 1378
wctime <b>169</b>	fwcsrtombs 1381
wctime_s 171	_fwcsrtombs_s 1384
wctob <b>1393</b>	_fwcstombs 1388
wctomb <b>1395</b> , 715, 718, 1375	_fwcstombs_s 1390
wctomb_s 1397, 1395	_fwctomb 1395
wetrans 1399, 1307	_fwctomb_s 1397
wctrans_t 1399	fwprintf 341
wctype <b>1401</b> , 623	fwprintf_s 343
wctype.h 34	fwscanf 359
wctype_t 34, 1401	fwscanf_s 361
_wdirent 902, 1009	getwc 388
_wdos_findclose 197	getwchar 391
_wdos_findfirst 197	_getws 451
_wdos_findnext 197	iswalnum 530
_wecvt <b>242</b>	iswascii 532
_wenviron 39	iswblank 535
WEOF 34, 122, 297-298, 345-346, 388, 391, 988, 990,	iswentrl 537
1319	iswcsym 539
_wexecl <b>259</b>	iswcsymf 541
_wexecle <b>259</b>	iswctype 623
_wexeclp <b>259</b>	iswdigit 543
_wexeclpe 259	iswgraph 546
_wexecv 259	iswlower 551
_wexecve 259	iswprint 615
_wexecvp 259	iswpunct 617
_wexecvpe 259	iswspace 619
wfcvt 275	iswupper 621
_wfdopen 278	iswxdigit 625
_wfind_t 32	_itow 627
wfindfirst 310	

ltow 669 wcserror s 1201 putwc 988 wcserrorlen s 1203 putwchar 990 wcsftime 1204 \_putws 997 \_wcsicmp 1208 \_wcsicoll 1210 snwprintf s 1145 swprintf\_s 1165 \_wcsinc 727 swscanf 1169 wesleat 1212 swscanf\_s 1171 weslepy 1213 towctrans 1307 wcslen 1214 towlower 1303 \_wcslwr 1217 towupper 1305 wesneat 1220 ulltow 1313 wesneat s 1222 \_ultow 1315 wcsncmp 1224 ungetwc 1319 wesnent 743 utime 1327 \_wcsncoll 1226 \_vbwprintf 1337 wcsncpy 1228 vfwprintf 1342 wcsncpy\_s 1230 vfwprintf\_s 1344 \_wcsnextc 749 vfwscanf 1346 \_wcsnicmp 1232 vfwscanf\_s 1348 \_wcsnicoll 1234 vsnwprintf 1360 \_wcsninc 751 \_vsnwprintf 1358 wcsnlen\_s 1216 vsnwprintf\_s 1362 wcsnset 1236 vswprintf 1364 \_wcsnset 1236 vswprintf\_s 1366 wcspbrk 1238 vswscanf 1368 wesrchr 1240 vswscanf\_s 1370 \_wcsrev 1242 vwprintf 1350 wesrtombs 1381 vwprintf\_s 1352 wcsrtombs\_s 1384 vwscanf 1354 \_wcsset 1244 vwscanf\_s 1356 wcsspn 1246 waccess 64 wcsspnp 760 wcsstr 1249 wasctime 72 \_wasctime 72 westod 1252 \_wasctime\_s 74 westoimax 1263 wchdir 132 wcstok 1254 \_wchmod 135 wcstok\_s 1257 \_wclosedir 152 westol 1259 wcreat 165 westoll 1261 wertomb 1375 wcstombs 1388 wertomb s 1378 westombs s 1390 wcscat 1181 westoul 1265 wescat s 1183 westoull 1267 weschr 1185 wcstoumax 1269 wescmp 1187 \_wcsupr 1271 wcscmpi 1189 wcsxfrm 1273 wescoll 1190 wctime 169 \_\_wctime 169 wescpy 1191 \_wctime\_s 171 wcscpy\_s 1193 wesespn 1195 wctob 1393 \_wcsdec 725 wctomb 1395 wcsdup 1198 wctomb\_s 1397 wctrans 1399 \_wcsdup 1198 \_wcserror 1200 wctype 1401

wdos findclose 197 wstat 1175 \_wstrdate 1197 wdos findfirst 197 wdos findnext 197 wstrftime ms 1204 \_wexecl 259 \_wstrtime 1251 \_wexecle 259 \_wsystem 1280 \_wexeclp 259 \_wtempnam 1286 wexeclpe 259 wtmpnam 1301 wexecv 259 wtmpnam s 1299 \_wtof 84 \_wexecve 259 \_wtoi 85 \_wexecvp 259 \_wtol 86 \_wexecvpe 259 \_wfdopen 278 wtoll 87 \_wunlink 1322 wfindfirst 310 wfindfirsti64 310 wunsetenv 1326 \_wfindnext 313 Win32 Functions \_wfopen 328 \_beginthread 92 \_wfopen\_s 331 \_beginthreadex 92 \_wfreopen 354 cwait 173 \_wfreopen\_s 356 \_cwait 173 \_wfsopen 366 \_endthread 253 \_wfullpath 377 \_endthreadex 253 \_wgetcwd 397 wait 1372 \_wgetdcwd 399 \_\_win\_alloc\_flags 39 \_win\_realloc\_flags 39 \_wgetenv 406 \_wmakepath 675 window coordinates 47 \_wmkdir 794 Windows classification 58 \_wmktemp 799 WinMain 671, 671-672 \_wopen 897 \_winmajor 39 \_wopendir 901 \_winminor 39 \_wperror 919 wint\_t 34 \_wpopen 977 \_winver 39 wprintf 980 WM QUIT 672 wprintf s 986 wmain 671, 38-39 \_wputenv 992 \_wmakepath 675 wreaddir 1008 wmemchr 774 wremove 1024 wmemcmp 776 \_wrename 1025 wmemcpy 778 \_wrewinddir 1027 wmemcpy\_s 780 wrmdir 1030 wmemmove 785 wscanf 1037 wmemmove s 787 wscanf s 1043 wmemset 791 \_wmkdir 794 \_wsearchenv 1055 wsetenv 1078 wmktemp **799** wsetlocale 1090 wopen **897** \_wopendir 901, 152, 1027 \_wspawnl 1153 wP tmpdir 1286 \_wspawnle 1153 \_wspawnlp 1153 wParam 672 \_wspawnlpe 1153 \_wperror 919 \_wspawnv 1153 \_wpopen 977 \_wspawnve 1153 wprintf **980**, 982-983 wprintf\_s 986 \_wspawnvp 1153 \_wputenv 992 \_wspawnvpe 1153 wr\_date 198 \_wsplitpath2 1161 wr\_time 198 \_wsplitpath 1159

_wrapon <b>1403</b>
_wreaddir 1008, 902
_wremove 1024
_wrename <b>1025</b>
_wrewinddir 1027
write 1405
_write <b>1405</b>
writev 1405
_wrmdir 1030
wscanf 1037
wscanf_s 1043
_wsearchenv 1055
_wsetenv 1078
_wsetlocale 1090
_wsopen 1147
_wspawnl 1153
_wspawnle 1153
_wspawnlp 1153
_wspawnlpe 1153
_wspawnv 1153
_wspawnve 1153
_wspawnvp 1153
_wspawnvpe 1153
_wsplitpath2 1161
_wsplitpath 1159
_wstat <b>1175</b> , 1177
_wstati64 <b>1175</b> , 1177
_wstrdate 1197
_wstrftime_ms 1204, 1204
_wstrtime 1251
_wstrtime 1251 _wsystem 1280
_wtempnam 1286
_wtmpnam 1301
_wtmpnam_s 1299
wtof <b>84</b>
_wtoi 85
_wtol <b>86</b>
_wtoll <b>87</b>
_wunlink <b>1322</b>
_wunsetenv 1326
_wutime <b>1327</b>
wWinMain <b>671</b> , 671



X\_OK 64 XRES16COLOR 1123 XRES256COLOR 1123



y0 **96**, 16, 96, 1412 y1 **96**, 16, 96, 1412 YESEXPR 891 yn **96**, 16, 96, 1412



zentohan 706