# Open Watcom Code Generator Interface

# Table of Contents

Introduction	•••
General	
Segments	
Labels	
Back Handles	
Type definitions	
Procedure Declarations	2
Expressions	2
Leaf Nodes	
Assignment Operations	•••
Arithmetic/logical operations	
Procedure calls	
Comparison/short-circuit operations	2
Control flow operations	
Select and Switch statements.	
Other	
Data Generation	
Front End Routines	•••
Debugging Information	
Registers	
Miscellaneous	•••
A. Pre-defined macros	
B. Register constants	
C. Debugging Open Watcom Code Generator	

# Introduction

The code generator (back end) interface is a set of procedure calls. These are divided into following category of routines.

Code Generation (CG)
Data Generation (DG)
Miscellaneous Back End (BE)
Front end supplied (FE)
Debugger information (DB)

# General

# cg\_init\_info BEInit( cg\_switches switches, cg\_target\_switches targ\_switches, uint optsize, proc\_revision proc )

Initialize the code generator. This must be the first routine to be called.

Parameter	Definition
switches	Select code generation options. The options are bits, so may be combined with the bit-wise operator  . Options apply to the entire compilation unit. The bit values are defined below.
targ_switches	Target specific switches. The bit values are defined below.
optsize	A number between 0 and 100. 0 means optimize for speed, 100 means optimize for size. Anything in between selects a compromise between speed and size.
proc	The target hardware configuration, defined below.
Returns	Information about the code generator revision in a cg_init_info structure, defined below.
Switch	Definition

CGSW\_GEN\_NO\_OPTIMIZATION

Turn off optimizations.

*CGSW\_GEN\_DBG\_NUMBERS* Generate line number debugging information.

CGSW\_GEN\_FORTRAN\_ALIASING

Assume pointers are only used for parameter passing.

CGSW\_GEN\_DBG\_DF Generate debugging information in DWARF format.

CGSW\_GEN\_DBG\_CV Generate debugging information in CodeView format. If neither

CGSW\_GEN\_DBG\_DF nor CGSW\_GEN\_DBG\_CV is set, debugging

information (if any) is generated in the Watcom format.

CGSW\_GEN\_RELAX\_ALIAS Assume that a static/extern variable and a pointer to that same variable

are not used within the same routine.

CGSW\_GEN\_DBG\_LOCALS Generate local symbol information for use by a debugger.

CGSW\_GEN\_DBG\_TYPES Generate typing information for use by a debugger.

CGSW\_GEN\_LOOP\_UNROLLING

Turn on loop unrolling.

CGSW\_GEN\_LOOP\_OPTIMIZATION

Turn on loop optimizations.

#### CGSW GEN INS SCHEDULING

Turn on instruction scheduling.

#### CGSW\_GEN\_MEMORY\_LOW\_FAILS

Allow the code generator to run out of memory without being able to generate object code (allows the 386 compiler to use EBP as a cache register).

#### CGSW\_GEN\_FP\_UNSTABLE\_OPTIMIZATION

Allow the code generator to perform optimizations that are mathematically correct, but are numerically unstable. E.g. converting division by a constant to a multiplication by the reciprocal.

#### CGSW\_GEN\_NULL\_DEREF\_OK

NULL points to valid memory and may be dereferenced.

#### CGSW\_GEN\_FPU\_ROUNDING\_INLINE

Inline floating-point value rounding (actually truncation) routine when converting floating-point values to integers.

#### CGSW\_GEN\_FPU\_ROUNDING\_OMIT

Omit floating-point value rounding entirely and use FPU default. Results will not be ISO C compliant.

#### CGSW\_GEN\_ECHO\_API\_CALLS

Log each call to the code generator with its arguments and return value. Only available in debug builds.

CGSW\_GEN\_OBJ\_ELF Emit ELF object files.

CGSW\_GEN\_OBJ\_COFF Emit COFF object files. For Intel compilers, OMF object files will be

emitted in the absence of either switch.

#### CGSW GEN OBJ ENDIAN BIG

Emit big-endian object files (COFF or ELF). If

CGSW\_GEN\_OBJ\_ENDIAN\_BIG is not set, little-endian objects will

be generated.

x86 Switch Definition

CGSW\_GEN\_I\_MATH\_INLINE Do not check arguments for operators like O\_SQRT. This allows the

compiler to use some specialty x87 instructions.

Generate Phar Lap EZ-OMF object files. CGSW\_X86\_EZ\_OMF

CGSW\_X86\_BIG\_DATA Use segmented pointers (16:16 or 16:32). This defines TY\_POINTER

to be equivalent to TY\_HUGE\_POINTER.

CGSW\_X86\_BIG\_CODE Use inter segment (far) call and return instructions.

CGSW\_X86\_CHEAP\_POINTER Assume far objects are addressable by one segment value. This must be

used in conjunction with CGSW\_X86\_BIG\_DATA. It defines TY\_POINTER to be equivalent to TY\_FAR\_POINTER.

CGSW X86 FLAT MODEL Assume all segment registers address the same base memory.

*CGSW\_X86\_FLOATING\_FS* Does FS float (or is it pegged to DGROUP).

*CGSW\_X86\_FLOATING\_GS* Does GS float (or is it pegged to DGROUP).

CGSW X86 FLOATING ES Does ES float (or is it pegged to DGROUP).

CGSW\_X86\_FLOATING\_SS Does SS float (or is it pegged to DGROUP).

CGSW\_X86\_FLOATING\_DS Does DS float (or is it pegged to DGROUP).

CGSW\_X86\_USE\_32 Generate code into a use32 segment (versus use16).

CGSW\_X86\_INDEXED\_GLOBALS

Generate all global and static variable references as an offset past EBX.

CGSW\_X86\_WINDOWS Generate windows prolog/epilog sequences for all routines.

CGSW\_X86\_CHEAP\_WINDOWS

Generate windows prolog/epilog sequences assuming that call backs

functions are defined as \_\_export.

CGSW\_GEN\_NO\_CALL\_RET\_TRANSFORM

Do not change a CALL followed by a RET into a JMP. This is used for some older overlay managers that cannot handle a JMP to an overlay.

CGSW\_X86\_CONST\_IN\_CODE Generate all constant data into the code segment. This only applies to

the internal code generator data, such as floating point constants. The

front end decides where its data goes using BESetSeg().

CGSW X86 NEED STACK FRAME

Generate a traceable stack frame. The first instructions will be **INC BP** if the routine uses a far return instruction, followed by **PUSH BP** and

MOV BP,SP. (ESP and EBP for 386 targets).

CGSW\_X86\_LOAD\_DS\_DIRECTLY

Generate code to load DS directly. By default, a call to \_\_GETDS

routine is generated.

CGSW\_X86\_GEN\_FWAIT\_386 Generate FWAIT instructions on 386 and later CPUs. The 386 never

needs FWAIT for data synchronization, but FWAIT may still be needed

for accurate exception reporting.

RISC Switch Definition

CGSW\_RISC\_ASM\_OUTPUT Print final pseudo-assembly on the console. Debug builds only.

CGSW\_RISC\_OWL\_LOGGING Log calls to the Object Writer Library

CGSW\_RISC\_STACK\_INIT Pre-initialize stack variables to a known bit pattern.

CGSW\_RISC\_EXCEPT\_FILTER\_USED Set when SEH (Structured Exception Handling) is used.

The supported proc revision CPU values are:

```
CPU_86
CPU_186
CPU_286
CPU_386
CPU_486
CPU_586
```

The supported proc\_revision FPU values are:

```
FPU_NONE
FPU_87
FPU_387
FPU_586
FPU_EMU
FPU_E87
FPU_E387
FPU_E586
```

The supported proc\_revision WEITEK values are:

```
WTK_NONE
WTK_1167
WTK_3167
WTK_4167
```

The following example sets the processor revision information to indicate a 386 with 387 and Weitek 3167.

```
proc_revision proc;

SET_CPU( proc, CPU_386 );
SET_FPU( proc, FPU_387 );
SET_WTK( proc, WTK_3167 );
```

The return value structure is defined as follows:

```
typedef union
              cg_init_info {
  struct {
    unsigned revision : 10; /* contains II_REVISION */
    unsigned target : 5; /* has II_TARG_??? */
   unsigned is_large : 1; /* 1 if 16 bit host */
  } version;
  int
         success;
} cg_init_info;
enum {
  II_TARG_8086,
  II_TARG_80386,
  II_TARG_STUB,
  II_TARG_CHECK,
  II_TARG_370,
  II_TARG_AXP,
  II_TARG_PPC,
  II_TARG_MIPS
};
```

## void BEStart()

Start the code generator. Must be called immediately after all calls to BEDefSeg have been made. This restriction is relaxed somewhat for the 80(x)86 code generator. See BEDefSeg for details.

### void BEStop()

Normal termination of code generator. This must be the second last routine called.

## void BEAbort()

Abnormal termination of code generator. This must be the second last routine called.

### void BEFini()

Finalize the code generator. This must be the last routine called.

### patch\_handle BEPatch()

Allocate a patch handle which can be used to create a patchable integer (an integer which will have a constant value provided sometime while the codegen is handling the CGDone call). See CGPatchNode.

### void BEPatchInteger( patch\_handle hdl, signed\_32 value )

Patch the integer corresponding to the given handle to have the given value. This may be called repeatedly with different values, providing CGPatchNode has been called and BEFiniPatch has not been called.

Parameter	Definition
hdl	A patch_handle returned from an earlier invocation of BEPatch which has had a node allocated for it via CGPatchNode. If CGPatchNode has not been called with the handle given, the behaviour is undefined.
value	A signed 32-bit integer value. This will be the new value of the node which has been associated with the patch handle.

# cg\_name BEFiniPatch( patch\_handle hdl )

This must be called to free up resources used by the given handle. After this, the handle must not be used again.

# Segments

The object file produced by the code generator is composed of various segments. These are defined by the front end. A program may have as many data and code segments as required by the front end. Each segment may be regarded as an individual file of objects, and may be created simultaneously. There is a current segment, selected by BESetSeg(), into which all DG routines generate their data. The code for each routine is generated into the segment returned by the FESegID() call when it is passed the cg\_sym\_handle for the routine. It is illegal to write data to the code segment for a routine in between the CGProcDecl call and the CGReturn call.

The following routines are used for initializing, finalizing, defining and selecting segments.

# void BEDefSeg( segment\_id segid, seg\_attr attr, char \*str, uint algn )

Define a segment. This must be called after BEInit and before BEStart. For the 80(x)86 code generator, you are allowed to define additional segments after BEStart if they are:

- 1. Code Segments
- 2. PRIVATE data segments.

Parameter	Definition
segid	A non-negative integer used as an identifier for the segment. It is arbitrarily picked by the front end.
attr	Segment attribute bits, defined below.
str	The name given to the segment.
algn	The segment alignment requirements. The code generator will pick the next larger alignment allowed by the object module format. For example, 9 would select paragraph alignment.
Attribute	Definition
EXEC	This is a code segment.
GLOBAL	The segment is accessible to other modules. (versus PRIVATE).
INIT	The segment is statically initialized.
ROM	The segment is read only.
BACK	The code generator may put its data here. One segment must be marked with this attribute. It may not be a COMMON, PRIVATE or EXEC segment. If the front end requires code in the EXEC segment, the CGSW_X86_CONST_IN_CODE switch must be passed to BEInit().

**COMMON** All occurrences of this segment will be overlayed. This is used for FORTRAN common

blocks.

**PRIVATE** The segment is non combinable. This is used for far data items.

**GIVEN\_NAME** Normally, the back end feels free to prepend or append strings to the segment name passed in by the front end. This allows a naive front end to specify a constant set of segment names, and have the code generator mangle them in such a manner that they work properly in concert with the set of cg\_switches that have been specified (e.g. prepending the module name to the code segments when CGSW\_X86\_BIG\_CODE is specified on the x86). When GIVEN\_NAME is specified, the back end outputs the segment name to the object file

exactly as given.

THREAD LOCAL Segment contains thread local data. Such segments may need special handling in executable modules.

### segment\_id BESetSeg( segment\_id segid )

Select the current segment for data generation routines. Code for a routine is always output into the segment returned by FESegID when it is passed the routine symbol handle.

Definition **Parameter** 

segid Selects the current segment.

Returns The previous current segment.

**Notes:** When emitting data into an EXEC or BACK segment, be aware that the code generator is at liberty to emit code and/or back end data into that segment anytime you make a call to a code generation routine (CG\*). Do NOT expect data items to be contiguous in the segment if you have made an intervening CG\* call.

# segment\_id BEGetSeg( void )

Return the current segment for generation routines.

Returns The current segment.

# void BEFlushSeg( segment\_id segid )

BEFlushSeg informs the back end that no more code/data will be generated in the specified segment. For code segments, it must be called after the CGReturn() for the final function which is placed in the segment. This causes the code generator to flush all pending information associated with the segment and allows the front end to free all the back handles for symbols which were referenced by the code going into the segment. (The FORTRAN compiler uses this since each function has its own symbol table which is thrown out at the end of the function).

Parameter Definition

segid The code segment id.

# Labels

The back end uses a **label\_handle** for flow of control. Each **label\_handle** is a unique code label. These labels may only be used for flow of control. In order to define a label in a data segment, a **back\_handle** must be used.

# label\_handle BENewLabel()

Allocate a new control flow label.

**Returns** A new label\_handle.

# void BEFiniLabel( label\_handle lbl )

Indicate that a label\_handle will not be used by the front end anymore. This allows the back end to free some memory at some later stage.

Parameter Definition

*lbl* A label\_handle

# **Back Handles**

A **back\_handle** is the front end's handle for a code generator symbol table entry. A **cg\_sym\_handle** is the code generator's handle for a front end symbol table entry. The back end may call FEBack, passing in any cg\_sym\_handle that has been passed to it. The front end must allocate a back\_handle via BENewBack if one does not exist. Subsequent calls to FEBack should return the same back\_handle. This mechanism is used so that the back end does not have to do symbol table searches. For example:

```
back_handle FEBack( SYMPOINTER sym )
{
    if( sym->back == NULL ) {
        sym->back = BENewBack( sym );
    }
    return( sym->back );
}
```

It is the responsibility of the front end to free each back\_handle, via BEFreeBack, when it frees the corresponding cg\_sym\_handle entry.

A back\_handle for a symbol having automatic or register storage duration (auto back\_handle) may not be freed until CGReturn is called. A back\_handle for a symbol having static storage duration, (static back\_handle) may not be freed until BEStop is called or until after a BEFlushSeg is done for a segment and the back\_handle will never be referenced by any other function.

The code generator will not require a back handle for symbols which are not defined in the current compilation unit.

The front end must define the location of all symbols with static storage duration by passing the appropriate back\_handle to DGLabel. It must also reserve the correct amount of space for that variable using DGBytes or DGUBytes.

The front end may also allocate an back\_handle with static storage duration that has no cg\_sym\_handle associated with it (anonymous back\_handle) by calling BENewBack(NULL). These are useful for literal strings. These must also be freed after calling BEStop.

# back\_handle BENewBack( cg\_sym\_handle sym )

Allocate a new back\_handle.

Parameter	Definition
sym	The front end symbol handle to be associated with the back_handle. It may be NULL.
Returns	A new back_handle.

# void BEFiniBack( back\_handle bck )

Indicate that bck will never be passed to the back end again, except to BEFreeBack. This allows the code generator to free some memory at some later stage.

Parameter Definition

bck A back\_handle.

# void BEFreeBack( back\_handle bck )

Free the back\_handle **bck**. See the preamble in this section for restrictions on freeing a back\_handle.

Parameter Definition

bckA back\_handle.

# Type definitions

Base types are defined as constants. All other types (structures, arrays, unions, etc) are simply defined by their length. The base types are:

Type C type

TY\_UINT\_1 unsigned char

TY\_INT\_1 signed char

TY\_UINT\_2 unsigned short

TY\_INT\_2 signed short

TY\_UINT\_4 unsigned long

TY\_INT\_4 signed long

TY\_UINT\_8 unsigned long long

TY\_INT\_8 signed long long

TY\_LONG\_POINTER far \*

TY\_HUGE\_POINTER huge \*

TY\_NEAR\_POINTER near \*

TY\_LONG\_CODE\_PTR (far \*)()

TY\_NEAR\_CODE\_PTR (near \*)()

TY\_SINGLE float

TY\_DOUBLE double

TY\_LONG\_DOUBLE long double

TY\_INTEGER int

TY\_UNSIGNED unsigned int

TY\_POINTER \*

 $TY\_CODE\_PTR$  (\*)()

TY\_BOOLEAN The result of a comparison or flow operator. May also be used as an integer.

TY DEFAULT Used to indicate default conversion

**TY\_NEAR\_INTEGER** The result of subtracting 2 near pointers

**TY\_LONG\_INTEGER** The result of subtracting 2 far pointers

TY\_HUGE\_INTEGER The result of subtracting 2 huge pointers

There are two special constants.

TY\_FIRST\_FREE The first user definable type

TY\_LAST\_FREE The last user definable type.

#### void BEDefType( cg\_type what, uint align, unsigned\_32 len )

Define a new type to the code generator.

Parameter Definition

what An integral value greater than or equal to TY\_FIRST\_FREE and less then or equal to

TY\_LAST\_FREE, used as the type identifier.

align Currently ignored.

*len* The length of the new type.

# void BEAliasType( cg\_type what, cg\_type to )

Define a type to be an alias for an existing type.

Parameter Definition

what Will become an alias for an existing type.

to An existing type.

# unsigned\_32 BETypeLength( cg\_type type )

Return the length of a previously defined type, or a base type.

Parameter Definition

*type* A previously defined type.

**Returns** The length associated with the type.

# uint BETypeAlign( cg\_type type )

Return the alignment requirements of a type. This is always 1 for x86 and 370 machines.

 Parameter
 Definition

 type
 A previously defined type.

 Returns
 The alignment requirements of type as declared in BEDefType, or for a base type, as defined by the machine architecture.

# **Procedure Declarations**

#### void CGProcDecl( cg\_sym\_handle name, cg\_type type )

Declare a new procedure. This must be the first routine to be called when generating each procedure.

Parameter Definition

name The front end symbol table entry for the procedure. A back\_handle will be requested.

*type* The return type of the procedure. Use TY\_INTEGER for void functions.

# void CGParmDecl( cg\_sym\_handle name, cg\_type type )

Declare a new parameter to the current function. The calls to this function define the order of the parameters. This function must be called immediately after calling CGProcDecl. Parameters are defined in left to right order, as defined by the procedure prototype.

ParameterDefinitionnameThe symbol table entry for the parameter.typeThe type of the parameter.

# label\_handle CGLastParm()

End a parameter declaration section. This function must be called after the last parameter has been declared. Prior to this function, the only calls the front-end is allowed to make are CGParmDecl and CGAutoDecl.

# void CGAutoDecl( cg\_sym\_handle name, cg\_type type )

Declare an automatic variable.

This routine may be called at any point in the generation of a function between the calls to CGProcDecl and CGReturn, but must be called before **name** is passed to CGFEName.

ParameterDefinitionnameThe symbol table entry for the variable.typeThe type of the variable.

# temp\_handle CGTemp( cg\_type type )

Yields a temporary with procedure scope. This can be used for things such as iteration counts for FORTRAN do loops, or a variable in which to store the return value of a function. This routine should be used **only if necessary**. It should be used when the front end requires a temporary which persists across a flow of control boundary. Other temporary results are handled by the expression trees.

Parameter	Definition
type	The type of the new temporary.
Returns	A temp_handle which may be passed to CGTempName. This will be freed and invalidated by the back end when CGReturn is called.

# **Expressions**

Expression processing involves building an expression tree in the back end, using calls to CG routines. There are routines to generate leaf nodes, binary and unary nodes, and others. These routines return a handle for a node in a back end tree structure, called a **cg\_name**. This handle must be exactly once in a subsequent call to a CG routine. A tree may be built in any order, but a cg\_name is invalidated by a call to any CG routine with return type void. The exception to this rule is CGTrash.

There is no equivalent of the C address of operator. All leaf nodes generated for symbols, via CGFEName, CGBackName and CGTempName, yield the address of that symbol, and it is the responsibility of the front end to use an indirection operator to get its value. The following operators are available:

0-ary Operator	C equivalent
O_NOP	N/A
Unary Operator	C equivalent
O_UMINUS	-X
O_COMPLEMENT	x
O_POINTS	(*x)
O_CONVERT	x=y
O_ROUND	Do not use!
$O\_LOG$	log(x)
O_COS	cos(x)
O_SIN	sin(x)
O_TAN	tan(x)
O_SQRT	sqrt(x)
O_FABS	fabs(x)
O_ACOS	acos(x)
O_ASIN	asin(x)
O_ATAN	atan(x)
O_COSH	cosh(x)

O_SINH	sinh(x)
O_TANH	tanh(x)
O_EXP	exp(x)
O_LOG10	log10(x)
O_PARENTHESIS	This operator represents the "strong" parenthesises of FORTRAN and C. It prevents the back end from performing certain mathematically correct, but floating point incorrect optimizations. E.g. in the expression "(a*2.4)/2.0", t back end is not allowed constant fold the expression into "a*1.2".
Binary Operator	C equivalent
O_PLUS	+
O_MINUS	-
O_TIMES	*
O_DIV	/
O_MOD	%
O_AND	&
O_OR	
O_XOR	^
O_RSHIFT	<b>&gt;&gt;</b>
O_LSHIFT	<b>&lt;&lt;</b>
O_COMMA	,
O_TEST_TRUE	(x & y)!=0
O_TEST_FALSE	(x & y) == 0
O_EQ	==
O_NE	!=
$O\_GT$	>
O_LE	<=
O_LT	<
O_GE	>=

the

O_POW	pow(x, y)
O_ATAN2	atan2(x, y)
O_FMOD	fmod(x, y)
O CONVERT	See below.

The binary O\_CONVERT operator is only available on the x86 code generator. It is used for based pointer operations (the result type of the CGBinary call must be a far pointer type). It effectively performs a MK\_FP operation with the left hand side providing the offset portion of the address, and the right hand side providing the segment value. If the right hand side expression is the address of a symbol, or the type of the expression is a far pointer, then the segment value for the symbol, or the segment value of the expression is used as the segment value after the O\_CONVERT operation.

Short circuit operators	C equivalent
O_FLOW_AND	&&
O_FLOW_OR	
$O\_FLOW\_NOT$	!
Control flow operators	C equivalent
O_GOTO	goto label;
O_LABEL	label:;
O_IF_TRUE	if(x) goto label;
O_IF_FALSE	if( $!(x)$ ) goto label;
O_INVOKE_LABEL	GOSUB (Basic)
O_LABEL_RETURN	RETURN (Basic)

The type passed into a CG routine is used by the back end as the type for the resulting node. If the node is an operator node (CGBinary, CGUnary) the back end will convert the operands to the result type before performing the operation. If the type TY\_DEFAULT is passed, the code generator will use default conversion rules to determine the resulting type of the node. These rules are the same as the ANSI C value preserving rules, with the exception that characters are not promoted to integers before doing arithmetic operations.

For example, if a node of type TY\_UINT\_2 and a node of type TY\_INT\_4 are to be added, the back end will automatically convert the operands to TY\_INT\_4 before performing the addition. The resulting node will have type TY\_INT\_4.

# Leaf Nodes

### cg\_name CGInteger( signed\_32 val, cg\_type type )

Create an integer constant leaf node.

Parameter Definition

*val* The integral value.

*type* An integral type.

# cg\_name CGInt64( signed\_64 val, cg\_type type )

Create an 64-bit integer constant leaf node.

Parameter Definition

*val* The 64-bit integer value.

*type* An integral type.

# cg\_name CGFloat( char \*num, cg\_type type )

Create a floating-point constant leaf node.

Parameter Definition

*num* A NULL terminated E format string. (-1.23456E-102)

*type* A floating point type.

# cg\_name CGFEName( cg\_sym\_handle sym, cg\_type type )

Create a leaf node representing the address of the back\_handle associated with **sym**. If sym represents an automatic variable or a parameter, CGAutoDecl or CGParmDecl must be called before this routine is first used.

Parameter Definition

*sym* The front end symbol.

*type* The type to be associated with the value of the symbol.

## cg\_name CGBackName( back\_handle bck, cg\_type type )

Create a leaf node which represents the address of the back\_handle.

Parameter Definition

bck A back handle.

*type* The type to be associated with the **value** of the symbol.

## cg\_name CGTempName( temp\_handle temp, cg\_type type )

Create a leaf node which yields the address of the temp\_handle.

Parameter Definition

*temp* A temp\_handle.

*type* The type to be associated with the **value** of the symbol.

# Assignment Operations

### cg\_name CGAssign( cg\_name dest, cg\_name src, cg\_type type )

Create an assignment node.

Parameter	Definition
dest	The destination address.
src	The source value.
type	The type to which the destination address points.
Returns	The value of the right hand side.

### cg\_name CGLVAssign( cg\_name dest, cg\_name src, cg\_type type )

Like CGAssign, but yields the address of the destination.

# cg\_name CGPreGets( cg\_op op, cg\_name dest, cg\_name src, cg\_type type )

Used for the C expressions a += b,  $a \neq b$ .

Parameter	Definition
op	The arithmetic operator to be used.
dest	The address of the destination.
src	The value of the right hand side.
type	The type to which the destination address points.
Returns	The value of the left hand side.

# cg\_name CGLVPreGets( cg\_op op, cg\_name dest, cg\_name src, cg\_type type )

Like CGPreGets, but yields the address of the destination.

# cg\_name CGPostGets( cg\_op op, cg\_name dest, cg\_name src, cg\_type type )

Used for the C expressions a++, a--. No automatic scaling is done for pointers.

Parameter	Definition
op	The operator.
dest	The address of the destination
src	The value of the increment.
type	The type of the destination.
Returns	The value of the left hand side before the operation occurs.

# Arithmetic/logical operations

#### cg\_name CGBinary( cg\_op op, cg\_name left, cg\_name right, cg\_type type )

Binary operations. No automatic scaling is done for pointer operations.

ParameterDefinitionopThe operator.leftThe value of the left hand side.rightThe value of the right hand side.typeThe result type.ReturnsThe value of the result.

## cg\_name CGUnary( cg\_op op, cg\_name name, cg\_type type )

Unary operations.

ParameterDefinitionopThe operator.nameThe value of operand.typeThe result type.ReturnsThe value of the result.

## cg\_name CGIndex( cg\_name name, cg\_name by, cg\_type type, cg\_type ptype )

Obsolete. Do not use.

# Procedure calls

### call\_handle CGInitCall( cg\_name name, cg\_type type, cg\_sym\_handle aux\_info )

Initiate a procedure call.

Parameter Definition

*name* The address of the routine to call.

*type* The return type of the routine.

aux\_info A handle which the back end may passed to FEAuxInfo to determine the attributes of the

call.

**Returns** A call\_handle to be passed to the following routines.

## void CGAddParm( call\_handle call, cg\_name name, cg\_type type )

Add a parameter to a call\_handle. The order of parameters is defined by the order in which they are passed to this routine. Parameters should be added in right to left order, as defined by the procedure call.

Parameter Definition

call A call\_handle.

*name* The value of the parameter.

*type* The type of the parameter. This type will be passed to FEParmType to determine the actual

type to be used when passing the parameter. For instance, characters are usually passes as

integers in C.

# cg\_name CGCall( call\_handle call )

Turn a call\_handle into a cg\_name by performing the call. This may be immediately followed by an optional addition operation, to reference a field in a structure return value. An indirection operator must immediately follow, even if the function has no return value.

Parameter Definition

call A call\_handle.

**Returns** The address of the function return value.

# Comparison/short-circuit operations

# cg\_name CGCompare( cg\_op op, cg\_name left, cg\_name right, cg\_type type )

Compare two values.

Parameter	Definition
op	The comparison operator.
left	The value of the left hand side.
right	The value of the right hand side.
type	The type to which to convert the operands to before performing comparison.
Returns	A TY_BOOLEAN cg_name, which may be passed to a control flow CG routine, or used in an expression as an integral value.

# Control flow operations

### cg\_name CGFlow( cg\_op op, cg\_name left, cg\_name right )

Perform short-circuit boolean operations.

Parameter	Definition
op	An operator.
left	A TY_BOOLEAN or integral cg_name.
right	A TY_BOOLEAN or integral cg_name, or NULL if op is O_FLOW_NOT.
Returns	A TY_BOOLEAN cg_name.

### cg\_name CGChoose( cg\_name sel, cg\_name n1, cg\_name n2, cg\_type type )

Used for the C expression sel? n1: n2.

Parameter	Definition
sel	A TY_BOOLEAN or integral cg_name used as the selector
n1	The value to return if <b>sel</b> is non-zero.
<i>n</i> 2	The value to return if <b>sel</b> is zero.
type	The type to which convert the result.
Returns	The value of <b>n1</b> or <b>n2</b> depending upon the truth of <b>sel</b> .

# cg\_name CGWarp( cg\_name before, label\_handle label, cg\_name after )

To be used for FORTRAN statement functions.

Parameter	Definition
before	An arbitrary expression tree to be evaluated before <b>label</b> is called. This is used to assign values to statement function arguments, which are usually temporaries allocated with CGTemp.
label	A label_handle to invoke via O_CALL_LABEL.
after	An arbitrary expression tree to be evaluated after <b>label</b> is called. This is used to retrieve the statement function return value.

The value of **after**. This can be passed to CGEval, to guarantee that nested statement Returns

functions are fully evaluated before their parameter variables are reassigned, as in

f(1,f(2,3,4),5).

### void CG3WayControl( cg\_name expr, label\_handle lt, label\_handle eq, label\_handle gt )

Used for the FORTRAN arithmetic if statement. Go to label lt, eq or gt depending on whether expr is less than, equal to, or greater than zero.

Parameter	Definition	
expr	The selector value	
lt	A label_handle.	
eq	A label_handle.	
gt	A label_handle.	

### void CGControl( cg\_op op, cg\_name expr, label\_handle lbl )

Generate conditional and unconditional flow of control.

Parameter	Definition
op	a control flow operator.
expr	A TY_BOOLEAN expression if op is O_IF_TRUE or O_IF_FALSE. NULL otherwise.
lbl	The target label.

# void CGBigLabel( back\_handle lbl )

Generate a label which may be branched to from a nested procedure or used in NT structured exception handling. Don't use this call unless you \*really\*, \*really\* need to. It kills a lot of optimizations.

Parameter	Definition
lbl	A back_handle. There must be a front end symbol associated with this back handle.

# void CGBigGoto( back\_handle value, int level )

Generate a branch to a label in an outer procedure.

Parameter	Definition
lbl	A back_handle. There must be a front end symbol associated with this back handle.
level	The lexical level of the target label.

# Select and Switch statements.

The select routines are used as follows. CGSelOther should always be used even if there is no otherwise/default case.

```
end_label = BENewLabel();
sel_label = BENewLabel();
CGControl( O_GOTO, NULL, sel_label );
sel_handle = CGSelInit();
case_label = BENewLabel();
CGControl(O_LABEL, NULL, case_label);
CGSelCase( sel_handle, case_label, case_value );
   ... generate code associated with "case_value" here.
CGControl( O_GOTO, NULL, end_label ); // or else, fall through
other_label = BENewLabel();
CGControl(O_LABEL, NULL, other_label);
CGSelOther( sel_handle, other_label );
    ... generate "otherwise" code here
CGControl( O_GOTO, NULL, end_label ); // or else, fall through
CGControl(O_LABEL, NULL, sel_label);
CGSelect( sel_handle );
CGControl(O_LABEL, NULL, end_label);
```

### sel\_handle CGSelInit()

Create a sel handle.

**Returns** A sel\_handle to be passed to the following routines.

### void CGSelCase( sel\_handle s, label\_handle lbl, signed\_32 val )

Add a single value case to a select or switch.

Parameter	Definition
S	A sel_handle obtained from CGSelInit().
lbl	The label to be associated with the case value.
val	The case value.

### void CGSelRange( sel\_handle s, signed\_32 lo, signed\_32 hi, label\_handle lbl )

Add a range of values to a select. All values are eventually converted into unsigned types to generate the switch code, so lo and hi must have the same sign.

Parameter	Definition
S	A sel_handle obtained from CGSelInit().
lo	The lower bound of the case range.
hi	The upper bound of the case range.
lbl	The label to be associated with the case value.

### void CGSelOther( sel\_handle s, label\_handle lbl )

Add the otherwise case to a select.

Parameter	Definition
S	A sel_handle.
lbl	The label to be associated with the otherwise case.

### void CGSelect( sel\_handle s, cg\_name expr )

Add the select expression to a select statement and generate code. This must be the last routine called for a given select statement. It invalidates the sel\_handle.

Parameter	Definition
S	A sel_handle.
expr	The value we are selecting.

# void CGSelectRestricted( sel\_handle s, cg\_name expr, cg\_switch\_type allowed )

Identical to CGSelect, except that only switch generation techniques corresponding to the set of allowed methods will be considered when determining how to produce code.

Parameter	Definition
S	A sel_handle.
expr	The value we are selecting.
allowed	The allowed methods of generating code. Must be a combination (non-empty) of the following bits:
	CG_SWITCH_SCAN CG_SWITCH_BSEARCH

CG\_SWITCH\_TABLE

# Other

### void CGReturn( cg\_name name, cg\_type type )

Return from a function. This is the last routine that may be called in any routine. Multiple return statements must be implemented with assignments to a temporary variable (CGTemp) and a branch to a label generated just before this routine call.

 Parameter
 Definition

 name
 The value of the return value, or NULL.

 type
 The type of the return value. Use TY\_INTEGER for void functions.

### cg\_name CGEval( cg\_name name )

Evaluate this expression tree now and assign its value to a leaf node. Used to force the order of operations. This should only be used if necessary. Normally, the expression trees adequately define the order of operations. This usually used to force the order of parameter evaluation.

 Parameter
 Definition

 name
 The tree to be evaluated.

 Returns
 A leaf node containing the value of the tree.

# void CGDone( cg\_name name )

Generate the tree and throw away the resultant value. For example, CGAssign yields a value which may not be needed, but must be passed to this routine to cause the tree to be generated. This routine invalidates all cg\_name handles. After this routine has returned, any pending inline function expansions will have been performed.

ParameterDefinitionnameThe cg\_name to be generated/discarded.

# void CGTrash( cg\_name name )

Like CGDone, but used for partial expression trees. This routine does not cause all existing cg\_names to become invalid.

### cg\_type CGType( cg\_name name )

Returns the type of the given cg\_name.

Parameter Definition name A cg\_name. Returns The type of the cg\_name.

### cg\_name \*CGDuplicate( cg\_name name )

Create two copies of a cg\_name.

Parameter Definition name The cg\_name to be duplicated. Returns A pointer to an array of two new cg\_names, each representing the same value as the original. These should be copied out of the array immediately since subsequent calls to CGDuplicate will overwrite the array.

### cg\_name CGBitMask( cg\_name name, byte start, byte len, cg\_type type )

Yields the address of a bit field. This address may not really be used except with an indirection operator or as the destination of an assignment operation.

Parameter	Definition
name	The address of the integral variable containing the bit field.
start	The position of the least significant bit of the bit field. 0 indicates the least significant bit of the host data type.
len	The length of the bit field in bits.
type	The integral type of the value containing the bit field.
Returns	The address of the bit field. To reference field2 in the following C structure for a little endian target, use start=4, len=5, and type=TY_INT_2. For a big endian target, start=7.
:	def struct { short field1 : 4; short field2 : 5; short field3 : 7;

}

### cg\_name CGVolatile( cg\_name name )

Indicate that the given address points to a volatile location. This back end does not remember this information beyond this node in the expression tree. If an address points to a volatile location, the front end must call this routine each time that address is used.

 Parameter
 Definition

 name
 The address of the volatile location.

 Returns
 A new cg\_name representing the same value as name.

### cg\_name CGCallback( cg\_callback func, void \*ptr )

When a callback node is inserted into the tree, the code generator will call the given function with the pointer as a parameter when it turns the node into an instruction. This can be used to retrieve order information about the placement of nodes in the instruction stream.

Parameter	Definition
func	This is a pointer to a function which is compatible with the C type "void (*)(void *)". This function will be called with the second parameter to this function as it's only parameter sometime during the execution of the CGDone call.
ptr	This will be a parameter to the function given as the first parameter.

### cg\_name CGPatchNode( patch\_handle hdl, cg\_type type )

This prepares a leaf node to hold an integer constant which will be provided sometime during the execution of the CGDone call by means of a BEPatchInteger() call. It is an error to insert a patch node into the tree and not call BEPatchInteger().

Parameter	Definition
hdl	A handle for a patch allocated with BEPatch().
tvpe	The actual type of the node. Must be an integer type.

# **Data Generation**

The following routines generate a data item described at the current location in the current segment, and increment the current location by the size of the generated object.

### void DGLabel( back\_handle bck )

Generate the label for a given back\_handle.

Parameter Definition

bck A back\_handle.

# void DGBackPtr( back\_handle bck, segment\_id segid, signed\_32 offset, cg\_type type )

Generate a pointer to the label defined by the back\_handle.

Parameter	Definition
bck	A back_handle.
segid	The segment_id of the segment in which the label for <b>bck</b> will be defined if it has not already been passed to DGLabel.
offset	A value to be added to the generated pointer value.
type	The pointer type to be used.

# void DGFEPtr( cg\_sym\_handle sym, cg\_type type, signed\_32 offset )

Generate a pointer to the label associated with sym.

Parameter	Definition
sym	A cg_sym_handle.
type	The pointer type to be used.
offset	A value to be added to the generated pointer value.

### void DGInteger( unsigned\_32 value, cg\_type type )

Generate an integer.

**Parameter** Definition

value An integral value.

The integral type to be used. type

### void DGInteger64( unsigned\_64 value, cg\_type type )

Generate an 64-bit integer.

Parameter Definition

value An 64-bit integer value.

The integral type to be used. type

### void DGFloat( char \*value, cg\_type type )

Generate a floating-point constant.

**Parameter** Definition

An E format string (ie: 1.2345e-134) value

type The floating point type to be used.

# void DGChar( char value )

Generate a character constant. Will be translated if cross compiling.

**Parameter** Definition

value A character value.

### void DGString( char \*value, uint len )

Generate a character string. Will be translated if cross compiling.

Parameter Definition

Pointer to the characters to put into the segment. It is not necessarily a null terminated value

string.

len The length of the string.

### void DGBytes( unsigned\_32 len, byte \*src )

Generate raw binary data.

Parameter Definition

src Pointer to the data.

*len* The length of the byte stream.

### void DGIBytes( unsigned\_32 len, byte pat )

Generate the byte pat, len times.

Parameter Definition

*pat* The pattern byte.

*len* The number of times to repeat the byte.

### void DGUBytes( unsigned\_32 len )

Generate len undefined bytes.

Parameter Definition

*len* The size by which to increase the segment.

# void DGAlign( uint align )

Align the segment to an align byte boundary. Any slack bytes will have an undefined value.

Parameter Definition

*align* The desired alignment boundary.

# unsigned\_32 DGSeek( unsigned\_32 where )

Seek to a location within a segment.

Parameter Definition

*where* The location within the segment.

**Returns** The current location in the segment before the seek takes place.

# unsigned long DGTell()

Returns The current location within the segment.

# unsigned long DGBackTell( back\_handle bck )

Returns The location of the label within its segment. The label must have been previously

generated via DGLabel.

# Front End Routines

### void FEGenProc( cg\_sym\_handle sym )

This routine will be called when the back end is generating a tree and encounters a function call having the **call\_class** FECALL\_GEN\_MAKE\_CALL\_INLINE. The front end must save its current state and start generating code for **sym**. FEGenProc calls may be nested if the code generator encounters an inline within the code for an inline function. The front end should maintain a state stack. It is up to the front end to prevent infinite recursion.

Parameter Definition

**sym** The cg\_sym\_handle of the function to be generated.

### back\_handle FEBack( cg\_sym\_handle sym )

Return, and possibly allocate using BENewBack, a back handle for sym. See the example under "Back Handles" on page 15

Parameter Definition

sym

**Returns** A back\_handle.

### segment\_id FESegID( cg\_sym\_handle sym )

Return the segment\_id for symbol **sym**. A negative value may be returned to indicate that the symbol is defined in an unknown PRIVATE segment which has been defined in another module. If two symbols have the same negative value returned, the back end assumes that they are both defined in the same (unknown) segment.

Parameter Definition

sym A cg\_sym\_handle.

**Returns** A segment\_id.

### char \*FEModuleName()

**Returns** A null terminated string which is the name of the module being compiled. This is usually

the file name with path and extension information stripped.

### char FEStackCheck( cg\_sym\_handle sym )

**Returns** 1 if stack checking required for this routine

### unsigned FELexLevel( cg\_sym\_handle sym )

**Returns** The lexical level of routine sym. This must be zero for all languages except Pascal. In

Pascal, 1 indicates the level of the main program. Each nested procedures adds an

additional level.

### char \*FEName( cg\_sym\_handle sym )

**Returns** A NULL terminated character string which is the name of sym. A null string should be

returned if the symbol has no name. NULL should never be returned.

### char \*FEExtName( cg\_sym\_handle sym, int request )

**Returns** A various kind in dependency on request parameter.

Request parameter Returns

EXTN\_BASENAME NULL terminated character string which is the name of sym. A null string should be

returned if the symbol has no name. NULL should never be returned.

EXTN\_PATTERN NULL terminated character string which is the pattern for symbol name decoration. '\*'

is replaced by symbol name. '^' is replaced by its upper case equivalent. '!' is replaced by its lower case equivalent. '#' is replaced by '@nnn' where nnn is decimal number representing total size of all function parameters. If an '\' is present, the character

following is used literally.

EXTN\_PRMSIZE Returns int value which represent size of all parameters when symbol is function.

### cg\_type FEParmType( cg\_sym\_handle func, cg\_sym\_handle parm, cg\_type type )

**Returns** The type to which to promote an argument with a given type before passing it to a

procedure. Type will be a dealiased type.

### int FETrue()

**Returns** The value of TRUE. This is normally 1.

### char FEMoreMem( size\_t size )

Release memory for the back end to use.

Parameter Definition

size is the amount of memory required

**Returns** 1 if at least **size** bytes were released. May always return 0 if memory is not a scarce

resource in the host environment.

### dbg\_type FEDbgType( cg\_sym\_handle sym )

**Returns** The dbg\_type handle for the symbol sym.

### fe\_attr FEAttr( cg\_sym\_handle sym )

Return symbol attributes for **sym**. These are bits combinable with the bit-wise or operator |.

Parameter Definition

sym A cg\_sym\_handle.

Return value Definition

*FE\_PROC* A procedure.

**FE\_STATIC** A static or external symbol.

FE\_GLOBAL Is a global (extern) symbol.

**FE\_IMPORT** Needs to be imported.

**FE\_CONSTANT** The symbol is read only.

**FE\_MEMORY** This automatic variable needs a memory location.

**FE\_VISIBLE** Accessible outside this procedure?

**FE\_NOALIAS** No pointers point to this symbol.

FE\_UNIQUE This symbol should have an address which is different from all other symbols

with the FE\_UNIQUE attribute.

**FE\_COMMON** There might be multiple definitions of this symbol in a program, and it should be

generated in such a way that all versions of the symbol are merged into one copy

by the linker.

FE\_ADDR\_TAKEN The symbol has had it's address taken somewhere in the program (not

necessarally visible to the code generator).

**FE\_VOLATILE** The symbol is "volatile" (in the C language sense).

**FE\_INTERNAL** The symbol is not at file scope.

### void FEMessage( fe\_msg femsg, void \*extra )

Relays information to the front end.

Parameter Definition

femsg Defined below.

extra Extra information. The type and meaning depends on the value of **femsg** and is indicated

below.

FEMSG\_INFO\_FILE Informational message about file. extra (void) is ignored.

FEMSG\_CODE\_SIZE Code size. Extra (int) is the size of the generated code.

FEMSG\_DATA\_SIZE Data size. Extra (int) is the size of the generated data.

**FEMSG\_ERROR** A back end error message. Extra (char \*) is the error message.

**FEMSG\_FATAL** A fatal code generator error. Extra (char \*) is the reason for the fatal

error. The front end should issue this message and exit immediately to

the system.

FEMSG INFO PROC Informational message about current procedure. Extra (char \*) is a

message.

FEMSG\_BAD\_PARM\_REGISTER

Invalid parameter register returned from FEAuxInfo. Extra (int) is

position of the offending parameter.

FEMSG\_BAD\_RETURN\_REGISTER

Invalid return register returned from FEAuxInfo. Extra (aux\_handle) is

the offending aux\_handle.

FEMSG\_REGALLOC\_DIED The register alloc ran out of memory. Extra (cg\_sym\_handle) is the

procedure which was not fully optimized.

FEMSG\_SCOREBOARD\_DIED The register scoreboard ran out of memory. Extra (cg\_sym\_handle) is

the procedure which was not fully optimized.

FEMSG\_PEEPHOLE\_FLUSHED

Peep hole optimizer flushed due to lack of memory. (void)

FEMSG\_BACK\_END\_ERROR BAD NEWS! Internal compiler error. Extra (int) is an internal error

number.

FEMSG\_BAD\_SAVE Invalid register modification information return from FEAuxInfo.

Extra (aux\_handle) is the offending aux\_handle.

FEMSG\_WANT\_MORE\_DATA The back end wants more data space. Extra (int) is amount of

additional memory needed to run. (DOS real mode hosts only).

**FEMSG BLIP** Blip. Let the world know we're still alive by printing a dot on the

screen. This is called approximately every 4 seconds during code

generation. (void)

FEMSG\_BAD\_LINKAGE Cannot resolve linkage conventions. 370 only. (sym)

FEMSG\_SCHEDULER\_DIED Instruction scheduler ran out of memory. Extra (cg\_sym\_handle) is the

procedure which was not fully optimized.

FEMSG\_NO\_SEG\_REGS (Only occurs in the x86 version). The cg\_switches did not allow any

segment registers to float, but the user has requested a far pointer indirection. Extra (cg\_sym\_handle) is the procedure which contained

the far pointer usage.

FEMSG\_SYMBOL\_TOO\_LONG Given symbol is too long and is truncated to maximum permited length

for current module output format. Extra (cg\_sym\_handle) is the symbol

which was truncated.

### void \*FEAuxInfo( void \*extra, aux\_class class )

relay information to back end

Parameter Definition

*extra* Extra information. Its type and meaning is determined by the value of class.

class Defined below.

Parameters Return Value

(cg\_sym\_handle, FEINF\_AUX\_LOOKUP)

aux\_handle - given a cg\_sym\_handle, return an aux\_handle.

(aux\_handle, FEINF\_CALL\_BYTES)

byte\_seq \* - A pointer to bytes to be generated instead of a call, or NULL if a call is to be generated.

```
typedef struct byte_seq {
    char length;
    char data[1];
} byte_seq;
```

( aux\_handle, FEINF\_CALL\_CLASS )

call\_class \* - returns call\_class of the given aux\_handle. See definitions below.

(short, FEINF\_FREE\_SEGMENT)

short - A free segment value which is free memory for the code generator to use. The first word at segment:0 is the size of the free memory in bytes. (DOS real mode host only)

(NULL, FEINF\_OBJECT\_FILE\_NAME)

char \* - The name of the object file to be generated.

#### (aux handle, FEINF PARM REGS)

hw\_reg\_set[] - The set of register to be used as parameters.

#### ( aux\_handle, FEINF\_RETURN\_REG )

hw\_reg\_set \* - The return register. This is only called if the routine is declared to have the FEINF\_SPECIAL\_RETURN call\_class.

#### ( NULL, FEINF\_REVISION\_NUMBER )

int - Front end revision number. Must return II\_REVISION.

#### ( aux\_handle, FEINF\_SAVE\_REGS )

hw\_reg\_set \* - Registers which are preserved by the routine.

#### (cg\_sym\_handle, FEINF\_SHADOW\_SYMBOL)

cg\_sym\_handle - An alternate handle for a symbol. Required for FORTRAN. Usually implemented by turning on the LSB of a pointer or MSB of an integer.

#### (NULL, FEINF\_SOURCE\_NAME)

char \* - The name of the source file to be put into the object file.

#### (cg\_sym\_handle, FEINF\_TEMP\_LOC\_NAME)

Return one of TEMP\_LOC\_NO, TEMP\_LOC\_YES,

TEMP\_LOC\_QUIT. After the back end has assigned stack locations to those temporaries which were not placed in registers, it begins to call FEAuxInfo with this request and passes in the cg\_sym\_handle for each of those temporaries. If the front end responds with TEMP\_LOC\_QUIT the back end will stop making FEINF\_TEMP\_LOC\_NAME requests. If the front end responds with TEMP\_LOC\_YES the back end will then perform a FEINF\_TEMP\_LOC\_TELL request (see next). If the front end returns TEMP\_LOC\_NO the back end moves onto the next cg\_sym\_handle in its list.

#### (int, FEINF\_TEMP\_LOC\_TELL)

Returns nothing. The 'int' value passed in is the relative position on the stack for the temporary identified by the cg\_sym\_handle passed in from the previous FEINF\_TEMP\_LOC\_NAME. The value for an individual temporary has no meaning, but the difference between two of the values is the number of bytes between the addresses of the temporaries on the stack.

#### (void \*, FEINF\_NEXT\_DEPENDENCY)

Returns the handle of the next dependency file for which information is available. To start the list off, the back end passes in NULL for the dependency file handle.

#### (void \*, FEINF\_DEPENDENCY\_TIMESTAMP)

Given the dependency file handle from the last FEINF\_NEXT\_DEPENDENCY request, return pointer to an unsigned long containing a timestamp value for the dependency file.

#### (void \*, FEINF\_DEPENDENCY\_NAME)

Given the dependency file handle from the last

FEINF\_NEXT\_DEPENDENCY request, return a pointer to a string containing the name for the dependency file.

#### (NULL, FEINF\_SOURCE\_LANGUAGE)

Returns a pointer to a string which identifies the source language of the pointer. E.g. "C" for C, "FORTRAN" for FORTRAN, "CPP" for C++.

#### ( cg\_sym\_handle, FEINF\_DEFAULT\_IMPORT\_RESOLVE )

Only called for imported symbols. Returns a cg\_sym\_handle for another imported symbol which the reference should be resolved to if certain conditions are met (see FEINF\_IMPORT\_TYPE request). If NULL or the original cg\_sym\_handle is returned, there is no default import resolution symbol.

#### (int, FEINF\_UNROLL\_COUNT)

Returns a user-specified unroll count, or 0 if the user did not specify an unroll count. The parameter is the nesting level of the loop for which the request is being made. Loops which are not contained inside of other loops are nesting level 1. If this function returns a non-zero value, the loop in question will be unrolled that many times (there will be (count + 1) copies of the body).

#### x86 Parameters

#### Return value

#### (NULL, FEINF\_CODE\_GROUP)

char \* - The name of the code group.

#### (aux\_handle, FEINF\_STRETURN\_REG)

hw\_reg\_set \* - The register which points to a structure return value. Only called if the routine has the FEINF\_SPECIAL\_STRUCT\_RETURN attribute.

#### (void \*, FEINF\_NEXT\_IMPORT)

void \* (See notes at end) - A handle for the next symbol to generate a reference to in the object file.

#### (void\*, FEINF\_IMPORT\_NAME)

char \* - The EXTDEF name to generate given a handle

#### (void \*, FEINF\_NEXT\_IMPORT\_S)

void \* (See notes at end) - A handle for the next symbol to generate a reference to in the object file.

#### (void\*, FEINF IMPORT NAME S)

Returns a cg\_sym\_handle. The EXTDEF name symbol reference to generate given a handle.

#### (void\*, FEINF\_NEXT\_LIBRARY)

void \* (See notes at end) - Handle for the next library required

#### (void\*, FEINF\_LIBRARY\_NAME)

char \* - The library name to generate given a handle

#### (NULL, FEINF DATA GROUP)

char \* - Used to name DGROUP exactly. NULL means use no group at all.

#### ( segment\_id, FEINF\_CLASS\_NAME )

NULL - Used to name the class of a segment.

(NULL, FEINF\_USED\_8087) NULL - Indicate that 8087 instructions were generated.

#### (NULL, FEINF\_STACK\_SIZE\_8087)

int - How many 8087 registers are reserved for stack.

#### (NULL, FEINF\_CODE\_LABEL\_ALIGNMENT)

char \* - An array x, such that x[i] is the label alignment requirements for labels nested within i loops.

#### (NULL, FEINF\_PROEPI\_DATA\_SIZE)

int - How much stack is reserved for the prolog hook routine.

#### ( cg\_sym\_handle, FEINF\_IMPORT\_TYPE )

Returns IMPORT\_IS\_WEAK, IMPORT\_IS\_LAZY,

IMPORT\_IS\_CONDITIONAL or

IMPORT\_IS\_CONDITIONAL\_PURE. If the

FEINF\_DEFAULT\_IMPORT\_RESOLVE request returned a default resolution symbol the back end then performs an

FEINF\_IMPORT\_TYPE request to determine the type of the resolution. IMPORT\_IS\_WEAK generates a weak import (the symbol is not searched for in libraries). IMPORT\_IS\_LAZY generates a lazy import (the symbol is searched for in libraries).

IMPORT\_IS\_CONDITIONAL is used for eliminating unused virtual functions. The default symbol resolution is used if none of the conditional symbols are referenced/defined by the program. The back end is informed of the list of conditional symbols by the following three aux requests. IMPORT\_IS\_CONDITIONAL\_PURE is used for eliminating unused pure virtual functions.

#### (cg\_sym\_handle, FEINF\_CONDITIONAL\_IMPORT)

Returns void \*. Once the back end determines that it has a conditional import, it performs this request to get a conditional list handle which is the head of the list of conditional symbols.

#### (void \*, FEINF\_CONDITIONAL\_SYMBOL)

Returns a cg\_sym\_handle. Give an conditional list handle, return the front end symbol associated with it.

#### (void \*, FEINF\_NEXT\_CONDITIONAL)

Given an conditional list handle, return the next conditional list handle. Return NULL at the end of the list.

#### ( aux\_handle, FEINF\_VIRT\_FUNC\_REFERENCE )

Returns void \*. When performing an indirect function call, the back end invokes FEAuxInfo passing the aux\_handle supplied with the CGInitCall. If the indirect call is referencing a C++ virtual function, the front end should return a magic cookie which is the head of a list of

virtual functions that might be invoked by this call. If it is not a virtual function invocation, return NULL.

#### (void \*, FEINF\_VIRT\_FUNC\_NEXT\_REFERENCE)

Returns void \*. Given the magic cookie returned by the FEINF\_VIRT\_FUNC\_REFERENCE or a previous FEINF\_VIRT\_FUNC\_NEXT\_REFRENCE, return the next magic cookie in the list of virtual functions that might be refrenced from this

indirect call. Return NULL if at the end of the list.

#### (void \*, FEINF\_VIRT\_FUNC\_SYM)

Returns cg\_sym\_handle. Given a magic cookie from a

FEINF\_VIRT\_FUNC\_REFERENCE or

FEINF VIRT FUNC NEXT REFERENCE, return the

cg\_sym\_handle for that entry in the list of virtual functions that might be invoked.

#### (segment\_id, FEINF\_PEGGED\_REGISTER)

Returns a pointer at a hw\_reg\_set or NULL. If the pointer is non-NULL and the hw\_reg\_set is not EMPTY, the hw\_reg\_set will indicate a segment register that is pegged (pointing) to the given segment\_id. The code generator will use this segment register in any references to objects in the segment. If the pointer is NULL or the hw\_reg\_set is EMPTY, the code generator uses the cg\_switches to determine if a segment register is pointing at the segment or if it will have to load one.

Call Class

Meaning

#### FECALL\_GEN\_REVERSE\_PARMS

Reverse the parameter list.

**FECALL GEN ABORTS** Routine never returns, optimize caller and callee.

**FECALL\_GEN\_NORETURN** Routine never returns, no optimization, portable.

#### FECALL\_GEN\_PARMS\_BY\_ADDRESS

Pass parameters by reference.

#### FECALL\_GEN\_MAKE\_CALL\_INLINE

Call should be inline. FEGenProc will be called for code sequence when required.

x86 Call Class Meaning

**FECALL\_X86\_FAR\_CALL** Does routine require a far call/return.

FECALL\_X86\_LOAD\_DS\_ON\_CALL

Load DS from DGROUP prior to call.

FECALL\_X86\_CALLER\_POPS Caller pops/removes parms from the stack.

#### FECALL\_X86\_ROUTINE\_RETURN

Routine allocates structure return memory.

FECALL\_X86\_SPECIAL\_RETURN

Routine has non-default return register.

FECALL\_X86\_NO\_MEMORY\_CHANGED

Routine modifies no visible statics.

FECALL\_X86\_NO\_MEMORY\_READ

Routine reads no visible statics.

FECALL\_X86\_MODIFY\_EXACT

Routine modifies no parameter registers.

FECALL\_X86\_SPECIAL\_STRUCT\_RETURN

Routine has special struct return register.

 $FECALL\_X86\_NO\_STRUCT\_REG\_RETURNS$ 

Pass 2/4/8 byte structs on stack, as opposed to registers.

FECALL\_X86\_NO\_FLOAT\_REG\_RETURNS

Return floats as structs.

**FECALL\_X86\_INTERRUPT** Routine is an interrupt routine.

FECALL\_X86\_NO\_8087\_RETURNS

No return values in the 8087.

FECALL\_X86\_LOAD\_DS\_ON\_ENTRY

Load ds with dgroup on entry.

**FECALL\_GEN\_DLL\_EXPORT** Is routine an OS/2 export symbol?

FECALL\_X86\_PROLOG\_FAT\_WINDOWS

Generate the real mode windows prolog code.

FECALL\_X86\_GENERATE\_STACK\_FRAME

Always generate a traceable prolog.

FECALL\_X86\_EMIT\_FUNCTION\_NAME

Emit the function name in front of the function in the code segment.

FECALL\_X86\_GROW\_STACK Emit a call to grow the stack on entry

FECALL\_X86\_PROLOG\_HOOKS

Generate a prolog hook call.

FECALL\_X86\_EPILOG\_HOOKS

Generate an epilog hook call.

FECALL\_X86\_THUNK\_PROLOG

Generate a thunking prolog for routines calling 16 bit code.

FECALL\_X86\_FAR16\_CALL Performs a 16:16 call in the 386 compiler.

FECALL\_X86\_TOUCH\_STACK Certain people (who shall remain nameless) have implemented an operating system (which shall remain nameless) that can't be bothered figuring out whether a page reference is in the stack or not. This attribute forces the first reference to the stack (after a routine prologue has grown it) to be through the SS register.

# **Debugging Information**

These routines generate information about types, symbols, etc.

### void DBLineNum( uint no )

Set the current source line number.

Parameter Definition

**no** Is the current source line number.

### void DBModSym( cg\_sym\_handle sym, cg\_type indirect )

Define a symbol within the module (file scope).

Parameter Definition

*sym* is a front end symbol handle.

*indirect* is the type of indirection needed to obtain the value

# void DBObject( dbg\_type tipe, dbg\_loc loc )

Define a function as being a member function of a C++ class, and identify the type of the class and the location of the object being manipulated. This function may only be done after the DBModSym for the function.

Parameter Definition

*tipe* is the debug type of the class that the function is a member of.

*loc* is a location expression that evaluates to the address of the object being manipulated by the

function (the contents of the 'this' pointer in C++). This parameter is NULL if the routine

is a static member function.

# void DBLocalSym( cg\_sym\_handle sym, cg\_type indirect )

As DBModSym but for local (routine scope) symbols.

### void DBGenSym( cg\_sym\_handle sym, dbg\_loc loc, int scoped )

Define a symbol either with module scope ('scoped' == 0) or within the current block ('scoped' != 0). This routine superseeds both DBLocalSym and DBModuleSym. The 'loc' parameter is a location expression (explained later) which allows an aribitrary sequence of operations to locate the storage for the symbol.

Parameter	Definition
sym	is a front end symbol handle.
loc	the location expression which is evaluated by the debugger to locate the lvalue of the symbol.
scoped	whether the symbol is file scoped or not.

### void DBBegBlock()

Open a new scope level.

### void DBEndBlock()

Close the current scope level.

### dbg\_type DBScalar( char \*name, cg\_type tipe )

Defines the string **name** to have type **tipe**.

### dbg\_type DBScope( char \*name )

define a symbol which "scopes" subsequent symbols. In C, the keywords **enum**, **union**, **struct** may perform this function as in **struct foo**.

# dbg\_name DBBegName( const char \*name, dbg\_type scope )

start a type name whose type is yet undetermined

### dbg\_type DBForward( dbg\_name name )

declare a type to be a forward reference

# dbg\_type DBEndName( dbg\_name name, dbg\_type tipe )

complete the definition of a type name.

### dbg\_type DBArray( dbg\_type index, dbg\_type base )

define a C array type

### dbg\_type DBIntArray( unsigned\_32 hi, dbg\_type base )

define a C array type

### dbg\_type DBSubRange( signed\_32 lo, signed\_32 hi, dbg\_type base )

define an integer range type

### dbg\_type DBPtr( cg\_type ptr\_type, dbg\_type base )

declare a pointer type

### dbg\_type DBBasedPtr( cg\_type ptr\_type, dbg\_type base, dbg\_loc seg\_loc )

declare a based pointer type. The 'seg\_loc' parameter is a location expression which evaluates to the base address for the pointer after the indirection has been performed. Before the location expression is evaluated, the current lvalue of the pointer symbol associated with this type is pushed onto the expression stack (needed for based on self pointers).

### dbg\_struct DBBegStruct()

start a structure type definition

# void DBAddField( dbg\_struct st, unsigned\_32 off, char \*nm, dbg\_type base )

add a field to a structure

# void DBAddBitField( dbg\_struct st, unsigned\_32 off, byte strt, byte len, char \*nm, dbg\_type base )

add a bit field to a structure

# void DBAddLocField( dbg\_struct st, dbg\_loc loc, uint attr, byte strt, byte len, char \*nm, dbg\_type base )

Add a field or bit field to a structure with a generalized location expression 'loc'. The location expression should assume the the address of the base of the structure has already been pushed onto the debugger's evaluation stack. The 'attr' parameter contains a zero or more of the following attributes or'd together:

Attribute Definition

**FIELD\_ATTR\_INTERNAL** the field is internally generated by the compiler and would not be normally visible to the user.

*FIELD\_ATTR\_PUBLIC* the field has the C++ 'public' attribute.

FIELD\_ATTR\_PROTECTED the field has the C++ 'protected' attribute.

FIELD\_ATTR\_PRIVATE the field has the C++ 'private' attribute.

If the field being described is \_not\_ a bit field, the 'len' parameter should be set to zero.

### void DBAddInheritance( dbg\_struct st, dbg\_type inherit, dbg\_loc adjust )

Add the fields of an inherited structure to the current structure being defined.

Parameter	Definition
st	the dbg_struct handle for the structure currently being defined.
inherit	the dbg_type of a previously defined structure which is being inherited.
adjust	a location expression which evaluates to a value which is the amount to adjust the field offsets by in the inherited structure to access them in the current structure. The base address of the symbol associated with the structure type is pushed onto the location expression stack before the expression is evaluated.

### dbg\_type DBEndStruct( dbg\_struct st )

end a structure definition

# dbg\_enum DBBegEnum( cg\_type tipe )

begin defining an enumerated type

# void DBAddConst( dbg\_enum en, const char \*nm, signed\_32 val )

add a symbolic constant to an enumerated type

# void DBAddConst64( dbg\_enum en, const char \*nm, signed\_64 val )

add a symbolic 64-bit integer constant to an enumerated type

### dbg\_type DBEndEnum( dbg\_enum en )

finish declaring an enumerated type

### dbg\_proc DBBegProc( cg\_type call\_type, dbg\_type ret )

begin the a current procedure

### void DBAddParm( dbg\_proc pr, dbg\_type tipe )

declare a parameter to the procedure

### dbg\_type DBEndProc( proc\_list \*pr )

end the current procedure

### dbg\_type DBFtnType( char \*name, dbg\_ftn\_type tipe )

declare a fortran COMPLEX type

### dbg\_type DBCharBlock( unsigned\_32 len )

declare a type to be a block of length len characters

### dbg\_type DBIndCharBlock( back\_handle len, cg\_type len\_type, int off )

declare a type to be a block of characters. The length is found at run-time at back\_handle **len** + offset **off**. The integral type of the back\_handle location is **len\_type** 

### dbg\_type DBLocCharBlock( dbg\_loc loc, cg\_type len\_type )

declare a type to be a block of characters. The length is found at run-time at the address specified by the location expression **loc**. The integral type of the location is **len\_type** 

# dbg\_type DBFtnArray( back\_handle dims, cg\_type lo\_bound\_tipe, cg\_type num\_elts\_tipe, int off, dbg\_type base )

define a FORTRAN array dimension slice. **dims** is a back handle + offset **off** which will point to a structure at run-time. The structure contains the array low bound (type **lo\_bound\_tipe**) followed by the number of elements (type **num\_elts\_tipe**). **base** is the element type of the array.

### dbg\_type DBDereference( cg\_type ptr\_type, dbg\_type base )

declare a type to need an implicit de-reference to retrieve the value (for FORTRAN parameters)

**Notes:** This routine has been superceded by the use of location expressions.

### dbg\_loc DBLocInit( void )

create an initial empty location expression

### dbg\_loc DBLocSym( dbg\_loc loc, cg\_sym\_handle sym )

push the address of 'sym' on to the expression stack

### dbg\_loc DBLocTemp( dbg\_loc loc, temp\_handle tmp )

push the address of 'tmp' on to the expression stack

### dbg\_loc DBLocConst( dbg\_loc loc, unsigned\_32 val )

push the constant 'val' on to the expression stack

### dbg\_loc DBLocOp( dbg\_loc loc, dbg\_loc\_op op, unsigned other )

perform the following list of operations on the expression stack

Operation Definition

- **DB\_OP\_POINTS** take the top of the expression stack and use it as the address in an indirection operation. The result type of the operation is given by the 'other' parameter which must be a cg\_type which resolves to either an unsigned\_16, unsigned\_32, a 16-bit far pointer, or a 32-bit far pointer.
- **DB\_OP\_ZEX** zero extend the top of the stack. The 'other' parameter is a cg\_type which is either 1 byte in size or 2 bytes in size. That size determines how much of the original top of stack value to leave untouched.
- **DB\_OP\_XCHG** exchange the top of stack value with the stack entry indexed by 'other'.
- **DB\_OP\_MK\_FP** take the top two entries on the stack. Make the second entry the segment value and the first entry the offset value of an address.
- **DB\_OP\_ADD** add the top two stack entries together.
- **DB\_OP\_DUP** duplicate the top stack entry.
- **DB\_OP\_POP** pop off (throw away) the top stack entry.

### void DBLocFini( dbg\_loc loc )

the given location expression will not be used anymore.

### unsigned DBSrcFile( char \*fname )

add the file name into the list of source files for positon info, return handle to this name

**Notes:** Handle 0 is reserved for base source file name and is added by BE automatically during initialization.

### void DBSrcCue( unsigned fno, unsigned line, unsigned col )

add source position info for the appropriate source file

# Registers

The hw\_reg\_set type is an abstract data type capable of representing any combination of machine registers. It must be manipulated using the following macros. A parameter **c**, **c1**, **c2**, etc. indicate a register constant such as HW\_EAX must be used. Anything else must be a variable of type **hw\_reg\_set**.

The following are used for static initialization.

```
HW_D_1(c1)
HW_NotD_1(c1)
HW_D_2(c1, c2)
HW_NotD_2(c1, c2)
HW_D_3(c1, c2, c3)
HW_NotD_3(c1, c2, c3)
HW_D_4(c1, c2, c3, c4)
HW_NotD_4( c1, c2, c3, c4 )
HW_D_5(c1, c2, c3, c4, c5)
HW_NotD_5( c1, c2, c3, c4, c5 )
HW_D(c1)
HW_NotD(c1)
hw_reg_set regs[] = {
    /* the EAX register */
    HW_D ( HW_EAX ),
    /\,^\star all registers except EDX and EBX ^\star/\,
    HW_NotD_2( HW_EDX, HW_EBX )
};
```

The following are to build registers dynamically.

Macro	Usage
HW_CEqual(a, c)	Is <b>a</b> equal to <b>c</b>
HW_COvlap(a, c)	Does a overlap with c
HW_CSubset(a, c)	Is a subset of c
HW_CAsgn( dst, c )	Assign c to dst
HW_CTurnOn( dst, c )	Turn on registers c in dst.
HW_CTurnOff( dst, c )	Turn off registers c in dst.
HW_COnlyOn(a, c)	Turn off all registers except $\mathbf{c}$ in $\mathbf{dst}$ .
HW_Equal(a, b)	Is <b>a</b> equal to <b>b</b>
HW_Ovlap(a, b)	Does <b>a</b> overlap with <b>b</b>

```
HW\_Subset(a, b)
                                  Is a subset of b
HW_Asgn(dst, b)
                                  Assign b to dst
HW_TurnOn( dst, b )
                                  Turn on registers b in dst.
HW\_TurnOff(dst, b)
                                  Turn off registers b in dst.
HW_OnlyOn(dst, b)
                                  Turn off all registers except b in dst.
```

The following example selects the low order 16 bits of any register. that has a low part.

```
hw_reg_set low16( hw_reg_set reg )
    hw_reg_set low;
    HW_CAsqn( low, HW_EMPTY );
    HW_CTurnOn( low, HW_AX );
    HW_CTurnOn( low, HW_BX );
    HW_CTurnOn( low, HW_CX );
    HW_CTurnOn( low, HW_DX );
    if( HW_Ovlap( reg, low ) ) {
        HW_OnlyOn( reg, low );
    }
}
```

The following register constants are defined for all targets.

**HW\_EMPTY** The null register set.

**HW\_UNUSED** The set of unused register entries.

HW\_FULL All possible registers.

The following example yields the set of all valid machine registers.

```
hw_reg_set reg;
HW_CAsqn( reg, HW_FULL );
HW_CTurnOff( reg, HW_UNUSED );
```

## Miscellaneous

I apologize for my lack of consistency in this document. I use the terms function, routine, procedure interchangeably, as well as index, subscript - select, switch - parameter, argument - etc. I come from a multiple language background and will always be hopelessly confused.

The NEXT\_IMPORT/NEXT\_IMPORT\_S/NEXT\_LIBRARY are used as follows.

```
handle = NULL;
for(;;) {
   handle = FEAuxInfo( handle, NEXT_IMPORT );
   if( handle == NULL )
        break;
   do_something( FEAuxInfo( handle, IMPORT_NAME ) );
}
```

The FREE\_SEGMENT request is used as follows.

```
segment = 0;
for(;;) {
    segment = FEAuxInfo( segment, FREE_SEGMENT );
    if( segment == NULL )
        break;
    segment_size = *(short *)MK_FP( segment, 0 ) * 16;
    this_is_my_memory_now( MK_FP( segment, 0 ), segment_size );
}
```

The main line in Pascal is defined to be lexical level 1. Add 1 for each nested subroutine level. C style routines are defined to be lexical level 0.

The following types are defined by the code generator header files:

```
Utility type
                 Definition
bool
                 (unsigned char) 0 = \text{false}, non-0 = \text{true}.
byte
                 (unsigned char)
int 8
                 (signed char)
int_16
                 (signed short)
int_32
                 (signed long)
signed_8
                 (signed char)
signed_16
                 (signed short)
signed_32
                 (signed long)
```

uint (unsigned) uint\_8 (unsigned char) uint 16 (unsigned short) uint 32 (unsigned long) unsigned\_8 (unsigned char) unsigned\_16 (unsigned short) unsigned\_32 (unsigned long) real (float) reallong (double) pointer (void \*) **Type** Definition aux\_class (enum) Passed as 2nd parameter to FEAuxInfo. aux\_handle (void \*) A handle used as 1st parameter to FEAuxInfo. back\_handle (void \*) A handle for a back end symbol table entry. (struct) Passed to back end in response to FEINF\_CALL\_BYTES FEAuxInfo request. byte\_seq call\_class (unsigned long) A set of combinable bits indicating the call attributes for a routine. call\_handle (void \*) A handle to be used in CGInitCall, CGAddParm and CGCall. (union) The return value of BEInit. cg\_init\_info cg\_name (void \*) A handle for a back end expression tree node. (enum) An operator to be used in building expressions. cg\_op cg\_switches (unsigned\_32) A set of combinable bits indicating the code generator options. cg\_sym\_handle (uint) A handle for a front end symbol table entry. (unsigned short) A code generator type. cg\_type fe\_attr (enum) A set of combinable bits indicating symbol attributes. hw\_reg\_set (struct hw\_reg\_set) A structure representing a hardware register. label\_handle (void \*) A handle for a code generator code label. linkage\_regs (struct) For 370 linkage conventions.

```
more_cg_types (enum)
fe_msg
               (enum) The 1st parameter to FEMessage.
               (enum) The 3rd parameter to BEInit.
proc_revision
seg_attr
               (enum) A set of combinable bits indicate the attributes of a segment.
segment_id
               (int) A segment identifier.
sel_handle
               (void *) A handle to be used in the CGSel calls.
temp_handle
               (void *) A handle for a code generator temporary.
Misc Type
               Definition
HWT
               hw_reg_part
hw_reg_part
               (unsigned)
dbg\_enum
               (void *)
dbg_ftn_type
               (enum)
               (void *)
dbg_name
dbg_proc
               (void *)
dbg_struct
               (void *)
dbg_type
               (unsigned short)
predefined_cg_types (enum)
```

## A. Pre-defined macros

The following macros are defined by the code generator include files.

```
C_FRONT_END
CPU_MASK
DBG_FWD_TYPE
DBG_NIL_TYPE
DO_FLOATING_FIXUPS
DO_SYM_FIXUPS
FALSE
FIX_SYM_OFFSET
FIX_SYM_RELOFF
FIX_SYM_SEGMENT
FLOATING_FIXUP_BYTE
FORTRAN_FRONT_END
FPU_MASK
FRONT_END_MASK
FUNCS_IN_OWN_SEGMENTS
GET_CPU
GET_FPU
GET_WTK
HWREG_INCLUDED
HW_0
HW_1
HW_2
HW_3
HW_64
HW_Asgn
HW_CAsgn
HW_CEqual
HW_COMMA
HW_COnlyOn
HW_COvlap
HW_CSubset
HW_CTurnOff
HW_CTurnOn
HW_D
HW_D_1
HW_D_2
HW_D_3
HW D 4
HW_D_5
HW_DEFINE_COMPOUND
HW\_DEFINE\_GLOBAL\_CONST
HW_DEFINE_SIMPLE
```

HW\_Equal

```
HW_ITER
HW_NotD
HW_NotD_1
HW_NotD_2
HW_NotD_3
HW_NotD_4
HW_NotD_5
HW_OnlyOn
HW_Op1
HW_Op2
HW_Op3
HW_Op4
HW_Op5
HW_Ovlap
HW\_Subset
HW_TurnOff
HW_TurnOn
II_REVISION
MAX_POSSIBLE_REG
MIN_OP
NULL
NULLCHAR
O_FIRST_COND
O_FIRST_FLOW
O_LAST_COND
O_LAST_FLOW
SEG_EXTRN_FAR
SET_CPU
SET_FPU
SET_WTK
SYM_FIXUP_BYTE
TRUE
TY_HUGE_CODE_PTR
WTK_MASK
_AL
_{AX}
_BL
_BP
BX
_CG_H_INCLUDED
_CL
_CMS
_CX
_DI
_DL
_DX
_HOST_INTEGER
_OS
_SI
_TARG_AUX_SHIFT
_TARG_CGSWITCH_SHIFT
far
huge
interrupt
```

near offsetof

# B. Register constants

The following register constants are defined for x86 targets.

HW\_AH HW\_AL HW\_BH HW\_BL HW\_CH HW\_CL  $HW_DH$  $HW_DL$ HW\_SI HW\_DI HW\_BP HW\_SP  $HW_DS$ HW\_ES HW\_CS HW\_SS HW\_ST0 HW\_ST1  $HW\_ST2$ HW\_ST3 HW\_ST4 HW\_ST5 HW\_ST6 HW\_ST7 HW\_FS HW\_GS HW\_AX  $HW_BX$ HW\_CX  $HW_DX$ HW\_EAX HW\_EBX HW\_ECX HW\_EDX HW\_ESI HW\_EDI HW\_ESP

The following registers are defined for the Alpha AXP target.

```
HW_R0-HW_R31
HW_D0-HW_D31
```

HW\_EBP

```
HW_W0-HW_W31
HW_B0-HW_B31
HW_F0-HW_F31
```

The following registers are defined for the PowerPC target.

```
HW_R0-HW_R31
HW_Q3-HW_Q29
HW_D0-HW_D31
HW_W0-HW_W31
HW_B0-HW_B31
HW_F0-HW_F31
```

The following registers are defined for the MIPS32 target.

```
HW_R0-HW_R31
HW_Q2-HW_Q24
HW_D0-HW_D31
HW_W0-HW_W31
HW_B0-HW_B31
HW_F0-HW_F31
HW_FD0-HW_FD30
```

# C. Debugging Open Watcom Code Generator

If you want to use vc.dbg command, make sure you have a tmp directory in root of used filesystem (see bld/cg/dumpio.c for details).

Notes: Make a s:\tmp to facilitate debugging in s:\brad :) Yeah, it's a cheap and sleazy hack...

If you need to dump something and don't know the routine to call, try "e/s Dump" and see what pops up...

### Instructions

You can get a dump of instructions for current function via *DumpRange* anytime between *FixEdges* and start of *GenObject*.

You can dump an individual instruction via *DumpIns* 

If you need live info for a basic block, find address and call *DumpABlk(block)*.

### **Symbols**

If you need to see a list of symbols, use *DumpSymTab*. To look at one symbol, use *DumpSym*.

#### Tree Problems

Find the line number of a piece of source near the problem. Do a "bif { edx == LINENUMBER } DBSrcCue" to stop near that Go to CGDone in order to see what resulting tree is (DumpTree) If there is a problem with tree, but not with API calls, do to DBSrcCue as above and then break on next appropriate CG API call.

### Optimization Problems (Loopopts at all)

Find the ordinal of the problem function in the file (ie 4th function) Do a "bcnt 4 FixEdges" in order to stop on 4th call (for example) to FixEdges Dump instructions (using DumpRange) and see if problem is in trees If not, go to RegAlloc and see if problem shows up yet If so, binary search between FixEdges and RegAlloc to find optimization at fault.

### Instruction Select Problems

Go to *RegAlloc* for appropriate function (called once per function when not -od) Find address of instruction which gets translated or handled improperly. (Look in results of *DumpRange* for this address). Do a "bif { eax == address } *ExpandIns*" to look at what we do to this instruction (trace through).

## Register Allocation Problem

## Instruction Encoding Problem

Go to *RegAlloc* invocation for routine in question. Go to *GenObject* and call *DumpRange*. Find address of instruction that gets encoded incorrectly, and do a "bif { eax == address } *GenObjCode*" Trace into *GenObjCode* at appropriate time.

Α

arithmetic if 38 assignment 29-30

В

back handle 15-16, 47, 51 BEAbort 7 BEAliasType 18 BEDefSeg 9 BEDefType 18 BEFini 7 BEFiniBack 16 BEFiniLabel 13 BEFlushSeg 10 BEFreeBack 16 BEGetSeg 10 BEInit 3 BENewBack 15 BENewLabel 13 BESetSeg 10 BEStart 7 BEStop 7 BETypeAlign 19 BETypeLength 18 bit fields 44 boolean expressions 35, 37

C

calling conventions 55, 59
CG3WayControl 38
CGAddParm 33
CGAssign 29
CGAutoDecl 21
CGBackName 28
CGBigGoto 38
CGBigLabel 38
CGBinary 31
CGBitMask 44
CGChoose 37
CGCompare 35

CGControl 38 CGDone 43 CGDuplicate 44 CGEval 43 CGFEName 27 CGFloat 27 CGFlow 37 CGIndex 31 CGInitCall 33 CGInt64 27 CGInteger 27 CGLastParm 21 CGLVAssign 29 CGLVPreGets 29 CGParmDecl 21 CGPostGets 30 CGPreGets 29 CGProcDecl 21 CGReturn 43 CGSelCase 39 CGSelect 40 CGSelInit 39 CGSelOther 40 CGSelRange 40 CGTemp 22 CGTempName 28 CGTrash 43 CGType 44 CGUnary 31 CGVolatile 45 CGWarp 37 character 48 control flow 38-40 conversions 25

D

data 47
DBAddBitField 65
DBAddConst 66
DBAddConst64 66
DBAddField 65
DBAddInheritance 66
DBAddLocField 65
DBAddParm 67
DBArray 65
DBBasedPtr 65
DBBegBlock 64
DBBegEnum 66
DBBegName 64

DBBegProc 67
DBBegStruct 65
DBCharBlock 67
DBDereference 68
DBEndBlock 64
DBEndEnum 67
DBEndName 64
DBEndProc 67
DBEndStruct 66
DBForward 64
DBFtnArray 67
DBFtnType 67
DBGenSym 64
DBIndCharBlock 67
DBIntArray 65
DBLineNum 63
DBLocalSym 63
DBLocCharBlock 67
DBLocConst 68
DBLocFini 69
DBLocInit 68
DBLocOp 68
DBLocSym 68
DBLocTemp 68
DBModSym 63
DBObject 63
DBPtr 65
DBScalar 64
DBScope 64
DBSrcCue 69
DBSrcFile 69
DBSubRange 65
DGAlign 49
DGBackPtr 47
DGBackTell 50
DGBytes 49
DGChar 48
DGFEPtr 47
DGFloat 48
DGIBytes 49
DGInteger 48
DGInteger64 48
DGLabel 47
DGSeek 49
DGString 48
DGTell 50
DGUBytes 49



error messages 54 expressions 23, 31, 43-45



FEAttr 53 FEAuxInfo 55 FEBack 51 FEDbgType 53 FEExtName 52 FEGenProc 51 FELexLevel 52 FEMessage 54 FEModuleName 51 FEMoreMem 52 FEName 52 FEParmType 52 FESegID 51 FEStackCheck 52 FETrue 52 floating point constant 27, 48 FORTRAN 37-38 functions 21, 33, 43, 51



inline procedures 51 integers 27



label code 13 data 15, 28, 47 0

operators 23 options 3, 5

P

pascal 52 procedures 21, 33, 43, 51

R

registers 71 relocatable data item 47 routines 21, 33, 43, 51

S

segments 9-10, 47, 49-51 short circuit operations 35, 37 stack probes 52 statement functions 37

**T** 

temporaries 22, 28 types predefined 73 typing 17-19, 25, 44 V

variables 22, 27-28 volatile 45