■ NetApp

Reference

Set up and administration

NetApp December 01, 2022

This PDF was generated from https://docs.netapp.com/us-en/cloud-manager-setup-admin/reference-permissions.html on December 01, 2022. Always check docs.netapp.com for the latest.

Table of Contents

| Reference. | | | . 1 |
|------------|-----|------|------|------|------|------|------|------|------|------|------|------|------|------|------|------|------|------|-----|
| Permissi | ons | | . 1 |
| Ports | | | 52 |

Reference

Permissions

Permissions summary for BlueXP

In order to use the features and services in BlueXP, you'll need to provide permissions so that BlueXP can perform operations in your cloud environment. Use the links on this page to quickly access the permissions that you need based on your goal.

AWS permissions

| Purpose | Description | Link |
|----------------------------------|---|--|
| Connector deployment | The user who creates a Connector from BlueXP needs specific permissions to deploy the instance in AWS. | Create a Connector in AWS from BlueXP |
| Connector operation | policy to the instance that provides the permissions required to manage resources and processes in your AWS account. You need to set up the policy yourself if you launch a Connector from the marketplace or if you add | AWS permissions for the Connector |
| | more AWS credentials to a Connector. You also need to ensure that the policy is up to date as new permissions are added in subsequent releases. | |
| Cloud Volumes ONTAP operation | An IAM role must be attached to each Cloud Volumes ONTAP node in AWS. The same is true for the HA mediator. The default option is to let BlueXP create the IAM roles for you, but you can use your own. | Learn how to set up the IAM roles yourself |

Azure permissions

| Purpose | Description | Link |
|----------------------|--|---|
| Connector deployment | When you deploy a Connector from BlueXP, you need to use an Azure account or service principal that has permissions to deploy the Connector VM in Azure. | Create a Connector in Azure from BlueXP |

| Purpose | Description | Link |
|---------------------|--|-------------------------------------|
| Connector operation | When BlueXP deploys the Connector VM in Azure, it creates a custom role that provides the permissions required to manage resources and processes within that Azure subscription. | Azure permissions for the Connector |
| | You need to set up the custom role yourself if you launch a Connector from the marketplace or if you add more Azure credentials to a Connector. | |
| | You also need to ensure that the policy is up to date as new permissions are added in subsequent releases. | |

Google Cloud permissions

| Purpose | Description | Link |
|----------------------|--|--|
| Connector deployment | The Google Cloud user who deploys a Connector from BlueXP needs specific permissions to deploy the Connector in Google Cloud. | Set up permissions to deploy the Connector |
| Connector operation | The service account for the Connector VM instance must have specific permissions for day-to-day operations. You need to associate the service account with the Connector when you deploy it from BlueXP. You also need to ensure that the policy is up to date as new permissions are added in subsequent releases. | Set up a service account for the Connector |

AWS permissions for the Connector

When BlueXP launches the Connector instance in AWS, it attaches a policy to the instance that provides the Connector with permissions to manage resources and processes within that AWS account. The Connector uses the permissions to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Key Management Service (KMS), and more.

IAM policies

The IAM policies available below provide the permissions that a Connector needs to manage resources and processes within your public cloud environment based on your AWS region.

If you create a Connector in a standard AWS region directly from BlueXP, BlueXP automatically applies policies to the Connector. You don't need to do anything in this case.

If you deploy the Connector from the AWS Marketplace or if you manually install the Connector on a Linux host, then you'll need to set up the policies yourself.

You also need to ensure that the policies are up to date as new permissions are added in subsequent releases.

| Select your region to view the required policies: | |
|---|--|
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |

Standard regions

For standard regions, the permissions are spread across two policies. Two policies are required due to a maximum character size limit for managed policies in AWS.

The first policy provides permissions for the following services:

- Cloud Backup
- · Cloud Data Sense
- Cloud Tiering
- Cloud Volumes ONTAP
- FSx for ONTAP
- · S3 bucket discovery

The second policy provides permissions for the following services:

- AppTemplate tagging
- · Global File Cache
- Kubernetes

Policy #1

```
{
    "Version": "2012-10-17",
    "Statement": [
            "Sid": "cvoServicePolicy",
            "Effect": "Allow",
            "Action": [
                "ec2:DescribeInstances",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:DescribeInstanceAttribute",
                "ec2:DescribeRouteTables",
                "ec2:DescribeImages",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:ModifyVolumeAttribute",
                "ec2:CreateSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcs",
                "ec2:DescribeDhcpOptions",
                "ec2:CreateSnapshot",
                "ec2:DescribeSnapshots",
                "ec2:GetConsoleOutput",
                "ec2:DescribeKeyPairs",
                "ec2:DescribeRegions",
                "ec2:DescribeTags",
                "ec2:AssociateIamInstanceProfile",
                "ec2:DescribeIamInstanceProfileAssociations",
                "ec2:DisassociateIamInstanceProfile",
                "ec2:CreatePlacementGroup",
                "ec2:DescribeReservedInstancesOfferings",
                "ec2:AssignPrivateIpAddresses",
                "ec2:CreateRoute",
                "ec2:DescribeVpcs",
```

```
"ec2:ReplaceRoute",
"ec2:UnassignPrivateIpAddresses",
"ec2:DeleteSecurityGroup",
"ec2:DeleteNetworkInterface",
"ec2:DeleteSnapshot",
"ec2:DeleteTags",
"ec2:DeleteRoute",
"ec2:DeletePlacementGroup",
"ec2:DescribePlacementGroups",
"cloudformation:CreateStack",
"cloudformation:DescribeStacks",
"cloudformation:DescribeStackEvents",
"cloudformation: Validate Template",
"cloudformation:DeleteStack",
"iam:PassRole",
"iam:CreateRole",
"iam:PutRolePolicy",
"iam:CreateInstanceProfile",
"iam:AddRoleToInstanceProfile",
"iam: RemoveRoleFromInstanceProfile",
"iam:ListInstanceProfiles",
"iam:DeleteRole",
"iam:DeleteRolePolicy",
"iam: DeleteInstanceProfile",
"iam:GetRolePolicy",
"iam:GetRole",
"sts:DecodeAuthorizationMessage",
"sts:AssumeRole",
"s3:GetBucketTagging",
"s3:GetBucketLocation",
"s3:ListBucket",
"s3:CreateBucket",
"s3:GetLifecycleConfiguration",
"s3:ListBucketVersions",
"s3:GetBucketPolicyStatus",
"s3:GetBucketPublicAccessBlock",
"s3:GetBucketPolicy",
"s3:GetBucketAcl",
"s3:PutObjectTagging",
"s3:GetObjectTagging",
"s3:DeleteObject",
"s3:DeleteObjectVersion",
"s3:PutObject",
"s3:ListAllMyBuckets",
"s3:GetObject",
"s3:GetEncryptionConfiguration",
```

```
"kms:List*",
        "kms:ReEncrypt*",
        "kms:Describe*",
        "kms:CreateGrant",
        "ce:GetReservationUtilization",
        "ce:GetDimensionValues",
        "ce:GetCostAndUsage",
        "ce:GetTags",
        "fsx:Describe*",
        "fsx:List*"
    ],
    "Resource": "*"
},
    "Sid": "backupPolicy",
    "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
        "ec2:StopInstances",
        "ec2:DescribeInstances",
        "ec2:DescribeInstanceStatus",
        "ec2:RunInstances",
        "ec2:TerminateInstances",
        "ec2:DescribeInstanceAttribute",
        "ec2:DescribeImages",
        "ec2:CreateTags",
        "ec2:CreateVolume",
        "ec2:CreateSecurityGroup",
        "ec2:DescribeSubnets",
        "ec2:DescribeVpcs",
        "ec2:DescribeRegions",
        "cloudformation:CreateStack",
        "cloudformation: DeleteStack",
        "cloudformation:DescribeStacks",
        "kms:List*",
        "kms:Describe*",
        "ec2:describeVpcEndpoints",
        "kms:ListAliases",
        "athena:StartQueryExecution",
        "athena:GetQueryResults",
        "athena:GetQueryExecution",
        "glue:GetDatabase",
        "glue:GetTable",
        "glue:CreateTable",
        "glue:CreateDatabase",
        "glue:GetPartitions",
```

```
"glue:BatchCreatePartition",
        "qlue:BatchDeletePartition"
   ],
   "Resource": "*"
} ,
    "Sid": "backupS3Policy",
   "Effect": "Allow",
    "Action": [
       "s3:GetBucketLocation",
        "s3:ListAllMyBuckets",
        "s3:ListBucket",
        "s3:CreateBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketAcl",
        "s3:PutBucketPublicAccessBlock",
        "s3:GetObject",
        "s3:PutEncryptionConfiguration",
        "s3:DeleteObject",
        "s3:DeleteObjectVersion",
        "s3:ListBucketMultipartUploads",
        "s3:PutObject",
        "s3:PutBucketAcl",
        "s3:AbortMultipartUpload",
        "s3:ListMultipartUploadParts",
        "s3:DeleteBucket",
        "s3:GetObjectVersionTagging",
        "s3:GetObjectVersionAcl",
        "s3:GetObjectRetention",
        "s3:GetObjectTagging",
        "s3:GetObjectVersion",
        "s3:PutObjectVersionTagging",
        "s3:PutObjectRetention",
        "s3:DeleteObjectTagging",
        "s3:DeleteObjectVersionTagging",
        "s3:GetBucketObjectLockConfiguration",
        "s3:GetBucketVersioning",
        "s3:PutBucketObjectLockConfiguration",
        "s3:PutBucketVersioning",
        "s3:BypassGovernanceRetention",
        "s3:PutBucketPolicy",
        "s3:PutBucketOwnershipControls"
   ],
```

```
"Resource": [
       "arn:aws:s3:::netapp-backup-*"
   1
},
   "Sid": "fabricPoolS3Policy",
    "Effect": "Allow",
    "Action": [
        "s3:CreateBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock",
       "s3:DeleteBucket"
   ],
    "Resource": [
        "arn:aws:s3:::fabric-pool*"
   ]
},
   "Sid": "fabricPoolPolicy",
    "Effect": "Allow",
   "Action": [
        "ec2:DescribeRegions"
   ],
   "Resource": "*"
},
    "Effect": "Allow",
   "Action": [
        "ec2:StartInstances",
        "ec2:StopInstances",
        "ec2:TerminateInstances"
   ],
    "Condition": {
        "StringLike": {
            "ec2:ResourceTag/netapp-adc-manager": "*"
        }
    },
    "Resource": [
        "arn:aws:ec2:*:*:instance/*"
```

```
},
        "Effect": "Allow",
        "Action": [
            "ec2:StartInstances",
            "ec2:TerminateInstances",
            "ec2:AttachVolume",
            "ec2:DetachVolume",
            "ec2:StopInstances",
           "ec2:DeleteVolume"
        ],
        "Condition": {
            "StringLike": {
                "ec2:ResourceTag/WorkingEnvironment": "*"
        },
        "Resource": [
           "arn:aws:ec2:*:*:instance/*"
        ]
    },
        "Effect": "Allow",
        "Action": [
            "ec2:AttachVolume",
           "ec2:DetachVolume"
        "Resource": [
           "arn:aws:ec2:*:*:volume/*"
       ]
    },
        "Effect": "Allow",
        "Action": [
          "ec2:DeleteVolume"
        ],
        "Condition": {
            "StringLike": {
               "ec2:ResourceTag/WorkingEnvironment": "*"
            }
        },
        "Resource": [
          "arn:aws:ec2:*:*:volume/*"
        ]
   }
]
```

}

Policy #2

```
{
 "Version": "2012-10-17",
 "Statement": [
     "Sid": "K8sServicePolicy",
     "Effect": "Allow",
     "Action": [
          "ec2:DescribeRegions",
          "eks:ListClusters",
          "eks:DescribeCluster",
          "iam:GetInstanceProfile"
     ],
     "Resource": "*"
    },
        "Sid": "GFCservicePolicy",
        "Effect": "Allow",
        "Action": [
            "cloudformation:DescribeStacks",
            "cloudwatch:GetMetricStatistics",
            "cloudformation:ListStacks"
        ],
        "Resource": "*"
   } ,
        "Effect": "Allow",
        "Action": [
            "ec2:StartInstances",
            "ec2:TerminateInstances",
            "ec2:AttachVolume",
            "ec2:DetachVolume"
        ],
        "Condition": {
            "StringLike": {
               "ec2:ResourceTag/GFCInstance": "*"
            }
        },
        "Resource": [
           "arn:aws:ec2:*:*:instance/*"
       1
   },
```

```
"Sid": "tagServicePolicy",
    "Effect": "Allow",
    "Action": [
        "ec2:CreateTags",
        "ec2:DeleteTags",
        "ec2:DescribeTags",
        "tag:getResources",
        "tag:getTagKeys",
        "tag:getTagValues",
        "tag:TagResources",
        "tag:UntagResources"
],
    "Resource": "*"
}
```

```
{
    "Version": "2012-10-17",
    "Statement": [
            "Effect": "Allow",
            "Action": [
                "iam:ListInstanceProfiles",
                "iam:CreateRole",
                "iam:DeleteRole",
                "iam:PutRolePolicy",
                "iam:CreateInstanceProfile",
                "iam: DeleteRolePolicy",
                "iam:AddRoleToInstanceProfile",
                "iam: RemoveRoleFromInstanceProfile",
                "iam:DeleteInstanceProfile",
                "ec2:ModifyVolumeAttribute",
                "sts:DecodeAuthorizationMessage",
                "ec2:DescribeImages",
                "ec2:DescribeRouteTables",
                "ec2:DescribeInstances",
                "iam:PassRole",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:DeleteVolume",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DeleteNetworkInterface",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcs",
                "ec2:DescribeDhcpOptions",
                "ec2:CreateSnapshot",
                "ec2:DeleteSnapshot",
```

```
"ec2:DescribeSnapshots",
        "ec2:StopInstances",
        "ec2:GetConsoleOutput",
        "ec2:DescribeKeyPairs",
        "ec2:DescribeRegions",
        "ec2:DeleteTags",
        "ec2:DescribeTags",
        "cloudformation:CreateStack",
        "cloudformation: DeleteStack",
        "cloudformation: DescribeStacks",
        "cloudformation: DescribeStackEvents",
        "cloudformation: Validate Template",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:ListAllMyBuckets",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:CreateBucket",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "kms:List*",
        "kms:ReEncrypt*",
        "kms:Describe*",
        "kms:CreateGrant",
        "ec2: Associate Iam Instance Profile",
        "ec2:DescribeIamInstanceProfileAssociations",
        "ec2:DisassociateIamInstanceProfile",
        "ec2:DescribeInstanceAttribute",
        "ce:GetReservationUtilization",
        "ce:GetDimensionValues",
        "ce:GetCostAndUsage",
        "ce:GetTags",
        "ec2:CreatePlacementGroup",
        "ec2:DeletePlacementGroup"
    ],
    "Resource": "*"
},
{
    "Sid": "fabricPoolPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
```

```
"s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock"
    ],
    "Resource": [
        "arn:aws-us-gov:s3:::fabric-pool*"
},
    "Sid": "backupPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:ListAllMyBuckets",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock"
    ],
    "Resource": [
        "arn:aws-us-gov:s3:::netapp-backup-*"
},
    "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
        "ec2:TerminateInstances",
        "ec2:AttachVolume",
        "ec2:DetachVolume"
    ],
    "Condition": {
        "StringLike": {
```

```
"ec2:ResourceTag/WorkingEnvironment": "*"
              }
           },
           "Resource": [
              "arn:aws-us-gov:ec2:*:*:instance/*"
       },
        {
           "Effect": "Allow",
           "Action": [
               "ec2:AttachVolume",
               "ec2:DetachVolume"
           ],
           "Resource": [
               "arn:aws-us-gov:ec2:*:*:volume/*"
           ]
       }
}
```

```
{
    "Version": "2012-10-17",
    "Statement": [{
            "Effect": "Allow",
            "Action": [
                "ec2:DescribeInstances",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:DescribeRouteTables",
                "ec2:DescribeImages",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:ModifyVolumeAttribute",
                "ec2:DeleteVolume",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DeleteNetworkInterface",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcs",
                "ec2:DescribeDhcpOptions",
                "ec2:CreateSnapshot",
                "ec2:DeleteSnapshot",
                "ec2:DescribeSnapshots",
                "ec2:GetConsoleOutput",
                "ec2:DescribeKeyPairs",
                "ec2:DescribeRegions",
                "ec2:DeleteTags",
                "ec2:DescribeTags",
                "cloudformation:CreateStack",
                "cloudformation: DeleteStack",
                "cloudformation:DescribeStacks",
                "cloudformation: DescribeStackEvents",
                "cloudformation: Validate Template",
                "iam:PassRole",
```

```
"iam:CreateRole",
        "iam:DeleteRole",
        "iam:PutRolePolicy",
        "iam:CreateInstanceProfile",
        "iam:DeleteRolePolicy",
        "iam:AddRoleToInstanceProfile",
        "iam: RemoveRoleFromInstanceProfile",
        "iam:DeleteInstanceProfile",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:ListAllMyBuckets",
        "kms:List*",
        "kms:Describe*",
        "ec2: Associate Iam Instance Profile",
        "ec2:DescribeIamInstanceProfileAssociations",
        "ec2:DisassociateIamInstanceProfile",
        "ec2:DescribeInstanceAttribute",
        "ec2:CreatePlacementGroup",
        "ec2:DeletePlacementGroup",
        "iam:ListinstanceProfiles"
    ],
    "Resource": "*"
},
    "Sid": "fabricPoolPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions"
    ],
    "Resource": [
        "arn:aws-iso:s3:::fabric-pool*"
},
    "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
        "ec2:StopInstances",
        "ec2:TerminateInstances",
        "ec2:AttachVolume",
```

```
"ec2:DetachVolume"
            ],
            "Condition": {
                 "StringLike": {
                     "ec2:ResourceTag/WorkingEnvironment": "*"
            },
            "Resource": [
                 "arn:aws-iso:ec2:*:*:instance/*"
            1
        },
        {
            "Effect": "Allow",
            "Action": [
                 "ec2:AttachVolume",
                 "ec2:DetachVolume"
            ],
            "Resource": [
                 "arn:aws-iso:ec2:*:*:volume/*"
        }
    ]
}
```

How the AWS permissions are used

The following sections describe how the permissions are used for each NetApp cloud service. This information can be helpful if your corporate policies dictate that permissions are only provided as needed.

AppTemplate tags

The Connector makes the following API requests to manage tags on AWS resources when you use the AppTemplate Tagging service:

- ec2:CreateTags
- · ec2:DeleteTags
- · ec2:DescribeTags
- · tag:getResources
- tag:getTagKeys
- tag:getTagValues
- tag:TagResources
- tag:UntagResources

Cloud Backup

The Connector makes the following API requests to deploy the restore instance for Cloud Backup:

- ec2:StartInstances
- ec2:StopInstances
- ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:DescribeInstanceAttribute
- ec2:DescribeImages
- · ec2:CreateTags
- ec2:CreateVolume
- ec2:CreateSecurityGroup
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:DescribeRegions
- · cloudformation:CreateStack
- cloudformation:DeleteStack
- · cloudformation:DescribeStacks

The Connector makes the following API requests to manage backups in Amazon S3:

- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:CreateBucket
- s3:GetLifecycleConfiguration
- s3:PutLifecycleConfiguration
- s3:PutBucketTagging
- s3:ListBucketVersions
- s3:GetBucketAcl
- s3:PutBucketPublicAccessBlock
- · kms:List*
- · kms:Describe*
- · s3:GetObject
- ec2:describeVpcEndpoints
- · kms:ListAliases
- s3:PutEncryptionConfiguration

The Connector makes the following API requests when you use the Search & Restore method to restore volumes and files:

- s3:CreateBucket
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:GetBucketAcl
- s3:ListBucket
- s3:ListBucketVersions
- s3:ListBucketMultipartUploads
- s3:PutObject
- s3:PutBucketAcl
- s3:PutLifecycleConfiguration
- s3:PutBucketPublicAccessBlock
- s3:AbortMultipartUpload
- s3:ListMultipartUploadParts
- athena:StartQueryExecutionc
- athena:GetQueryResults
- athena:GetQueryExecution
- · athena:StopQueryExecution
- · glue:CreateDatabase
- · glue:CreateTable
- glue:BatchDeletePartition

The Connector makes the following API requests when you use DataLock and Ransomware protection for your volume backups:

- s3:GetObjectVersionTagging
- s3:GetBucketObjectLockConfiguration
- s3:GetObjectVersionAcl
- s3:PutObjectTagging
- s3:DeleteObject
- s3:DeleteObjectTagging
- s3:GetObjectRetention
- · s3:DeleteObjectVersionTagging
- s3:PutObject
- · s3:GetObject
- s3:PutBucketObjectLockConfiguration
- s3:GetLifecycleConfiguration
- s3:ListBucketByTags

- s3:GetBucketTagging
- s3:DeleteObjectVersion
- s3:ListBucketVersions
- s3:ListBucket
- s3:PutBucketTagging
- s3:GetObjectTagging
- s3:PutBucketVersioning
- s3:PutObjectVersionTagging
- · s3:GetBucketVersioning
- s3:GetBucketAcl
- · s3:BypassGovernanceRetention
- s3:PutObjectRetention
- s3:GetBucketLocation
- s3:GetObjectVersion

The Connector makes the following API requests if you use a different AWS account for your Cloud Volumes ONTAP backups than you're using for the source volumes:

- s3:PutBucketPolicy
- s3:PutBucketOwnershipControls

Cloud Data Sense

The Connector makes the following API requests to deploy the Cloud Data Sense instance:

- ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:CreateTags
- ec2:CreateVolume
- ec2:AttachVolume
- ec2:CreateSecurityGroup
- · ec2:DeleteSecurityGroup
- ec2:DescribeSecurityGroups
- ec2:CreateNetworkInterface
- ec2:DescribeNetworkInterfaces
- · ec2:DeleteNetworkInterface
- ec2:DescribeSubnets
- · ec2:DescribeVpcs
- ec2:CreateSnapshot

- ec2:DescribeRegions
- · cloudformation:CreateStack
- cloudformation:DeleteStack
- · cloudformation:DescribeStacks
- cloudformation:DescribeStackEvents
- · iam:AddRoleToInstanceProfile
- ec2:AssociatelamInstanceProfile
- ec2:DescribelamInstanceProfileAssociations

The Connector makes the following API requests to scan S3 buckets when you use Cloud Data Sense:

- iam:AddRoleToInstanceProfile
- ec2:AssociatelamInstanceProfile
- ec2:DescribelamInstanceProfileAssociations
- s3:GetBucketTagging
- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:GetBucketPolicyStatus
- s3:GetBucketPolicy
- s3:GetBucketAcl
- · s3:GetObject
- · iam:GetRole
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:PutObject
- sts:AssumeRole

Cloud Tiering

The Connector makes the following API requests to tier data to Amazon S3 when you use Cloud Tiering.

| Action | Used for set up? | Used for daily operations? |
|------------------------------|------------------|----------------------------|
| s3:CreateBucket | Yes | No |
| s3:PutLifecycleConfiguration | Yes | No |
| s3:GetLifecycleConfiguration | Yes | Yes |
| ec2:DescribeRegions | Yes | Yes |

Cloud Volumes ONTAP

The Connector makes the following API requests to deploy and manage Cloud Volumes ONTAP in AWS.

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|--|---|----------------------|----------------------------|--------------------|
| Create and manage IAM roles and | iam:ListInstanceProfi les | Yes | Yes | No |
| instance profiles for Cloud Volumes ONTAP instances | iam:CreateRole | Yes | No | No |
| | iam:DeleteRole | No | Yes | Yes |
| | iam:PutRolePolicy | Yes | No | No |
| | iam:CreateInstanceP rofile | Yes | No | No |
| | iam:DeleteRolePolic y | No | Yes | Yes |
| | iam:AddRoleToInsta nceProfile | Yes | No | No |
| | iam:RemoveRoleFro mlnstanceProfile | No | Yes | Yes |
| | iam:DeleteInstanceP rofile | No | Yes | Yes |
| | iam:PassRole | Yes | No | No |
| | ec2:AssociatelamIns tanceProfile | Yes | Yes | No |
| | ec2:DescribelamInst anceProfileAssociations | Yes | Yes | No |
| | ec2:Disassociatelam InstanceProfile | No | Yes | No |
| Decode authorization status messages | sts:DecodeAuthoriza tionMessage | Yes | Yes | No |
| Describe the specified images (AMIs) available to the account | ec2:DescribeImages | Yes | Yes | No |
| Describe the route tables in a VPC (required for HA pairs only) | ec2:DescribeRouteT ables | Yes | No | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|--|-----------------------------------|----------------------|----------------------------|--------------------|
| Stop, start, and | ec2:StartInstances | Yes | Yes | No |
| monitor instances | ec2:StopInstances | Yes | Yes | No |
| | ec2:DescribeInstanc | Yes | Yes | No |
| | ec2:DescribeInstanc eStatus | Yes | Yes | No |
| | ec2:RunInstances | Yes | No | No |
| | ec2:TerminateInstan | No | No | Yes |
| | ec2:ModifyInstanceA ttribute | No | Yes | No |
| Verify that enhanced networking is enabled for supported instance types | ec2:DescribeInstanc eAttribute | No | Yes | No |
| Tag resources with the "WorkingEnvironme nt" and "WorkingEnvironme ntld" tags which are used for maintenance and cost allocation | ec2:CreateTags | Yes | Yes | No |
| Manage EBS | ec2:CreateVolume | Yes | Yes | No |
| volumes that Cloud Volumes ONTAP uses as back-end | ec2:DescribeVolume s | Yes | Yes | Yes |
| storage | ec2:ModifyVolumeAt tribute | No | Yes | Yes |
| | ec2:AttachVolume | Yes | Yes | No |
| | ec2:DeleteVolume | No | Yes | Yes |
| | ec2:DetachVolume | No | Yes | Yes |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|---|---------------------------------------|----------------------|----------------------------|--------------------|
| Create and manage security groups for | ec2:CreateSecurityG roup | Yes | No | No |
| Cloud Volumes ONTAP | ec2:DeleteSecurityG roup | No | Yes | Yes |
| | ec2:DescribeSecurit yGroups | Yes | Yes | Yes |
| | ec2:RevokeSecurity GroupEgress | Yes | No | No |
| | ec2:AuthorizeSecurit yGroupEgress | Yes | No | No |
| | ec2:AuthorizeSecurit yGroupIngress | Yes | No | No |
| | ec2:RevokeSecurity GroupIngress | Yes | Yes | No |
| Create and manage network interfaces | ec2:CreateNetworkInterface | Yes | No | No |
| for Cloud Volumes ONTAP in the target subnet | ec2:DescribeNetwor kInterfaces | Yes | Yes | No |
| | ec2:DeleteNetworkIn terface | No | Yes | Yes |
| | ec2:ModifyNetworkIn terfaceAttribute | No | Yes | No |
| Get the list of destination subnets | ec2:DescribeSubnet s | Yes | Yes | No |
| and security groups | ec2:DescribeVpcs | Yes | Yes | No |
| Get DNS servers and the default domain name for Cloud Volumes ONTAP instances | ec2:DescribeDhcpO ptions | Yes | No | No |
| Take snapshots of | ec2:CreateSnapshot | Yes | Yes | No |
| EBS volumes for Cloud Volumes | ec2:DeleteSnapshot | No | Yes | Yes |
| ONTAP | ec2:DescribeSnapsh ots | No | Yes | No |
| Capture the Cloud Volumes ONTAP console, which is attached to AutoSupport messages | ec2:GetConsoleOutp ut | Yes | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|---|-------------------------------------|----------------------|----------------------------|--------------------|
| Get the list of available key pairs | ec2:DescribeKeyPair s | Yes | No | No |
| Get the list of available AWS regions | ec2:DescribeRegion s | Yes | Yes | No |
| Manage tags for resources associated with Cloud Volumes ONTAP instances | ec2:DeleteTags | No | Yes | Yes |
| | ec2:DescribeTags | No | Yes | No |
| Create and manage stacks for AWS | cloudformation:Creat eStack | Yes | No | No |
| CloudFormation templates | cloudformation:Delet eStack | Yes | No | No |
| | cloudformation:Desc ribeStacks | Yes | Yes | No |
| | cloudformation:Desc ribeStackEvents | Yes | No | No |
| | cloudformation:Valid ateTemplate | Yes | No | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|--|-----------------------------------|----------------------|----------------------------|--------------------|
| Create and manage | s3:CreateBucket | Yes | Yes | No |
| an S3 bucket that a Cloud Volumes | s3:DeleteBucket | No | Yes | Yes |
| ONTAP system uses as a capacity tier for | s3:GetLifecycleConfi guration | No | Yes | No |
| data tiering | s3:PutLifecycleConfi guration | No | Yes | No |
| | s3:PutBucketTaggin | No | Yes | No |
| | s3:ListBucketVersion s | No | Yes | No |
| | s3:GetBucketPolicyS tatus | No | Yes | No |
| | s3:GetBucketPublic AccessBlock | No | Yes | No |
| | s3:GetBucketAcl | No | Yes | No |
| | s3:GetBucketPolicy | No | Yes | No |
| | s3:PutBucketPublicA ccessBlock | No | Yes | No |
| | s3:GetBucketTaggin | No | Yes | No |
| | s3:GetBucketLocatio | No | Yes | No |
| | s3:ListAllMyBuckets | No | No | No |
| | s3:ListBucket | No | Yes | No |
| Enable data | kms:List* | Yes | Yes | No |
| encryption of Cloud Volumes ONTAP | kms:ReEncrypt* | Yes | No | No |
| using the AWS Key Management | kms:Describe* | Yes | Yes | No |
| Service (KMS) | kms:CreateGrant | Yes | Yes | No |
| Obtain AWS cost data for Cloud | ce:GetReservationUt ilization | No | Yes | No |
| Volumes ONTAP | ce:GetDimensionVal | No | Yes | No |
| | ce:GetCostAndUsag e | No | Yes | No |
| | ce:GetTags | No | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|---|--------------------------------------|----------------------|----------------------------|--------------------|
| Create and manage an AWS spread placement group for two HA nodes and the mediator in a single AWS Availability Zone | ec2:CreatePlacemen tGroup | Yes | No | No |
| | ec2:DeletePlacemen tGroup | No | Yes | Yes |
| Create reports | fsx:Describe* | No | Yes | No |
| | fsx:List* | No | Yes | No |
| Create and manage aggregates that support the Amazon EBS Elastic Volumes feature | ec2:DescribeVolume sModifications | No | Yes | No |
| | ec2:ModifyVolume | No | Yes | No |

Global File Cache

The Connector makes the following API requests to deploy Global File Cache instances during deployment:

- · cloudformation:DescribeStacks
- · cloudwatch:GetMetricStatistics
- · cloudformation:ListStacks

FSx for ONTAP

The Connector makes the following API requests to manage FSx for ONTAP:

- · ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:DescribeInstanceAttribute
- ec2:DescribeRouteTables
- ec2:DescribeImages
- ec2:CreateTags
- ec2:DescribeVolumes
- ec2:DescribeSecurityGroups
- ec2:DescribeNetworkInterfaces
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:DescribeDhcpOptions
- ec2:DescribeSnapshots
- ec2:DescribeKeyPairs
- ec2:DescribeRegions

- · ec2:DescribeTags
- · ec2:DescribelamInstanceProfileAssociations
- ec2:DescribeReservedInstancesOfferings
- ec2:describeVpcEndpoints
- ec2:DescribeVpcs
- · ec2:DescribeVolumesModifications
- ec2:DescribePlacementGroups
- kms:List*
- kms:Describe*
- · kms:CreateGrant
- · kms:ListAliases
- fsx:Describe*
- fsx:List*

Kubernetes

The Connector makes the following API requests to discover and manage Amazon EKS clusters:

- ec2:DescribeRegions
- · eks:ListClusters
- eks:DescribeCluster
- · iam:GetInstanceProfile

S3 bucket discovery

The Connector makes the following API request to discover Amazon S3 buckets:

s3:GetEncryptionConfiguration

Azure permissions for the Connector

When BlueXP launches the Connector VM in Azure, it attaches a custom role to the VM that provides the Connector with permissions to manage resources and processes within that Azure subscription. The Connector uses the permissions to make API calls to several Azure services.

Custom role permissions

The custom role shown below provides the permissions that a Connector needs to manage resources and processes within your Azure network.

When you create a Connector directly from BlueXP, BlueXP automatically applies this custom role to the Connector.

If you deploy the Connector from the Azure Marketplace or if you manually install the Connector on a Linux host, then you'll need to set up the custom role yourself.

You also need to ensure that the role is up to date as new permissions are added in subsequent releases.

```
{
    "Name": "BlueXP Operator",
    "Actions": [
                   "Microsoft.Compute/disks/delete",
                    "Microsoft.Compute/disks/read",
                    "Microsoft.Compute/disks/write",
                    "Microsoft.Compute/locations/operations/read",
                    "Microsoft.Compute/locations/vmSizes/read",
                    "Microsoft.Resources/subscriptions/locations/read",
                    "Microsoft.Compute/operations/read",
                    "Microsoft.Compute/virtualMachines/instanceView/read",
                    "Microsoft.Compute/virtualMachines/powerOff/action",
                    "Microsoft.Compute/virtualMachines/read",
                    "Microsoft.Compute/virtualMachines/restart/action",
                    "Microsoft.Compute/virtualMachines/deallocate/action",
                    "Microsoft.Compute/virtualMachines/start/action",
                    "Microsoft.Compute/virtualMachines/vmSizes/read",
                    "Microsoft.Compute/virtualMachines/write",
                    "Microsoft.Compute/images/read",
                    "Microsoft.Network/locations/operationResults/read",
                    "Microsoft.Network/locations/operations/read",
                    "Microsoft.Network/networkInterfaces/read",
                    "Microsoft.Network/networkInterfaces/write",
                    "Microsoft.Network/networkInterfaces/join/action",
                    "Microsoft.Network/networkSecurityGroups/read",
                    "Microsoft.Network/networkSecurityGroups/write",
                    "Microsoft.Network/networkSecurityGroups/join/action",
                    "Microsoft.Network/virtualNetworks/read",
"Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read",
                    "Microsoft.Network/virtualNetworks/subnets/read",
                    "Microsoft.Network/virtualNetworks/subnets/write",
"Microsoft.Network/virtualNetworks/subnets/virtualMachines/read",
"Microsoft.Network/virtualNetworks/virtualMachines/read",
"Microsoft.Network/virtualNetworks/subnets/join/action",
                    "Microsoft.Resources/deployments/operations/read",
                    "Microsoft.Resources/deployments/read",
                    "Microsoft.Resources/deployments/write",
                    "Microsoft.Resources/resources/read",
"Microsoft.Resources/subscriptions/operationresults/read",
```

```
"Microsoft.Resources/subscriptions/resourceGroups/delete",
"Microsoft.Resources/subscriptions/resourceGroups/read",
"Microsoft.Resources/subscriptions/resourcegroups/resources/read",
"Microsoft.Resources/subscriptions/resourceGroups/write",
                    "Microsoft.Storage/checknameavailability/read",
                    "Microsoft.Storage/operations/read",
                    "Microsoft.Storage/storageAccounts/listkeys/action",
                    "Microsoft.Storage/storageAccounts/read",
                    "Microsoft.Storage/storageAccounts/delete",
                    "Microsoft.Storage/storageAccounts/write",
"Microsoft.Storage/storageAccounts/blobServices/containers/read",
"Microsoft.Storage/storageAccounts/blobServices/containers/write",
                    "Microsoft.Storage/usages/read",
                    "Microsoft.Compute/snapshots/write",
                    "Microsoft.Compute/snapshots/read",
                    "Microsoft.Compute/availabilitySets/write",
                    "Microsoft.Compute/availabilitySets/read",
                    "Microsoft.Compute/disks/beginGetAccess/action",
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreemen
ts/read",
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreemen
ts/write",
                    "Microsoft.Network/loadBalancers/read",
                    "Microsoft.Network/loadBalancers/write",
                    "Microsoft.Network/loadBalancers/delete",
"Microsoft.Network/loadBalancers/backendAddressPools/read",
"Microsoft.Network/loadBalancers/loadBalancingRules/read",
                    "Microsoft.Network/loadBalancers/probes/read",
                    "Microsoft.Network/loadBalancers/probes/join/action",
                    "Microsoft.Authorization/locks/*",
                    "Microsoft.Network/routeTables/join/action",
                    "Microsoft.NetApp/netAppAccounts/read",
                    "Microsoft.NetApp/netAppAccounts/capacityPools/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/write",
```

```
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",
                    "Microsoft.Network/privateEndpoints/write",
"Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/acti
on",
"Microsoft.Storage/storageAccounts/privateEndpointConnections/read",
"Microsoft.Storage/storageAccounts/managementPolicies/read",
"Microsoft.Storage/storageAccounts/managementPolicies/write",
                    "Microsoft.Network/privateEndpoints/read",
                    "Microsoft.Network/privateDnsZones/write",
"Microsoft.Network/privateDnsZones/virtualNetworkLinks/write",
                    "Microsoft.Network/virtualNetworks/join/action",
                    "Microsoft.Network/privateDnsZones/A/write",
                    "Microsoft.Network/privateDnsZones/read",
"Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",
"Microsoft.Resources/deployments/operationStatuses/read",
                    "Microsoft.Insights/Metrics/Read",
                    "Microsoft.Compute/virtualMachines/extensions/write",
                    "Microsoft.Compute/virtualMachines/extensions/delete",
                    "Microsoft.Compute/virtualMachines/extensions/read",
                    "Microsoft.Compute/virtualMachines/delete",
                    "Microsoft.Network/networkInterfaces/delete",
                    "Microsoft.Network/networkSecurityGroups/delete",
                    "Microsoft.Resources/deployments/delete",
                    "Microsoft.Compute/diskEncryptionSets/read",
                    "Microsoft.Compute/snapshots/delete",
                    "Microsoft.Network/privateEndpoints/delete",
                    "Microsoft.Compute/availabilitySets/delete",
                    "Microsoft.KeyVault/vaults/read",
                    "Microsoft.KeyVault/vaults/accessPolicies/write",
                    "Microsoft.Compute/diskEncryptionSets/write",
                    "Microsoft.KeyVault/vaults/deploy/action",
                    "Microsoft.Compute/diskEncryptionSets/delete",
                    "Microsoft.Resources/tags/read",
                    "Microsoft.Resources/tags/write",
                    "Microsoft.Resources/tags/delete",
                    "Microsoft.Network/applicationSecurityGroups/write",
                    "Microsoft.Network/applicationSecurityGroups/read",
```

```
"Microsoft.Network/applicationSecurityGroups/joinIpConfiguration/action",
"Microsoft.Network/networkSecurityGroups/securityRules/write",
                    "Microsoft.Network/applicationSecurityGroups/delete",
"Microsoft.Network/networkSecurityGroups/securityRules/delete",
"Microsoft.ContainerService/managedClusters/listClusterUserCredential/acti
on",
                    "Microsoft.ContainerService/managedClusters/read",
                    "Microsoft.Synapse/workspaces/write",
                    "Microsoft.Synapse/workspaces/read",
                    "Microsoft.Synapse/workspaces/delete",
                    "Microsoft.Synapse/register/action",
                    "Microsoft.Synapse/checkNameAvailability/action",
                    "Microsoft.Synapse/workspaces/operationStatuses/read",
                    "Microsoft.Synapse/workspaces/firewallRules/read",
"Microsoft.Synapse/workspaces/replaceAllIpFirewallRules/action",
                    "Microsoft.Synapse/workspaces/operationResults/read",
                    "Microsoft.Network/publicIPAddresses/delete",
"Microsoft.ManagedIdentity/userAssignedIdentities/assign/action"
   ],
    "NotActions": [],
    "AssignableScopes": [],
    "Description": "BlueXP Permissions",
    "IsCustom": "true"
}
```

How Azure permissions are used

The following sections describe how the permissions are used for each NetApp cloud service. This information can be helpful if your corporate policies dictate that permissions are only provided as needed.

AppTemplate tags

The Connector makes the following API requests to manage tags on Azure resources when you use the AppTemplate Tagging service:

- · Microsoft.Resources/resources/read
- · Microsoft.Resources/subscriptions/operationresults/read
- · Microsoft.Resources/subscriptions/resourceGroups/read
- · Microsoft.Resources/subscriptions/resourcegroups/resources/read
- Microsoft.Resources/tags/read

· Microsoft.Resources/tags/write

Azure NetApp Files

The Connector makes the following API requests to manage Azure NetApp Files working environments:

- · Microsoft.NetApp/netAppAccounts/read
- Microsoft.NetApp/netAppAccounts/capacityPools/read
- Microsoft.NetApp/netAppAccounts/capacityPools/volumes/write
- Microsoft.NetApp/netAppAccounts/capacityPools/volumes/read
- Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete

Cloud Backup

The Connector makes the following API requests for backup and restore operations:

- Microsoft.Compute/virtualMachines/read
- · Microsoft.Compute/virtualMachines/start/action
- Microsoft.Compute/virtualMachines/deallocate/action
- · Microsoft.Storage/storageAccounts/listkeys/action
- · Microsoft.Storage/storageAccounts/read
- · Microsoft.Storage/storageAccounts/write
- Microsoft.Storage/storageAccounts/blobServices/containers/read
- Microsoft.KeyVault/vaults/read
- · Microsoft.KeyVault/vaults/accessPolicies/write
- Microsoft.Network/networkInterfaces/read
- Microsoft.Resources/subscriptions/locations/read
- Microsoft.Network/virtualNetworks/read
- Microsoft.Network/virtualNetworks/subnets/read
- · Microsoft.Resources/subscriptions/resourceGroups/read
- Microsoft.Resources/subscriptions/resourcegroups/resources/read
- Microsoft.Resources/subscriptions/resourceGroups/write
- Microsoft.Authorization/locks/*
- · Microsoft.Network/privateEndpoints/write
- Microsoft.Network/privateEndpoints/read
- Microsoft.Network/privateDnsZones/virtualNetworkLinks/write
- Microsoft.Network/virtualNetworks/join/action
- · Microsoft.Network/privateDnsZones/A/write
- Microsoft.Network/privateDnsZones/read
- Microsoft.Network/privateDnsZones/virtualNetworkLinks/read
- Microsoft.Compute/virtualMachines/extensions/delete

- · Microsoft.Compute/virtualMachines/delete
- Microsoft.Network/networkInterfaces/delete
- · Microsoft.Network/networkSecurityGroups/delete
- · Microsoft.Resources/deployments/delete
- Microsoft.Network/publicIPAddresses/delete
- Microsoft.Storage/storageAccounts/blobServices/containers/write
- Microsoft.ManagedIdentity/userAssignedIdentities/assign/action

The Connector makes the following API requests when you use the Search & Restore functionality:

- · Microsoft.Synapse/workspaces/write
- · Microsoft.Synapse/workspaces/read
- · Microsoft.Synapse/workspaces/delete
- Microsoft.Synapse/register/action
- · Microsoft.Synapse/checkNameAvailability/action
- · Microsoft.Synapse/workspaces/operationStatuses/read
- · Microsoft.Synapse/workspaces/firewallRules/read
- Microsoft.Synapse/workspaces/replaceAllIpFirewallRules/action
- · Microsoft.Synapse/workspaces/operationResults/read

Cloud Data Sense

The Connector makes the following API requests when you use Cloud Data Sense.

| Action | Used for set up? | Used for daily operations? |
|---|------------------|----------------------------|
| Microsoft.Compute/locations/operat ions/read | Yes | Yes |
| Microsoft.Compute/locations/vmSiz es/read | Yes | Yes |
| Microsoft.Compute/operations/read | Yes | Yes |
| Microsoft.Compute/virtualMachines/instanceView/read | Yes | Yes |
| Microsoft.Compute/virtualMachines/powerOff/action | Yes | No |
| Microsoft.Compute/virtualMachines/read | Yes | Yes |
| Microsoft.Compute/virtualMachines/restart/action | Yes | No |
| Microsoft.Compute/virtualMachines/ start/action | Yes | No |
| Microsoft.Compute/virtualMachines/ vmSizes/read | No | Yes |

| Action | Used for set up? | Used for daily operations? |
|---|------------------|----------------------------|
| Microsoft.Compute/virtualMachines/write | Yes | No |
| Microsoft.Compute/images/read | Yes | Yes |
| Microsoft.Compute/disks/delete | Yes | No |
| Microsoft.Compute/disks/read | Yes | Yes |
| Microsoft.Compute/disks/write | Yes | No |
| Microsoft.Storage/checknameavaila bility/read | Yes | Yes |
| Microsoft.Storage/operations/read | Yes | Yes |
| Microsoft.Storage/storageAccounts/ listkeys/action | Yes | No |
| Microsoft.Storage/storageAccounts/read | Yes | Yes |
| Microsoft.Storage/storageAccounts/ write | Yes | No |
| Microsoft.Storage/storageAccounts/delete | No | Yes |
| Microsoft.Storage/storageAccounts/blobServices/containers/read | Yes | Yes |
| Microsoft.Network/networkInterface s/read | Yes | Yes |
| Microsoft.Network/networkInterface s/write | Yes | No |
| Microsoft.Network/networkInterface s/join/action | Yes | No |
| Microsoft.Network/networkSecurity Groups/read | Yes | Yes |
| Microsoft.Network/networkSecurity Groups/write | Yes | No |
| Microsoft.Resources/subscriptions/l ocations/read | Yes | Yes |
| Microsoft.Network/locations/operationResults/read | Yes | Yes |
| Microsoft.Network/locations/operations/read | Yes | Yes |
| Microsoft.Network/virtualNetworks/r ead | Yes | Yes |
| Microsoft.Network/virtualNetworks/c hecklpAddressAvailability/read | Yes | Yes |

| Action | Used for set up? | Used for daily operations? |
|--|------------------|----------------------------|
| Microsoft.Network/virtualNetworks/s ubnets/read | Yes | Yes |
| Microsoft.Network/virtualNetworks/s ubnets/virtualMachines/read | Yes | Yes |
| Microsoft.Network/virtualNetworks/virtualMachines/read | Yes | Yes |
| Microsoft.Network/virtualNetworks/s ubnets/join/action | Yes | No |
| Microsoft.Network/virtualNetworks/s ubnets/write | Yes | No |
| Microsoft.Network/routeTables/join/action | Yes | No |
| Microsoft.Resources/deployments/o perations/read | Yes | Yes |
| Microsoft.Resources/deployments/r ead | Yes | Yes |
| Microsoft.Resources/deployments/ write | Yes | No |
| Microsoft.Resources/resources/rea d | Yes | Yes |
| Microsoft.Resources/subscriptions/ operationresults/read | Yes | Yes |
| Microsoft.Resources/subscriptions/r esourceGroups/delete | Yes | No |
| Microsoft.Resources/subscriptions/r esourceGroups/read | Yes | Yes |
| Microsoft.Resources/subscriptions/r esourcegroups/resources/read | Yes | Yes |
| Microsoft.Resources/subscriptions/r esourceGroups/write | Yes | No |

Cloud Tiering

The Connector makes the following API requests when you set up Cloud Tiering.

- Microsoft.Storage/storageAccounts/listkeys/action
- Microsoft.Resources/subscriptions/resourceGroups/read
- Microsoft.Resources/subscriptions/locations/read

The Connector makes the following API requests for daily operations.

- $\bullet \ \, {\sf Microsoft.Storage/storageAccounts/blobServices/containers/read}$
- Microsoft.Storage/storageAccounts/blobServices/containers/write

- $\bullet \ \, {\sf Microsoft.Storage/storageAccounts/managementPolicies/read}$
- Microsoft.Storage/storageAccounts/managementPolicies/write
- Microsoft.Storage/storageAccounts/read

Cloud Volumes ONTAP

The Connector makes the following API requests to deploy and manage Cloud Volumes ONTAP in AWS.

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|---|---|----------------------|----------------------------|--------------------|
| Create VMs, stop, start, delete, and obtain the status of the system | Microsoft.Compute/I ocations/operations/r ead | Yes | Yes | No |
| | Microsoft.Compute/I ocations/vmSizes/re ad | Yes | Yes | No |
| | Microsoft.Resources /subscriptions/locatio ns/read | Yes | No | No |
| | Microsoft.Compute/o perations/read | Yes | Yes | No |
| | Microsoft.Compute/v irtualMachines/insta nceView/read | Yes | Yes | No |
| | Microsoft.Compute/v irtualMachines/powe rOff/action | Yes | Yes | No |
| | Microsoft.Compute/v irtualMachines/read | Yes | Yes | No |
| | Microsoft.Compute/v irtualMachines/restar t/action | Yes | Yes | No |
| | Microsoft.Compute/v irtualMachines/start/action | Yes | Yes | No |
| | Microsoft.Compute/v irtualMachines/deall ocate/action | No | Yes | Yes |
| | Microsoft.Compute/v irtualMachines/vmSi zes/read | No | Yes | No |
| | Microsoft.Compute/v irtualMachines/write | Yes | Yes | No |
| Enable deployment from a VHD | Microsoft.Compute/i mages/read | Yes | No | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|---|---|----------------------|----------------------------|--------------------|
| Create and manage network interfaces in the target subnet | Microsoft.Network/n etworkInterfaces/rea d | Yes | Yes | No |
| | Microsoft.Network/n etworkInterfaces/writ e | Yes | Yes | No |
| | Microsoft.Network/n etworkInterfaces/join /action | Yes | Yes | No |
| Create predefined network security groups | Microsoft.Network/n etworkSecurityGroup s/read | Yes | Yes | No |
| | Microsoft.Network/n etworkSecurityGroup s/write | Yes | Yes | No |
| | Microsoft.Network/n etworkSecurityGroup s/join/action | Yes | No | No |
| Get network information about regions, the target | Microsoft.Network/lo cations/operationRe sults/read | Yes | Yes | No |
| VNet and subnet, and add the VMs to VNets | Microsoft.Network/lo cations/operations/re ad | Yes | Yes | No |
| | Microsoft.Network/vir tualNetworks/read | Yes | No | No |
| | Microsoft.Network/vir tualNetworks/checkl pAddressAvailability/ read | Yes | No | No |
| | Microsoft.Network/vir tualNetworks/subnet s/read | Yes | Yes | No |
| | Microsoft.Network/vir tualNetworks/subnet s/virtualMachines/re ad | Yes | Yes | No |
| | Microsoft.Network/vir tualNetworks/virtual Machines/read | Yes | Yes | No |
| | Microsoft.Network/vir tualNetworks/subnet s/join/action | Yes | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|-----------------------------------|---|----------------------|----------------------------|--------------------|
| Create and manage resource groups | Microsoft.Resources /deployments/operati ons/read | Yes | Yes | No |
| | Microsoft.Resources /deployments/read | Yes | Yes | No |
| | Microsoft.Resources /deployments/write | Yes | Yes | No |
| | Microsoft.Resources /resources/read | Yes | Yes | No |
| | Microsoft.Resources /subscriptions/operat ionresults/read | Yes | Yes | No |
| | Microsoft.Resources /subscriptions/resour ceGroups/delete | Yes | Yes | Yes |
| | Microsoft.Resources /subscriptions/resour ceGroups/read | No | Yes | No |
| | Microsoft.Resources /subscriptions/resour cegroups/resources/ read | Yes | Yes | No |
| | Microsoft.Resources /subscriptions/resour ceGroups/write | Yes | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|--|--|----------------------|----------------------------|--------------------|
| Manage Azure storage accounts | Microsoft.Compute/d isks/read | Yes | Yes | Yes |
| and disks | Microsoft.Compute/d isks/write | Yes | Yes | No |
| | Microsoft.Compute/d isks/delete | Yes | Yes | Yes |
| | Microsoft.Storage/ch ecknameavailability/r ead | Yes | Yes | No |
| | Microsoft.Storage/op erations/read | Yes | Yes | No |
| | Microsoft.Storage/st orageAccounts/listke ys/action | Yes | Yes | No |
| | Microsoft.Storage/st orageAccounts/read | Yes | Yes | No |
| | Microsoft.Storage/st orageAccounts/delet e | No | Yes | Yes |
| | Microsoft.Storage/st orageAccounts/write | Yes | Yes | No |
| | Microsoft.Storage/us ages/read | No | Yes | No |
| Enable backups to Blob storage and encryption of storage accounts | Microsoft.Storage/st orageAccounts/blob Services/containers/r ead | Yes | Yes | No |
| | Microsoft.KeyVault/v aults/read | Yes | Yes | No |
| | Microsoft.KeyVault/v aults/accessPolicies/ write | Yes | Yes | No |
| Enable VNet service endpoints for data tiering | Microsoft.Network/vir tualNetworks/subnet s/write | Yes | Yes | No |
| | Microsoft.Network/ro uteTables/join/action | Yes | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|--|---|----------------------|----------------------------|--------------------|
| Create and manage Azure managed snapshots | Microsoft.Compute/s napshots/write | Yes | Yes | No |
| | Microsoft.Compute/s napshots/read | Yes | Yes | No |
| | Microsoft.Compute/s napshots/delete | No | Yes | Yes |
| | Microsoft.Compute/d isks/beginGetAccess /action | No | Yes | No |
| Create and manage availability sets | Microsoft.Compute/a vailabilitySets/write | Yes | No | No |
| | Microsoft.Compute/a vailabilitySets/read | Yes | No | No |
| Enable programmatic deployments from the marketplace | Microsoft.Marketplac eOrdering/offertypes /publishers/offers/pla ns/agreements/read | Yes | No | No |
| | Microsoft.Marketplac eOrdering/offertypes /publishers/offers/pla ns/agreements/write | Yes | Yes | No |
| Manage a load balancer for HA | Microsoft.Network/lo adBalancers/read | Yes | Yes | No |
| pairs | Microsoft.Network/lo adBalancers/write | Yes | No | No |
| | Microsoft.Network/lo adBalancers/delete | No | Yes | Yes |
| | Microsoft.Network/lo adBalancers/backen dAddressPools/read | Yes | Yes | No |
| | Microsoft.Network/lo adBalancers/loadBal ancingRules/read | Yes | No | No |
| | Microsoft.Network/lo adBalancers/probes/ read | Yes | No | No |
| | Microsoft.Network/lo adBalancers/probes/ join/action | Yes | No | No |
| Enable management of locks on Azure disks | Microsoft.Authorizati on/locks/* | Yes | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|---|---|----------------------|----------------------------|--------------------|
| Enable private endpoints for HA pairs when there's no connectivity outside the subnet | Microsoft.Network/pr ivateEndpoints/write | Yes | Yes | No |
| | Microsoft.Storage/st orageAccounts/Priva teEndpointConnectio nsApproval/action | Yes | No | No |
| | Microsoft.Storage/st orageAccounts/priva teEndpointConnectio ns/read | Yes | Yes | Yes |
| | Microsoft.Network/pr ivateEndpoints/read | Yes | Yes | Yes |
| | Microsoft.Network/pr ivateDnsZones/write | Yes | Yes | No |
| | Microsoft.Network/pr ivateDnsZones/virtu alNetworkLinks/write | Yes | Yes | No |
| | Microsoft.Network/vir tualNetworks/join/act ion | Yes | Yes | No |
| | Microsoft.Network/pr ivateDnsZones/A/wri te | Yes | Yes | No |
| | Microsoft.Network/pr ivateDnsZones/read | Yes | Yes | No |
| | Microsoft.Network/pr ivateDnsZones/virtu alNetworkLinks/read | Yes | Yes | No |
| Required by Azure for some VM deployments, depending on the underlying physical hardware | Microsoft.Resources /deployments/operati onStatuses/read | Yes | Yes | No |
| Remove resources from a resource group in case of | Microsoft.Network/pr ivateEndpoints/delet e | Yes | Yes | No |
| deployment failure or deletion | Microsoft.Compute/a vailabilitySets/delete | Yes | Yes | No |

| Purpose | Action | Used for deployment? | Used for daily operations? | Used for deletion? |
|--|--|----------------------|----------------------------|--------------------|
| Enable the use of customer-managed encryption keys when using the API | Microsoft.Compute/d iskEncryptionSets/re ad | Yes | Yes | Yes |
| | Microsoft.Compute/d iskEncryptionSets/wr ite | Yes | Yes | No |
| | Microsoft.KeyVault/v aults/deploy/action | Yes | No | No |
| | Microsoft.Compute/d iskEncryptionSets/de lete | Yes | Yes | Yes |
| Configure an application security group for an HA pair | Microsoft.Network/a pplicationSecurityGr oups/write | No | Yes | No |
| to isolate the HA interconnect and cluster network NICs | Microsoft.Network/a pplicationSecurityGr oups/read | No | Yes | Yes |
| | Microsoft.Network/a pplicationSecurityGr oups/joinIpConfigura tion/action | No | Yes | No |
| | Microsoft.Network/n etworkSecurityGroup s/securityRules/write | Yes | Yes | No |
| | Microsoft.Network/a pplicationSecurityGr oups/delete | No | Yes | No |
| | Microsoft.Network/n etworkSecurityGroup s/securityRules/delet e | No | Yes | Yes |
| Read, write, and delete tags | Microsoft.Resources /tags/read | No | Yes | No |
| associated with Cloud Volumes ONTAP resources | Microsoft.Resources /tags/write | Yes | Yes | No |
| | Microsoft.Resources /tags/delete | Yes | No | No |
| Encrypt storage accounts during creation | Microsoft.ManagedId entity/userAssignedI dentities/assign/actio n | Yes | Yes | No |

Global File Cache

The Connector makes the following API requests when you use Global File Cache:

- · Microsoft.Insights/Metrics/Read
- · Microsoft.Compute/virtualMachines/extensions/write
- · Microsoft.Compute/virtualMachines/extensions/read
- Microsoft.Compute/virtualMachines/extensions/delete
- Microsoft.Compute/virtualMachines/delete
- Microsoft.Network/networkInterfaces/delete
- Microsoft.Network/networkSecurityGroups/delete
- Microsoft.Resources/deployments/delete

Kubernetes

The Connector makes the following API requests to discover and manage clusters running in Azure Kubernetes Service (AKS):

- · Microsoft.Compute/virtualMachines/read
- · Microsoft.Resources/subscriptions/locations/read
- · Microsoft.Resources/subscriptions/operationresults/read
- · Microsoft.Resources/subscriptions/resourceGroups/read
- Microsoft.Resources/subscriptions/resourcegroups/resources/read
- Microsoft.ContainerService/managedClusters/read
- Microsoft.ContainerService/managedClusters/listClusterUserCredential/action

Change log

As permissions are added and removed, we'll note them in the sections below.

December 1, 2022

The following permissions were added to the JSON policy:

• Microsoft.Storage/storageAccounts/blobServices/containers/write

This permission is required for Cloud Backup and Cloud Tiering.

Microsoft.Network/publicIPAddresses/delete

This permissions is required for Cloud Backup.

The following permissions were removed from the JSON policy because they are no longer required:

- · Microsoft.Compute/images/write
- Microsoft.Network/loadBalancers/backendAddressPools/join/action
- Microsoft.Network/loadBalancers/frontendIPConfigurations/read

· Microsoft.Storage/storageAccounts/regeneratekey/action

Google Cloud permissions for the Connector

BlueXP requires permissions to perform actions in Google Cloud. These permissions are included in a custom role provided by NetApp. You might want to understand what BlueXP does with these permissions.

Service account permissions

The custom role shown below provides the permissions that a Connector needs to manage resources and processes within your Google Cloud network.

You'll need to apply this custom role to a service account that gets attached to the Connector VM. View step-by-step instructions.

You also need to ensure that the role is up to date as new permissions are added in subsequent releases.

```
title: NetApp BlueXP
description: Permissions for the service account associated with the
Connector instance.
stage: GA
includedPermissions:
- iam.serviceAccounts.actAs
- compute.regionBackendServices.create
- compute.regionBackendServices.get
- compute.regionBackendServices.list
- compute.networks.updatePolicy
- compute.backendServices.create
- compute.addresses.list
- compute.disks.create
- compute.disks.createSnapshot
- compute.disks.delete
- compute.disks.get
- compute.disks.list
- compute.disks.setLabels
- compute.disks.use
- compute.firewalls.create
- compute.firewalls.delete
- compute.firewalls.get
- compute.firewalls.list
- compute.globalOperations.get
- compute.images.get
- compute.images.getFromFamily
- compute.images.list
- compute.images.useReadOnly
- compute.instances.addAccessConfig
```

- compute.instances.attachDisk
- compute.instances.create
- compute.instances.delete
- compute.instances.detachDisk
- compute.instances.get
- compute.instances.getSerialPortOutput
- compute.instances.list
- compute.instances.setDeletionProtection
- compute.instances.setLabels
- compute.instances.setMachineType
- compute.instances.setMetadata
- compute.instances.setTags
- compute.instances.start
- compute.instances.stop
- compute.instances.updateDisplayDevice
- compute.machineTypes.get
- compute.networks.get
- compute.networks.list
- compute.projects.get
- compute.regions.get
- compute.regions.list
- compute.snapshots.create
- compute.snapshots.delete
- compute.snapshots.get
- compute.snapshots.list
- compute.snapshots.setLabels
- compute.subnetworks.get
- compute.subnetworks.list
- compute.subnetworks.use
- compute.subnetworks.useExternalIp
- compute.zoneOperations.get
- compute.zones.get
- compute.zones.list
- compute.instances.setServiceAccount
- deploymentmanager.compositeTypes.get
- deploymentmanager.compositeTypes.list
- deploymentmanager.deployments.create
- deploymentmanager.deployments.delete
- deploymentmanager.deployments.get
- deploymentmanager.deployments.list
- deploymentmanager.manifests.get
- deploymentmanager.manifests.list
- deploymentmanager.operations.get
- deploymentmanager.operations.list
- deploymentmanager.resources.get
- deploymentmanager.resources.list

- deploymentmanager.typeProviders.getdeploymentmanager.typeProviders.list
 - deploymentmanager.types.get
 - deploymentmanager.types.list
 - logging.logEntries.list
 - logging.privateLogEntries.list
- resourcemanager.projects.get
- storage.buckets.create
- storage.buckets.delete
- storage.buckets.get
- storage.buckets.list
- cloudkms.cryptoKeyVersions.useToEncrypt
- cloudkms.cryptoKeys.get
- cloudkms.cryptoKeys.list
- cloudkms.keyRings.list
- storage.buckets.update
- iam.serviceAccounts.getIamPolicy
- iam.serviceAccounts.list
- storage.objects.get
- storage.objects.list
- monitoring.timeSeries.list
- storage.buckets.getIamPolicy

How Google Cloud permissions are used

| Actions | Purpose |
|---|---|
| compute.disks.create compute.disks.createSnapshot compute.disks.delete compute.disks.get compute.disks.list compute.disks.setLabels compute.disks.use | To create and manage disks for Cloud Volumes ONTAP. |
| compute.firewalls.createcompute.firewalls.deletecompute.firewalls.getcompute.firewalls.list | To create firewall rules for Cloud Volumes ONTAP. |
| - compute.globalOperations.get | To get the status of operations. |
| compute.images.getcompute.images.getFromFamilycompute.images.listcompute.images.useReadOnly | To get images for VM instances. |
| - compute.instances.attachDisk - compute.instances.detachDisk | To attach and detach disks to Cloud Volumes ONTAP. |

| Actions | Purpose |
|---|--|
| - compute.instances.create - compute.instances.delete | To create and delete Cloud Volumes ONTAP VM instances. |
| - compute.instances.get | To list VM instances. |
| - compute.instances.getSerialPortOutput | To get console logs. |
| - compute.instances.list | To retrieve the list of instances in a zone. |
| - compute.instances.setDeletionProtection | To set deletion protection on the instance. |
| - compute.instances.setLabels | To add labels. |
| - compute.instances.setMachineType - compute.instances.setMinCpuPlatform | To change the machine type for Cloud Volumes ONTAP. |
| - compute.instances.setMetadata | To add metadata. |
| - compute.instances.setTags | To add tags for firewall rules. |
| compute.instances.startcompute.instances.stopcompute.instances.updateDisplayDevice | To start and stop Cloud Volumes ONTAP. |
| - compute.machineTypes.get | To get the numbers of cores to check qoutas. |
| - compute.projects.get | To support multi-projects. |
| compute.snapshots.createcompute.snapshots.deletecompute.snapshots.getcompute.snapshots.listcompute.snapshots.setLabels | To create and manage persistent disk snapshots. |
| compute.networks.get compute.regions.get compute.regions.list compute.subnetworks.get compute.subnetworks.list compute.zoneOperations.get compute.zones.get compute.zones.list | To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance. |

| Actions | Purpose |
|---|--|
| deploymentmanager.compositeTypes.get deploymentmanager.deployments.create deploymentmanager.deployments.delete deploymentmanager.deployments.get deploymentmanager.deployments.list deploymentmanager.manifests.get deploymentmanager.manifests.list deploymentmanager.operations.get deploymentmanager.operations.list deploymentmanager.resources.get deploymentmanager.resources.list deploymentmanager.typeProviders.get deploymentmanager.typeProviders.list deploymentmanager.types.get deploymentmanager.types.get deploymentmanager.types.list | To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager. |
| logging.logEntries.listlogging.privateLogEntries.list | To get stack log drives. |
| - resourcemanager.projects.get | To support multi-projects. |
| storage.buckets.createstorage.buckets.deletestorage.buckets.getstorage.buckets.liststorage.buckets.update | To create and manage a Google Cloud Storage bucket for data tiering. |
| cloudkms.cryptoKeyVersions.useToEncryptcloudkms.cryptoKeys.getcloudkms.cryptoKeys.listcloudkms.keyRings.list | To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP. |
| compute.instances.setServiceAccount iam.serviceAccounts.actAs iam.serviceAccounts.getIamPolicy iam.serviceAccounts.list storage.objects.get storage.objects.list | To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket. |
| - compute.addresses.list | To retrieve the addresses in a region when deploying an HA pair. |
| compute.backendServices.createcompute.regionBackendServices.createcompute.regionBackendServices.getcompute.regionBackendServices.list | To configure a backend service for distributing traffic in an HA pair. |
| - compute.networks.updatePolicy | To apply firewall rules on the VPCs and subnets for an HA pair. |
| compute.subnetworks.usecompute.subnetworks.useExternallpcompute.instances.addAccessConfig | To enable Cloud Data Sense. |

| Actions | Purpose |
|--|--|
| - container.clusters.get - container.clusters.list | To discover Kubernetes clusters running in Google Kubernetes Engine. |
| - compute.instanceGroups.get - compute.addresses.get | To create and manage storage VMs on HA pairs. |
| - monitoring.timeSeries.list - storage.buckets.getlamPolicy | To discover information about Google Cloud Storage buckets. |

Ports

Security group rules in AWS

The AWS security group for the Connector requires both inbound and outbound rules.

Inbound rules

| Protocol | Port | Purpose |
|----------|------|---|
| SSH | 22 | Provides SSH access to the Connector host |
| HTTP | 80 | Provides HTTP access from client web browsers to the local user interface |
| HTTPS | 443 | Provides HTTPS access from client web browsers to the local user interface, and connections from the Cloud Data Sense instance |
| TCP | 3128 | Provides Cloud Volumes ONTAP with internet access to send AutoSupport messages to NetApp Support. You must manually open this port after deployment. Learn more about the Connector's proxy server. |
| TCP | 9060 | Provides the ability to enable and use Cloud Data Sense and Cloud Backup in Government Cloud deployments. This port is also required for Cloud Backup if you disable the SaaS interface in your BlueXP account. |

Outbound rules

The predefined security group for the Connector opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined security group for the Connector includes the following outbound rules.

| Protocol | Port | Purpose |
|----------|------|----------------------|
| All TCP | All | All outbound traffic |
| All UDP | All | All outbound traffic |

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by the Connector.



The source IP address is the Connector host.

| Service | Prot ocol | | Destination | Purpose |
|------------------------------|-----------|----------|--|--|
| API calls and AutoSupport | HTT PS | 44 3 | Outbound internet and ONTAP cluster management LIF | API calls to AWS and ONTAP, to Cloud Data Sense, to the Ransomware service, and sending AutoSupport messages to NetApp |
| API calls | TCP | 30 00 | ONTAP HA mediator | Communication with the ONTAP HA mediator |
| | TCP | 80 88 | Backup to S3 | API calls to Backup to S3 |
| DNS | UDP | 53 | DNS | Used for DNS resolve by BlueXP |

Security group rules in Azure

The Azure security group for the Connector requires both inbound and outbound rules.

Inbound rules

| Protoc ol | Port | Purpose |
|--------------|----------|---|
| SSH | 22 | Provides SSH access to the Connector host |
| HTTP | 80 | Provides HTTP access from client web browsers to the local user interface |
| HTTPS | 443 | Provides HTTPS access from client web browsers to the local user interface, and connections from the Cloud Data Sense instance |
| TCP | 312 8 | Provides Cloud Volumes ONTAP with internet access to send AutoSupport messages to NetApp Support. You must manually open this port after deployment. Learn more about the Connector's proxy server. |
| TCP | 906 0 | Provides the ability to enable and use Cloud Data Sense and Cloud Backup in Government Cloud deployments. This port is also required for Cloud Backup if you disable the SaaS interface in your BlueXP account. |

Outbound rules

The predefined security group for the Connector opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined security group for the Connector includes the following outbound rules.

| Protoc ol | Por t | Purpose |
|--------------|----------|----------------------|
| All TCP | All | All outbound traffic |
| All UDP | All | All outbound traffic |

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by the Connector.



The source IP address is the Connector host.

| Service | Prot ocol | | Destination | Purpose |
|---------|-----------|----|--|--|
| | | | Outbound internet and ONTAP cluster management LIF | API calls to Azure and ONTAP, to Cloud Data Sense, to the Ransomware service, and sending AutoSupport messages to NetApp |
| DNS | UDP | 53 | DNS | Used for DNS resolve by BlueXP |

Firewall rules in Google Cloud

The Google Cloud firewall rules for the Connector requires both inbound and outbound rules.

Inbound rules

| Protocol | Port | Purpose |
|----------|------|---|
| SSH | 22 | Provides SSH access to the Connector host |
| HTTP | 80 | Provides HTTP access from client web browsers to the local user interface |
| HTTPS | 443 | Provides HTTPS access from client web browsers to the local user interface |
| TCP | 3128 | Provides Cloud Volumes ONTAP with internet access to send AutoSupport messages to NetApp Support. You must manually open this port after deployment. Learn more about the Connector's proxy server. |

Outbound rules

The predefined firewall rules for the Connector opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined firewall rules for the Connector includes the following outbound rules.

| Protocol | Port | Purpose |
|----------|------|----------------------|
| All TCP | All | All outbound traffic |
| All UDP | All | All outbound traffic |

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by the Connector.



The source IP address is the Connector host.

| Service | Prot ocol | | Destination | Purpose |
|---------|-----------|----|--|--|
| | | | Outbound internet and ONTAP cluster management LIF | API calls to GCP and ONTAP, to Cloud Data Sense, to the Ransomware service, and sending AutoSupport messages to NetApp |
| DNS | UDP | 53 | DNS | Used for DNS resolve by BlueXP |

Ports for the on-prem Connector

The Connector uses the following *inbound* ports when installed manually on an on-premises Linux host.

These inbound rules apply to both deployment models for the on-prem Connector: installed with internet access or without internet access.

| Protocol | Port | Purpose |
|----------|------|--|
| HTTP | 80 | Provides HTTP access from client web browsers to the local user interface |
| HTTPS | 443 | Provides HTTPS access from client web browsers to the local user interface |

Copyright information

Copyright © 2022 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.