■ NetApp

Reference

Set up and administration

NetApp March 10, 2023

This PDF was generated from https://docs.netapp.com/us-en/cloud-manager-setup-admin/reference-permissions.html on March 10, 2023. Always check docs.netapp.com for the latest.

Table of Contents

| Reference |
 |
. 1 |
|---------------|------|------|------|------|------|------|------|------|------|------|------|------|------|------|------|---------|
| Permissions . |
 |
. 1 |
| Ports |
 |
56 |

Reference

Permissions

Permissions summary for BlueXP

In order to use the features and services in BlueXP, you'll need to provide permissions so that BlueXP can perform operations in your cloud environment. Use the links on this page to quickly access the permissions that you need based on your goal.

AWS permissions

Purpose	Description	Link
Connector deployment	The user who creates a Connector from BlueXP needs specific permissions to deploy the instance in AWS.	Create a Connector in AWS from BlueXP
Connector operation	policy to the instance that provides the permissions required to manage resources and processes in your AWS account. You need to set up the policy yourself if you launch a Connector from the marketplace or if you add	AWS permissions for the Connector
	more AWS credentials to a Connector. You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.	
Cloud Volumes ONTAP operation	An IAM role must be attached to each Cloud Volumes ONTAP node in AWS. The same is true for the HA mediator. The default option is to let BlueXP create the IAM roles for you, but you can use your own.	Learn how to set up the IAM roles yourself

Azure permissions

Purpose	Description	Link
Connector deployment	When you deploy a Connector from BlueXP, you need to use an Azure account or service principal that has permissions to deploy the Connector VM in Azure.	Create a Connector in Azure from BlueXP

Purpose	Description	Link
Connector operation	When BlueXP deploys the Connector VM in Azure, it creates a custom role that provides the permissions required to manage resources and processes within that Azure subscription.	Azure permissions for the Connector
	You need to set up the custom role yourself if you launch a Connector from the marketplace or if you add more Azure credentials to a Connector.	
	You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.	

Google Cloud permissions

Purpose	Description	Link
Connector deployment	The Google Cloud user who deploys a Connector from BlueXP needs specific permissions to deploy the Connector in Google Cloud.	Set up permissions to deploy the Connector
Connector operation	The service account for the Connector VM instance must have specific permissions for day-to-day operations. You need to associate the service account with the Connector when you deploy it from BlueXP. You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.	Set up a service account for the Connector

AWS permissions for the Connector

When BlueXP launches the Connector instance in AWS, it attaches a policy to the instance that provides the Connector with permissions to manage resources and processes within that AWS account. The Connector uses the permissions to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Key Management Service (KMS), and more.

IAM policies

The IAM policies available below provide the permissions that a Connector needs to manage resources and processes within your public cloud environment based on your AWS region.

If you create a Connector in a standard AWS region directly from BlueXP, BlueXP automatically applies policies to the Connector. You don't need to do anything in this case.

If you deploy the Connector from the AWS Marketplace or if you manually install the Connector on a Linux host, then you'll need to set up the policies yourself.

You also need to ensure that the policies are up to date as new permissions are added in subsequent releases.

Select your region to view the required policies:	

Standard regions

For standard regions, the permissions are spread across two policies. Two policies are required due to a maximum character size limit for managed policies in AWS.

The first policy provides permissions for the following services:

- Cloud Backup
- · Cloud Data Sense
- Cloud Tiering
- Cloud Volumes ONTAP
- FSx for ONTAP
- · S3 bucket discovery

The second policy provides permissions for the following services:

- AppTemplate tagging
- · Global File Cache
- Kubernetes

Policy #1

```
{
    "Statement": [
            "Action": [
                "ec2:DescribeInstances",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:DescribeInstanceAttribute",
                "ec2:DescribeRouteTables",
                "ec2:DescribeImages",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:ModifyVolumeAttribute",
                "ec2:CreateSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcs",
                "ec2:DescribeDhcpOptions",
                "ec2:CreateSnapshot",
                "ec2:DescribeSnapshots",
                "ec2:GetConsoleOutput",
                "ec2:DescribeKeyPairs",
                "ec2:DescribeRegions",
                "ec2:DescribeTags",
                "ec2: Associate Iam Instance Profile",
                "ec2:DescribeIamInstanceProfileAssociations",
                "ec2:DisassociateIamInstanceProfile",
                "ec2:CreatePlacementGroup",
                "ec2:DescribeReservedInstancesOfferings",
                "ec2:AssignPrivateIpAddresses",
                "ec2:CreateRoute",
                "ec2:DescribeVpcs",
                "ec2:ReplaceRoute",
                "ec2:UnassignPrivateIpAddresses",
                "ec2:DeleteSecurityGroup",
```

```
"ec2:DeleteNetworkInterface",
"ec2:DeleteSnapshot",
"ec2:DeleteTags",
"ec2:DeleteRoute",
"ec2:DeletePlacementGroup",
"ec2:DescribePlacementGroups",
"ec2:DescribeVolumesModifications",
"ec2:ModifyVolume",
"cloudformation:CreateStack",
"cloudformation: DescribeStacks",
"cloudformation:DescribeStackEvents",
"cloudformation: Validate Template",
"cloudformation: DeleteStack",
"iam:PassRole",
"iam:CreateRole",
"iam:PutRolePolicy",
"iam:CreateInstanceProfile",
"iam: AddRoleToInstanceProfile",
"iam: RemoveRoleFromInstanceProfile",
"iam:ListInstanceProfiles",
"iam:DeleteRole",
"iam: DeleteRolePolicy",
"iam:DeleteInstanceProfile",
"iam:GetRolePolicy",
"iam:GetRole",
"sts:DecodeAuthorizationMessage",
"sts:AssumeRole",
"s3:GetBucketTagging",
"s3:GetBucketLocation",
"s3:ListBucket",
"s3:CreateBucket",
"s3:GetLifecycleConfiguration",
"s3:ListBucketVersions",
"s3:GetBucketPolicyStatus",
"s3:GetBucketPublicAccessBlock",
"s3:GetBucketPolicy",
"s3:GetBucketAcl",
"s3:PutObjectTagging",
"s3:GetObjectTagging",
"s3:DeleteObject",
"s3:DeleteObjectVersion",
"s3:PutObject",
"s3:ListAllMyBuckets",
"s3:GetObject",
"s3:GetEncryptionConfiguration",
"kms:List*",
```

```
"kms:ReEncrypt*",
        "kms:Describe*",
        "kms:CreateGrant",
        "ce:GetReservationUtilization",
        "ce:GetDimensionValues",
        "ce:GetCostAndUsage",
        "ce:GetTags",
        "fsx:Describe*",
        "fsx:List*"
    ],
    "Resource": "*",
    "Effect": "Allow",
    "Sid": "cvoServicePolicy"
},
    "Action": [
        "ec2:StartInstances",
        "ec2:StopInstances",
        "ec2:DescribeInstances",
        "ec2:DescribeInstanceStatus",
        "ec2:RunInstances",
        "ec2:TerminateInstances",
        "ec2:DescribeInstanceAttribute",
        "ec2:DescribeImages",
        "ec2:CreateTags",
        "ec2:CreateVolume",
        "ec2:CreateSecurityGroup",
        "ec2:DescribeSubnets",
        "ec2:DescribeVpcs",
        "ec2:DescribeRegions",
        "cloudformation:CreateStack",
        "cloudformation: DeleteStack",
        "cloudformation:DescribeStacks",
        "kms:List*",
        "kms:Describe*",
        "ec2:DescribeVpcEndpoints",
        "kms:ListAliases",
        "athena:StartQueryExecution",
        "athena:GetQueryResults",
        "athena:GetQueryExecution",
        "glue:GetDatabase",
        "glue:GetTable",
        "glue:CreateTable",
        "glue:CreateDatabase",
        "glue:GetPartitions",
        "glue:BatchCreatePartition",
```

```
"glue:BatchDeletePartition"
    ],
    "Resource": "*",
    "Effect": "Allow",
    "Sid": "backupPolicy"
},
    "Action": [
        "s3:GetBucketLocation",
        "s3:ListAllMyBuckets",
        "s3:ListBucket",
        "s3:CreateBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketAcl",
        "s3:PutBucketPublicAccessBlock",
        "s3:GetObject",
        "s3:PutEncryptionConfiguration",
        "s3:DeleteObject",
        "s3:DeleteObjectVersion",
        "s3:ListBucketMultipartUploads",
        "s3:PutObject",
        "s3:PutBucketAcl",
        "s3:AbortMultipartUpload",
        "s3:ListMultipartUploadParts",
        "s3:DeleteBucket",
        "s3:GetObjectVersionTagging",
        "s3:GetObjectVersionAcl",
        "s3:GetObjectRetention",
        "s3:GetObjectTagging",
        "s3:GetObjectVersion",
        "s3:PutObjectVersionTagging",
        "s3:PutObjectRetention",
        "s3:DeleteObjectTagging",
        "s3:DeleteObjectVersionTagging",
        "s3:GetBucketObjectLockConfiguration",
        "s3:GetBucketVersioning",
        "s3:PutBucketObjectLockConfiguration",
        "s3:PutBucketVersioning",
        "s3:BypassGovernanceRetention",
        "s3:PutBucketPolicy",
        "s3:PutBucketOwnershipControls"
    ],
    "Resource": [
```

```
"arn:aws:s3:::netapp-backup-*"
    ],
    "Effect": "Allow",
    "Sid": "backupS3Policy"
},
   "Action": [
        "s3:CreateBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock",
       "s3:DeleteBucket"
   ],
    "Resource": [
        "arn:aws:s3:::fabric-pool*"
   ],
    "Effect": "Allow",
   "Sid": "fabricPoolS3Policy"
},
   "Action": [
       "ec2:DescribeRegions"
   ],
    "Resource": "*",
   "Effect": "Allow",
   "Sid": "fabricPoolPolicy"
},
    "Condition": {
        "StringLike": {
            "ec2:ResourceTag/netapp-adc-manager": "*"
    },
    "Action": [
        "ec2:StartInstances",
       "ec2:StopInstances",
       "ec2:TerminateInstances"
    ],
    "Resource": [
        "arn:aws:ec2:*:*:instance/*"
```

```
],
    "Effect": "Allow"
},
   "Condition": {
       "StringLike": {
            "ec2:ResourceTag/WorkingEnvironment": "*"
    } ,
    "Action": [
       "ec2:StartInstances",
        "ec2:TerminateInstances",
       "ec2:AttachVolume",
       "ec2:DetachVolume",
       "ec2:StopInstances",
        "ec2:DeleteVolume"
   ],
    "Resource": [
      "arn:aws:ec2:*:*:instance/*"
   "Effect": "Allow"
},
   "Action": [
       "ec2:AttachVolume",
       "ec2:DetachVolume"
    "Resource": [
       "arn:aws:ec2:*:*:volume/*"
   ],
   "Effect": "Allow"
},
    "Condition": {
       "StringLike": {
            "ec2:ResourceTag/WorkingEnvironment": "*"
    } ,
    "Action": [
       "ec2:DeleteVolume"
   ],
   "Resource": [
    "arn:aws:ec2:*:*:volume/*"
   "Effect": "Allow"
```

```
}
```

Policy #2

```
{
    "Statement": [
            "Action": [
                "ec2:DescribeRegions",
                "eks:ListClusters",
                "eks:DescribeCluster",
                "iam:GetInstanceProfile"
            ],
            "Resource": "*",
            "Effect": "Allow",
            "Sid": "K8sServicePolicy"
        },
            "Action": [
                "cloudformation:DescribeStacks",
                "cloudwatch: GetMetricStatistics",
                "cloudformation:ListStacks"
            ],
            "Resource": "*",
            "Effect": "Allow",
            "Sid": "GFCservicePolicy"
        },
            "Condition": {
                "StringLike": {
                    "ec2:ResourceTag/GFCInstance": "*"
                }
            },
            "Action": [
                "ec2:StartInstances",
                "ec2:TerminateInstances",
                "ec2:AttachVolume",
                "ec2:DetachVolume"
            ],
            "Resource": [
              "arn:aws:ec2:*:*:instance/*"
            "Effect": "Allow"
        },
```

```
"Action": [
                "ec2:CreateTags",
                "ec2:DeleteTags",
                "ec2:DescribeTags",
                "tag:getResources",
                "tag:getTagKeys",
                "tag:getTagValues",
                "tag:TagResources",
                "tag:UntagResources"
           ],
            "Resource": "*",
            "Effect": "Allow",
            "Sid": "tagServicePolicy"
        }
   ]
}
```

```
{
    "Version": "2012-10-17",
    "Statement": [
            "Effect": "Allow",
            "Action": [
                "iam:ListInstanceProfiles",
                "iam:CreateRole",
                "iam:DeleteRole",
                "iam:PutRolePolicy",
                "iam:CreateInstanceProfile",
                "iam: DeleteRolePolicy",
                "iam:AddRoleToInstanceProfile",
                "iam: RemoveRoleFromInstanceProfile",
                "iam:DeleteInstanceProfile",
                "ec2:ModifyVolumeAttribute",
                "sts:DecodeAuthorizationMessage",
                "ec2:DescribeImages",
                "ec2:DescribeRouteTables",
                "ec2:DescribeInstances",
                "iam:PassRole",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:DeleteVolume",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DeleteNetworkInterface",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcs",
                "ec2:DescribeDhcpOptions",
                "ec2:CreateSnapshot",
                "ec2:DeleteSnapshot",
```

```
"ec2:DescribeSnapshots",
        "ec2:StopInstances",
        "ec2:GetConsoleOutput",
        "ec2:DescribeKeyPairs",
        "ec2:DescribeRegions",
        "ec2:DeleteTags",
        "ec2:DescribeTags",
        "cloudformation:CreateStack",
        "cloudformation: DeleteStack",
        "cloudformation: DescribeStacks",
        "cloudformation: DescribeStackEvents",
        "cloudformation: Validate Template",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:ListAllMyBuckets",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:CreateBucket",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "kms:List*",
        "kms:ReEncrypt*",
        "kms:Describe*",
        "kms:CreateGrant",
        "ec2: Associate Iam Instance Profile",
        "ec2:DescribeIamInstanceProfileAssociations",
        "ec2:DisassociateIamInstanceProfile",
        "ec2:DescribeInstanceAttribute",
        "ce:GetReservationUtilization",
        "ce:GetDimensionValues",
        "ce:GetCostAndUsage",
        "ce:GetTags",
        "ec2:CreatePlacementGroup",
        "ec2:DeletePlacementGroup"
    ],
    "Resource": "*"
},
{
    "Sid": "fabricPoolPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
```

```
"s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock"
    ],
    "Resource": [
        "arn:aws-us-gov:s3:::fabric-pool*"
},
    "Sid": "backupPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:ListAllMyBuckets",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock"
    ],
    "Resource": [
        "arn:aws-us-gov:s3:::netapp-backup-*"
},
    "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
        "ec2:TerminateInstances",
        "ec2:AttachVolume",
        "ec2:DetachVolume"
    ],
    "Condition": {
        "StringLike": {
```

```
"ec2:ResourceTag/WorkingEnvironment": "*"
              }
           },
           "Resource": [
              "arn:aws-us-gov:ec2:*:*:instance/*"
       },
        {
           "Effect": "Allow",
           "Action": [
               "ec2:AttachVolume",
               "ec2:DetachVolume"
           ],
           "Resource": [
               "arn:aws-us-gov:ec2:*:*:volume/*"
           ]
       }
}
```

```
{
    "Version": "2012-10-17",
    "Statement": [{
            "Effect": "Allow",
            "Action": [
                "ec2:DescribeInstances",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:DescribeRouteTables",
                "ec2:DescribeImages",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:ModifyVolumeAttribute",
                "ec2:DeleteVolume",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DeleteNetworkInterface",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcs",
                "ec2:DescribeDhcpOptions",
                "ec2:CreateSnapshot",
                "ec2:DeleteSnapshot",
                "ec2:DescribeSnapshots",
                "ec2:GetConsoleOutput",
                "ec2:DescribeKeyPairs",
                "ec2:DescribeRegions",
                "ec2:DeleteTags",
                "ec2:DescribeTags",
                "cloudformation:CreateStack",
                "cloudformation: DeleteStack",
                "cloudformation:DescribeStacks",
                "cloudformation: DescribeStackEvents",
                "cloudformation: Validate Template",
                "iam:PassRole",
```

```
"iam:CreateRole",
        "iam:DeleteRole",
        "iam:PutRolePolicy",
        "iam:CreateInstanceProfile",
        "iam:DeleteRolePolicy",
        "iam:AddRoleToInstanceProfile",
        "iam: RemoveRoleFromInstanceProfile",
        "iam:DeleteInstanceProfile",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:ListAllMyBuckets",
        "kms:List*",
        "kms:Describe*",
        "ec2: Associate Iam Instance Profile",
        "ec2:DescribeIamInstanceProfileAssociations",
        "ec2:DisassociateIamInstanceProfile",
        "ec2:DescribeInstanceAttribute",
        "ec2:CreatePlacementGroup",
        "ec2:DeletePlacementGroup",
        "iam:ListinstanceProfiles"
    ],
    "Resource": "*"
},
    "Sid": "fabricPoolPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions"
    ],
    "Resource": [
        "arn:aws-iso:s3:::fabric-pool*"
},
    "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
        "ec2:StopInstances",
        "ec2:TerminateInstances",
        "ec2:AttachVolume",
```

```
"ec2:DetachVolume"
            ],
            "Condition": {
                 "StringLike": {
                     "ec2:ResourceTag/WorkingEnvironment": "*"
            },
            "Resource": [
                 "arn:aws-iso:ec2:*:*:instance/*"
            1
        },
        {
            "Effect": "Allow",
            "Action": [
                 "ec2:AttachVolume",
                 "ec2:DetachVolume"
            ],
            "Resource": [
                 "arn:aws-iso:ec2:*:*:volume/*"
        }
    ]
}
```

How the AWS permissions are used

The following sections describe how the permissions are used for each NetApp cloud service. This information can be helpful if your corporate policies dictate that permissions are only provided as needed.

AppTemplate tags

The Connector makes the following API requests to manage tags on AWS resources when you use the AppTemplate Tagging service:

- ec2:CreateTags
- · ec2:DeleteTags
- · ec2:DescribeTags
- · tag:getResources
- tag:getTagKeys
- tag:getTagValues
- tag:TagResources
- tag:UntagResources

Cloud Backup

The Connector makes the following API requests to deploy the restore instance for Cloud Backup:

- ec2:StartInstances
- ec2:StopInstances
- ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:DescribeInstanceAttribute
- · ec2:DescribeImages
- · ec2:CreateTags
- ec2:CreateVolume
- ec2:CreateSecurityGroup
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:DescribeRegions
- · cloudformation:CreateStack
- cloudformation:DeleteStack
- · cloudformation:DescribeStacks

The Connector makes the following API requests to manage backups in Amazon S3:

- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:CreateBucket
- s3:GetLifecycleConfiguration
- s3:PutLifecycleConfiguration
- s3:PutBucketTagging
- s3:ListBucketVersions
- s3:GetBucketAcl
- s3:PutBucketPublicAccessBlock
- · kms:List*
- · kms:Describe*
- s3:GetObject
- ec2:DescribeVpcEndpoints
- · kms:ListAliases
- s3:PutEncryptionConfiguration

The Connector makes the following API requests when you use the Search & Restore method to restore volumes and files:

- s3:CreateBucket
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:GetBucketAcl
- s3:ListBucket
- s3:ListBucketVersions
- s3:ListBucketMultipartUploads
- s3:PutObject
- s3:PutBucketAcl
- s3:PutLifecycleConfiguration
- s3:PutBucketPublicAccessBlock
- s3:AbortMultipartUpload
- s3:ListMultipartUploadParts
- athena:StartQueryExecutionc
- athena:GetQueryResults
- athena:GetQueryExecution
- · athena:StopQueryExecution
- · glue:CreateDatabase
- · glue:CreateTable
- glue:BatchDeletePartition

The Connector makes the following API requests when you use DataLock and Ransomware protection for your volume backups:

- s3:GetObjectVersionTagging
- s3:GetBucketObjectLockConfiguration
- s3:GetObjectVersionAcl
- s3:PutObjectTagging
- s3:DeleteObject
- s3:DeleteObjectTagging
- s3:GetObjectRetention
- · s3:DeleteObjectVersionTagging
- s3:PutObject
- · s3:GetObject
- s3:PutBucketObjectLockConfiguration
- s3:GetLifecycleConfiguration
- s3:ListBucketByTags

- s3:GetBucketTagging
- s3:DeleteObjectVersion
- s3:ListBucketVersions
- s3:ListBucket
- s3:PutBucketTagging
- s3:GetObjectTagging
- s3:PutBucketVersioning
- s3:PutObjectVersionTagging
- · s3:GetBucketVersioning
- s3:GetBucketAcl
- · s3:BypassGovernanceRetention
- s3:PutObjectRetention
- s3:GetBucketLocation
- s3:GetObjectVersion

The Connector makes the following API requests if you use a different AWS account for your Cloud Volumes ONTAP backups than you're using for the source volumes:

- s3:PutBucketPolicy
- s3:PutBucketOwnershipControls

Cloud Data Sense

The Connector makes the following API requests to deploy the Cloud Data Sense instance:

- ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:CreateTags
- ec2:CreateVolume
- ec2:AttachVolume
- ec2:CreateSecurityGroup
- · ec2:DeleteSecurityGroup
- ec2:DescribeSecurityGroups
- ec2:CreateNetworkInterface
- ec2:DescribeNetworkInterfaces
- · ec2:DeleteNetworkInterface
- ec2:DescribeSubnets
- · ec2:DescribeVpcs
- ec2:CreateSnapshot

- ec2:DescribeRegions
- · cloudformation:CreateStack
- · cloudformation:DeleteStack
- · cloudformation:DescribeStacks
- cloudformation:DescribeStackEvents
- iam:AddRoleToInstanceProfile
- ec2:AssociatelamInstanceProfile
- ec2:DescribelamInstanceProfileAssociations

The Connector makes the following API requests to scan S3 buckets when you use Cloud Data Sense:

- iam:AddRoleToInstanceProfile
- ec2:AssociatelamInstanceProfile
- · ec2:DescribelamInstanceProfileAssociations
- s3:GetBucketTagging
- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:GetBucketPolicyStatus
- s3:GetBucketPolicy
- s3:GetBucketAcl
- · s3:GetObject
- · iam:GetRole
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:PutObject
- sts:AssumeRole

Cloud Tiering

The Connector makes the following API requests to tier data to Amazon S3 when you use Cloud Tiering.

Action	Used for set up?	Used for daily operations?
s3:CreateBucket	Yes	No
s3:PutLifecycleConfiguration	Yes	No
s3:GetLifecycleConfiguration	Yes	Yes
ec2:DescribeRegions	Yes	No
ec2:DescribeVpcEndpoints	Yes	No

Cloud Volumes ONTAP

The Connector makes the following API requests to deploy and manage Cloud Volumes ONTAP in AWS.

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage IAM roles and	iam:ListInstanceProfi les	Yes	Yes	No
instance profiles for Cloud Volumes	iam:CreateRole	Yes	No	No
ONTAP instances	iam:DeleteRole	No	Yes	Yes
	iam:PutRolePolicy	Yes	No	No
	iam:CreateInstanceP rofile	Yes	No	No
	iam:DeleteRolePolic y	No	Yes	Yes
	iam:AddRoleToInsta nceProfile	Yes	No	No
	iam:RemoveRoleFro mlnstanceProfile	No	Yes	Yes
	iam:DeleteInstanceP rofile	No	Yes	Yes
	iam:PassRole	Yes	No	No
	ec2:AssociateIamIns tanceProfile	Yes	Yes	No
	ec2:DescribelamInst anceProfileAssociati ons	Yes	Yes	No
	ec2:Disassociatelam InstanceProfile	No	Yes	No
Decode authorization status messages	sts:DecodeAuthoriza tionMessage	Yes	Yes	No
Describe the specified images (AMIs) available to the account	ec2:DescribeImages	Yes	Yes	No
Describe the route tables in a VPC (required for HA pairs only)	ec2:DescribeRouteT ables	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Stop, start, and	ec2:StartInstances	Yes	Yes	No
monitor instances	ec2:StopInstances	Yes	Yes	No
	ec2:DescribeInstanc	Yes	Yes	No
	ec2:DescribeInstanc eStatus	Yes	Yes	No
	ec2:RunInstances	Yes	No	No
	ec2:TerminateInstan	No	No	Yes
	ec2:ModifyInstanceA ttribute	No	Yes	No
Verify that enhanced networking is enabled for supported instance types	ec2:DescribeInstanc eAttribute	No	Yes	No
Tag resources with the "WorkingEnvironme nt" and "WorkingEnvironme ntld" tags which are used for maintenance and cost allocation	ec2:CreateTags	Yes	Yes	No
Manage EBS	ec2:CreateVolume	Yes	Yes	No
volumes that Cloud Volumes ONTAP uses as back-end storage	ec2:DescribeVolume s	Yes	Yes	Yes
	ec2:ModifyVolumeAt tribute	No	Yes	Yes
	ec2:AttachVolume	Yes	Yes	No
	ec2:DeleteVolume	No	Yes	Yes
	ec2:DetachVolume	No	Yes	Yes

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage security groups for Cloud Volumes ONTAP	ec2:CreateSecurityG roup	Yes	No	No
	ec2:DeleteSecurityG roup	No	Yes	Yes
	ec2:DescribeSecurit yGroups	Yes	Yes	Yes
	ec2:RevokeSecurity GroupEgress	Yes	No	No
	ec2:AuthorizeSecurit yGroupEgress	Yes	No	No
	ec2:AuthorizeSecurit yGroupIngress	Yes	No	No
	ec2:RevokeSecurity GroupIngress	Yes	Yes	No
Create and manage network interfaces	ec2:CreateNetworkInterface	Yes	No	No
for Cloud Volumes ONTAP in the target subnet	ec2:DescribeNetwor kInterfaces	Yes	Yes	No
	ec2:DeleteNetworkIn terface	No	Yes	Yes
	ec2:ModifyNetworkIn terfaceAttribute	No	Yes	No
Get the list of destination subnets	ec2:DescribeSubnet s	Yes	Yes	No
and security groups	ec2:DescribeVpcs	Yes	Yes	No
Get DNS servers and the default domain name for Cloud Volumes ONTAP instances	ec2:DescribeDhcpO ptions	Yes	No	No
Take snapshots of	ec2:CreateSnapshot	Yes	Yes	No
EBS volumes for Cloud Volumes	ec2:DeleteSnapshot	No	Yes	Yes
ONTAP	ec2:DescribeSnapsh ots	No	Yes	No
Capture the Cloud Volumes ONTAP console, which is attached to AutoSupport messages	ec2:GetConsoleOutp ut	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Get the list of available key pairs	ec2:DescribeKeyPair s	Yes	No	No
Get the list of available AWS regions	ec2:DescribeRegion s	Yes	Yes	No
Manage tags for resources	ec2:DeleteTags	No	Yes	Yes
associated with Cloud Volumes ONTAP instances	ec2:DescribeTags	No	Yes	No
Create and manage stacks for AWS	cloudformation:Creat eStack	Yes	No	No
CloudFormation templates	cloudformation:Delet eStack	Yes	No	No
	cloudformation:Desc ribeStacks	Yes	Yes	No
	cloudformation:Desc ribeStackEvents	Yes	No	No
	cloudformation:Valid ateTemplate	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage	s3:CreateBucket	Yes	Yes	No
an S3 bucket that a Cloud Volumes ONTAP system uses as a capacity tier for	s3:DeleteBucket	No	Yes	Yes
	s3:GetLifecycleConfi guration	No	Yes	No
data tiering	s3:PutLifecycleConfi guration	No	Yes	No
	s3:PutBucketTaggin	No	Yes	No
	s3:ListBucketVersion s	No	Yes	No
	s3:GetBucketPolicyS tatus	No	Yes	No
	s3:GetBucketPublic AccessBlock	No	Yes	No
	s3:GetBucketAcl	No	Yes	No
	s3:GetBucketPolicy	No	Yes	No
	s3:PutBucketPublicA ccessBlock	No	Yes	No
	s3:GetBucketTaggin	No	Yes	No
	s3:GetBucketLocatio	No	Yes	No
	s3:ListAllMyBuckets	No	No	No
	s3:ListBucket	No	Yes	No
Enable data	kms:List*	Yes	Yes	No
encryption of Cloud Volumes ONTAP	kms:ReEncrypt*	Yes	No	No
using the AWS Key Management	kms:Describe*	Yes	Yes	No
Service (KMS)	kms:CreateGrant	Yes	Yes	No
Obtain AWS cost data for Cloud	ce:GetReservationUt ilization	No	Yes	No
Volumes ONTAP	ce:GetDimensionVal	No	Yes	No
	ce:GetCostAndUsag e	No	Yes	No
	ce:GetTags	No	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage an AWS spread placement group for two HA nodes and the mediator in a single AWS Availability Zone	ec2:CreatePlacemen tGroup	Yes	No	No
	ec2:DeletePlacemen tGroup	No	Yes	Yes
Create reports	fsx:Describe*	No	Yes	No
	fsx:List*	No	Yes	No
Create and manage aggregates that support the Amazon EBS Elastic Volumes feature	ec2:DescribeVolume sModifications	No	Yes	No
	ec2:ModifyVolume	No	Yes	No

Global File Cache

The Connector makes the following API requests to deploy Global File Cache instances during deployment:

- · cloudformation:DescribeStacks
- · cloudwatch:GetMetricStatistics
- · cloudformation:ListStacks

FSx for ONTAP

The Connector makes the following API requests to manage FSx for ONTAP:

- · ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:DescribeInstanceAttribute
- ec2:DescribeRouteTables
- ec2:DescribeImages
- ec2:CreateTags
- ec2:DescribeVolumes
- ec2:DescribeSecurityGroups
- ec2:DescribeNetworkInterfaces
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:DescribeDhcpOptions
- ec2:DescribeSnapshots
- ec2:DescribeKeyPairs
- ec2:DescribeRegions

- · ec2:DescribeTags
- · ec2:DescribelamInstanceProfileAssociations
- ec2:DescribeReservedInstancesOfferings
- ec2:DescribeVpcEndpoints
- ec2:DescribeVpcs
- ec2:DescribeVolumesModifications
- ec2:DescribePlacementGroups
- · kms:List*
- kms:Describe*
- · kms:CreateGrant
- · kms:ListAliases
- fsx:Describe*
- fsx:List*

Kubernetes

The Connector makes the following API requests to discover and manage Amazon EKS clusters:

- ec2:DescribeRegions
- · eks:ListClusters
- eks:DescribeCluster
- · iam:GetInstanceProfile

S3 bucket discovery

The Connector makes the following API request to discover Amazon S3 buckets:

s3:GetEncryptionConfiguration

Change log

As permissions are added and removed, we'll note them in the sections below.

14 February, 2023

The following permission is now required for Cloud Tiering:

ec2:DescribeVpcEndpoints

Azure permissions for the Connector

When BlueXP launches the Connector VM in Azure, it attaches a custom role to the VM that provides the Connector with permissions to manage resources and processes within that Azure subscription. The Connector uses the permissions to make API calls to several Azure services.

Custom role permissions

The custom role shown below provides the permissions that a Connector needs to manage resources and processes within your Azure network.

When you create a Connector directly from BlueXP, BlueXP automatically applies this custom role to the Connector.

If you deploy the Connector from the Azure Marketplace or if you manually install the Connector on a Linux host, then you'll need to set up the custom role yourself.

You also need to ensure that the role is up to date as new permissions are added in subsequent releases.

```
{
    "Name": "BlueXP Operator",
    "Actions": [
                    "Microsoft.Compute/disks/delete",
                    "Microsoft.Compute/disks/read",
                    "Microsoft.Compute/disks/write",
                    "Microsoft.Compute/locations/operations/read",
                    "Microsoft.Compute/locations/vmSizes/read",
                    "Microsoft.Resources/subscriptions/locations/read",
                    "Microsoft.Compute/operations/read",
                    "Microsoft.Compute/virtualMachines/instanceView/read",
                    "Microsoft.Compute/virtualMachines/powerOff/action",
                    "Microsoft.Compute/virtualMachines/read",
                    "Microsoft.Compute/virtualMachines/restart/action",
                    "Microsoft.Compute/virtualMachines/deallocate/action",
                    "Microsoft.Compute/virtualMachines/start/action",
                    "Microsoft.Compute/virtualMachines/vmSizes/read",
                    "Microsoft.Compute/virtualMachines/write",
                    "Microsoft.Compute/images/read",
                    "Microsoft.Network/locations/operationResults/read",
                    "Microsoft.Network/locations/operations/read",
                    "Microsoft.Network/networkInterfaces/read",
                    "Microsoft.Network/networkInterfaces/write",
                    "Microsoft.Network/networkInterfaces/join/action",
                    "Microsoft.Network/networkSecurityGroups/read",
                    "Microsoft.Network/networkSecurityGroups/write",
                    "Microsoft.Network/networkSecurityGroups/join/action",
                    "Microsoft.Network/virtualNetworks/read",
"Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read",
                    "Microsoft.Network/virtualNetworks/subnets/read",
                    "Microsoft.Network/virtualNetworks/subnets/write",
"Microsoft.Network/virtualNetworks/subnets/virtualMachines/read",
```

```
"Microsoft.Network/virtualNetworks/virtualMachines/read",
"Microsoft.Network/virtualNetworks/subnets/join/action",
                    "Microsoft.Resources/deployments/operations/read",
                    "Microsoft.Resources/deployments/read",
                    "Microsoft.Resources/deployments/write",
                    "Microsoft.Resources/resources/read",
"Microsoft.Resources/subscriptions/operationresults/read",
"Microsoft.Resources/subscriptions/resourceGroups/delete",
"Microsoft.Resources/subscriptions/resourceGroups/read",
"Microsoft.Resources/subscriptions/resourcegroups/resources/read",
"Microsoft.Resources/subscriptions/resourceGroups/write",
                    "Microsoft.Storage/checknameavailability/read",
                    "Microsoft.Storage/operations/read",
                    "Microsoft.Storage/storageAccounts/listkeys/action",
                    "Microsoft.Storage/storageAccounts/read",
                    "Microsoft.Storage/storageAccounts/delete",
                    "Microsoft.Storage/storageAccounts/write",
"Microsoft.Storage/storageAccounts/blobServices/containers/read",
"Microsoft.Storage/storageAccounts/blobServices/containers/write",
"Microsoft.Storage/storageAccounts/listAccountSas/action",
                    "Microsoft.Storage/usages/read",
                    "Microsoft.Compute/snapshots/write",
                    "Microsoft.Compute/snapshots/read",
                    "Microsoft.Compute/availabilitySets/write",
                    "Microsoft.Compute/availabilitySets/read",
                    "Microsoft.Compute/disks/beginGetAccess/action",
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreemen
ts/read",
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreemen
ts/write",
                    "Microsoft.Network/loadBalancers/read",
                    "Microsoft.Network/loadBalancers/write",
                    "Microsoft.Network/loadBalancers/delete",
"Microsoft.Network/loadBalancers/backendAddressPools/read",
```

```
"Microsoft.Network/loadBalancers/backendAddressPools/join/action",
"Microsoft.Network/loadBalancers/loadBalancingRules/read",
                    "Microsoft.Network/loadBalancers/probes/read",
                    "Microsoft.Network/loadBalancers/probes/join/action",
                    "Microsoft.Authorization/locks/*",
                    "Microsoft.Network/routeTables/join/action",
                    "Microsoft.NetApp/netAppAccounts/read",
                    "Microsoft.NetApp/netAppAccounts/capacityPools/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/write",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",
                    "Microsoft.Network/privateEndpoints/write",
"Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/acti
on",
"Microsoft.Storage/storageAccounts/privateEndpointConnections/read",
"Microsoft.Storage/storageAccounts/managementPolicies/read",
"Microsoft.Storage/storageAccounts/managementPolicies/write",
                    "Microsoft.Network/privateEndpoints/read",
                    "Microsoft.Network/privateDnsZones/write",
"Microsoft.Network/privateDnsZones/virtualNetworkLinks/write",
                    "Microsoft.Network/virtualNetworks/join/action",
                    "Microsoft.Network/privateDnsZones/A/write",
                    "Microsoft.Network/privateDnsZones/read",
"Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",
"Microsoft.Resources/deployments/operationStatuses/read",
                    "Microsoft.Insights/Metrics/Read",
                    "Microsoft.Compute/virtualMachines/extensions/write",
                    "Microsoft.Compute/virtualMachines/extensions/delete",
                    "Microsoft.Compute/virtualMachines/extensions/read",
                    "Microsoft.Compute/virtualMachines/delete",
                    "Microsoft.Network/networkInterfaces/delete",
                    "Microsoft.Network/networkSecurityGroups/delete",
                    "Microsoft.Resources/deployments/delete",
                    "Microsoft.Compute/diskEncryptionSets/read",
```

```
"Microsoft.Compute/snapshots/delete",
                    "Microsoft.Network/privateEndpoints/delete",
                    "Microsoft.Compute/availabilitySets/delete",
                    "Microsoft.KeyVault/vaults/read",
                    "Microsoft.KeyVault/vaults/accessPolicies/write",
                    "Microsoft.Compute/diskEncryptionSets/write",
                    "Microsoft.KeyVault/vaults/deploy/action",
                    "Microsoft.Compute/diskEncryptionSets/delete",
                    "Microsoft.Resources/tags/read",
                    "Microsoft.Resources/tags/write",
                    "Microsoft.Resources/tags/delete",
                    "Microsoft.Network/applicationSecurityGroups/write",
                    "Microsoft.Network/applicationSecurityGroups/read",
"Microsoft.Network/applicationSecurityGroups/joinIpConfiguration/action",
"Microsoft.Network/networkSecurityGroups/securityRules/write",
                    "Microsoft.Network/applicationSecurityGroups/delete",
"Microsoft.Network/networkSecurityGroups/securityRules/delete",
"Microsoft.ContainerService/managedClusters/listClusterUserCredential/acti
on",
                    "Microsoft.ContainerService/managedClusters/read",
                    "Microsoft.Synapse/workspaces/write",
                    "Microsoft.Synapse/workspaces/read",
                    "Microsoft.Synapse/workspaces/delete",
                    "Microsoft.Synapse/register/action",
                    "Microsoft.Synapse/checkNameAvailability/action",
                    "Microsoft.Synapse/workspaces/operationStatuses/read",
                    "Microsoft.Synapse/workspaces/firewallRules/read",
"Microsoft.Synapse/workspaces/replaceAllIpFirewallRules/action",
                    "Microsoft.Synapse/workspaces/operationResults/read",
                    "Microsoft.Network/publicIPAddresses/delete",
"Microsoft.Synapse/workspaces/privateEndpointConnectionsApproval/action",
"Microsoft.ManagedIdentity/userAssignedIdentities/assign/action"
    1,
    "NotActions": [],
    "AssignableScopes": [],
    "Description": "BlueXP Permissions",
    "IsCustom": "true"
}
```

How Azure permissions are used

The following sections describe how the permissions are used for each NetApp cloud service. This information can be helpful if your corporate policies dictate that permissions are only provided as needed.

AppTemplate tags

The Connector makes the following API requests to manage tags on Azure resources when you use the AppTemplate Tagging service:

- · Microsoft.Resources/resources/read
- Microsoft.Resources/subscriptions/operationresults/read
- · Microsoft.Resources/subscriptions/resourceGroups/read
- · Microsoft.Resources/subscriptions/resourcegroups/resources/read
- · Microsoft.Resources/tags/read
- · Microsoft.Resources/tags/write

Azure NetApp Files

The Connector makes the following API requests to manage Azure NetApp Files working environments:

- Microsoft.NetApp/netAppAccounts/read
- Microsoft.NetApp/netAppAccounts/capacityPools/read
- Microsoft.NetApp/netAppAccounts/capacityPools/volumes/write
- Microsoft.NetApp/netAppAccounts/capacityPools/volumes/read
- Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete

Cloud Backup

The Connector makes the following API requests for backup and restore operations:

- Microsoft.Compute/virtualMachines/read
- · Microsoft.Compute/virtualMachines/start/action
- · Microsoft.Compute/virtualMachines/deallocate/action
- Microsoft.Storage/storageAccounts/listkeys/action
- Microsoft.Storage/storageAccounts/read
- Microsoft.Storage/storageAccounts/write
- · Microsoft.Storage/storageAccounts/blobServices/containers/read
- Microsoft.Storage/storageAccounts/listAccountSas/action
- · Microsoft.KeyVault/vaults/read
- Microsoft.KeyVault/vaults/accessPolicies/write
- Microsoft.Network/networkInterfaces/read
- Microsoft.Resources/subscriptions/locations/read
- Microsoft.Network/virtualNetworks/read
- · Microsoft.Network/virtualNetworks/subnets/read

- · Microsoft.Resources/subscriptions/resourceGroups/read
- · Microsoft.Resources/subscriptions/resourcegroups/resources/read
- · Microsoft.Resources/subscriptions/resourceGroups/write
- · Microsoft.Authorization/locks/*
- · Microsoft.Network/privateEndpoints/write
- · Microsoft.Network/privateEndpoints/read
- Microsoft.Network/privateDnsZones/virtualNetworkLinks/write
- · Microsoft.Network/virtualNetworks/join/action
- Microsoft.Network/privateDnsZones/A/write
- · Microsoft.Network/privateDnsZones/read
- · Microsoft.Network/privateDnsZones/virtualNetworkLinks/read
- · Microsoft.Compute/virtualMachines/extensions/delete
- Microsoft.Compute/virtualMachines/delete
- Microsoft.Network/networkInterfaces/delete
- · Microsoft.Network/networkSecurityGroups/delete
- · Microsoft.Resources/deployments/delete
- Microsoft.Network/publicIPAddresses/delete
- Microsoft.Storage/storageAccounts/blobServices/containers/write
- · Microsoft.ManagedIdentity/userAssignedIdentities/assign/action

The Connector makes the following API requests when you use the Search & Restore functionality:

- Microsoft.Synapse/workspaces/write
- Microsoft.Synapse/workspaces/read
- · Microsoft.Synapse/workspaces/delete
- Microsoft.Synapse/register/action
- Microsoft.Synapse/checkNameAvailability/action
- · Microsoft.Synapse/workspaces/operationStatuses/read
- Microsoft.Synapse/workspaces/firewallRules/read
- Microsoft.Synapse/workspaces/replaceAllIpFirewallRules/action
- · Microsoft.Synapse/workspaces/operationResults/read
- Microsoft.Synapse/workspaces/privateEndpointConnectionsApproval/action

Cloud Data Sense

The Connector makes the following API requests when you use Cloud Data Sense.

Action	Used for set up?	Used for daily operations?
Microsoft.Compute/locations/operat ions/read	Yes	Yes

Action	Used for set up?	Used for daily operations?
Microsoft.Compute/locations/vmSiz es/read	Yes	Yes
Microsoft.Compute/operations/read	Yes	Yes
Microsoft.Compute/virtualMachines/instanceView/read	Yes	Yes
Microsoft.Compute/virtualMachines/powerOff/action	Yes	No
Microsoft.Compute/virtualMachines/read	Yes	Yes
Microsoft.Compute/virtualMachines/restart/action	Yes	No
Microsoft.Compute/virtualMachines/ start/action	Yes	No
Microsoft.Compute/virtualMachines/ vmSizes/read	No	Yes
Microsoft.Compute/virtualMachines/write	Yes	No
Microsoft.Compute/images/read	Yes	Yes
Microsoft.Compute/disks/delete	Yes	No
Microsoft.Compute/disks/read	Yes	Yes
Microsoft.Compute/disks/write	Yes	No
Microsoft.Storage/checknameavaila bility/read	Yes	Yes
Microsoft.Storage/operations/read	Yes	Yes
Microsoft.Storage/storageAccounts/ listkeys/action	Yes	No
Microsoft.Storage/storageAccounts/read	Yes	Yes
Microsoft.Storage/storageAccounts/ write	Yes	No
Microsoft.Storage/storageAccounts/delete	No	Yes
Microsoft.Storage/storageAccounts/blobServices/containers/read	Yes	Yes
Microsoft.Network/networkInterface s/read	Yes	Yes
Microsoft.Network/networkInterface s/write	Yes	No

Action	Used for set up?	Used for daily operations?
Microsoft.Network/networkInterface s/join/action	Yes	No
Microsoft.Network/networkSecurity Groups/read	Yes	Yes
Microsoft.Network/networkSecurity Groups/write	Yes	No
Microsoft.Resources/subscriptions/l ocations/read	Yes	Yes
Microsoft.Network/locations/operationResults/read	Yes	Yes
Microsoft.Network/locations/operations/read	Yes	Yes
Microsoft.Network/virtualNetworks/r ead	Yes	Yes
Microsoft.Network/virtualNetworks/c hecklpAddressAvailability/read	Yes	Yes
Microsoft.Network/virtualNetworks/s ubnets/read	Yes	Yes
Microsoft.Network/virtualNetworks/s ubnets/virtualMachines/read	Yes	Yes
Microsoft.Network/virtualNetworks/virtualMachines/read	Yes	Yes
Microsoft.Network/virtualNetworks/s ubnets/join/action	Yes	No
Microsoft.Network/virtualNetworks/s ubnets/write	Yes	No
Microsoft.Network/routeTables/join/action	Yes	No
Microsoft.Resources/deployments/o perations/read	Yes	Yes
Microsoft.Resources/deployments/r ead	Yes	Yes
Microsoft.Resources/deployments/ write	Yes	No
Microsoft.Resources/resources/rea	Yes	Yes
Microsoft.Resources/subscriptions/ operationresults/read	Yes	Yes
Microsoft.Resources/subscriptions/r esourceGroups/delete	Yes	No

Action	Used for set up?	Used for daily operations?
Microsoft.Resources/subscriptions/r esourceGroups/read	Yes	Yes
Microsoft.Resources/subscriptions/r esourcegroups/resources/read	Yes	Yes
Microsoft.Resources/subscriptions/r esourceGroups/write	Yes	No

Cloud Tiering

The Connector makes the following API requests when you set up Cloud Tiering.

- Microsoft.Storage/storageAccounts/listkeys/action
- Microsoft.Resources/subscriptions/resourceGroups/read
- · Microsoft.Resources/subscriptions/locations/read

The Connector makes the following API requests for daily operations.

- Microsoft.Storage/storageAccounts/blobServices/containers/read
- Microsoft.Storage/storageAccounts/blobServices/containers/write
- Microsoft.Storage/storageAccounts/managementPolicies/read
- · Microsoft.Storage/storageAccounts/managementPolicies/write
- · Microsoft.Storage/storageAccounts/read

Cloud Volumes ONTAP

The Connector makes the following API requests to deploy and manage Cloud Volumes ONTAP in Azure.

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage VMs	Microsoft.Compute/I ocations/operations/r ead	Yes	Yes	No
	Microsoft.Compute/I ocations/vmSizes/re ad	Yes	Yes	No
	Microsoft.Resources /subscriptions/locatio ns/read	Yes	No	No
	Microsoft.Compute/o perations/read	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/insta nceView/read	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/powe rOff/action	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/read	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/restar t/action	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/start/ action	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/deall ocate/action	No	Yes	Yes
	Microsoft.Compute/v irtualMachines/vmSi zes/read	No	Yes	No
	Microsoft.Compute/v irtualMachines/write	Yes	Yes	No
	Microsoft.Compute/v irtualMachines/delet e	Yes	Yes	Yes
	Microsoft.Resources /deployments/delete	Yes	No	No
Enable deployment from a VHD	Microsoft.Compute/i mages/read	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage network interfaces in the target subnet	Microsoft.Network/n etworkInterfaces/rea d	Yes	Yes	No
	Microsoft.Network/n etworkInterfaces/writ e	Yes	Yes	No
	Microsoft.Network/n etworkInterfaces/join /action	Yes	Yes	No
	Microsoft.Network/n etworkInterfaces/del ete	Yes	Yes	No
Create and manage network security groups	Microsoft.Network/n etworkSecurityGroup s/read	Yes	Yes	No
	Microsoft.Network/n etworkSecurityGroup s/write	Yes	Yes	No
	Microsoft.Network/n etworkSecurityGroup s/join/action	Yes	No	No
	Microsoft.Network/n etworkSecurityGroup s/delete	No	Yes	Yes

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Get network information about regions, the target	Microsoft.Network/lo cations/operationRe sults/read	Yes	Yes	No
VNet and subnet, and add the VMs to VNets	Microsoft.Network/lo cations/operations/re ad	Yes	Yes	No
	Microsoft.Network/vir tualNetworks/read	Yes	No	No
	Microsoft.Network/vir tualNetworks/checkl pAddressAvailability/ read	Yes	No	No
	Microsoft.Network/vir tualNetworks/subnet s/read	Yes	Yes	No
	Microsoft.Network/vir tualNetworks/subnet s/virtualMachines/re ad	Yes	Yes	No
	Microsoft.Network/vir tualNetworks/virtual Machines/read	Yes	Yes	No
	Microsoft.Network/vir tualNetworks/subnet s/join/action	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage resource groups	Microsoft.Resources /deployments/operati ons/read	Yes	Yes	No
	Microsoft.Resources /deployments/read	Yes	Yes	No
	Microsoft.Resources /deployments/write	Yes	Yes	No
	Microsoft.Resources /resources/read	Yes	Yes	No
	Microsoft.Resources /subscriptions/operat ionresults/read	Yes	Yes	No
	Microsoft.Resources /subscriptions/resour ceGroups/delete	Yes	Yes	Yes
	Microsoft.Resources /subscriptions/resour ceGroups/read	No	Yes	No
	Microsoft.Resources /subscriptions/resour cegroups/resources/ read	Yes	Yes	No
	Microsoft.Resources /subscriptions/resour ceGroups/write	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Manage Azure storage accounts	Microsoft.Compute/d isks/read	Yes	Yes	Yes
and disks	Microsoft.Compute/d isks/write	Yes	Yes	No
	Microsoft.Compute/d isks/delete	Yes	Yes	Yes
	Microsoft.Storage/ch ecknameavailability/r ead	Yes	Yes	No
	Microsoft.Storage/op erations/read	Yes	Yes	No
	Microsoft.Storage/st orageAccounts/listke ys/action	Yes	Yes	No
	Microsoft.Storage/st orageAccounts/read	Yes	Yes	No
	Microsoft.Storage/st orageAccounts/delet e	No	Yes	Yes
	Microsoft.Storage/st orageAccounts/write	Yes	Yes	No
	Microsoft.Storage/us ages/read	No	Yes	No
Enable backups to Blob storage and encryption of storage accounts	Microsoft.Storage/st orageAccounts/blob Services/containers/r ead	Yes	Yes	No
	Microsoft.KeyVault/v aults/read	Yes	Yes	No
	Microsoft.KeyVault/v aults/accessPolicies/ write	Yes	Yes	No
Enable VNet service endpoints for data tiering	Microsoft.Network/vir tualNetworks/subnet s/write	Yes	Yes	No
	Microsoft.Network/ro uteTables/join/action	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage Azure managed	Microsoft.Compute/s napshots/write	Yes	Yes	No
snapshots	Microsoft.Compute/s napshots/read	Yes	Yes	No
	Microsoft.Compute/s napshots/delete	No	Yes	Yes
	Microsoft.Compute/d isks/beginGetAccess /action	No	Yes	No
Create and manage availability sets	Microsoft.Compute/a vailabilitySets/write	Yes	No	No
	Microsoft.Compute/a vailabilitySets/read	Yes	No	No
Enable programmatic deployments from the marketplace	Microsoft.Marketplac eOrdering/offertypes /publishers/offers/pla ns/agreements/read	Yes	No	No
	Microsoft.Marketplac eOrdering/offertypes /publishers/offers/pla ns/agreements/write	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Manage a load balancer for HA	Microsoft.Network/lo adBalancers/read	Yes	Yes	No
pairs	Microsoft.Network/lo adBalancers/write	Yes	No	No
	Microsoft.Network/lo adBalancers/delete	No	Yes	Yes
	Microsoft.Network/lo adBalancers/backen dAddressPools/read	Yes	No	No
	Microsoft.Network/lo adBalancers/backen dAddressPools/join/ action	Yes	No	No
	Microsoft.Network/lo adBalancers/loadBal ancingRules/read	Yes	No	No
	Microsoft.Network/lo adBalancers/probes/ read	Yes	No	No
	Microsoft.Network/lo adBalancers/probes/ join/action	Yes	No	No
Enable management of locks on Azure disks	Microsoft.Authorizati on/locks/*	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Enable private endpoints for HA	Microsoft.Network/pr ivateEndpoints/write	Yes	Yes	No
pairs when there's no connectivity outside the subnet	Microsoft.Storage/st orageAccounts/Priva teEndpointConnectio nsApproval/action	Yes	No	No
	Microsoft.Storage/st orageAccounts/priva teEndpointConnectio ns/read	Yes	Yes	Yes
	Microsoft.Network/pr ivateEndpoints/read	Yes	Yes	Yes
	Microsoft.Network/pr ivateDnsZones/write	Yes	Yes	No
	Microsoft.Network/pr ivateDnsZones/virtu alNetworkLinks/write	Yes	Yes	No
	Microsoft.Network/vir tualNetworks/join/act ion	Yes	Yes	No
	Microsoft.Network/pr ivateDnsZones/A/wri te	Yes	Yes	No
	Microsoft.Network/pr ivateDnsZones/read	Yes	Yes	No
	Microsoft.Network/pr ivateDnsZones/virtu alNetworkLinks/read	Yes	Yes	No
Required for some VM deployments, depending on the underlying physical hardware	Microsoft.Resources /deployments/operati onStatuses/read	Yes	Yes	No
Remove resources from a resource group in case of	Microsoft.Network/pr ivateEndpoints/delet e	Yes	Yes	No
deployment failure or deletion	Microsoft.Compute/a vailabilitySets/delete	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Enable the use of customer-managed encryption keys when using the API	Microsoft.Compute/d iskEncryptionSets/re ad	Yes	Yes	Yes
	Microsoft.Compute/d iskEncryptionSets/wr ite	Yes	Yes	No
	Microsoft.KeyVault/v aults/deploy/action	Yes	No	No
	Microsoft.Compute/d iskEncryptionSets/de lete	Yes	Yes	Yes
Configure an application security group for an HA pair	Microsoft.Network/a pplicationSecurityGr oups/write	No	Yes	No
to isolate the HA interconnect and cluster network NICs	Microsoft.Network/a pplicationSecurityGr oups/read	No	Yes	No
	Microsoft.Network/a pplicationSecurityGr oups/joinIpConfigura tion/action	No	Yes	No
	Microsoft.Network/n etworkSecurityGroup s/securityRules/write	Yes	Yes	No
	Microsoft.Network/a pplicationSecurityGr oups/delete	No	Yes	Yes
	Microsoft.Network/n etworkSecurityGroup s/securityRules/delet e	No	Yes	Yes
Read, write, and delete tags	Microsoft.Resources /tags/read	No	Yes	No
associated with Cloud Volumes ONTAP resources	Microsoft.Resources /tags/write	Yes	Yes	No
	Microsoft.Resources /tags/delete	Yes	No	No
Encrypt storage accounts during creation	Microsoft.ManagedId entity/userAssignedI dentities/assign/actio n	Yes	Yes	No

Global File Cache

The Connector makes the following API requests when you use Global File Cache:

- · Microsoft.Insights/Metrics/Read
- Microsoft.Compute/virtualMachines/extensions/write
- · Microsoft.Compute/virtualMachines/extensions/read
- Microsoft.Compute/virtualMachines/extensions/delete
- · Microsoft.Compute/virtualMachines/delete
- · Microsoft.Network/networkInterfaces/delete
- Microsoft.Network/networkSecurityGroups/delete
- · Microsoft.Resources/deployments/delete

Kubernetes

The Connector makes the following API requests to discover and manage clusters running in Azure Kubernetes Service (AKS):

- · Microsoft.Compute/virtualMachines/read
- · Microsoft.Resources/subscriptions/locations/read
- · Microsoft.Resources/subscriptions/operationresults/read
- · Microsoft.Resources/subscriptions/resourceGroups/read
- · Microsoft.Resources/subscriptions/resourcegroups/resources/read
- Microsoft.ContainerService/managedClusters/read
- Microsoft.ContainerService/managedClusters/listClusterUserCredential/action

Change log

As permissions are added and removed, we'll note them in the sections below.

5 January, 2023

The following permissions were added to the JSON policy:

- Microsoft.Storage/storageAccounts/listAccountSas/action
- Microsoft.Synapse/workspaces/privateEndpointConnectionsApproval/action

These permissions are required for Cloud Backup.

Microsoft.Network/loadBalancers/backendAddressPools/join/action

This permission is required for Cloud Volumes ONTAP deployment.

1 December, 2022

The following permissions were added to the JSON policy:

Microsoft.Storage/storageAccounts/blobServices/containers/write

This permission is required for Cloud Backup and Cloud Tiering.

· Microsoft.Network/publicIPAddresses/delete

This permissions is required for Cloud Backup.

The following permissions were removed from the JSON policy because they are no longer required:

- · Microsoft.Compute/images/write
- · Microsoft.Network/loadBalancers/frontendIPConfigurations/read
- Microsoft.Storage/storageAccounts/regeneratekey/action

Google Cloud permissions for the Connector

BlueXP requires permissions to perform actions in Google Cloud. These permissions are included in a custom role provided by NetApp. You might want to understand what BlueXP does with these permissions.

Service account permissions

The custom role shown below provides the permissions that a Connector needs to manage resources and processes within your Google Cloud network.

You'll need to apply this custom role to a service account that gets attached to the Connector VM. View step-by-step instructions.

You also need to ensure that the role is up to date as new permissions are added in subsequent releases.

```
title: NetApp BlueXP
description: Permissions for the service account associated with the
Connector instance.
stage: GA
includedPermissions:
- iam.serviceAccounts.actAs
- compute.regionBackendServices.create
- compute.regionBackendServices.get
- compute.regionBackendServices.list
- compute.networks.updatePolicy
- compute.backendServices.create
- compute.addresses.list
- compute.disks.create
- compute.disks.createSnapshot
- compute.disks.delete
- compute.disks.get
- compute.disks.list
- compute.disks.setLabels
- compute.disks.use
- compute.firewalls.create
```

```
- compute.firewalls.delete
- compute.firewalls.get
- compute.firewalls.list
- compute.globalOperations.get
- compute.images.get
- compute.images.getFromFamily
- compute.images.list
```

- compute.images.useReadOnly
- compute.instances.addAccessConfig
- compute.instances.attachDisk
- compute.instances.create
- compute.instances.delete
- compute.instances.detachDisk
- compute.instances.get
- compute.instances.getSerialPortOutput
- compute.instances.list
- compute.instances.setDeletionProtection
- compute.instances.setLabels
- compute.instances.setMachineType
- compute.instances.setMetadata
- compute.instances.setTags
- compute.instances.start
- compute.instances.stop
- compute.instances.updateDisplayDevice
- compute.instanceGroups.get
- compute.addresses.get
- compute.instances.updateNetworkInterface
- compute.machineTypes.get
- compute.networks.get
- compute.networks.list
- compute.projects.get
- compute.regions.get
- compute.regions.list
- compute.snapshots.create
- compute.snapshots.delete
- compute.snapshots.get
- compute.snapshots.list
- compute.snapshots.setLabels
- compute.subnetworks.get
- compute.subnetworks.list
- compute.subnetworks.use
- compute.subnetworks.useExternalIp
- compute.zoneOperations.get
- compute.zones.get
- compute.zones.list
- compute.instances.setServiceAccount

```
    deploymentmanager.compositeTypes.get

- deploymentmanager.compositeTypes.list
- deploymentmanager.deployments.create
- deploymentmanager.deployments.delete
- deploymentmanager.deployments.get
- deploymentmanager.deployments.list
- deploymentmanager.manifests.get
- deploymentmanager.manifests.list
- deploymentmanager.operations.get
- deploymentmanager.operations.list
- deploymentmanager.resources.get
- deploymentmanager.resources.list
- deploymentmanager.typeProviders.get
- deploymentmanager.typeProviders.list
- deploymentmanager.types.get
- deploymentmanager.types.list
- logging.logEntries.list
- logging.privateLogEntries.list
- resourcemanager.projects.get
- storage.buckets.create
- storage.buckets.delete
- storage.buckets.get
- storage.buckets.list
- cloudkms.cryptoKeyVersions.useToEncrypt
- cloudkms.cryptoKeys.get
- cloudkms.cryptoKeys.list
- cloudkms.keyRings.list
- storage.buckets.update
- iam.serviceAccounts.getIamPolicy
- iam.serviceAccounts.list
- storage.objects.get
- storage.objects.list
- monitoring.timeSeries.list
- storage.buckets.getIamPolicy
- cloudkms.cryptoKeys.getIamPolicy
- cloudkms.cryptoKeys.setIamPolicy
- cloudkms.keyRings.get
- cloudkms.keyRings.getIamPolicy
- cloudkms.keyRings.setIamPolicy
```

How Google Cloud permissions are used

Actions	Purpose
- compute.disks.create - compute.disks.createSnapshot - compute.disks.delete - compute.disks.get - compute.disks.list - compute.disks.setLabels - compute.disks.use	To create and manage disks for Cloud Volumes ONTAP.
compute.firewalls.createcompute.firewalls.deletecompute.firewalls.getcompute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.
- compute.globalOperations.get	To get the status of operations.
compute.images.getcompute.images.getFromFamilycompute.images.listcompute.images.useReadOnly	To get images for VM instances.
compute.instances.attachDiskcompute.instances.detachDisk	To attach and detach disks to Cloud Volumes ONTAP.
- compute.instances.create - compute.instances.delete	To create and delete Cloud Volumes ONTAP VM instances.
- compute.instances.get	To list VM instances.
- compute.instances.getSerialPortOutput	To get console logs.
- compute.instances.list	To retrieve the list of instances in a zone.
- compute.instances.setDeletionProtection	To set deletion protection on the instance.
- compute.instances.setLabels	To add labels.
compute.instances.setMachineTypecompute.instances.setMinCpuPlatform	To change the machine type for Cloud Volumes ONTAP.
- compute.instances.setMetadata	To add metadata.
- compute.instances.setTags	To add tags for firewall rules.
compute.instances.startcompute.instances.stopcompute.instances.updateDisplayDevice	To start and stop Cloud Volumes ONTAP.
- compute.machineTypes.get	To get the numbers of cores to check qoutas.
- compute.projects.get	To support multi-projects.
 compute.snapshots.create compute.snapshots.delete compute.snapshots.get compute.snapshots.list compute.snapshots.setLabels 	To create and manage persistent disk snapshots.

Actions	Purpose
- compute.networks.get - compute.networks.list - compute.regions.get - compute.regions.list - compute.subnetworks.get - compute.subnetworks.list - compute.zoneOperations.get - compute.zones.get - compute.zones.list	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.
 deploymentmanager.compositeTypes.list deploymentmanager.deployments.create deploymentmanager.deployments.delete deploymentmanager.deployments.get deploymentmanager.deployments.list deploymentmanager.manifests.get deploymentmanager.manifests.list deploymentmanager.operations.get deploymentmanager.operations.list deploymentmanager.resources.get deploymentmanager.resources.list deploymentmanager.typeProviders.get deploymentmanager.typeProviders.list deploymentmanager.types.get deploymentmanager.types.get deploymentmanager.types.list 	To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.
logging.logEntries.listlogging.privateLogEntries.list	To get stack log drives.
- resourcemanager.projects.get	To support multi-projects.
storage.buckets.createstorage.buckets.deletestorage.buckets.getstorage.buckets.liststorage.buckets.update	To create and manage a Google Cloud Storage bucket for data tiering.
cloudkms.cryptoKeyVersions.useToEncryptcloudkms.cryptoKeys.getcloudkms.cryptoKeys.listcloudkms.keyRings.list	To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.
 compute.instances.setServiceAccount iam.serviceAccounts.actAs iam.serviceAccounts.getIamPolicy iam.serviceAccounts.list storage.objects.get storage.objects.list 	To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.
- compute.addresses.list	To retrieve the addresses in a region when deploying an HA pair.

Actions	Purpose
compute.backendServices.createcompute.regionBackendServices.getcompute.regionBackendServices.list	To configure a backend service for distributing traffic in an HA pair.
- compute.networks.updatePolicy	To apply firewall rules on the VPCs and subnets for an HA pair.
compute.subnetworks.usecompute.subnetworks.useExternallpcompute.instances.addAccessConfig	To enable Cloud Data Sense.
- container.clusters.get - container.clusters.list	To discover Kubernetes clusters running in Google Kubernetes Engine.
compute.instanceGroups.getcompute.addresses.getcompute.instances.updateNetworkInterface	To create and manage storage VMs on Cloud Volumes ONTAP HA pairs.
- monitoring.timeSeries.list - storage.buckets.getlamPolicy	To discover information about Google Cloud Storage buckets.
 cloudkms.cryptoKeys.get cloudkms.cryptoKeys.getlamPolicy cloudkms.cryptoKeys.list cloudkms.cryptoKeys.setlamPolicy cloudkms.keyRings.get cloudkms.keyRings.getlamPolicy cloudkms.keyRings.list cloudkms.keyRings.setlamPolicy 	To select your own customer-managed keys in the Cloud Backup activation wizard instead of using the default Google-managed encryption keys.

Change log

As permissions are added and removed, we'll note them in the sections below.

6 February, 2023

The following permission was added to this policy:

• compute.instances.updateNetworkInterface

This permission is required for Cloud Volumes ONTAP.

27 January, 2023

The following permissions were added to the policy:

- cloudkms.cryptoKeys.getlamPolicy
- cloudkms.cryptoKeys.setlamPolicy
- cloudkms.keyRings.get
- cloudkms.keyRings.getlamPolicy
- cloudkms.keyRings.setlamPolicy

These permissions are required for Cloud Backup.

Ports

Security group rules in AWS

The AWS security group for the Connector requires both inbound and outbound rules.

Inbound rules

Protocol	Port	Purpose
SSH	22	Provides SSH access to the Connector host
HTTP	80	Provides HTTP access from client web browsers to the local user interface
HTTPS	443	Provides HTTPS access from client web browsers to the local user interface, and connections from the Cloud Data Sense instance
TCP	3128	Provides Cloud Volumes ONTAP with internet access to send AutoSupport messages to NetApp Support. You must manually open this port after deployment. Learn more about the Connector's proxy server.
TCP	9060, 9061	Provides the ability to enable and use Cloud Data Sense and Cloud Backup in Government Cloud deployments. These ports are also required for Cloud Backup if you disable the SaaS interface in your BlueXP account.

Outbound rules

The predefined security group for the Connector opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined security group for the Connector includes the following outbound rules.

Protocol	Port	Purpose
All TCP	All	All outbound traffic
All UDP	All	All outbound traffic

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by the Connector.



The source IP address is the Connector host.

Service	Prot ocol	Destination	Purpose
API calls and AutoSupport		Outbound internet and ONTAP cluster management LIF	API calls to AWS and ONTAP, to Cloud Data Sense, to the Ransomware service, and sending AutoSupport messages to NetApp

Service	Prot ocol	_	Destination	Purpose
API calls	TCP	30 00	ONTAP HA mediator	Communication with the ONTAP HA mediator
	TCP	80 80	Data Sense	Probe to Data Sense instance during deployment
	TCP	80 88	Backup to S3	API calls to Backup to S3
DNS	UDP	53	DNS	Used for DNS resolve by BlueXP

Security group rules in Azure

The Azure security group for the Connector requires both inbound and outbound rules.

Inbound rules

Protoc ol	Port	Purpose
SSH	22	Provides SSH access to the Connector host
HTTP	80	Provides HTTP access from client web browsers to the local user interface
HTTP S	443	Provides HTTPS access from client web browsers to the local user interface, and connections from the Cloud Data Sense instance
TCP	3128	Provides Cloud Volumes ONTAP with internet access to send AutoSupport messages to NetApp Support. You must manually open this port after deployment. Learn more about the Connector's proxy server.
TCP	9060, 9061	Provides the ability to enable and use Cloud Data Sense and Cloud Backup in Government Cloud deployments. These ports are also required for Cloud Backup if you disable the SaaS interface in your BlueXP account.

Outbound rules

The predefined security group for the Connector opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined security group for the Connector includes the following outbound rules.

Protoc ol	Por t	Purpose
All TCP	All	All outbound traffic
All UDP	All	All outbound traffic

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by the Connector.



The source IP address is the Connector host.

Service	Prot ocol	_	Destination	Purpose
API calls and AutoSupport	HTT PS	44 3	Outbound internet and ONTAP cluster management LIF	API calls to Azure and ONTAP, to Cloud Data Sense, to the Ransomware service, and sending AutoSupport messages to NetApp
API calls	TCP	80 80	Data Sense	Probe to Data Sense instance during deployment
DNS	UDP	53	DNS	Used for DNS resolve by BlueXP

Firewall rules in Google Cloud

The Google Cloud firewall rules for the Connector requires both inbound and outbound rules.

Inbound rules

Protocol	Port	Purpose
SSH	22	Provides SSH access to the Connector host
HTTP	80	Provides HTTP access from client web browsers to the local user interface
HTTPS	443	Provides HTTPS access from client web browsers to the local user interface
TCP	3128	Provides Cloud Volumes ONTAP with internet access to send AutoSupport messages to NetApp Support. You must manually open this port after deployment. Learn more about the Connector's proxy server.

Outbound rules

The predefined firewall rules for the Connector opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined firewall rules for the Connector includes the following outbound rules.

Protocol	Port	Purpose
All TCP	All	All outbound traffic
All UDP	All	All outbound traffic

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by the Connector.



The source IP address is the Connector host.

Service	Prot ocol		Destination	Purpose
API calls and AutoSupport	HTT PS	44 3	Outbound internet and ONTAP cluster management LIF	API calls to GCP and ONTAP, to Cloud Data Sense, to the Ransomware service, and sending AutoSupport messages to NetApp
API calls	TCP	80 80	Data Sense	Probe to Data Sense instance during deployment
DNS	UDP	53	DNS	Used for DNS resolve by BlueXP

Ports for the on-prem Connector

The Connector uses the following *inbound* ports when installed manually on an on-premises Linux host.

These inbound rules apply to both deployment models for the on-prem Connector: installed with internet access or without internet access.

Protocol	Port	Purpose	
HTTP	80	Provides HTTP access from client web browsers to the local user interface	
HTTPS	443	Provides HTTPS access from client web browsers to the local user interface	

Copyright information

Copyright © 2023 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.