■ NetApp

Permissions

Set up and administration

NetApp October 25, 2022

This PDF was generated from https://docs.netapp.com/us-en/cloud-manager-setup-admin/reference-permissions.html on October 25, 2022. Always check docs.netapp.com for the latest.

Table of Contents

P	ermissions	1
	Permissions summary for Cloud Manager	1
	AWS permissions for the Connector	2
	Azure permissions for the Connector	8
	Google Cloud permissions for the Connector	6

Permissions

Permissions summary for Cloud Manager

In order to use the features and services in Cloud Manager, you'll need to provide permissions so that Cloud Manager can perform operations in your cloud environment. Use the links on this page to quickly access the permissions that you need based on your goal.

AWS permissions

Purpose	Description	Link
Connector deployment	The user who creates a Connector from Cloud Manager needs specific permissions to deploy the instance in AWS.	Create a Connector in AWS from Cloud Manager
Connector operation	When Cloud Manager launches the Connector, it attaches a policy to the instance that provides the permissions required to manage resources and processes in your AWS account. You need to set up the policy yourself if you launch a Connector from the marketplace or if you add more AWS credentials to a Connector. You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.	AWS permissions for the Connector
Cloud Volumes ONTAP operation	An IAM role must be attached to each Cloud Volumes ONTAP node in AWS. The same is true for the HA mediator. The default option is to let Cloud Manager create the IAM roles for you, but you can use your own.	Learn how to set up the IAM roles yourself

Azure permissions

Purpose	Description	Link
Connector deployment	When you deploy a Connector from Cloud Manager, you need to use an Azure account or service principal that has permissions to deploy the Connector VM in Azure.	Create a Connector in Azure from Cloud Manager

Purpose	Description	Link
Connector operation	When Cloud Manager deploys the Connector VM in Azure, it creates a custom role that provides the permissions required to manage resources and processes within that Azure subscription.	Azure permissions for the Connector
	You need to set up the custom role yourself if you launch a Connector from the marketplace or if you add more Azure credentials to a Connector.	
	You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.	

Google Cloud permissions

Purpose	Description	Link	
Connector deployment	The Google Cloud user who deploys a Connector from Cloud Manager needs specific permissions to deploy the Connector in Google Cloud.	Set up permissions to deploy the Connector	
Connector operation	The service account for the Connector VM instance must have specific permissions for day-to-day operations. You need to associate the service account with the Connector when you deploy it from Cloud Manager. You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.	Set up a service account for the Connector	

AWS permissions for the Connector

When Cloud Manager launches the Connector instance in AWS, it attaches a policy to the instance that provides the Connector with permissions to manage resources and processes within that AWS account. The Connector uses the permissions to make API calls to several AWS services, including EC2, S3, CloudFormation, IAM, the Key Management Service (KMS), and more.

IAM policy

The IAM policy shown below provides the permissions that a Connector needs to manage resources and processes within your public cloud environment based on your AWS region.

When you create a Connector directly from Cloud Manager, Cloud Manager automatically applies this policy to the Connector.

If you deploy the Connector from the AWS Marketplace or if you manually install the Connector on a Linux host, then you'll need to set up the policy yourself.

You also need to ensure that the policy is up to date as new permissions are added in subsequent releases.

Standard regions

```
"Version": "2012-10-17",
"Statement": [
    "Sid": "cvoServicePolicy",
    "Effect": "Allow",
    "Action": [
      "ec2:DescribeInstances",
      "ec2:DescribeInstanceStatus",
      "ec2:RunInstances",
      "ec2:ModifyInstanceAttribute",
      "ec2:DescribeInstanceAttribute",
      "ec2:DescribeRouteTables",
      "ec2:DescribeImages",
      "ec2:CreateTags",
      "ec2:CreateVolume",
      "ec2:DescribeVolumes",
      "ec2:ModifyVolumeAttribute",
      "ec2:CreateSecurityGroup",
      "ec2:DescribeSecurityGroups",
      "ec2:RevokeSecurityGroupEgress",
      "ec2:AuthorizeSecurityGroupEgress",
      "ec2:AuthorizeSecurityGroupIngress",
      "ec2:RevokeSecurityGroupIngress",
      "ec2:CreateNetworkInterface",
      "ec2:DescribeNetworkInterfaces",
      "ec2:ModifyNetworkInterfaceAttribute",
      "ec2:DescribeSubnets",
      "ec2:DescribeVpcs",
      "ec2:DescribeDhcpOptions",
      "ec2:CreateSnapshot",
      "ec2:DescribeSnapshots",
      "ec2:GetConsoleOutput",
      "ec2:DescribeKeyPairs",
      "ec2:DescribeRegions",
      "ec2:DescribeTags",
      "cloudformation:CreateStack",
      "cloudformation: DescribeStacks",
      "cloudformation:DescribeStackEvents",
      "cloudformation: Validate Template",
      "iam:PassRole",
      "iam:CreateRole",
      "iam:PutRolePolicy",
      "iam:CreateInstanceProfile",
```

```
"iam:AddRoleToInstanceProfile",
"iam: RemoveRoleFromInstanceProfile",
"iam:ListInstanceProfiles",
"sts:DecodeAuthorizationMessage",
"ec2:AssociateIamInstanceProfile",
"ec2:DescribeIamInstanceProfileAssociations",
"ec2:DisassociateIamInstanceProfile",
"s3:GetBucketTagging",
"s3:GetBucketLocation",
"s3:ListBucket",
"s3:CreateBucket",
"s3:GetLifecycleConfiguration",
"s3:ListBucketVersions",
"s3:GetBucketPolicyStatus",
"s3:GetBucketPublicAccessBlock",
"s3:GetBucketPolicy",
"s3:GetBucketAcl",
"kms:List*",
"kms:ReEncrypt*",
"kms:Describe*",
"kms:CreateGrant",
"ce:GetReservationUtilization",
"ce:GetDimensionValues",
"ce:GetCostAndUsage",
"ce:GetTags",
"ec2:CreatePlacementGroup",
"ec2:DescribeReservedInstancesOfferings",
"sts:AssumeRole",
"ec2:AssignPrivateIpAddresses",
"ec2:CreateRoute",
"ec2:DescribeVpcs",
"ec2:ReplaceRoute",
"ec2:UnassignPrivateIpAddresses",
"s3:PutObjectTagging",
"s3:GetObjectTagging",
"fsx:Describe*",
"fsx:List*",
"ec2:DeleteSecurityGroup",
"ec2:DeleteNetworkInterface",
"ec2:DeleteSnapshot",
"ec2:DeleteTags",
"ec2:DeleteRoute",
"ec2:DeletePlacementGroup",
"iam:DeleteRole",
"iam:DeleteRolePolicy",
"iam:DeleteInstanceProfile",
```

```
"cloudformation: DeleteStack",
    "ec2:DescribePlacementGroups",
    "iam:GetRolePolicy",
        "s3:ListAllMyBuckets",
    "s3:GetObject",
    "iam:GetRole",
    "s3:DeleteObject",
    "s3:DeleteObjectVersion",
    "s3:PutObject",
        "ec2:ModifyVolume",
    "ec2:DescribeVolumesModifications",
        "s3:GetEncryptionConfiguration"
  ],
  "Resource": "*"
},
  "Sid": "backupPolicy",
  "Effect": "Allow",
  "Action": [
    "ec2:StartInstances",
    "ec2:StopInstances",
        "ec2:DescribeInstances",
    "ec2:DescribeInstanceStatus",
    "ec2:RunInstances",
    "ec2:TerminateInstances",
    "ec2:DescribeInstanceAttribute",
    "ec2:DescribeImages",
    "ec2:CreateTags",
    "ec2:CreateVolume",
    "ec2:CreateSecurityGroup",
    "ec2:DescribeSubnets",
    "ec2:DescribeVpcs",
    "ec2:DescribeRegions",
    "cloudformation:CreateStack",
    "cloudformation: DeleteStack",
    "cloudformation: DescribeStacks",
    "kms:List*",
    "kms:Describe*",
    "ec2:describeVpcEndpoints",
    "kms:ListAliases",
    "athena:StartQueryExecution",
    "athena:GetQueryResults",
    "athena:GetQueryExecution",
    "athena:StopQueryExecution",
    "glue:CreateDatabase",
    "glue:CreateTable",
```

```
"glue:BatchDeletePartition"
 1,
 "Resource": "*"
},
 "Sid": "backupS3Policy",
 "Effect": "Allow",
 "Action": [
    "s3:GetBucketLocation",
   "s3:ListAllMyBuckets",
   "s3:ListBucket",
   "s3:CreateBucket",
   "s3:GetLifecycleConfiguration",
   "s3:PutLifecycleConfiguration",
   "s3:PutBucketTagging",
   "s3:ListBucketVersions",
   "s3:GetBucketAcl",
   "s3:PutBucketPublicAccessBlock",
   "s3:GetObject",
    "s3:PutEncryptionConfiguration",
   "s3:DeleteObject",
   "s3:DeleteObjectVersion",
   "s3:ListBucketMultipartUploads",
   "s3:PutObject",
    "s3:PutBucketAcl",
    "s3:AbortMultipartUpload",
    "s3:ListMultipartUploadParts",
    "s3:DeleteBucket",
        "s3:GetObjectVersionTagging",
          "s3:GetObjectVersionAcl",
        "s3:GetObjectRetention",
        "s3:GetObjectTagging",
        "s3:GetObjectVersion",
        "s3:PutObjectVersionTagging",
        "s3:PutObjectRetention",
        "s3:DeleteObjectTagging",
        "s3:DeleteObjectVersionTagging",
        "s3:GetBucketObjectLockConfiguration",
        "s3:GetBucketVersioning",
        "s3:PutBucketObjectLockConfiguration",
        "s3:PutBucketVersioning",
        "s3:BypassGovernanceRetention"
 ],
 "Resource": [
    "arn:aws:s3:::netapp-backup-*"
```

```
},
  "Sid": "tagServicePolicy",
  "Effect": "Allow",
  "Action": [
    "ec2:CreateTags",
    "ec2:DeleteTags",
   "ec2:DescribeTags",
    "tag:getResources",
   "tag:getTagKeys",
    "tag:getTagValues",
    "tag:TagResources",
   "tag:UntagResources"
 ],
  "Resource": "*"
},
  "Sid": "fabricPoolS3Policy",
  "Effect": "Allow",
  "Action": [
    "s3:CreateBucket",
    "s3:GetLifecycleConfiguration",
    "s3:PutLifecycleConfiguration",
   "s3:PutBucketTagging",
    "s3:ListBucketVersions",
   "s3:GetBucketPolicyStatus",
    "s3:GetBucketPublicAccessBlock",
   "s3:GetBucketAcl",
   "s3:GetBucketPolicy",
    "s3:PutBucketPublicAccessBlock",
   "s3:DeleteBucket"
  1,
  "Resource": [
   "arn:aws:s3:::fabric-pool*"
 1
},
 "Sid": "fabricPoolPolicy",
 "Effect": "Allow",
  "Action": [
   "ec2:DescribeRegions"
 ],
 "Resource": "*"
},
  "Effect": "Allow",
```

```
"Action": [
    "ec2:StartInstances",
   "ec2:StopInstances",
   "ec2:TerminateInstances"
 ],
 "Condition": {
   "StringLike": {
     "ec2:ResourceTag/netapp-adc-manager": "*"
   }
 },
 "Resource": [
  "arn:aws:ec2:*:*:instance/*"
} ,
 "Effect": "Allow",
 "Action": [
   "ec2:StartInstances",
   "ec2:TerminateInstances",
   "ec2:AttachVolume",
   "ec2:DetachVolume"
 ],
 "Condition": {
   "StringLike": {
     "ec2:ResourceTag/GFCInstance": "*"
   }
 },
 "Resource": [
   "arn:aws:ec2:*:*:instance/*"
 1
},
 "Effect": "Allow",
 "Action": [
   "ec2:StartInstances",
   "ec2:TerminateInstances",
   "ec2:AttachVolume",
   "ec2:DetachVolume",
   "ec2:StopInstances",
   "ec2:DeleteVolume"
 ],
 "Condition": {
   "StringLike": {
     "ec2:ResourceTag/WorkingEnvironment": "*"
   }
  },
```

```
"Resource": [
   "arn:aws:ec2:*:*:instance/*"
 1
},
 "Effect": "Allow",
 "Action": [
   "ec2:AttachVolume",
  "ec2:DetachVolume"
 ],
 "Resource": [
  "arn:aws:ec2:*:*:volume/*"
},
 "Effect": "Allow",
 "Action": [
  "ec2:DeleteVolume"
 "Condition": {
   "StringLike": {
     "ec2:ResourceTag/WorkingEnvironment": "*"
   }
 },
 "Resource": [
  "arn:aws:ec2:*:*:volume/*"
 1
},
 "Sid": "K8sServicePolicy",
 "Effect": "Allow",
 "Action": [
   "ec2:DescribeRegions",
   "eks:ListClusters",
   "eks:DescribeCluster",
       "iam:GetInstanceProfiles"
 "Resource": "*"
} ,
 "Sid": "GFCservicePolicy",
 "Effect": "Allow",
 "Action": [
   "cloudformation:DescribeStacks",
   "cloudwatch:GetMetricStatistics",
   "cloudformation:ListStacks"
```

```
| Transfer | Tran
```

GovCloud (US) regions

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "iam:ListInstanceProfiles",
                "iam:CreateRole",
                "iam:DeleteRole",
                "iam:PutRolePolicy",
                "iam:CreateInstanceProfile",
                "iam:DeleteRolePolicy",
                "iam:AddRoleToInstanceProfile",
                "iam: RemoveRoleFromInstanceProfile",
                "iam: DeleteInstanceProfile",
                "ec2:ModifyVolumeAttribute",
                "sts:DecodeAuthorizationMessage",
                "ec2:DescribeImages",
                "ec2:DescribeRouteTables",
                "ec2:DescribeInstances",
                "iam:PassRole",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:DeleteVolume",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DeleteNetworkInterface",
```

```
"ec2:ModifyNetworkInterfaceAttribute",
        "ec2:DescribeSubnets",
        "ec2:DescribeVpcs",
        "ec2:DescribeDhcpOptions",
        "ec2:CreateSnapshot",
        "ec2:DeleteSnapshot",
        "ec2:DescribeSnapshots",
        "ec2:StopInstances",
        "ec2:GetConsoleOutput",
        "ec2:DescribeKeyPairs",
        "ec2:DescribeRegions",
        "ec2:DeleteTags",
        "ec2:DescribeTags",
        "cloudformation:CreateStack",
        "cloudformation: DeleteStack",
        "cloudformation:DescribeStacks",
        "cloudformation: DescribeStackEvents",
        "cloudformation: Validate Template",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:ListAllMyBuckets",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:CreateBucket",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "kms:List*",
        "kms:ReEncrypt*",
        "kms:Describe*",
        "kms:CreateGrant",
        "ec2:AssociateIamInstanceProfile",
        "ec2:DescribeIamInstanceProfileAssociations",
        "ec2:DisassociateIamInstanceProfile",
        "ec2:DescribeInstanceAttribute",
        "ce:GetReservationUtilization",
        "ce:GetDimensionValues",
        "ce:GetCostAndUsage",
        "ce:GetTags",
        "ec2:CreatePlacementGroup",
        "ec2:DeletePlacementGroup"
    ],
    "Resource": "*"
},
```

```
"Sid": "fabricPoolPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock"
    ],
    "Resource": [
        "arn:aws-us-gov:s3:::fabric-pool*"
},
    "Sid": "backupPolicy",
    "Effect": "Allow",
    "Action": [
        "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions",
        "s3:GetObject",
        "s3:ListBucket",
        "s3:ListAllMyBuckets",
        "s3:GetBucketTagging",
        "s3:GetBucketLocation",
        "s3:GetBucketPolicyStatus",
        "s3:GetBucketPublicAccessBlock",
        "s3:GetBucketAcl",
        "s3:GetBucketPolicy",
        "s3:PutBucketPublicAccessBlock"
    ],
    "Resource": [
        "arn:aws-us-gov:s3:::netapp-backup-*"
},
    "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
```

```
"ec2:TerminateInstances",
                "ec2:AttachVolume",
                "ec2:DetachVolume"
            ],
            "Condition": {
                "StringLike": {
                    "ec2:ResourceTag/WorkingEnvironment": "*"
            },
            "Resource": [
                "arn:aws-us-gov:ec2:*:*:instance/*"
            1
        },
            "Effect": "Allow",
            "Action": [
                "ec2:AttachVolume",
                "ec2:DetachVolume"
            ],
            "Resource": [
                "arn:aws-us-gov:ec2:*:*:volume/*"
            1
       }
   1
}
```

C2S environment

```
{
    "Version": "2012-10-17",
    "Statement": [{
            "Effect": "Allow",
            "Action": [
                "ec2:DescribeInstances",
                "ec2:DescribeInstanceStatus",
                "ec2:RunInstances",
                "ec2:ModifyInstanceAttribute",
                "ec2:DescribeRouteTables",
                "ec2:DescribeImages",
                "ec2:CreateTags",
                "ec2:CreateVolume",
                "ec2:DescribeVolumes",
                "ec2:ModifyVolumeAttribute",
                "ec2:DeleteVolume",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
```

```
"ec2:DescribeSecurityGroups",
"ec2:RevokeSecurityGroupEgress",
"ec2:RevokeSecurityGroupIngress",
"ec2:AuthorizeSecurityGroupEgress",
"ec2:AuthorizeSecurityGroupIngress",
"ec2:CreateNetworkInterface",
"ec2:DescribeNetworkInterfaces",
"ec2:DeleteNetworkInterface",
"ec2:ModifyNetworkInterfaceAttribute",
"ec2:DescribeSubnets",
"ec2:DescribeVpcs",
"ec2:DescribeDhcpOptions",
"ec2:CreateSnapshot",
"ec2:DeleteSnapshot",
"ec2:DescribeSnapshots",
"ec2:GetConsoleOutput",
"ec2:DescribeKeyPairs",
"ec2:DescribeRegions",
"ec2:DeleteTags",
"ec2:DescribeTags",
"cloudformation:CreateStack",
"cloudformation: DeleteStack",
"cloudformation:DescribeStacks",
"cloudformation: DescribeStackEvents",
"cloudformation: Validate Template",
"iam:PassRole",
"iam:CreateRole",
"iam:DeleteRole",
"iam:PutRolePolicy",
"iam:CreateInstanceProfile",
"iam:DeleteRolePolicy",
"iam:AddRoleToInstanceProfile",
"iam: RemoveRoleFromInstanceProfile",
"iam:DeleteInstanceProfile",
"s3:GetObject",
"s3:ListBucket",
"s3:GetBucketTagging",
"s3:GetBucketLocation",
"s3:ListAllMyBuckets",
"kms:List*",
"kms:Describe*",
"ec2:AssociateIamInstanceProfile",
"ec2:DescribeIamInstanceProfileAssociations",
"ec2:DisassociateIamInstanceProfile",
"ec2:DescribeInstanceAttribute",
"ec2:CreatePlacementGroup",
```

```
"ec2:DeletePlacementGroup",
        "iam:ListinstanceProfiles"
    ],
    "Resource": "*"
},
{
    "Sid": "fabricPoolPolicy",
    "Effect": "Allow",
    "Action": [
       "s3:DeleteBucket",
        "s3:GetLifecycleConfiguration",
        "s3:PutLifecycleConfiguration",
        "s3:PutBucketTagging",
        "s3:ListBucketVersions"
   ],
    "Resource": [
       "arn:aws-iso:s3:::fabric-pool*"
},
   "Effect": "Allow",
    "Action": [
        "ec2:StartInstances",
        "ec2:StopInstances",
        "ec2:TerminateInstances",
        "ec2:AttachVolume",
        "ec2:DetachVolume"
   ],
    "Condition": {
        "StringLike": {
            "ec2:ResourceTag/WorkingEnvironment": "*"
        }
    },
    "Resource": [
       "arn:aws-iso:ec2:*:*:instance/*"
},
   "Effect": "Allow",
   "Action": [
        "ec2:AttachVolume",
        "ec2:DetachVolume"
    ],
    "Resource": [
       "arn:aws-iso:ec2:*:*:volume/*"
    ]
```

How the AWS permissions are used

The following sections describe how the permissions are used for each NetApp cloud service. This information can be helpful if your corporate policies dictate that permissions are only provided as needed.

AppTemplate tags

The Connector makes the following API requests to manage tags on AWS resources when you use the AppTemplate Tagging service:

- ec2:CreateTags
- ec2:DeleteTags
- · ec2:DescribeTags
- tag:getResources
- tag:getTagKeys
- tag:getTagValues
- · tag:TagResources
- tag:UntagResources

Cloud Backup

The Connector makes the following API requests to deploy the restore instance for Cloud Backup:

- ec2:StartInstances
- ec2:StopInstances
- ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:DescribeInstanceAttribute
- ec2:DescribeImages
- ec2:CreateTags
- ec2:CreateVolume
- ec2:CreateSecurityGroup
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:DescribeRegions
- · cloudformation:CreateStack

- cloudformation:DeleteStack
- · cloudformation:DescribeStacks

The Connector makes the following API requests to manage backups in Amazon S3:

- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:CreateBucket
- s3:GetLifecycleConfiguration
- s3:PutLifecycleConfiguration
- s3:PutBucketTagging
- s3:ListBucketVersions
- s3:GetBucketAcl
- s3:PutBucketPublicAccessBlock
- · kms:List*
- · kms:Describe*
- · s3:GetObject
- ec2:describeVpcEndpoints
- kms:ListAliases
- s3:PutEncryptionConfiguration

The Connector makes the following API requests when you use the Search & Restore method to restore volumes and files:

- s3:CreateBucket
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:GetBucketAcl
- s3:ListBucket
- s3:ListBucketVersions
- s3:ListBucketMultipartUploads
- s3:PutObject
- s3:PutBucketAcl
- s3:PutLifecycleConfiguration
- s3:PutBucketPublicAccessBlock
- s3:AbortMultipartUpload
- s3:ListMultipartUploadParts
- · athena:StartQueryExecutionc
- · athena:GetQueryResults

- athena:GetQueryExecution
- athena:StopQueryExecution
- glue:CreateDatabase
- glue:CreateTable
- · glue:BatchDeletePartition

The Connector makes the following API requests when you use DataLock and Ransomware protection for your volume backups:

- s3:GetObjectVersionTagging
- s3:GetBucketObjectLockConfiguration
- s3:GetObjectVersionAcl
- s3:PutObjectTagging
- s3:DeleteObject
- s3:DeleteObjectTagging
- s3:GetObjectRetention
- s3:DeleteObjectVersionTagging
- s3:PutObject
- s3:GetObject
- s3:PutBucketObjectLockConfiguration
- · s3:GetLifecycleConfiguration
- s3:ListBucketByTags
- s3:GetBucketTagging
- s3:DeleteObjectVersion
- s3:ListBucketVersions
- s3:ListBucket
- s3:PutBucketTagging
- s3:GetObjectTagging
- s3:PutBucketVersioning
- · s3:PutObjectVersionTagging
- s3:GetBucketVersioning
- s3:GetBucketAcl
- s3:BypassGovernanceRetention
- s3:PutObjectRetention
- s3:GetBucketLocation
- s3:GetObjectVersion

Cloud Data Sense

The Connector makes the following API requests to deploy the Cloud Data Sense instance:

- ec2:DescribeInstances
- · ec2:DescribeInstanceStatus
- ec2:RunInstances
- ec2:TerminateInstances
- ec2:CreateTags
- ec2:CreateVolume
- ec2:AttachVolume
- ec2:CreateSecurityGroup
- ec2:DeleteSecurityGroup
- ec2:DescribeSecurityGroups
- ec2:CreateNetworkInterface
- · ec2:DescribeNetworkInterfaces
- ec2:DeleteNetworkInterface
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:CreateSnapshot
- ec2:DescribeRegions
- · cloudformation:CreateStack
- cloudformation:DeleteStack
- · cloudformation:DescribeStacks
- · cloudformation:DescribeStackEvents
- iam:AddRoleToInstanceProfile
- ec2:AssociatelamInstanceProfile
- ec2:DescribelamInstanceProfileAssociations

The Connector makes the following API requests to scan S3 buckets when you use Cloud Data Sense:

- iam:AddRoleToInstanceProfile
- ec2:AssociatelamInstanceProfile
- ec2:DescribelamInstanceProfileAssociations
- s3:GetBucketTagging
- s3:GetBucketLocation
- s3:ListAllMyBuckets
- s3:ListBucket
- s3:GetBucketPolicyStatus
- s3:GetBucketPolicy
- s3:GetBucketAcl
- s3:GetObject

- iam:GetRole
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:PutObject
- sts:AssumeRole

Cloud Tiering

The Connector makes the following API requests to tier data to Amazon S3 when you use Cloud Tiering.

Action	Used for set up?	Used for daily operations?
s3:CreateBucket	Yes	No
s3:PutLifecycleConfiguration	Yes	No
s3:GetLifecycleConfiguration	Yes	Yes
ec2:DescribeRegions	Yes	Yes

Cloud Volumes ONTAP

The Connector makes the following API requests to deploy and manage Cloud Volumes ONTAP in AWS.

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage IAM roles and	iam:ListInstanceProfi les	Yes	Yes	No
instance profiles for Cloud Volumes	iam:CreateRole	Yes	No	No
ONTAP instances	iam:DeleteRole	No	Yes	Yes
	iam:PutRolePolicy	Yes	No	No
	iam:CreateInstanceP rofile	Yes	No	No
	iam:DeleteRolePolic y	No	Yes	Yes
	iam:AddRoleToInsta nceProfile	Yes	No	No
	iam:RemoveRoleFro mlnstanceProfile	No	Yes	Yes
	iam:DeleteInstanceP rofile	No	Yes	Yes
	iam:PassRole	Yes	No	No
	ec2:AssociatelamIns tanceProfile	Yes	Yes	No
	ec2:DescribelamInst anceProfileAssociations	Yes	Yes	No
	ec2:Disassociatelam InstanceProfile	No	Yes	No
Decode authorization status messages	sts:DecodeAuthoriza tionMessage	Yes	Yes	No
Describe the specified images (AMIs) available to the account	ec2:DescribeImages	Yes	Yes	No
Describe the route tables in a VPC (required for HA pairs only)	ec2:DescribeRouteT ables	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Stop, start, and	ec2:StartInstances	Yes	Yes	No
monitor instances	ec2:StopInstances	Yes	Yes	No
	ec2:DescribeInstanc	Yes	Yes	No
	ec2:DescribeInstanc eStatus	Yes	Yes	No
	ec2:RunInstances	Yes	No	No
	ec2:TerminateInstan	No	No	Yes
	ec2:ModifyInstanceA ttribute	No	Yes	No
Verify that enhanced networking is enabled for supported instance types	ec2:DescribeInstanc eAttribute	No	Yes	No
Tag resources with the "WorkingEnvironme nt" and "WorkingEnvironme ntld" tags which are used for maintenance and cost allocation	ec2:CreateTags	Yes	Yes	No
Manage EBS	ec2:CreateVolume	Yes	Yes	No
volumes that Cloud Volumes ONTAP uses as back-end	ec2:DescribeVolume s	Yes	Yes	Yes
storage	ec2:ModifyVolumeAt tribute	No	Yes	Yes
	ec2:AttachVolume	Yes	Yes	No
	ec2:DeleteVolume	No	Yes	Yes
	ec2:DetachVolume	No	Yes	Yes

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage security groups for	ec2:CreateSecurityG roup	Yes	No	No
Cloud Volumes ONTAP	ec2:DeleteSecurityG roup	No	Yes	Yes
	ec2:DescribeSecurit yGroups	Yes	Yes	Yes
	ec2:RevokeSecurity GroupEgress	Yes	No	No
	ec2:AuthorizeSecurit yGroupEgress	Yes	No	No
	ec2:AuthorizeSecurit yGroupIngress	Yes	No	No
	ec2:RevokeSecurity GroupIngress	Yes	Yes	No
Create and manage network interfaces	ec2:CreateNetworkInterface	Yes	No	No
for Cloud Volumes ONTAP in the target subnet	ec2:DescribeNetwor kInterfaces	Yes	Yes	No
	ec2:DeleteNetworkIn terface	No	Yes	Yes
	ec2:ModifyNetworkIn terfaceAttribute	No	Yes	No
Get the list of destination subnets	ec2:DescribeSubnet s	Yes	Yes	No
and security groups	ec2:DescribeVpcs	Yes	Yes	No
Get DNS servers and the default domain name for Cloud Volumes ONTAP instances	ec2:DescribeDhcpO ptions	Yes	No	No
Take snapshots of	ec2:CreateSnapshot	Yes	Yes	No
EBS volumes for Cloud Volumes	ec2:DeleteSnapshot	No	Yes	Yes
ONTAP	ec2:DescribeSnapsh ots	No	Yes	No
Capture the Cloud Volumes ONTAP console, which is attached to AutoSupport messages	ec2:GetConsoleOutp ut	Yes	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Get the list of available key pairs	ec2:DescribeKeyPair s	Yes	No	No
Get the list of available AWS regions	ec2:DescribeRegion s	Yes	Yes	No
Manage tags for resources associated with	ec2:DeleteTags	No	Yes	Yes
Cloud Volumes ONTAP instances	ec2:DescribeTags	No	Yes	No
Create and manage stacks for AWS CloudFormation templates	cloudformation:Creat eStack	Yes	No	No
	cloudformation:Delet eStack	Yes	No	No
	cloudformation:Desc ribeStacks	Yes	Yes	No
	cloudformation:Desc ribeStackEvents	Yes	No	No
	cloudformation:Valid ateTemplate	Yes	No	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage	s3:CreateBucket	Yes	Yes	No
an S3 bucket that a Cloud Volumes	s3:DeleteBucket	No	Yes	Yes
ONTAP system uses as a capacity tier for	s3:GetLifecycleConfi guration	No	Yes	No
data tiering	s3:PutLifecycleConfi guration	No	Yes	No
	s3:PutBucketTaggin	No	Yes	No
	s3:ListBucketVersion s	No	Yes	No
	s3:GetBucketPolicyS tatus	No	Yes	No
	s3:GetBucketPublic AccessBlock	No	Yes	No
	s3:GetBucketAcl	No	Yes	No
	s3:GetBucketPolicy	No	Yes	No
	s3:PutBucketPublicA ccessBlock	No	Yes	No
	s3:GetBucketTaggin	No	Yes	No
	s3:GetBucketLocatio	No	Yes	No
	s3:ListAllMyBuckets	No	No	No
	s3:ListBucket	No	Yes	No
Enable data	kms:List*	Yes	Yes	No
encryption of Cloud Volumes ONTAP	kms:ReEncrypt*	Yes	No	No
using the AWS Key Management	kms:Describe*	Yes	Yes	No
Service (KMS)	kms:CreateGrant	Yes	Yes	No
Obtain AWS cost data for Cloud	ce:GetReservationUt ilization	No	Yes	No
Volumes ONTAP	ce:GetDimensionVal	No	Yes	No
	ce:GetCostAndUsag e	No	Yes	No
	ce:GetTags	No	Yes	No

Purpose	Action	Used for deployment?	Used for daily operations?	Used for deletion?
Create and manage an AWS spread placement group for two HA nodes and the mediator in a single AWS Availability Zone	ec2:CreatePlacemen tGroup	Yes	No	No
	ec2:DeletePlacemen tGroup	No	Yes	Yes
Create reports	fsx:Describe*	No	Yes	No
	fsx:List*	No	Yes	No
Create and manage aggregates that support the Amazon EBS Elastic Volumes feature	ec2:DescribeVolume sModifications	No	Yes	No
	ec2:ModifyVolume	No	Yes	No

Global File Cache

The Connector makes the following API requests to deploy Global File Cache instances during deployment:

- · cloudformation:DescribeStacks
- · cloudwatch:GetMetricStatistics
- cloudformation:ListStacks

FSx for ONTAP

The Connector makes the following API requests to manage FSx for ONTAP:

- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:DescribeInstanceAttribute
- ec2:DescribeRouteTables
- ec2:DescribeImages
- ec2:CreateTags
- ec2:DescribeVolumes
- · ec2:DescribeSecurityGroups
- ec2:DescribeNetworkInterfaces
- ec2:DescribeSubnets
- ec2:DescribeVpcs
- ec2:DescribeDhcpOptions
- ec2:DescribeSnapshots
- ec2:DescribeKeyPairs
- ec2:DescribeRegions

- · ec2:DescribeTags
- · ec2:DescribelamInstanceProfileAssociations
- ec2:DescribeReservedInstancesOfferings
- ec2:describeVpcEndpoints
- ec2:DescribeVpcs
- ec2:DescribeVolumesModifications
- ec2:DescribePlacementGroups
- kms:List*
- kms:Describe*
- · kms:CreateGrant
- · kms:ListAliases
- fsx:Describe*
- fsx:List*

Kubernetes

The Connector makes the following API requests to discover and manage Amazon EKS clusters:

- · ec2:DescribeRegions
- eks:ListClusters
- eks:DescribeCluster
- · iam:GetInstanceProfile

S3 bucket discovery

The Connector makes the following API request to discover Amazon S3 buckets:

s3:GetEncryptionConfiguration

Azure permissions for the Connector

When Cloud Manager launches the Connector VM in Azure, it attaches a custom role to the VM that provides the Connector with permissions to manage resources and processes within that Azure subscription. The Connector uses the permissions to make API calls to several Azure services.

Custom role permissions

The custom role shown below provides the permissions that a Connector needs to manage resources and processes within your Azure network.

When you create a Connector directly from Cloud Manager, Cloud Manager automatically applies this custom role to the Connector.

If you deploy the Connector from the Azure Marketplace or if you manually install the Connector on a Linux host, then you'll need to set up the custom role yourself.

You also need to ensure that the role is up to date as new permissions are added in subsequent releases.

```
{
    "Name": "Cloud Manager Operator",
    "Actions": [
       "Microsoft.Compute/disks/delete",
                        "Microsoft.Compute/disks/read",
                        "Microsoft.Compute/disks/write",
                        "Microsoft.Compute/locations/operations/read",
                        "Microsoft.Compute/locations/vmSizes/read",
"Microsoft.Resources/subscriptions/locations/read",
                        "Microsoft.Compute/operations/read",
"Microsoft.Compute/virtualMachines/instanceView/read",
"Microsoft.Compute/virtualMachines/powerOff/action",
                        "Microsoft.Compute/virtualMachines/read",
"Microsoft.Compute/virtualMachines/restart/action",
"Microsoft.Compute/virtualMachines/deallocate/action",
                        "Microsoft.Compute/virtualMachines/start/action",
                        "Microsoft.Compute/virtualMachines/vmSizes/read",
                        "Microsoft.Compute/virtualMachines/write",
                        "Microsoft.Compute/images/write",
                        "Microsoft.Compute/images/read",
"Microsoft.Network/locations/operationResults/read",
                        "Microsoft.Network/locations/operations/read",
                        "Microsoft.Network/networkInterfaces/read",
                        "Microsoft.Network/networkInterfaces/write",
                        "Microsoft.Network/networkInterfaces/join/action",
                        "Microsoft.Network/networkSecurityGroups/read",
                        "Microsoft.Network/networkSecurityGroups/write",
"Microsoft.Network/networkSecurityGroups/join/action",
                        "Microsoft.Network/virtualNetworks/read",
"Microsoft.Network/virtualNetworks/checkIpAddressAvailability/read",
                        "Microsoft.Network/virtualNetworks/subnets/read",
                        "Microsoft.Network/virtualNetworks/subnets/write",
"Microsoft.Network/virtualNetworks/subnets/virtualMachines/read",
"Microsoft.Network/virtualNetworks/virtualMachines/read",
```

```
"Microsoft.Network/virtualNetworks/subnets/join/action",
                        "Microsoft.Resources/deployments/operations/read",
                        "Microsoft.Resources/deployments/read",
                        "Microsoft.Resources/deployments/write",
                        "Microsoft.Resources/resources/read",
"Microsoft.Resources/subscriptions/operationresults/read",
"Microsoft.Resources/subscriptions/resourceGroups/delete",
"Microsoft.Resources/subscriptions/resourceGroups/read",
"Microsoft.Resources/subscriptions/resourcegroups/resources/read",
"Microsoft.Resources/subscriptions/resourceGroups/write",
                        "Microsoft.Storage/checknameavailability/read",
                        "Microsoft.Storage/operations/read",
"Microsoft.Storage/storageAccounts/listkeys/action",
                        "Microsoft.Storage/storageAccounts/read",
                        "Microsoft.Storage/storageAccounts/delete",
"Microsoft.Storage/storageAccounts/regeneratekey/action",
                        "Microsoft.Storage/storageAccounts/write",
"Microsoft.Storage/storageAccounts/blobServices/containers/read",
                        "Microsoft.Storage/usages/read",
                        "Microsoft.Compute/snapshots/write",
                        "Microsoft.Compute/snapshots/read",
                        "Microsoft.Compute/availabilitySets/write",
                        "Microsoft.Compute/availabilitySets/read",
                        "Microsoft.Compute/disks/beginGetAccess/action",
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreemen
ts/read",
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreemen
ts/write",
                        "Microsoft.Network/loadBalancers/read",
                        "Microsoft.Network/loadBalancers/write",
                        "Microsoft.Network/loadBalancers/delete",
"Microsoft.Network/loadBalancers/backendAddressPools/read",
"Microsoft.Network/loadBalancers/backendAddressPools/join/action",
```

```
"Microsoft.Network/loadBalancers/frontendIPConfigurations/read",
"Microsoft.Network/loadBalancers/loadBalancingRules/read",
                        "Microsoft.Network/loadBalancers/probes/read",
"Microsoft.Network/loadBalancers/probes/join/action",
                        "Microsoft.Authorization/locks/*",
                        "Microsoft.Network/routeTables/join/action",
                        "Microsoft.NetApp/netAppAccounts/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/write",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/read",
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",
                        "Microsoft.Network/privateEndpoints/write",
"Microsoft.Storage/storageAccounts/PrivateEndpointConnectionsApproval/acti
on",
"Microsoft.Storage/storageAccounts/privateEndpointConnections/read",
"Microsoft.Storage/storageAccounts/managementPolicies/read",
"Microsoft.Storage/storageAccounts/managementPolicies/write",
                        "Microsoft.Network/privateEndpoints/read",
                        "Microsoft.Network/privateDnsZones/write",
"Microsoft.Network/privateDnsZones/virtualNetworkLinks/write",
                        "Microsoft.Network/virtualNetworks/join/action",
                        "Microsoft.Network/privateDnsZones/A/write",
                        "Microsoft.Network/privateDnsZones/read",
"Microsoft.Network/privateDnsZones/virtualNetworkLinks/read",
"Microsoft.Resources/deployments/operationStatuses/read",
                        "Microsoft.Insights/Metrics/Read",
"Microsoft.Compute/virtualMachines/extensions/write",
"Microsoft.Compute/virtualMachines/extensions/delete",
"Microsoft.Compute/virtualMachines/extensions/read",
```

```
"Microsoft.Compute/virtualMachines/delete",
                        "Microsoft.Network/networkInterfaces/delete",
                        "Microsoft.Network/networkSecurityGroups/delete",
                        "Microsoft.Resources/deployments/delete",
                        "Microsoft.Compute/diskEncryptionSets/read",
                        "Microsoft.Compute/snapshots/delete",
                        "Microsoft.Network/privateEndpoints/delete",
                        "Microsoft.Compute/availabilitySets/delete",
                        "Microsoft.Network/loadBalancers/delete",
                        "Microsoft.KeyVault/vaults/read",
                        "Microsoft.KeyVault/vaults/accessPolicies/write",
                        "Microsoft.Compute/diskEncryptionSets/write",
                        "Microsoft.KeyVault/vaults/deploy/action",
                        "Microsoft.Compute/diskEncryptionSets/delete",
                        "Microsoft.Resources/tags/read",
                        "Microsoft.Resources/tags/write",
                        "Microsoft.Resources/tags/delete",
"Microsoft.Network/applicationSecurityGroups/write",
"Microsoft.Network/applicationSecurityGroups/read",
"Microsoft.Network/applicationSecurityGroups/joinIpConfiguration/action",
"Microsoft.Network/networkSecurityGroups/securityRules/write",
"Microsoft.Network/applicationSecurityGroups/delete",
"Microsoft.Network/networkSecurityGroups/securityRules/delete"
   ],
    "NotActions": [],
    "AssignableScopes": [],
    "Description": "Cloud Manager Permissions",
    "IsCustom": "true"
}
```

How Azure permissions are used

Actions	Purpose
"Microsoft.Compute/locations/operations/read", "Microsoft.Compute/locations/vmSizes/read", "Microsoft.Compute/operations/read", "Microsoft.Compute/virtualMachines/instanceView/read", "Microsoft.Compute/virtualMachines/powerOff/action", "Microsoft.Compute/virtualMachines/read", "Microsoft.Compute/virtualMachines/restart/action", "Microsoft.Compute/virtualMachines/start/action", "Microsoft.Compute/virtualMachines/deallocate/action", "Microsoft.Compute/virtualMachines/deallocate/action", "Microsoft.Compute/virtualMachines/vmSizes/read", "Microsoft.Compute/virtualMachines/write",	Creates Cloud Volumes ONTAP and stops, starts, deletes, and obtains the status of the system.
"Microsoft.Compute/images/write", "Microsoft.Compute/images/read",	Enables Cloud Volumes ONTAP deployment from a VHD.
"Microsoft.Compute/disks/delete", "Microsoft.Compute/disks/read", "Microsoft.Compute/disks/write", "Microsoft.Storage/checknameavailability/read", "Microsoft.Storage/operations/read", "Microsoft.Storage/storageAccounts/listkeys/action", "Microsoft.Storage/storageAccounts/read", "Microsoft.Storage/storageAccounts/regeneratekey/action", "Microsoft.Storage/storageAccounts/write" "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/storageAccounts/delete", "Microsoft.Storage/usages/read",	Manages Azure storage accounts and disks, and attaches the disks to Cloud Volumes ONTAP.
"Microsoft.Storage/storageAccounts/blobServices/containers/read", "Microsoft.KeyVault/vaults/read", "Microsoft.KeyVault/vaults/accessPolicies/write"	Enables backups to Azure Blob storage and encryption of storage accounts
"Microsoft.Network/networkInterfaces/read", "Microsoft.Network/networkInterfaces/write", "Microsoft.Network/networkInterfaces/join/action",	Creates and manages network interfaces for Cloud Volumes ONTAP in the target subnet.
"Microsoft.Network/networkSecurityGroups/read", "Microsoft.Network/networkSecurityGroups/write", "Microsoft.Network/networkSecurityGroups/join/action ",	Creates predefined network security groups for Cloud Volumes ONTAP.

Actions	Purpose
"Microsoft.Resources/subscriptions/locations/read", "Microsoft.Network/locations/operationResults/read", "Microsoft.Network/locations/operations/read", "Microsoft.Network/virtualNetworks/read", "Microsoft.Network/virtualNetworks/checkIpAddressAv ailability/read", "Microsoft.Network/virtualNetworks/subnets/read", "Microsoft.Network/virtualNetworks/subnets/virtualMac hines/read", "Microsoft.Network/virtualNetworks/virtualMachines/read", "Microsoft.Network/virtualNetworks/virtualMachines/read", "Microsoft.Network/virtualNetworks/subnets/join/action",	Gets network information about regions, the target VNet and subnet, and adds Cloud Volumes ONTAP to VNets.
"Microsoft.Network/virtualNetworks/subnets/write", "Microsoft.Network/routeTables/join/action",	Enables VNet service endpoints for data tiering.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write",	Deploys Cloud Volumes ONTAP from a template.
"Microsoft.Resources/deployments/operations/read", "Microsoft.Resources/deployments/read", "Microsoft.Resources/deployments/write", "Microsoft.Resources/resources/read", "Microsoft.Resources/subscriptions/operationresults/read", "Microsoft.Resources/subscriptions/resourceGroups/delete", "Microsoft.Resources/subscriptions/resourceGroups/read", "Microsoft.Resources/subscriptions/resourcegroups/read", "Microsoft.Resources/subscriptions/resourcegroups/resources/read", "Microsoft.Resources/subscriptions/resourceGroups/write",	Creates and manages resource groups for Cloud Volumes ONTAP.
"Microsoft.Compute/snapshots/write", "Microsoft.Compute/snapshots/read", "Microsoft.Compute/snapshots/delete", "Microsoft.Compute/disks/beginGetAccess/action",	Creates and manages Azure managed snapshots.
"Microsoft.Compute/availabilitySets/write", "Microsoft.Compute/availabilitySets/read",	Creates and manages availability sets for Cloud Volumes ONTAP.
"Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/read", "Microsoft.MarketplaceOrdering/offertypes/publishers/offers/plans/agreements/write",	Enables programmatic deployments from the Azure Marketplace.

Actions	Purpose
"Microsoft.Network/loadBalancers/read", "Microsoft.Network/loadBalancers/write", "Microsoft.Network/loadBalancers/delete", "Microsoft.Network/loadBalancers/backendAddressPools/read", "Microsoft.Network/loadBalancers/backendAddressPools/join/action", "Microsoft.Network/loadBalancers/frontendIPConfigurations/read", "Microsoft.Network/loadBalancers/loadBalancingRules/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/read", "Microsoft.Network/loadBalancers/probes/join/action",	Manages an Azure load balancer for HA pairs.
"Microsoft.Authorization/locks/*",	Enables management of locks on Azure disks.
"Microsoft.Authorization/roleDefinitions/write", "Microsoft.Authorization/roleAssignments/write", "Microsoft.Web/sites/*"	Manages failover for HA pairs.
"Microsoft.Network/privateEndpoints/write", "Microsoft.Storage/storageAccounts/PrivateEndpointC onnectionsApproval/action", "Microsoft.Storage/storageAccounts/privateEndpointC onnections/read", "Microsoft.Network/privateEndpoints/read", "Microsoft.Network/privateDnsZones/write", "Microsoft.Network/privateDnsZones/virtualNetworkLi nks/write", "Microsoft.Network/virtualNetworks/join/action", "Microsoft.Network/privateDnsZones/A/write", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/read", "Microsoft.Network/privateDnsZones/virtualNetworkLi nks/read",	Enables the management of private endpoints. Private endpoints are used when connectivity isn't provided to outside the subnet. Cloud Manager creates the storage account for HA with only internal connectivity within the subnet.
"Microsoft.NetApp/netAppAccounts/capacityPools/volumes/delete",	Enables Cloud Manager to delete volumes for Azure NetApp Files.
"Microsoft.Resources/deployments/operationStatuses/read"	Azure requires this permission for some virtual machine deployments (it depends on the underlying physical hardware that's used during deployment).
"Microsoft.Resources/deployments/operationStatuses/read", "Microsoft.Insights/Metrics/Read", "Microsoft.Compute/virtualMachines/extensions/write", "Microsoft.Compute/virtualMachines/extensions/read", "Microsoft.Compute/virtualMachines/extensions/delete", "Microsoft.Compute/virtualMachines/delete", "Microsoft.Network/networkInterfaces/delete", "Microsoft.Network/networkSecurityGroups/delete", "Microsoft.Resources/deployments/delete",	

Actions	Purpose
"Microsoft.Network/privateEndpoints/delete", "Microsoft.Compute/availabilitySets/delete",	Enables Cloud Manager to remove resources from a resource group that belong to Cloud Volumes ONTAP in case of deployment failure or deletion.
"Microsoft.Compute/diskEncryptionSets/read" "Microsoft.Compute/diskEncryptionSets/write", "Microsoft.Compute/diskEncryptionSets/delete" "Microsoft.KeyVault/vaults/deploy/action", "Microsoft.KeyVault/vaults/read", "Microsoft.KeyVault/vaults/accessPolicies/write",	Enables use of customer-managed encryption keys with Cloud Volumes ONTAP. This feature is supported using APIs.
"Microsoft.Resources/tags/read", "Microsoft.Resources/tags/write", "Microsoft.Resources/tags/delete"	Enables you to manage tags on your Azure resources using the Cloud Manager Tagging service.
"Microsoft.Network/applicationSecurityGroups/write", "Microsoft.Network/applicationSecurityGroups/read", "Microsoft.Network/applicationSecurityGroups/joinIpC onfiguration/action", "Microsoft.Network/networkSecurityGroups/securityRu les/write", "Microsoft.Network/applicationSecurityGroups/delete", "Microsoft.Network/networkSecurityGroups/securityRu les/delete"	Enables Cloud Manager to configure an application security group for an HA pair, which isolates the HA interconnect and cluster network NICs.

Google Cloud permissions for the Connector

Cloud Manager requires permissions to perform actions in Google Cloud. These permissions are included in a custom role provided by NetApp. You might want to understand what Cloud Manager does with these permissions.

Service account permissions

The custom role shown below provides the permissions that a Connector needs to manage resources and processes within your Google Cloud network.

You'll need to apply this custom role to a service account that gets attached to the Connector VM. View step-by-step instructions.

You also need to ensure that the role is up to date as new permissions are added in subsequent releases.

```
title: NetApp Cloud Manager
description: Permissions for the service account associated with the
Connector instance.
stage: GA
includedPermissions:
- iam.serviceAccounts.actAs
- compute.regionBackendServices.create
- compute.regionBackendServices.get
```

- compute.regionBackendServices.list
- compute.networks.updatePolicy
- compute.backendServices.create
- compute.addresses.list
- compute.disks.create
- compute.disks.createSnapshot
- compute.disks.delete
- compute.disks.get
- compute.disks.list
- compute.disks.setLabels
- compute.disks.use
- compute.firewalls.create
- compute.firewalls.delete
- compute.firewalls.get
- compute.firewalls.list
- compute.globalOperations.get
- compute.images.get
- compute.images.getFromFamily
- compute.images.list
- compute.images.useReadOnly
- compute.instances.addAccessConfig
- compute.instances.attachDisk
- compute.instances.create
- compute.instances.delete
- compute.instances.detachDisk
- compute.instances.get
- compute.instances.getSerialPortOutput
- compute.instances.list
- compute.instances.setDeletionProtection
- compute.instances.setLabels
- compute.instances.setMachineType
- compute.instances.setMetadata
- compute.instances.setTags
- compute.instances.start
- compute.instances.stop
- compute.instances.updateDisplayDevice
- compute.machineTypes.get
- compute.networks.get
- compute.networks.list
- compute.projects.get
- compute.regions.get
- compute.regions.list
- compute.snapshots.create
- compute.snapshots.delete
- compute.snapshots.get
- compute.snapshots.list

- compute.snapshots.setLabels
- compute.subnetworks.get
- compute.subnetworks.list
- compute.subnetworks.use
- compute.subnetworks.useExternalIp
- compute.zoneOperations.get
- compute.zones.get
- compute.zones.list
- compute.instances.setServiceAccount
- deploymentmanager.compositeTypes.get
- deploymentmanager.compositeTypes.list
- deploymentmanager.deployments.create
- deploymentmanager.deployments.delete
- deploymentmanager.deployments.get
- deploymentmanager.deployments.list
- deploymentmanager.manifests.get
- deploymentmanager.manifests.list
- deploymentmanager.operations.get
- deploymentmanager.operations.list
- deploymentmanager.resources.get
- deploymentmanager.resources.list
- deploymentmanager.typeProviders.get
- deploymentmanager.typeProviders.list
- deploymentmanager.types.get
- deploymentmanager.types.list
- logging.logEntries.list
- logging.privateLogEntries.list
- resourcemanager.projects.get
- storage.buckets.create
- storage.buckets.delete
- storage.buckets.get
- storage.buckets.list
- cloudkms.cryptoKeyVersions.useToEncrypt
- cloudkms.cryptoKeys.get
- cloudkms.cryptoKeys.list
- cloudkms.keyRings.list
- storage.buckets.update
- iam.serviceAccounts.getIamPolicy
- iam.serviceAccounts.list
- storage.objects.get
- storage.objects.list
- monitoring.timeSeries.list
- storage.buckets.getIamPolicy

How Google Cloud permissions are used

Actions	Purpose
- compute.disks.create - compute.disks.createSnapshot - compute.disks.delete - compute.disks.get - compute.disks.list - compute.disks.setLabels - compute.disks.use	To create and manage disks for Cloud Volumes ONTAP.
compute.firewalls.createcompute.firewalls.deletecompute.firewalls.getcompute.firewalls.list	To create firewall rules for Cloud Volumes ONTAP.
- compute.globalOperations.get	To get the status of operations.
compute.images.getcompute.images.getFromFamilycompute.images.listcompute.images.useReadOnly	To get images for VM instances.
compute.instances.attachDiskcompute.instances.detachDisk	To attach and detach disks to Cloud Volumes ONTAP.
- compute.instances.create - compute.instances.delete	To create and delete Cloud Volumes ONTAP VM instances.
- compute.instances.get	To list VM instances.
- compute.instances.getSerialPortOutput	To get console logs.
- compute.instances.list	To retrieve the list of instances in a zone.
- compute.instances.setDeletionProtection	To set deletion protection on the instance.
- compute.instances.setLabels	To add labels.
compute.instances.setMachineTypecompute.instances.setMinCpuPlatform	To change the machine type for Cloud Volumes ONTAP.
- compute.instances.setMetadata	To add metadata.
- compute.instances.setTags	To add tags for firewall rules.
compute.instances.startcompute.instances.stopcompute.instances.updateDisplayDevice	To start and stop Cloud Volumes ONTAP.
- compute.machineTypes.get	To get the numbers of cores to check qoutas.
- compute.projects.get	To support multi-projects.
 compute.snapshots.create compute.snapshots.delete compute.snapshots.get compute.snapshots.list compute.snapshots.setLabels 	To create and manage persistent disk snapshots.

Actions	Purpose
- compute.networks.get - compute.networks.list - compute.regions.get - compute.regions.list - compute.subnetworks.get - compute.subnetworks.list - compute.zoneOperations.get - compute.zones.get - compute.zones.list	To get the networking information needed to create a new Cloud Volumes ONTAP virtual machine instance.
 deploymentmanager.compositeTypes.get deploymentmanager.deployments.create deploymentmanager.deployments.delete deploymentmanager.deployments.get deploymentmanager.deployments.list deploymentmanager.manifests.get deploymentmanager.manifests.list deploymentmanager.operations.get deploymentmanager.operations.list deploymentmanager.resources.get deploymentmanager.resources.list deploymentmanager.typeProviders.get deploymentmanager.typeProviders.list deploymentmanager.typeS.get deploymentmanager.types.get deploymentmanager.types.list 	To deploy the Cloud Volumes ONTAP virtual machine instance using Google Cloud Deployment Manager.
logging.logEntries.listlogging.privateLogEntries.list	To get stack log drives.
- resourcemanager.projects.get	To support multi-projects.
storage.buckets.createstorage.buckets.deletestorage.buckets.getstorage.buckets.liststorage.buckets.update	To create and manage a Google Cloud Storage bucket for data tiering.
cloudkms.cryptoKeyVersions.useToEncryptcloudkms.cryptoKeys.getcloudkms.cryptoKeys.listcloudkms.keyRings.list	To use customer-managed encryption keys from the Cloud Key Management Service with Cloud Volumes ONTAP.
 compute.instances.setServiceAccount iam.serviceAccounts.actAs iam.serviceAccounts.getIamPolicy iam.serviceAccounts.list storage.objects.get storage.objects.list 	To set a service account on the Cloud Volumes ONTAP instance. This service account provides permissions for data tiering to a Google Cloud Storage bucket.
- compute.addresses.list	To retrieve the addresses in a region when deploying an HA pair.

Actions	Purpose
compute.backendServices.createcompute.regionBackendServices.createcompute.regionBackendServices.getcompute.regionBackendServices.list	To configure a backend service for distributing traffic in an HA pair.
- compute.networks.updatePolicy	To apply firewall rules on the VPCs and subnets for an HA pair.
compute.subnetworks.usecompute.subnetworks.useExternallpcompute.instances.addAccessConfig	To enable Cloud Data Sense.
- container.clusters.get - container.clusters.list	To discover Kubernetes clusters running in Google Kubernetes Engine.
compute.instanceGroups.getcompute.addresses.get	To create and manage storage VMs on HA pairs.
- monitoring.timeSeries.list - storage.buckets.getlamPolicy	To discover information about Google Cloud Storage buckets.

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.