
This chapter will be renewed Object-Oriented Programming The Standard Template Library (STL) This chapter will be renewed The STL contains several kinds of entities. The three most important are containers, algorithms, and iterators. • A container (collection) is a way that stored data is organized in memory. Examples are stack, linked list, the array. The STL containers are implemented by template classes so they can be easily customized to hold different kinds of data. Algorithms are procedures that are applied to containers to process their data in various ways. For example, there are algorithms to sort, copy, search, and merge data. In the STL, algorithms are represented by template functions. These functions are not member functions of the container classes. You can increment an iterator, as you can a pointer, so it points in turn to each element in a container. Iterators are a key part of the STL because they connect algorithms with containers. The STL iterators are implemented by classes. @ ⊕ ⊕ ⊜



Containers:

Containers in the STL fall into two categories: sequential and associative.

The sequential containers are vector, list, and deque.

The associative containers are set, multiset, map, and multimap.

In addition, several containers are called abstract data types, which are specialized versions of other containers. These are stack, queue, and priority_queue.

Sequential containers: Elements of the sequential containers can be accessed by position, for example, by using an index. An ordinary C/C++ array is an example of a sequence container.

One problem with an ordinary C/C++ array is that you must specify its size at compile time, that is, in the source code. You must specify an array large enough to hold what you guess is the maximum amount of data.

When the program runs, you will either waste space in memory by not filling the array or run out of space.

The STL provides the **vector** container to avoid these difficulties.

The STL provides the list container, which is based on the idea of a linked list.

The third sequence container is the **deque**, which can be thought of as a combination of a stack and a queue. A deque combines these approaches so you can insert or delete data from either end. The word "deque" is derived from *Double-Ended QUEue*.

http://akademi.itu.edu.tr/en/buzluca



999 - 2010 — Feza BLD

123

Container	Characteristic	Advantages and Disadvantages			
Ordinary C++ array	Fixed size	Quick random access (by index number). Slow to insert or erase in the middle. Size cannot be changed at runtime.			
vector	Relocating, expandable array	Quick random access (by index number). Slow to insert or erase in the middle. Quick to insert or erase at end.			
list	Doubly linked list	Quick to insert or delete at any location. Quick access to both ends. Slow random access.			
deque	Like vector, but can be accessed at either end				

Associative containers:

An associative container is not sequential; instead it uses keys to access data. The keys, typically numbers or stings, are used automatically by the container to arrange the stored elements in a specific order.

For example if ${\bf m}$ is an STL ${\bf map}$ that stores students names and uses students IDs as a key, then the statement,

std::string name = m[1504125001];

initializes name to a string value in m associated with the key 1504125001.

There are two kinds of associative containers in the STL: maps and sets. A map associates a key with a value. For example student's number and the student's name.

A set is similar to a map, but it stores only the keys; there are no associated values. For example, only the number of students.

The map and set containers allow only one key of a given value to be stored. This makes sense in, say, a phone book where you can assume that multiple people don't have the same number.

On the other hand, the multimap and multiset containers allow multiple keys. In an English dictionary, there might be several entries for the word "set," for example.


http://akademi.itu.edu.tr/en/buzluca





999 - 2010 Feza BUZLUCA


Object-Oriented Programming This chapter will be renewed								
Basic associative containers are: map ,set, multimap, multiset.								
Container	Characteristics	Advantages and Disadvantages						
Мар	Associates key with element Only one key of each value allowed	Quick random access (by key). Inefficient if keys not evenly distributed.						
Multimap	Associates key with element Multiple key values allowed	Quick random access (by key). Inefficient if keys not evenly distributed.						
Set	Stores only the keys themselves Only one key of each value allowed	Quick random access (by key). Inefficient if keys not evenly distributed.						
Multiset	Stores only the keys themselves Multiple key values allowed	Quick random access (by key). Inefficient if keys not evenly distributed.						
http://akademi.itu.c		1999 - 2010 Feza BUZLUCA 12.6						

Object-Oriented Prog	ramming This chapter will be renewed						
Member Functions Algorithms are template functions of the STL, carrying out complex operations such as sorting and searching. They are not members of any template class. However, containers also need member functions to perform simpler tasks that are specific to a particular type of container. Some member functions common to all containers:							
size()	Returns the number of items in the container.						
empty()	Returns true if container is empty.						
max_size()	Returns size of the largest possible container.						
begin()	Returns an iterator to the start of the container for iterating forward through the container.						
end()	Returns an iterator to the past-the-end location in the container, used to end forward iteration.						
rbegin()	Returns a reverse iterator to the end of the container for iterating backward through the container.						
rend()	Returns a reverse iterator to the beginning of the container, used to end backward iteration. See Example e12_1.cpp						
http://akademi.itu.edu http://www.buzluca.int							










```
This chapter will be renewed
Object-Oriented Programming
    Data insertion:
  int main() {
     list<int> iList(5);
                                                         // empty list holds 5 ints
     list<int>::iterator it;
                                                         // iterator
     int data = 0;
                                                         // fill list with data
     for(it = iList.begin(); it != iList.end(); it++)
        *it = data += 2;
     for(it = iList.begin(); it != iList.end(); it++) cout << *it << ' ';
                                                                         // display list
     return 0;
  The first loop fills the container with the int values 2, 4, 6, 8, 10, showing that
  the overloaded * operator works on the left side of the equal sign as well as on
  the right. The second loop displays these values.
   Example: Shapes with the STL: Inheritance and Polymorphism
                                                            See Example: e12_8.cpp
                                          @⊕9⊜
```



```
Object-Oriented Programming This chapter will be renewed
      Using the reverse operator
   int main() {
                                               || array of ints
     int arr[] = \{ 2, 4, 6, 8, 10 \};
     list<int> iList(arr, arr+5);
                                               // list initialized to array
     list<int>:
                                  evit;
                                               // reverse iterator
                                               // iterate backwards
     revit = iList.rbegin();
     while( revit != iList.rend() )
                                               // through list,
                                               || displaying output
         cout << *revit++ << '
    return 0;
   Reverse iterators act like pointers to elements of the container, except that
   when you apply the increment operator to them, they move backward rather
   than forward.
   You must use the member functions rbegin() and rend() when you use a reverse
   iterator. (But don't try to use them with a normal forward iterator.)
   Confusingly, you're starting at the end of the container, but the member
   function is called rbegin(). Also, you must increment the iterator. Don't try to
   decrement a reverse iterator; revit-- doesn't do what you want. With a
   reverse_iterator, always go from rbegin() to rend() using the increment
   operator.
                                        @ ⊕ ⊕ ⊜
```

Object-Oriented Programming This chapter will be renewed Algorithms: Template functions. They are not members of any class. · These algorithms were designed to work with STL containers, but you can apply them also to ordinary C++ arrays. Examples: The find() Algorithm: Function prototype: Iterator find(Iterator first, Iterator last, Type const &value); Description: Element value is searched for in the range of the elements implied by the iterator range [first, last). An iterator pointing to the first element found is returned. If the element was not found, last is returned. The operator==() of the underlying data type is used to compare the elements. #include <iostream> #include <algorithm> // must be included for algorithms using namespace std; int arr[] = { 11, 22, 33, 44, 55, 66, 77, 88 }; void main() { int* ptr; ptr = find(arr, arr+8, 33); // find first 33 cout << "First object with value 33 found at offset " << (ptr-arr) << endl; The output from this program is First object with value 33 found at offset 2. **@** ⊕ ⊕ ⊜

```
Object-Oriented Programming This chapter will be renewed
      Using the find() algorithm with containers
   #include <iostream>
   #include <algorithm>
   #include <list>
  using namespace std;
  void main() {
     list<int> iList(5);
                                                                       // empty list holds 5 ints
     list<int>::iterator it;
                                                                       // iterator
                                                                       // fill list with data
     int data = 0;
     for(it = iList.begin(); it != iList.end(); it++)
          *it = data += 2;
     it = find(iList.begin(), iList.end(), 8);
                                                                       // look for number 8
     if( it != iList.end() ) cout << "\nFound 8";
else cout << "\nDid not find 8."; }
As an algorithm, find() takes three arguments. The first two are iterator values
specifying the range to be searched and the third is the value to be found.
Here I fill the container with the same 2, 4, 6, 8, 10 values as in the last example. Then I use the find() algorithm to look for the number 8. If find() returns iList.end(), I know it's reached the end of the container without finding a match. Otherwise, it must
have located an item with the value 8. Here the output is
  Found 8
                                                    @⊕9⊜
```

```
This chapter will be renewed
Object-Oriented Programming
  You can also use algorithms with user defined classes. But classes must include
  necessary operators, which are used by algorithms. For example the find()
  algorithm uses the operator == () of the underlying data type to compare the
  elements.
class ComplexT{
   float re,im;
 public:
   set(float r, float i){re=r; im=i;}
   bool operator==(const ComplexT &c) const{
          return re==c.re && im==c.im;
                                               int main(){
                                                  ComplexT z[3];
                                                  z[0].set(1.1, 1.2);
z[1].set(2.1, 2.2);
z[2].set(3.1, 3.2);
ComplexT zSearch;
                                                  zSearch.set(2.1, 2.2);
                                                  ComplexT *result;
result=find(z, z+3, zSearch);
                                                  if (result == z+3) cout << "Not found";
                                                                     cout << "Found";
                                                     else
   See Example: e12_9.cpp
                                                  return 0;
                                              <u>@</u>099
```

```
This chapter will be renewed
Object-Oriented Programming
      Example: sort()
 Function prototypes:
   void sort(Iterator first, Iterator last);
    void sort( Iterator first, Iterator last, comp);
 Description:
 •The first prototype: the elements in the range [first, last) are sorted in
 ascending order, using the operator<() of the underlying data type.

•The second prototype: the elements in the range [first, last) are sorted in
 ascending order, using the comp function object to compare the elements.
 Example:
 #include <iostream>
 #include <algorithm>
 #include <string>
 using namespace std;
 int main()
    string words[]= {"november", "kilo", "mike", "lima", "oscar", "quebec", "papa"};
    sort(words, words +7);
for(int i =0; i<7; i++) cout << words[i] << endl;</pre>
    return 0;
                                              @ ⊕ ⊕
```

```
This chapter will be renewed
Object-Oriented Programming
     Other prototype of sort() uses a given function to compare arguments.
 In this case the elements in the range (first, last) are sorted in ascending(?) order,
 using the comp function to compare the elements.
 The comp function can be a user written function:
 #include <iostream>
 #include <algorithm>
 #include <string>
 using namespace std;
 bool after( const string &left, const string &right)
    return left > right;
 int main()
    string words[]= {"november", "kilo", "mike", "lima", "oscar", "quebec", "papa"};
    sort(words, words +7, after);
for(int i =0; i<7; i++) cout << words[i] << endl;
                                                           || after is a pointer to a function
    return 0;
                              See Example: e12_10.cpp
                                                              See Example: e12_11.cpp
 In this example elements are sorted in descending order because of after function.
                                           @<u>0</u>99
```

This chapter will be renewed Object-Oriented Programming Some algorithms can take something called a function object as an argument. A function object is actually an object of a template class that has a single member function: the overloaded () operator. The names of these classes can be used as function names. In the header file functional there are many useful template classes which include a single member function the overloaded function call () operator. For example, a function object can be created from class greater to use with the sort algorithm: template<class T> #include <iostream> struct greater { #include <algorithm> bool **operator()**(const T& x, const T& y) const #include #include return x > y; using namespace std; int main() string words[]= {"november", "kilo", "mike", "lima", "oscar", "quebec", "papa"}; sort(words, words +7, **greater** < **string** > ()); // greater () is a function object for (int i = 0; i < 7; i + +) cout < < words[i] < endl; // greater () is a function object return 0; In this example elements are sorted in descending order because of greater function object. @ ⊕ ⊕ ⊜

Object-Oriented Programming This chapter will be renewed

Iterators and Algorithms

Besides acting as smart pointers to items in containers, iterators serve another important purpose in the STL. They determine which algorithms can be used with which containers.

In some theoretical sense, you should be able to apply every algorithm to every container. In fact, many algorithms will work with all the STL containers. However, some algorithms are inefficient (i.e., slow) when used with some containers. The sort() algorithm, for example, needs random access to the container it's trying to sort; otherwise, it would need to iterate through the container to find each element before moving it, a time-consuming approach.

Similarly, to be efficient, the reverse() algorithm needs to iterate backward as well as forward through a container.

Iterators provide an elegant way to match appropriate algorithms with containers. If you try to use an algorithm that's too powerful for a given container type, then you won't be able to find an iterator to connect them. If you try it, you will receive a compiler error alerting you to the problem.

The STL defines five types of iterators to make this scheme work.

- InputIterators: InputIterators can read elements from a container. The dereference operator is guaranteed to work as an rvalue in an expression, not as an Ivalue
- OutputIterators: OutputIterators can be used to write to a container. The dereference operator is guaranteed to work as an Ivalue in an expression, not as an rvalue.

http://akademi.itu.edu.tr/en/buzluc; http://www.buzluca.info



1999 - 2010 Feza BUZLUCA

- ForwardIterators: ForwardIterators combine InputIterators and OutputIterators. They can be used to traverse the container in one direction, for reading and/or writing.
- BidirectionalIterators: BidirectionalIterators allow the traversal of a container in both directions, for reading and writing.
 RandomAccessIterators: RandomAccessIterators provide access to any element
- RandomAccessIterators: RandomAccessIterators provide access to any element
 of the container at any moment. An algorithm such as sort() requires a
 RandomAccessIterator, and can therefore not be used with lists or maps, which
 only provide BidirectionalIterators.

Iterator	Step	Read	Write	Step	Random
Operation	Forward ++	value=*i	*i=value	Back 	Access [n]
Random-access iterator	×	×	×	×	×
Bidirectional iterator	x	×	x	×	
Forward iterator	x	×	x		
Output iterator	×		×		
Input iterator	×	×			
ttp://akademi.itu.edu.tr/en/buzluca		@080		Feza BUZLUC	A 12.23

Object-Oriented Programming This chapter will be renewed

If you confine yourself to the basic STL containers, you will be using only two kinds of iterators. The vector and deque require a random-access iterator, whereas the list, set, multiset, map, and multimap require only bi-directional iterators.

When you define an iterator, you must specify what kind of container it will be used for. For example, if you've defined a list holding elements of type int,

list<int> iList; // list of ints

then to define an iterator to this list you say

list<int>::iterator it; // iterator to list-of-ints

When you do this, the STL automatically makes this iterator a bi-directional iterator because that's what a list requires. An iterator to a vector or a deque, on the other hand, is automatically created as a random-access iterator.

http://akademi.itu.edu.tr/en/buzluca



1999 - 2010 Feza BUZLUCA

This chapter will be renewed Object-Oriented Programming Plugging iterators into ane algorithm: Every algorithm, depending on what it will do to the elements in a container, requires a certain kind of iterator. If the algorithm must access elements at arbitrary locations in the container, it requires a random-access iterator. If it will merely step forward through the iterator, it can use the less powerful forward iterator. **Algorithm** Output Forward Bidirectional Random Access Input for_each find × count copy replace unique reverse nth_element merge accumulate @⊕9⊜

Object-Oriented Programming This chapter will be renewed

Although each algorithm requires an iterator with a certain level of capability, a more powerful iterator will also work. The replace() algorithm requires a forward iterator, but it will work with a bi-directional or a random-access iterator as well.

- •Instead of an InputIterator it is also possible to use a Forward-, Bidirectional- or RandomAccessIterator.
- •Instead of an OutputIterator it is also possible to use a Forward-, Bidirectional- or RandomAccessIterator.
- Instead of a ForwardIterator it is also possible to use a Bidirectional- or RandomAccessIterator.
- •Instead of a BidirectionalIterator it is also possible to use a RandomAccessIterator. From the previous tables, you can figure out whether an algorithm will work with a given container. The table shows that the sort() algorithm, for example, requires a random-access iterator. The only containers that can handle random-access iterators are vectors and deques. There's no use trying to apply the sort() algorithm to lists, sets, maps, and so on.

Any algorithm that does not require a random-access iterator will work with any kind of STL container because all these containers use bi-directional iterators, which is only one grade below random access.

As you can see, comparatively few algorithms require random-access iterators. Therefore, most algorithms work with most containers.

Refer to file stl.html for memeber functions and algorithms of the STL.

http://akademi.itu.edu.tr/en/buzluca



999 - 2010 Feza BUZLUCA

This chapter will be renewed Object-Oriented Programming for each() algorithm: The for each() algorithm allows you to do something to every item in a container. You write your own function to determine what that "something" is. Your function can't change the elements in the container, but it can use or display their values. Function prototype: func for_each(InputIterator first, InputIterator last, Function func); Description: Each of the elements implied by the iterator range [first, last) is passed in turn to the function func. The function may not modify the elements it receives (as the used iterator is an input iterator). If the elements are to be transformed, transform() should be used. **Example:** for_each() is used to convert all the values of an array from inches to centimeters and display them. void in_to_cm(float in) // convert and display as centimeters cout << (in * 2.54) << ' '; int main() // array of inches values float array[] = { 3.5, 6.2, 1.0, 12.75, 4.33 }; // vector of inches values output as centimeters return 0; See Example:e12_12.cpp @09∋

Object-Oriented Programming This chapter will be renewed

Associative Containers

The two main categories of associative containers in the STL are maps and sets. A map (sometimes called a *dictionary* or *symbol table*) stores key and *value* pairs. The keys are arranged in sorted order.

A set is similar to a dictionary, but it stores only keys; there are no values.

In both a set and a map, only one example of each key can be stored. It's like a dictionary that forbids more than one entry for each word.

A multiset and a multimap are similar to a set and a map, but can include multiple instances of the same key.

The advantages of associative containers are that, given a specific key, you can quickly access the information associated with this key; it is much faster than by searching item by item through a sequence container. On normal associative containers, you can also quickly iterate through the container in sorted order.

Associative containers share many member functions with other containers. However, some algorithms, such as lower_bound() and upper_bound(), exist only for associative containers. Also, some member functions that do exist for other containers, such as the push and pop family (push_back() and so on), have no versions for associative containers.

http://akademi.itu.edu.tr/en/buzluca



1999 - 2010 Feza BUZLUCA

Object-Oriented Programming This chapter will be renewed The set class implements a set of (sorted) values. To use the set, the header file set must be included: #include <set> A set is filled with values, which may be of any container-acceptable type. Each value can be stored only once in a set. See Example: e12_13.cpp An important pair of member functions available only with associative containers is the lower_bound() and upper_bound(). set<string> city; The program first displays an set<string>::iterator iter; // iterator to set entire set of cities. The user is city.insert("Trabzon"); // insert city names then prompted to type in a pair of key values, and the program will iter = city.begin(); // display set display those keys that lie within while(iter != city.end()) this range. cout << *iter++ << endl; string lower, upper; // display entries in range cout << "\nEnter range (example A Azz): "; cin >> lower >> upper; iter = city.lower_bound(lower); while(iter != city.upper_bound(upper)) See Example: e12_14.cpp cout << *iter++ << endl; **@ ⊕ ⊕ ⊕**

This chapter will be renewed Object-Oriented Programming The map class implements a (sorted) associative array. To use the map, the header file map must be included: #include <map> A map is filled with Key/Value pairs, which may be of any container-acceptable The key is used for looking up the information belonging to the key. The associated information is the Value. For example, a phonebook uses the names of people as the key, and uses the telephone number and maybe other information as the value. Basically, the operations on a map are the storage of Key/Value combinations, and looking for a value, given a key. Each key can be stored only once in a map. If the same key is entered twice, the last entered key/value pair is stored, and the pair that was entered before is lost. **Example:** Cities and their plate numbers. void main() // set of string objects map<string,int> city_num; city_num["Trabzon"] = 61; // insert city names and numbers city_num["Adana"] = 01; string city_name; cout << "\nEnter a city: "; See Example: e12_15.cpp cin >> city_name; if (city_num.end() == city_num.find(city_name)) cout << city_name << " is not in the database" << endl; cout << "Number of " << city_name << ": " << city_num[city_name];</pre> <u>@</u> ⊕

Container Adaptors

It's possible to use basic containers to create another kind of container called a container adaptor. An adaptor is a sort of simplified or conceptual container that emphasizes certain aspects of a more basic container; it provides a different interface to the programmer.

The adaptors implemented in the STL are stacks, queues, and priority queues. A stack restricts access to pushing and popping a data item on and off the top of the stack.

In a queue, you push items at one end and pop them off the other end.

In a **priority queue**, you push data in the front in random order, but when you pop the data off the other end, you always pop the largest item stored: The priority queue automatically sorts the data for you.

Adaptors are template classes that translate functions used in the new container (such as push and pop) to functions used by the underlying container.

Stacks, queues, and priority queues can be created from different sequence containers, although the deque is often the most obvious choice.

You use a template within a template to instantiate a new container. For example, here's a stack object that holds type int, instantiated from the deque class: stack< int, deque<int> > int_stack;

By default, an STL stack adapts a deque. So you can define a stack as follows: stack< int > int_stack;

We could force a stack to adapt a vector with the definition:

stack< int, vector<int> > int_stack;

http://akademi.itu.edu.tr/en/buzluca



1999 - 2010 Feza BUZLLICA