Section 9: Virtual Memory (VM)

- Overview and motivation
- Indirection
- VM as a tool for caching
- Memory management/protection and address translation
- Virtual memory example

Simple Memory System Example

- **Addressing**
  - 14-bit virtual addresses
  - 12-bit physical address
  - Page size = 64 bytes





Simple Memory System Page Table

- Only showing first 16 entries (out of 256)

VPN	PPN	Valid
00	28	1
01	–	0
02	33	1
03	02	1
04	–	0
05	16	1
06	–	0
07	–	0

VPN	PPN	Valid
08	13	1
09	17	1
0A	09	1
0B	–	0
0C	–	0
0D	2D	1
0E	11	1
0F	0D	1

Simple Memory System TLB

- 16 entries
- 4-way associative



Set	Tag	PPN	Valid	Tag	PPN	Valid	Tag	PPN	Valid	Tag	PPN	Valid
0	03	–	0	09	0D	1	00	–	0	07	02	1
1	03	2D	1	02	–	0	04	–	0	0A	–	0
2	02	–	0	08	–	0	06	–	0	03	–	0
3	07	–	0	03	0D	1	0A	34	1	02	–	0

Simple Memory System Cache

- 16 lines, 4-byte block size
- Physically addressed
- Direct mapped



Idx	Tag	Valid	B0	B1	B2	B3
0	19	1	99	11	23	11
1	15	0	–	–	–	–
2	1B	1	00	02	04	08
3	36	0	–	–	–	–
4	32	1	43	6D	8F	09
5	0D	1	36	72	F0	1D
6	31	0	–	–	–	–
7	16	1	11	C2	DF	03

Idx	Tag	Valid	B0	B1	B2	B3
8	24	1	3A	00	51	89
9	2D	0	–	–	–	–
A	2D	1	93	15	DA	3B
B	0B	0	–	–	–	–
C	12	0	–	–	–	–
D	16	1	04	96	34	15
E	13	1	83	77	1B	D3
F	14	0	–	–	–	–

Current state of caches/tables

page size = 64 bytes

TLB

Set	Tag	PPN	Valid	Tag	PPN	Valid	Tag	PPN	Valid	Tag	PPN	Valid
0	03	–	0	09	0D	1	00	–	0	07	02	1
1	03	2D	1	02	–	0	04	–	0	0A	–	0
2	02	–	0	08	–	0	06	–	0	03	–	0
3	07	–	0	03	0D	1	0A	34	1	02	–	0

Page table

VPN	PPN	Valid
00	28	1
01	–	0
02	33	1
03	02	1
04	–	0
05	16	1
06	–	0
07	–	0

VPN	PPN	Valid
08	13	1
09	17	1
0A	09	1
0B	–	0
0C	–	0
0D	2D	1
0E	11	1
0F	0D	1

Cache

Idx	Tag	Valid	B0	B1	B2	B3
0	19	1	99	11	23	11
1	15	0	–	–	–	–
2	1B	1	00	02	04	08
3	36	0	–	–	–	–
4	32	1	43	6D	8F	09
5	0D	1	36	72	F0	1D
6	31	0	–	–	–	–
7	16	1	11	C2	DF	03

Idx	Tag	Valid	B0	B1	B2	B3
8	24	1	3A	00	51	89
9	2D	0	–	–	–	–
A	2D	1	93	15	DA	3B
B	0B	0	–	–	–	–
C	12	0	–	–	–	–
D	16	1	04	96	34	15
E	13	1	83	77	1B	D3
F	14	0	–	–	–	–

Address Translation Example #1

Virtual Address: 0x03D4



VPN 0x0F TLBI 3 TLBT 0x03 TLB Hit? Y Page Fault? N PPN: 0x0D

Physical Address



CO 0 CI 0x5 CT 0x0D Hit? Y Byte: 0x36

Address Translation Example #2

Virtual Address: 0x0B8F



VPN 0x2E TLBI 2 TLBT 0x0B TLB Hit? N Page Fault? ? PPN: TBD

Physical Address



CO ___ CI___ CT ____ Hit? __ Byte: ____

Address Translation Example #3

Virtual Address: 0x0020



VPN 0x00 TLBI 0 TLBT 0x00 TLB Hit? N Page Fault? N PPN: 0x28

Physical Address



CO 0 CI 0x8 CT 0x28 Hit? N Byte: Mem

Summary

- **Programmer's view of virtual memory**
  - Each process has its own private linear address space
  - Cannot be corrupted by other processes

- **System view of virtual memory**
  - Uses memory efficiently by caching virtual memory pages
    - Efficient only because of locality
  - Simplifies memory management and sharing
  - Simplifies protection by providing a convenient interpositioning point to check permissions

Memory System Summary

- **L1/L2 Memory Cache**
  - Purely a speed-up technique
  - Behavior invisible to application programmer and (mostly) OS
  - Implemented totally in hardware
- **Virtual Memory**
  - Supports many OS-related functions
    - Process creation, task switching, protection
  - Software
    - Allocates/shares physical memory among processes
    - Maintains high-level tables tracking memory type, source, sharing
    - Handles exceptions, fills in hardware-defined mapping tables
  - Hardware
    - Translates virtual addresses via mapping tables, enforcing permissions
    - Accelerates mapping via translation cache (TLB)