



Prerequisites

- ➤ Visual Studio 2015 or Higher
- ➤ Web Deploy 3.6 (download)
- > Aws Login (Use AD Cred)
- ➤ Siege Windows (<u>Download</u>)

Lets Build & Package


- ➤ Clone <u>Source Code</u> to C:\src
- CMD(Administrator) >> cd C:\src\sample-web-api
- Restore packages C:\temp\nuget.exe restore sample-web-api.sln
- Build & Package the solution (Select MsBuild Path)
 "C:\Program Files (x86)\MSBuild\14.0\Bin\MSBuild.exe" sample-web-api.sln /verbosity:minimal /p:outputPath="%cd%/build" /p:DeployOnBuild=True,DeployIISAppPath="Default Web Site/"





Lets Deploy To AWS EC2 Instance


Click on Launch EC2 Instance








Choose AMI



Choose an Instance Type








Configure Instance Details

Step 3: Configure Instance Details



Click on Advanced Details and add below powershell to the userdata select As text option







<powershell>

Set-ExecutionPolicy Unrestricted -Force

New-Item -ItemType directory -Path 'C:\temp'

Install IIS and Web Management Tools.

Import-Module ServerManager

install-windowsfeature web-server, web-webserver -IncludeAllSubFeature

install-windowsfeature web-mgmt-tools

Download And Install WebDeploymentAgent

\$url = "https://download.microsoft.com/download/0/1/D/01DC28EA-638C-4A22-A57B-4CEF97755C6C/WebDeploy_amd64_en-US.msi"

\$output = "C:\temp\webdeploy_3.6.msi"

\$start_time = Get-Date

\$wc = New-Object System.Net.WebClient

\$wc.DownloadFile(\$url, \$output)

Write-Output "Time taken: \$((Get-Date).Subtract(\$start_time).Seconds) second(s)"

msiexec /I \$output ADDLOCAL=all /passive /norestart LicenseAccepted="0" /I* C:\temp\msDeployInstall.log

Start-Sleep -s 60

#Add To Domain

\$svc_account = "directory.zuto.cloud\svc_domain_join"

\$svc_pwd_secure = ConvertTo-SecureString "C5trNsulgQV0" -AsPlainText -Force

\$creds = New-Object -typename System.Management.Automation.PSCredential -argumentlist (\$svc_account,\$svc_pwd_secure)

Add-Computer -DomainName directory.zuto.cloud -Credential \$creds -Restart

</powershell>






Add Storage

Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. Learn more about storage options in Amazon EC2.



Add Tags

Step 5: Add Tags

4 tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver.

A copy of a tag can be applied to volumes, instances or both.

lags will be applied to all instances and volumes. Learn more about tagging your Amazon EC2 resources.

Key (127 characters maximum)	Value (255 characters maximum)
lame	your-surname-application-name
Application	application-name
Owner	developer-name
Environment	dev

Add another tag

(Up to 50 tags maximum)





Review Instance Launch

Security Groups: HTTP, rdp_inbound, ms_deploy are setup upfront manually

Step 6: Configure Security Group

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can ε existing one below. Learn more about Amazon EC2 security groups.

Assign a security group: Ocreste a new security group

Select an existing security group

Security Group ID	Name
g-4250052b	allow_udp_dns_and_ssh
g-0f142166	awseb-e-nsehmtmpt3-stack-AWSEBLoadBalancerSecurityGroup-EMD2E60F8YST
g-5a2a1f33	awseb-e-nsehmtmpt3-stack-AWSEBSecurityGroup-1C05C6W1V8K8S
g-fd165594	default
sg-391e2b50	НТТР
g-976257fe	launch-wizard-10
sg-0bcc9262	launch-wizard-7
sg-06e3ca6f	launch-wizard-8
sg-8d192ce4	ms_deploy
gg-1c371575	quick-create-1
sg-f9faab90	rancher-security-group
sg-55a3f23c	RancherOS - HVM-v1-0-3-AutogenByAWSMP-
sg-e4ce9e8d	rdp_inbound
sg-d2f0a0bb	ssh_inbound


Cancel Previous Review and Launch Next: Configure Security Group

azon Web Services, Inc. or its affiliates. All rights reserved. Privacy Policy Terms of Use





Select a key pair



Wait for 10 mins

Deploy To Ec2


Via Command Line

"C:\Program Files (x86)\IIS\Microsoft Web Deploy V3/msdeploy" -verb:sync - source:package="%cd%/build/_PublishedWebsites/sample-web-api_Package/sample-web-api.zip" - dest:auto,computerName=https://10.132.xx.xxx:8172/MsDeploy.axd,userName="zuto\deploy",passwor d="9k4KRUFOJTwr",authType=Basic -debug -verbose -allowUntrusted





Verify App Status







Trouble Shooting RDP Access

Windows 9	Security		×
Enter y	our credentials		
These cr	edentials will be used to	connect to 10.132.43.17	4.
A	zuto\tmp_usr_1		
	•••••	ବ	
	Domain: zuto		
	Remember me		
More ch	oices		
Q,	zuto\a(min		
8	Use a different account		
	ОК	Cancel	

Username : zuto\tmp_usr_1

Password: p1CpBV7rNCus





ELB




Create ELB





re.

Classic Load Balancer



A Classic Load Balancer makes routing decisions at either the transport layer (TCP/SSL) or the application layer (HTTP/HTTPS), and supports either EC2-Classic or a VPC.

Step 1: Define Load Balancer

Basic Configuration

This wizard will walk you through setting up a new load balancer. Begin by giving your new load balancer a unique name so that you can identify it you might create. You will also need to configure ports and protocols for your load balancer. Traffic from your clients can be routed from any load k your EC2 instances. By default, we've configured your load balancer with a standard web server on port 80.

Load Balancer name:	srinivas-sunkari-elb-sample-web-api	
Create LB Inside:	vpc-4f5fd326 (10.132.0.0/16) vpc.eu-west-2	*
Create an internal load balancer:		
nable advanced VPC configuration:	€	

Listener Configuration:

Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
HTTP ▼	80	HTTP ▼	80

Add





Select Subnets

You will need to select a Subnet for each Availability Zone where you wish traffic to be routed by your load balancer. If you have instances in only one Availability Zone, please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

VPC vpc-4f5fd326 (10.132.0.0/16) | vpc.eu-west-2

Available subnets

Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
0	eu-west-2a	subnet-0f8d3f74	10.132.48.0/21	data.eu-west-2.az1
0	eu-west-2a	subnet-4172c03a	10.132.0.0/20	public.eu-west-2.az1
0	eu-west-2b	subnet-15cf0458	10.132.64.0/20	public.eu-west-2.az2
0	eu-west-2b	subnet-1acf0457	10.132.112.0/21	data.eu-west-2.az2

Selected subnets

Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
•	eu-west-2a	subnet-348f3d4f	10.132.32.0/20	private.eu-west-2.az1
0	eu-west-2b	subnet-f2ce05bf	10.132.96.0/20	private.eu-west-2.az2

Select Subnets

You will need to select a Subnet for each Availability Zone where you wish traffic to be routed by your load balancer. If you have instances in only one Availability Zone please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

VPC vpc-4f5fd326 (10.132.0.0/16) | vpc.eu-west-2

Available subnets

Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
0	eu-west-2a	subnet-0f8d3f74	10.132.48.0/21	data.eu-west-2.az1
0	eu-west-2a	subnet-4172c03a	10.132.0.0/20	public.eu-west-2.az1
0	eu-west-2b	subnet-15df0458	10.132.64.0/20	public.eu-west-2.az2
0	eu-west-2b	subnet-1act0457	10.132.112.0/21	data.eu-west-2.az2
Selected subnets	₩			
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
0	eu-west-2a	subnet-348f3d4f	10.132.32.0/20	private.eu-west-2.az
•	eu-west-2b	subnet-f2ce05bf	10.132.96.0/20	private.eu-west-2.az2

Step 2: Assign Security Groups

You have selected the option of having your Elastic Load Balancer inside of a VPC, which allows you to assign security groups to your load balancer. Please select the s

Assign a security group: Oreate a new security group

Select an existing security group


Security	Name	Description
sg-4250052b	allow_udp_dns_and_ssh	Allow UDP DNS traffic
sg-0f142166	awseb-e-nsehmtmpt3-stack-AVVSEBLoadBalancerSecurityGroup-EMD2E60F8YST	Load Balancer Security Group
sg-5a2a1f33	awseb-e-nsehmtmpt3-stack-AWSEBSecurityGroup-1C05C6W1V8K8S	VPC Security Group
sg-fd165594	default	default VPC security group
sg-391e2b50	НТТР	Ports Need To be open to access the web service
0700/74-	1	





Step 4: Configure Health Check


Your load balancer will automatically perform health checks on your EC2 instance:



Step 5: Add EC2 Instances

The table below lists all your running EC2 Instances. Check the boxes in the Select column to add those instances to this load balancer.

VPC vpc-4f5fd326 (10.132.0.0/16) | vpc.eu-west-2



Step 6: Add Tags

Apply tags to your resources to help organize and identify them.

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver. Learn more about tagging your Amazon EC2 resources.







Verify





Hit the ELB DNS Address








AMI





Create AMI









ASG





Create Auto Scaling Group


To create an Auto Scaling group, you will first need to choose a template that your Auto S a launch configuration or create a new one, and then apply it to your group.

Later, if you want to use a different template, you can create another launch configuration you can update the software that your group uses when it launches new instances.

- © Create a new launch configuration
- Create an Auto Scaling group from an existing launch configuration


Create Launch Configuration

An AMI is a template that contains the software configuration (operating system, application server, and applications) required to launch your instance. You



Create Launch Configuration

Amazon EC2 provides a wide selection of instance types optimized to fit different use cases, Instances are virtue of resources for your applications. Learn more about instance types and how they can meet your computing nee







Create Launch Configuration

Name	(j)	ssunkari-sample-web-api-lc
Purchasing option	(j)	Request Spot Instances
IAM role	(j)	ec2InstanceRole ▼
Monitoring	(i)	■ Enable CloudWatch detailed monitoring Learn more
▼ Advanced Details		
Kernel ID	(i)	Use default ▼
RAM Disk ID	(i)	Use default ▼
User data	(i)	 As text ○ As file □ Input is already base64 encoded
		(Optional)
IP Address Type	(i)	Only assign a public IP address to instances launched in the default VPC and subnet. (default) Assign a public IP address to every instance. Do not assign a public IP address to any instances.

Create Launch Configuration

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the roof volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. https://docs.aws.amazon.com/console/ec2/launchinstance/storage about storage options in Amazon EC2.









Add HTTP,rdp_inbound,ms_deploy Security Groups

Create Launch Configuration

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can add rules to allow specific traffic to reach your instance. For example, if you want to set up a web server and allow Internet traffic to reach your instance, add rules that allow unrestricted access to the HTTP and HTTPS ports. You can create a new security group or select from an existing one below. Learn more about Amazon EC2 security groups.









Ignore the VPC Warnings

Cancel and Exit Create Auto Scaling Group No default VPC found Select another VPC, or contact AWS Support if you want to create a new default VPC. Don't show me this aga Launch Configuration (i) ssunkari-sample-web-api-launch-config Group name (i) ssunkari-sample-web-api-asg Group size (i) Start with 1 instances Network (i) vpo-4f5fd326 (10.132.0.0/16) | vpc.eu-west-2 C Create new VPC Subnet (i) subnet-348f3d4f(10.132.32.0/20) | private.eu-west-2.az1 | eu-west-2a subnet-f2ce05bf(10.132.96.0/20) | private.eu-west-2.az2 | eu-west-2b Create new subnet No instances in this Auto Scaling group will be assigned a public IP address. 🕦 Advanced Details Load Balancing (i) Receive traffic from one or more load balancers Learn about Elastic Load Balancing Classic Load Balancers (1) ssunkari-elb-sample-web-api 🗶 Target Groups (i) Health Check Type (i) ● ELB
● EC2 Health Check Grace Period (1) 300 seconds Amazon EC2 Detailed Monitoring metrics, which are provided at 1 minute frequency, are Monitoring (i) not enabled for the launch configuration sample-web-api. Instances launched from it will use Basic Monitoring metrics, provided at 5 minute frequency. Learn more Instance Protection (i)





Add Scaling Policy

Create Auto Scaling Group

You can optionally add scaling policies if you want to adjust the size (number of instances) of your group automatically of instances or a percentage of the existing group size, or you can set the group to an exact size. When the alarm trig

- Keep this group at its initial size
- Use scaling policies to adjust the capacity of this group


Scale between 1 and 2 instances. These will be the minimum and maximum size of your group.

Name:	Scale Group Size
Metric type:	Average Network Out (Bytes) ▼
Target value:	100000
Instances need:	60 seconds to warm up after scaling
Disable scale-in:	

Tag New Instances

Create Auto Scaling Group

A tag consists of a case sensitive key-value pair that you can use to identify your group. For example, you could define a tag with Key = Environment and Value = Production. You can optionally choose to apply these tags to instances in the group when they launch. Learn more.




Add tag 46 remaining






Verify ASG



Verify ELB Should have







Load Testing

- > Extract siege-windows-3.0.5.zip to C:\siege-windows
- > cd siege-windows
- > siege -c50 -t300s http://elb-dns /api/text`