Operating Systems Lecture Notes

Anthony Catterwell

April 8, 2019

Contents

1	Lect	ture 2: Operating System Structure 2
	1.1	Architectural features affecting OS s
	1.2	Privileged instructions
	1.3	OS protections
	1.4	Crossing protection boundaries
	1.5	Syscall
	1.6	System call issues
	1.7	Exception handling and protection
	1.8	OS structure
	1.9	Operating system design and implementation
	1.10	System layers
		Major OS components
		OS structure
		Monolithic design
		Layering
		Hardware abstraction layer
		Microkernels
		Comparison of OS structures
		Loadable kernel modules
		Summary
		·
2	Lect	ture 3: Processes 9
	2.1	What is a "process"?
	2.2	What's "in" a process?
	2.3	The OS process namespace
	2.4	Representation of processes by the OS
	2.5	The PCB
	2.6	PCBs and CPU state
	2.7	Process execution states
	2.8	State queues
	2.9	PCBs and state queues
	2.10	Process creation
	2.11	Process creation semantics
		2.11.1 UNIX process creation details
	2.12	exec v.s. fork
	2.13	Method 1: vfork
	2.14	Method 2: copy-on-write
		Summary 16

1 Lecture 2: Operating System Structure

1.1 Architectural features affecting OSs

- These features were built primarily to support OSs:
 - timer (clock) operationg
 - synchronisation instructions
 - memory protection
 - I/O control operations
 - interrupts and exceptions
 - protected modes of operation (kernel vs. user mode)
 - privileged instructions
 - system calls (including software interrupts)
 - virtualisation architectures
- ASPLOS

1.2 Privileged instructions

- Some instructions are restricted to the OS
 - known as *privileged* instructions
- Only the OS can:
 - directly access I/O devices
 - manipulate memory state management (page table pointers, TLB loads, etc.)
 - manipulate special *mode bits* (interrupt priority level)
- Restrictions provide safety and security

1.3 OS protections

- So how does the process know if a privileged instruction should be executed?
 - the architecture must support at least two modes of operation: kernel mode, and user mode
 - mode is set by status bit in a protected processor register.
 - * user programs execute in user mode
 - * OS executes in kernel (privileged) mode (OS == kernel)
 - Privileged instructions can only be executed in kernel (privileged) mode
 - * if code running in user mode attempts to execute a privileged instruction, the illegal execution trap.


1.4 Crossing protection boundaries

- So how do user programs do something privileged?
 - e.g. how can you write to a disk if you can't execute any I/O instructions?
- User programs must call on OS procedure that is to ask the OS to do it for them.
 - OS defines a set of system calls

- User-mode program executes system call instruction
- Syscall instruction
 - like a protected procedure call

1.5 Syscall

- The syscall instruction atomically:
 - saves the current PC
 - sets the execution mode to privileged
 - sets the PC to a handler address
- Similar to a procedure call
 - Caller puts arguments in a place the callee expects (registers, or stack)
 - * One of the args is a syscall number, indicating which OS function to invoke
 - Callee (OS) saves caller's state (registers, other control states) so it can use the CPU
 - OS function code runs
 - * OS must verify caller's arguments (e.g. pointers)
 - OS returns using a special instruction
 - * Automatically sets PC to return address and sets execution mode to user.



1.6 System call issues

- A syscall is not a subroutine call, with the caller specifying the next PC.
 - the caller knows where the subroutines are located in memory; therefore they can be the target of an attack.
- The kernel saves state?
 - Prevents overwriting of values

- The kernel verify arguments
 - Prevents buggy code crashing the system
- Referring to kernel objects as arguments
 - Data copied between user buffer and kernel buffer.

1.7 Exception handling and protection

- All entries to the OS occur via the mechanism just shown
 - Acquiring privileged mode and branching to the trap handler are inseparable
- Terminology
 - Interrupt: asynchronous; caused by an external device
 - Exception: synchronous; unexpected problem with instruction
 - Trap: synchronous; intended transition to OS due to an instruction

In all three cases, they are instances of where something strange happens, and the OS takes control: whether by accident, or by intention.

• Privileged instructions and resources are the basis for most everything: memory protection, protected I/O, limiting user resource consumption.


1.8 OS structure

- The OS sits between application programs and the hardware
 - it mediates access and abstracts away ugliness
 - programs request services via traps or exceptions
 - devices request attention via interrupts

1.9 Operating system design and implementation

- Design and implementation of OS not "solvable", but some approaches have proven successful.
- Internal structure of different OSs can vary widely.
- Start the design by defining goals and specifications.
- Affected by choice of hardware, type of system.
- *User* goals, and *system* goals
 - User goals: OS should be convenient to use, easy to learn, reliable, safe, and fast
 - System goals: OS should be easy to design, implement, and maintain, as well as flexible, reliable, error-free, and efficient.
- Important principle to separate
 - **Policy**: What will be done?
 - **Mechanism**: *How* to do it?
- Mechanisms determine how to do something, policies decide what will be done.
- The separation of policy from mechanism is a very important principle, it allows maximum flexibility if policy decisions are to be changed later (e.g. timer).
- Specifying and designing an OS is a highly creative task of software enqineering.

1.10 System layers



1.11 Major OS components

- processes
- memory
- I/O
- secondary storage
- file systems
- protection
- shells
- GUI
- networking

1.12 OS structure

- There's no clear hierarchy within an OS each of them needs access to different things.
- An OS consists of all these components, plus:
 - many other components
 - system programs (privileged, and non-privileged)
- Major issue:
 - how do we organize all this?
 - what are all of the code modules, and where do they exist?
 - how do they cooperate?

- Massive software engineering and design problem
 - design a large, complex program that: performs well, is reliable, is extensible, and is backwards compatible.

1.13 Monolithic design

- Traditionally, OSs (like UNIX) were built as a monolithic entity User programs OS (everything) hardware
- Major advantage: cost of module interactions is low (procedure call)
- Disadvantages:
 - hard to understand
 - hard to modify
 - unreliable (no isolation between system modules)
 - hard to maintain
- What is the alternative?

 Find a way to organise the OS in order to simplify its design and implementation.

1.14 Layering

- The traditional approach is layering
 - implement OS as a set of layers
 - each layer presents an enhanced virtual machine to the layer above
- The first description of this approach was Dijkstra's THE system
 - Layer 5: Job managers execute users' programs
 - Layer 4: Device managers handle devices and provide buffering
 - Layer 3: Console manager implements virtual consoles
 - Layer 2: Page manager implements virtual memories for each process
 - Layer 1: Kernel implements a virtual processor for each process
 - Layer 0: Hardware
- Each layer can be tested and verified independently
- Imposes a hierarchical stricture
 - but real systems are more complex: file systems require VM services (buffer); VM would like to use files for its backing store
 - strict layering isn't flexible enough
- Poor performance: each layer crossing has overhead associated with it
- Disjunction between model and reality: systems modelled as layers, but not really built that way.


1.15 Hardware abstraction layer

- An example of layering in modern operating systems
- Goal: separates hardware-specific routines from the core OS

- Provides portability
- Improves readability


1.16 Microkernels

- Popular in the late 80s, early 90s
- Goal: minimize what happens in kernel; item organize rest of OS as user-level processes.
- This results in:
 - better reliability (isolation between components)
 - easy of extension and customisation
 - poor performance (user/kernel boundary crossings)
- First microkernel system was Hydra (CMU, 1970)
 - Contemporaries: Mach (CMU), Chorus (French UNIX-like OS), OS X (Apple), in some ways NT (Microsoft)




1.17 Comparison of OS structures

Windows



MINIX 3



1.18 Loadable kernel modules

- (Perhaps) the best practice for OS design
- Core services in the kernel, and others dynamically loaded
- Common implementations include: Solaris, Linux, etc.
- Advantages
 - convenient: no need for rebooting for newly added modules
 - efficient: no need for message passing unlike micro-kernel

- flexible: any module can call any other module unlike layered model

1.19 Summary

- Fundamental distinction between user and privileged mode supported by most hardware
- OS design has been an evolutionary process of trial and error.
- Successful OS designs have run the spectrum from monolithic, to layered, to micro-kernels
- The role and design of an OS are still evolving
- It is impossible to pick one "correct" way to structure an OS


2 Lecture 3: Processes

2.1 What is a "process"?

- \bullet The process is the OSs abstraction for execution
 - A process is a program in execution
- Simplest (classic) case: a sequential process
 - An address space (an abstraction of memory)
 - A single thread of execution (an abstraction of the CPU)
- A sequential process is:
 - The unit of execution
 - The unit of scheduling
 - The dynamic (active) execution context (as opposed to the program static, just a bunch of bytes)

2.2 What's "in" a process?

- A process consists of (at least):
 - An address space, containing:
 - * the code (instructions) for the running program
 - * the data for the running program (static data, heap data, stack)
 - *CPU state*, consisting of:
 - * the program counter (PC), indicating the next instruction;
 - * the stack pointer;
 - * other general purpose register values.
 - A set of *OS resources*
 - * open files, network connections, sound channels, ...
 - In other words, everything needed to run the program (or to restart, if interrupted).



2.3 The OS process namespace

- The particulars depend on the specific OS, but the principles are general;
- The name for a process is called a *process ID* (PID) (an integer);
- The PID namespace is global to the system;
- Operations that create processes return a PID (e.g. fork);
- Operations on processes take PIDs as an argument (e.g. kill, wait, nice).

2.4 Representation of processes by the OS

- The OS maintains a data structure to keep track of a process's state
 - called the process control block (PCB) or process descriptor;
 - identified by the PID.
- OS keeps all of a process's execution state in (or linked from) the PCB when the process isn't running
 - PC, SP, registers, etc.
 - when a process is unscheduled, the state is transferred out of the hardware into the PCB
 - (when a process is running, its state is spread between the PCB and the CPU).

2.5 The PCB

- The PCB is a data structure with many, many fields
 - PID
 - parent PID
 - execution state
 - PC, SP, registers


- address space info
- UNIX user id, group id
- scheduling priority
- accounting info
- pointers for state queues
- In Linux:
 - defined in task_struct (include/linux/sched.h)
 - Over 95 fields!

2.6 PCBs and CPU state

- When a process is running, its CPU state is inside the CPU
 - PC, SP, registers
 - CPU contains current values
- When the OS gets control because of a
 - Trap: program executes a syscall
 - Exception: program does something unexpected (e.g. page fault)
 - Interrupt: A hardware device requests service


the OS saves the CPU state of the running process in that process's PCB.

- When the OS returns the process to the running state
 - it loads the hardware registers with values from that process's PCB
 - e.g. general purpose registers, SP, instruction pointer
- This act of switching the CPU from one process to another is called a *context switch*
 - systems may do 100s or 1000s of switches per second;
 - takes a few microseconds on today's hardware;
 - still expensive relative to thread-based context switches.
- Choosing which process to run next is called *scheduling*.



2.7 Process execution states

- Each process has an execution state, which indicates what it's currently doing
 - ready: waiting to be assigned to a CPU could run, but another process has the CPU;
 - running: executing on a CPU it's the process that currently controls the CPU;
 - waiting (aka "blocked"): waiting for an event, e.g. I/O completion, or a messing from (or the completion of) another process cannot make progress until the event happens.
- As a process executes, it moves from state to state
 - UNIX: run top, STAT column shows current state
 - which state is a process most of the time?



2.8 State queues

- The OS maintains a collection of queues that represent the state of all processes in the system
 - typically one queue for each state (e.g. ready, waiting, ...);
 - each PCB is queued onto a state queue according to the current state of the process it represents;
 - as a process changes state, its PCB is unlinked from one queue, and linked onto another.
- The PCBs are moved between queues, which are represented as linked lists.
- There may be many wait queues, one for each type of wait (particular device, timer, message, ...).

2.9 PCBs and state queues

- PCBs are data structures
 - dynamically allocated inside OS memory.
- When a process is created:
 - OS allocates a PCB for it;
 - OS initializes PCB;
 - (OS does other things not related to the PCB);
 - OS puts PCB on the correct queue.
- As a process computes:
 - OS moves its PCB from queue to queue.
- When a process is terminated:
 - PCB may be retained for a while (to receive signals, etc.)

- eventually, OS deallocates the PCB.

2.10 Process creation

- New processes are created by existing processes
 - creator is called the *parent*;
 - created process is called the *child*;
 UNIX: do ps -ef, look for PPID field
 - what creates the first process, and when?
 on UNIX, this first process is init;
 on many Linux distributions, this is SystemD or Runit (on Void).


2.11 Process creation semantics

- (Depending on the OS) child processes inherit certain attributes of the parent. E.g.
 - Open file table: implies stdin/stdout/stderr;
 - On some systems, resource allocation to parent may be divided among children.
- (In Unix) when a child is created, the parent may either wait for the child to finish, or continue in parallel.

2.11.1 UNIX process creation details


- UNIX process creation through fork system call
 - creates and initializes a new PCB
 - * initializes kernel resources of new process with resources of parent (e.g. open files)
 - * initializes PC, SP to be same as parent.
 - creates a new address space
 - * initialises new address space with a copy of the entire contents of the address space of the parent
 - places new PCB on the ready queue.
- the fork system call "returns twice"
 - once into the parent, and once into the child
 - * returns the child's PID to the parent
 - * returns 0 to the child
- fork = "clone me".

The return value is used to determine whether we're the clone or the original.



2.12 exec v.s. fork

- Q: So how do we start a new program, instead of just forking the old program?
- A: First fork, then exec.
- exec
 - stops the current process
 - loads program 'prog' into the address space (i.e. overwrites the existing process image)
 - initialises hardware context, args for new program
 - places PCB onto ready queue
 - does not create a new process!



2.13 Method 1: vfork

- vfork is the older (now uncommon) of the two approaches.
- Instead of "child's address space is a copy of the parent's", the semantics are "child's address space is the parent's",
 - with a "promise" that the child won't modify the address space before doing an execve.
 - When execve is called, a new address space is created and it's loaded with the new executable.
 - Parent is blocked until execve is executed by child.
 - Saves wasted effort of duplicating parent's address space.

2.14 Method 2: copy-on-write

• Retains the original semantics, but copies "only what is necessary" rather than the entire address space.

• On fork:

- Create a new address space
- Initialise page tables with same mappings as the parent's (i.e. they both point to the same physical memory).
 - * (No copying of address space contents have occurred at this point with the sole exception of the top page of the stack.)
- Set both parent and child page tables to make all pages read-only
- If either parent or child writes to memory, an exception occurs.
- When exception occurs, OS copies the page, adjusts page tables, etc.

2.15 Summary

- Process
- PCB
- Process state
- ullet Context switch
- Process creation and termination