Runtime Configuration for MPC - Developper Manual

Sogeti High Tech July 22, 2013

Contents

1	Introduction	1
2	The module MPC_Config	1
3	Sources of the modules MPC_Config	2
	3.1 Details for the editor folder	2
	3.2 Details for the generated folder	2
	3.3 Details for the src folder	
4	The configuration system into MPC	3
	4.1 Configuration management workflow	3
	4.2 Steps for developper	3
5	The graphical editor interface	4
	5.1 The model	4
	5.2 The view	5
	5.3 The controller	6
	5.4 The XML handling	6
	5.5 Opening and saving local files	6

1 Introduction

Since MPC 2.4.1, a configuration system has been introduced through the module MPC_Config: it enables the user to setup some parameters at the runtime when running his binary with MPC.

This manual will explain to a developper how the configuration system is designed and how to add parameter into it

2 The module MPC_Config

All the configuration system is implemented into the MPC_Config module which gives functionnalities to generate:

- The configuration structure;
- The UNIX man for options list and values;
- The parsing source code;
- The displaying function.

This module also contains the graphical editor sources.

3 Sources of the modules MPC_Config

The module MPC_Config is subdivided into several directories:

- bin: contains the sources of the mpc_print_config executable;
- doc: contains the user and developper manuals describing the configuration system;
- editor: contains the graphical configuration editor;
- generated: contains all the generated files needed at the runtime (see §3.2 for more details);
- generators: contains all XSLT files used to generate the files in the generated folder;
- src: contains the sources for the configuration parsor from XML files (see §3.3 for more details).

3.1 Details for the editor folder

The editor folder contains:

- config: contains a set of different configs (valid, unvalid and malformed) which can be used as example for the editor;
- images: contains all the images used in the editor;
- javascript: contains all the JavaScript scripts used to load and edit configuration files;
- style: contains all the CSS files defining the editor style;
- index.html: the main file to open in a browser to use the graphical editor.

3.2 Details for the generated folder

Several files are generated using the XSLT in the generators folder:

- sctk_runtime_config_struct.h: define all the C data structures (struct, enum, etc.) of the MPC configuration structure;
- sctk_runtime_config_struct_meta.c: define meta-description (datatype, offset into the structure, etc.) to load the MPC configuration structure;
- sctk_runtime_config_struct_defaults.h: define functions prototypes initializing the MPC configuration structure with the default values;
- sctk_runtime_config_struct_defaults.c: initialize the MPC configuration structure with the default values;
- global-config-meta.xml: contains the contents of each config-meta.xml existing in MPC;
- mpc_config.5: UNIX man describing all the parameters (type, default value, doc) of the MPC configuration structure;
- mpc-config.xsd: scheme to validate the final configuration file.

3.3 Details for the src folder

The src folder contains the following files:

- sctk_runtime_config_mapper.{.h,.c}: provide the functions to convert the XML configuration file to the C structure;
- sctk_runtime_config_printer.{.h,.c}: use by the mpc_print_config executable to display the parameters for the XML configuration file, using the file sctk_runtime_config_struct_meta.c;
- sctk_runtime_config_selectors.{.h,.c}: handle selectors to select dynamically profiles at execution time;

- sctk_runtime_config_sources.{.h,.c}: provide the functions to open XML configuration files and to select profiles to apply;
- sctk_runtime_config_validation.{.h,.c}: provide a function to overwrite parameters with environment variables, and a function to check the values of the parameters;
- sctk_runtime_config_walk.{.h,.c}: use to run over the C configruation structure in order to display its contents;
- sctk_runtime_config.{.h,.c}: provide the interface that will be used in the other MPC modules.

A module sctk_libxml_helper.{.h, .c} is also developed to use libxml2 to read and write XML files.

4 The configuration system into MPC

4.1 Configuration management workflow

The workflow of configuration management can be described by steps:

- 1. Write a config-meta.xml for each MPC module which needs to be integrated into the configuration system;
- 2. Run mpc_gen_runtime_config which will:
 - Aggregate all the config-meta.xml to generate the global-config-meta.xml;
 - Apply XSLT transformations to generate source code for configuration management;
- 3. Compile MPC;

The Figure 1 summarized this process.

4.2 Steps for developper

A developper who wants to integrate his MPC module into the configuration system must:

- 1. Create a configuration file config-meta.xml in his module and define all the options he wants to parametrized;
- 2. Mark the dependency to the MPC_Config module by adding in the file module_dep: need_module MPC_Config;
- 3. Regenerate the MPC_Config auto-generated files by execution ./MPC_Tools/mpc_gen_runtime_config from mpc directory;
- 4. Include the header sctk_runtime_config.h in his source files;
- 5. Use the function sctk_runtime_config_get () to access to the configuration structure.




Figure 1: Representation of the workflow

5 The graphical editor interface

To edit the generated configuration files, an editor has been developed in HTML/JavaScript. The development has been validated on Firefox 10.0.8 ESR, but works with several others browsers as Google Chrome or Safari.

This section will only describe the JavaScript sources. In order to make future evolutions easy, the code is organized in a Model-View-Controller pattern. The model represents the data read from the XML configuration file: it is an association of hash tables which store propeties informations (name, type, value(s), etc.). The view is the graphical representation of the model, and the controller manages the events to synchronize both the model and the view. Some extra libraries have been included:

- EditorXML.js to manage the XML: conversion functions, getting child nodes, etc.;
- xmllint.js is a module compiled from libxml, which is used to validated the XML files (data and structure speaking);
- BlobBuilder.js and FileSaver.js to handle the saving of the new XML generated file.

5.1 The model

The model is handled in the EditorModel.js which can be separated in several parts:

- The functions used to create the model from an XML file;
- The functions used to update the model;
- The functions used to generate an XML file from the model.

A configuration file is divided in three parts, and each one has its own generation function:

- The profiles section is generated by createProfilesModel (config);
- 2. The networks section is generated by createNetworksModel (config);
- 3. The mappings section is generated by <code>createMappingsModel(config)</code>.

where config matches to the XML read configuration file converted into an DOM Document HTML Object.

The model generation has been thinked in such a way that it is fully automatic. While the XML configuration file is reading, the functions reads in the <code>sctk_runtime_config_meta.js</code> (which is a conversion of <code>sctk_runtime_config_meta.h</code> generated with XSL in JavaScript format) to get the type of each property. Depending on its type (param, array, struct, union), the model of a property is generated with one of the following functions:

```
createStructModel(xml, js);createArrayModel(xml, js);
```

- createParamModel(xml, js);
- createUnionModel(xml, js);

where xml matches to the property read in the XML configuration file and js is its meta-information.

If a new type called XXX is inserted in the configuration system, the developer just has to developed a function createXXXModel(xml, js) to create the associated model for a given property.

EditorModel.js also provides functions to update the model when a property value has been changed in the editor. Here is a list of some available functions:

- updateModel to update a module value in a profile;
- upateMappingsModel to update the mappings section;
- etc.

Finally, this file contains the XML generation functions. Each part of the configuration file has its own, and each type too. In this way, the XML generation is fully automatic:

- \bullet generateMappingsXmlConfig to generate the XML code for the mappings section;
- generateStructXML for a property of struct type;
- generateParamXML for a property of param type;
- etc.

5.2 The view

The view is handled in the EditorView.js which is also divided in several parts:

- The functions used to create the view from the model;
- The functions used to update the view when the model is updated.

As for the model, a generation function is developed for each part of a configuration file:

- The profiles section is generated by createProfilesView;
- The networks section is generated by createNetworksView;

3. The mappings section is generated by createMappingsView.

Each property type has its own function to create its representation:

- Numbers, function pointers and strings will be drawn an input text;
- Enumerators are represented with combo box;
- Sizes are an association between an input text and a combo box.

5.3 The controller

The file EditorController.js gives functionnalities to manage editor events to synchronize the model and the view.

- Adding/deleting new elements (profiles, mappings, etc.);
- · Property updating;
- etc.

5.4 The XML handling

The file EditorXML. is implements some functions to manage XML files.

The StringToXML (resp. XMLToString) converts an XML document into a string (resp. a string to an XML document). formatXML formats a XML code to respect indentation tags.

XML parsing functions are also implemented:

- getNodes gets all the XML elements matching to a given name;
- hasChild returns the child of a given XML element;
- getChildNodes returns all the child of a given XML element;
- getNodeValue returns the text value of a given XML element.

To ensure the portability of the editor, the <code>getElementsByClassName</code> has been recoded: it returns all the XML elements of a given node (the entire document by default) matching to a class name.

5.5 Opening and saving local files

JavaScript forbids to open and save local files for security reasons.

However, the module FileReader (new in HTML5) lets the user to open local files. Events are associated to this class:

- onload is triggered at the end of the file reading. Once the content loaded, it is analyzed by xmllint.js and the associated XSD file to validate its consistency. If the XML file is not valid, it will not be opened, and an error message will be displayed. Otherwise, the file will be loaded.
- onerror is triggered when an error occurs during the file reading. If this event is catched, the XML file will
 not be loaded.

To save files on a local disk storage, classes <code>BlobBuilder.js</code> and <code>FileSaver.js</code> have been added to the editor.