Operating Systems - Revision

Contents

- The Kernel
- Devices
 - Interrupts
- An aside on Storage Structure
- Direct Memory Access (DMA)
- <u>Multiprocessor systems</u>
 - Non-Uniform Memory Access (NUMA) Systems
- Multi-programming
- Resource manangement
- How are syscalls used?
- How does a syscall *actually* work?
- Subsystems
- Kernel Structures
 - Monolithic Kernel
 - Layered Kernels
 - Microkernel
 - Modular Kernels
 - Hybrid Kernels
- PCI
- <u>I/O Address ranges</u>
- Memory-mapped I/O
- I/O device control registers
- Polling
- Process Control Block (PCB)
- [[#Process <u>Scheduling</u>|Process <u>Scheduling</u>]]
 - [[#Process <u>Scheduling</u> #Context Switching|Context Switching]]
 - [[#Process Scheduling #An aside on fork() ing|An aside on fork() ing]]
- Inter-process Communication
 - Shared Memory
 - Message Passing
 - Signals
- Models of multi-threading
- Issues with threading
 - <u>`fork()` and `exec()`</u>

- [[#Issues with threading#Handling <u>Signals</u>]Handling <u>Signals</u>]]
- Cancelling Threads
- Thread-Local Storage
- Thread Control Blocks (TCBs)
- Process and Thread Behaviour
- Goals of Scheduling
 - Performance
 - Fairness
- Classes of Schedulers
 - Batch
 - Interactive
- Real-time
- Types of Scheduling
 - Non-preemptive
 - Preemptive
- Algorithms
 - First-come First-served (FCFS)
 - Shortest Job First (SJF)
 - Round-Robin (RR)
 - Priority (PRIO)
 - Multiple Queues (MQ)
 - Multilevel Feedback Queue (MLFQ)
- Logical Address Spaces vs. Physical Address Spaces
- Dynamic Loading and Dynamically Linked Libraries (DLLs)
- Contiguous Memory Allocation
- Translation Look-aside Buffer (TLB)
- Benefits of Paging
 - Shared Pages
 - Read-only code pages
- Page Table Structures
 - Hierarchical paging
 - Hashed Page Tables
 - Inverted Page Tables
- Swapping
- Page Fault
- Page Replacement
 - FIFO Page Replacement
 - Belady's Anomaly
 - Optimal Page Replacement

- Least Recently Used (LRU) Page Replacement
- Second Chance Page Replacement
 - Enhanced Second Choice
- Counting-Based Page Replacement
- Thrashing
 - Cause of thrashing
- Working Set
- Kernel Memory Allocation
 - Buddy System
 - Slab Allocation
- Hard Disk Drives (HDDs)
 - HDD Scheduling
 - FCFS Scheduling
 - SSTF Scheduling
 - SCAN Scheduling
 - C-SCAN
- NonVolatile Memory (NVM) devices
 - NAND` Flash Controller Algorithms
 - NVM Scheduling
- Error Detection and Correction
- Storage Device Management
 - Formatting
 - Partition
- RAID
 - RAID Levels
- File
 - Access Methods
- Directory
- Memory-Mapped files
- File system structure
- [[#How <u>directories</u> are actually implemented|How <u>directories</u> are actually implemented]]
 - [[#How directories are actually implemented#Linear list|Linear list]]
 - [[#How <u>directories</u> are actually implemented#Hash Table|Hash Table]]
- Allocating disk space
 - Contiguous allocation of files
 - · Linked allocation of files
 - Indexed Allocation of files
- Deleting files
- Recovering files

- Race Conditions
- Critical Section
- Preemptive kernel solution
- Hardware support
- Mutex Locks
- Semaphores
 - How to synchronise with semaphores
- Deadlocks
- Benefits and Features
- Building a VM
 - VCPU
 - [[#VCPU#VMs executing <u>privileged</u> instructions|VMs executing <u>privileged</u> instructions]]
 - [[#Building a VM#Nested <u>Page Tables</u>|Nested <u>Page Tables</u>]]

What is an Operating System? (Intro)

A *computer system* consists of the **hardware**, the **application programs** (apps), and the *operating system* (OS). The OS controls the hardware and coordinates its use among the various apps.

The Kernel

While there are multiple definitions on *what* an operating system *actually is*, a common definition is that the OS is actually the **kernel** - a program running on the computer at all times. Other programs, such as the application programs ran by a user, will interact with this kernel to access the underlying hardware.

Devices


For computers to provide functionality, they will need **devices** to communicate with the outside world. The OS supports these in the form of a **device driver**; software that understands the device controller and provides an interface to the rest of the computer system. Devices are not just I/O - **storage controllers** are a form of device for the computer to access physical storage (like *disks*).

Interrupts

As the time to complete tasks is dependent on many unpredictable factors, the device uses **interrupts** to inform the driver that an operation has finished. This is sent along the **system bus** (the main communications path between components).

When the CPU receives an interrupt, it stops its current task and transfers execution to the location the interrupt service resides. As interrupts occur often, a table (often called the

interrupt vector) of pointers to these interrupt routines. OSes also have the architecture to store the current execution state, so that on completion of the interrupt, the CPU resumes its previous execution. If an interrupt were to modify this state in some way, it must still store the current state and resume had the interrupt not occurred.



The CPU checks for interrupts (on an *interrupt request line*) between executing every instruction.

Most CPUs will have two interrupt request lines: a **maskable** and **non-maskable** one. Most device controllers will assert their interrupts to the maskable line, which can be ignored by the CPU before the execution of critical instruction sequences that must not be interrupted. Non-maskable interrupts are reserved for "catastrophic" memory errors, such as unrecoverable memory errors and other forms of massive irretrievable data loss. Computers may also use *interrupt chaining* to point to lists of many interrupt vectors if they have many devices.

An aside on Storage Structure

When we talk about "memory" on a computer, this can refer to a variety of actual storage mediums. All of the following could be referred to as "memory":

Name	Storage Tier	Volatility
Registers	Primary	Volatile
Cache	Primary	Volatile
Main memory (RAM)	Secondary	Volatile
Hard Disk Drives	Secondary	Non-volatile
Optical Disks	Tertiary	Non-volatile
Magnetic Tapes	Tertiary	Non-volatile


The further down this list we get, the storage capacity gets larger, and the memory access time also gets slower.

Direct Memory Access (DMA)


We can't simply use <u>Interrupts</u> for bulk data transfer as they have a lot of overhead. **DMA** is used to solve this: after setting up all the buffers/pointers/etc for the device controller, DMA transfers an entire block of data directly to the device with *no CPU intervention*.

Multiprocessor systems

Many computers these days have moved away from having a single *processor* (core/processing unit/CPU/whatever you want to call it) and now utilise **multiple processors**. This is commonly implemented *symmetrically* - all processors perform all tasks.




This is slightly different from a *multicore* system in which actual *cores* are located on the same processor. The main difference here is the addition of a secondary cache for all cores to use.



Non-Uniform Memory Access (NUMA) Systems

<u>Multiprocessor systems</u> don't intuitively scale with more cores as the *system bus* becomes the major bottleneck. NUMA solves this by connecting all CPUs with a *shared system interconnect*, making them all share the same physical address space. This allows all CPUs to access memory in parallel without contention.



Multi-programming


The fact that users typically *want* to run more than one program at a time, and that it would be inefficient to leave the CPU or I/O devices idle for long periods of time. The OS achieves this with **multi-programming**. It keeps multiple programs being executed (*processes*) in memory at once, and then picks one of these processes to execute. If this active process has to wait (e.g. for an I/O <u>device</u>), then the CPU *switches to another process* while it waits, returning once done.

Multitasking is an extension of multi-programming where this switching happens so fast a user is led to believe the programs are executing in parallel.

Privileges

The OS's <u>kernel</u> also provides security and abstraction benefits. It allows application program developers to avoid worrying about how to interact with the hardware, instead making them focus on how to interact with the *kernel* instead. This also acts as a security against malicious code, as the kernel checks how applications make requests for hardware resources.

An architecture that wishes to support privileges must support *atleast two modes*: *kernel* mode and *user* mode. For example, the $\times 86$ architecture supports 4 protection modes.



This gives the more user-accessible applications less kernel instructions it can execute. If an application wants to do something privileged (i.e. *read from storage*) it must perform a syscall.

Syscalls

System calls (syscalls) provide an interface to kernel mode instructions for lesser privileged programs. Syscalls usually come in one of six categories:

- process control
- file management
- device management
- information maintenance
- communications
- protection

How are syscalls used?


The OS usually provides an *Application Programming Interface* (API) which supplies all the syscalls an application (user-space program) can use. These syscalls will often take **parameters** (for example, if we wanted to open() a file, *what file* do we want to actually open?) These parameters are passed into a register, and when the OS switches to kernel mode to actually perform the operation, it will read from this register to execute the desired operation.

How does a syscall actually work?

When a CPU (core) receives a syscall instruction, it will

- 1. Save the current *Program Counter* (PC)
 - The control state, registers, and other necessary information is also saved.
- 2. Set the current execution mode to privileged (kernel)
- 3. Set the PC to a syscall handler address

It will then read any necessary parameters and execute the code related to that syscall, before returning to **user** mode and resuming the program from there (using the saved processor information as mentioned earlier).



OS Structure

Subsystems

When designing an OS, we must consider interactions between *subsystem services*, operating on a level between <u>The Kernel</u> and the user-space programs (**importantly**, **these programs operate** *outside* **of the kernel**). Some of these are interfaces for <u>Syscalls</u>, but generally these fall into the following categories (*not to be confused with the categories of syscalls mentioned above*):

File management

- Programs that create/delete/copy/rename/print/list/generally access and manipulate files/directories of files
 - Directories are technically files too, but this will be covered later

Status information

 Programs that ask the system for information. Simple examples may be the data/time, currently available memory, or the number of users. More complex information, such as verbose logging, may also be requested.

File modification

 Not to be confused with <u>File management</u>, these programs access and manipulate the content of files. For example, a program may want to search the contents of a file for a given word (e.g. grep)

Programming language support

 While users can download the compilers/assemblers/debuggers for any language they desire, common languages (such as C, C++, Java, Python) can come prepackaged with the OS.

Program loading and execution

 Necessary programs to actually run user-space applications. Examples would be loaders and linkers (which I don't believe are covered on this course? just know they're needed for some programs to execute)

Communications

 This includes both communicating between processes on the same system and between other computer systems entirely. This may include sending messages (e.g. email), logging in remotely (e.g. ssh), and transferring files.

Background services

 Often known as services or daemons, these are constantly running in the background - whenever execution is not focused on anything direct (a form of Multi-programming).

Kernel Structures

When deciding how to fit all these services together, we must decide what our *goals* are. No structure will satisfy everyone, and come with their own benefits and drawbacks. For example, compare *MacOS* and *Linux*. Linux only enforces rules in it's kernel; it's up to developers to create their own user-accessible environment (*distro*). As a result, two computers both running Linux can look (and possibly operate) very differently. On the other hand, *MacOS* enforces rules all the way to the desktop environment, meaning that two people's Macbooks will operate (and likely look) very similar.

Monolithic Kernel

The simplest method of structuring an OS is, simply, not structuring it. All functionality is put into a single file which runs in a single address space. This is called a **monolithic** kernel, and is what the original UNIX implementation uses.

	(the users)			
	shells and commands compilers and interpreters system libraries			
ſ	system-call interface to the kernel			
kernel	signals terminal handling character I/O system terminal drivers	file system swapping block I/O system disk and tape drivers	CPU scheduling page replacement demand paging virtual memory	
	kernel interface to the hardware			
	terminal controllers terminals	device controllers disks and tapes	memory controllers physical memory	

The major advantage of monolithic kernels is that the cost of <u>Subsystems</u> talking to each other is very low. However, monolithic kernels are massive and therefore difficult to understand and modify. Also, due to the lack of isolation between the services, they're a bit unreliable (compared to other kernels) and are difficult to debug or maintain. Monolithic approaches are usually referred to as **tightly coupled** systems, which is a practise software engineers like to *avoid if possible*!

Layered Kernels

Aiming to solve the tight-coupling problems of the <u>Monolithic Kernel</u> through designing a **loosely coupled** system, Layered kernels act in a similar method to <u>Privileges</u> (namely the rings in x86), in which layers closer to the hardware provide interfaces for those layers closer to what a user can interact with.

Any layer will use the services provided to it (through an interface) of the lower layers. *Dijkstra* provided such the first example of such an OS with his annoyingly-confusingly named THE system:

- 5. **Job Managers** layer that executes the user's programs
- 4. **Device Managers** layer that handles the <u>Devices</u> and provides <u>buffering</u>
- 3. **Console Manager** layer that implements *virtual consoles*
- 2. **Page Manager** layer that implements and managers *virtual memory pages* for each process
 - 1. **Kernel** layer that implements a virtual processor for each process


2. Hardware

Advantages of this hierarchical structure are that debugging is much simpler, as we can isolate problems to certain layers (it'll never be a bug in a higher layer than where the error's occurring). However, in practise, this mentality that "lower layers would never

need higher ones" is too limiting (for example, virtual memory would likely want some <u>real secondary storage</u> to handle backup files). Also, this design comes with *insane* overhead if we need to commonly cross layers (which subsystem interaction likely will do **all the time**).

Microkernel

The idea of a microkernel is to put *only what is necessary* into the kernel. Anything else is implemented as a user-space program. Typically, only minimal process and memory management are implemented in the kernel.



However, if services (now living in user-space) need to talk to each other, this must be down via the kernel.

The advantages of a micro-kernel are that it is much smaller, and therefore more reliable and easier to maintain. It also allows for customisability since even basic services are swappable. Also, since these live in user-space, *extensions* can be easily created on that same layer.

However, microkernels still have poor performance due to the constant mode switching necessary.

Modular Kernels

Modular kernels are not independent of any other kernels; they are more an idea to support extensions (and are a popular feature of *Linux*, which uses a <u>Monolithic Kernel</u>). These modules can be loaded into the kernel and can communicate with previous services at boot or runtime. These modules can communicate with other modules through an interface; this does not add an overhead due to the linked nature of the kernel.

Hybrid Kernels


We don't have to choose between *one* of the previous designs. Many modern OSes mix and match features of each design to try and get the benefits of all of kernel structures.

I/O Subsystems

I/O devices (actually all devices, but we might as well just focus on I/O devices for this section) communicate with the main machine via a **port**. If the devices share a common set of wires (e.g. like on a motherboard connecting a storage drive) this connection is called a **bus**, and the messages sent to/from the device(s) are conveyed by patterns of timed electrical voltages. If Device 1 is plugged into Device 2 which is plugged into Device 3 which is connected to the computer, this is also a bus (known as a *daisy chain*).


PCI

As buses are common in computer architecture, the *PCIe* standard is widely adopted. This bus connects the processor-memory subsystem to other fast devices (i.e <u>secondary</u> <u>storage</u>), and an *expansion bus* is used to connect to relatively slower devices. PCI is a multi-lane bus to allow simultaneous messages to be sent at once.



PCI also has evolved through multiple generations; if we describe a device as having "*PCIe gen3 x8*" it means it is compatible with **third** generation PCIe and uses **eight** lanes. Like other <u>Devices</u>, PCIe does come with a *controller* in the form of a ***fibre channel** (FC)*. Due to PCI's (and other buses') complexity, this controller is often implemented as a separate circuit board that connects to a bus. Other devices, such as an SSD, also have a controller

for the main unit.



I/O Address ranges

To transfer data over I/O, the device controller has some registers for data and control signals that the processor can read and write bit patterns into. These address ranges are usually reserved for specific devices:

I/O address range (hexadecimal)	Device
000-00F	DMA controller
020–021	interrupt controller
040–043	timer
200–20F	game controller
2F8–2FF	serial port (secondary)
320–32F	hard-disk controller
378–37F	parallel port
3D0-3DF	graphics controller
3F0-3F7	diskette-drive controller
3F8-3FF	serial port (primary)

Memory-mapped I/O

An alternative I/O data transfer method to <u>I/O Address ranges</u>, memory-mapped I/O is the process of assigning these registers into the standard address space of the processor (e.g. not in any hard-coded specific place). To avoid applications overwriting this information with their own data, these ranges are usually outside the *actual physical address space* (think in

the hundreds of terabytes on a 32GB system).

This is actually preferable to address ranges for massive data transfer, since writing millions of bytes to (e.g. graphics) device memory has significantly less overhead than issuing millions of I/O instructions (and even less so with <u>DMA</u>, which is only now <u>actually being used on modern graphics cards</u>).

I/O device control registers

I/O device controllers contain (usually) four registers, typically between 1-4 bytes in size. Some also have a *FIFO* chip that can hold several bytes of data beyond the size of the data register, until the device/host is able to receive the data.

Register	What it do
Data-in register	The host reads this to get input
Data-out register	The host writes to this to send output
Status register	Contains bits the host can read to indicate status (command completed, byte available in data-in, device error, etc)
Control register	The host can write to this to change stuff on the device (e.g. enabling parity checking, changing word length, selecting speeds, etc)

Polling

Using these <u>registers</u>, if a host wants to communicate to a controller it must complete a basic handshaking procedure:

- 1. The host repeatedly writes busy into the *status* register until it becomes clear.
- 2. The host sets the write bit in the status register (editor's note: book calls this the command register and refuses to elaborate. I'm assuming it means the status register) and also writes a byte into the data-out register.
- 3. The host sets the command-ready bit in the status register.
- 4. The controller notices the command-ready bit is set and sets the busy bit.
- 5. The controller then sees the write bit from earlier (indicating the host wishes to write to the device) and performs the necessary I/O.
- 6. The controller clears the command-ready, error (this indicates the I/O succeeded), and busy (indicating I/O operation has finished) bits in the status register.

This is repeated for each byte.

Polling a device is done in three CPU instruction cycles:


- read a device register
- 2. logical-and extract a status bit
- branch if not zero

Polling becomes inefficient if it is attempted repeatedly to no avail, and this is when Interrupts would be better used.

Processes

A *process* is just an instance of a program *in execution*, a single flow of instructions. This means we can have multiple instances of a program at once, visualised as different processes. Only one process can run on a processor core at any instant.

When a program is executed (and a process is created), it's memory layout is divided into multiple sections:



- Text the actual code to be executed
- Data the (global) variables
- Heap memory dynamically allocated during runtime
- Stack memory used for temporary data storage required to invoked functions (local variables, return addresses, function parameters, etc)

It will be of note that the stack and heap *grow toward each other*; it's the responsibility of the OS to make sure these two don't overlap.

Processes can also be an environment for other code to execute in; the *JVM*, for example, is a process that interprets *Java* code and executes on behalf of that code.

Each process has a *process ID* (PID), the namespace of which is *global* to the system to ensure only one process at a time has a specific PID (there are *some* exceptions like cgroups, but these aren't covered in the course so shhhh).

Process Control Block (PCB)

The OS represents processes using a *process control block* (PCB) (also sometimes called a *task control block*). It contains many pieces of information associated with that process, including (but not limited to):

Name	Information provided
Process state	New/Ready/Running/Waiting/Halted
Process number	PID
Program Counter	The address of the next instruction to be executed
Parent pointer	If the process was the result of a $fork()$, the PCB of the process that it was $fork()$ ed from
List of children	If the process fork() s, the PCB(s) of the process(es) that result from the fork()
Registers	Bunch of stuff needed for the program, depends on architecture (accumulators, index registers, stack pointers, etc)
Memory Limits	Where the program can store things
List of open files	List of open files
Scheduling priority	Used to schedule the next instruction on Multi-programming systems
Exit (return) code value	The code returned once the program has finished execution

Processes can also be represented as Threads, discussed later.

Process Scheduling


We will likely have situations where more than one process wants to run at the same time. However, as previously mentioned, only one process can run on a CPU core at once. Therefore, the need to *schedule* multiple processes.

To achieve this, when a process is created, it is put into a *ready queue* to wait and execute (this queue is generally stored as a linked list which each item's header contains pointers to the first PCB in the list, and each PCB includes a field that points to the next PCB in the queue).

Both fork() s and <u>Interrupts</u> are added to the ready queue, as they're still just all processes at the end of the day.

Context Switching

To achieve <u>Multi-programming</u>, we need to swap between execution of multiple processes. However, we need to save the current running process's *context*, and this is formally known as *context switching*. We *save the state* of the CPU core, load in our new process, then *load the state* back once we're finished.



An aside on fork() ing

When a process fork() s, the child PCB is an *identical copy* with the exception of PID argument on the top of the stack.

If we wish to start a new program without forking the old program, we can fork() then exec, which:

- 1. stops the current process
- loads the program into address space (which overwrites the existing process image)
- 3. initialises the PCB for the new program and places it onto the ready queue

This doesn't create a new process.

Also, the initial idea of implementing <code>fork()</code> by copying the **entire** parent space is slow. There are two methods (covered in this course) to solve this:


- vfork() sets the child's address space to be the parent's address space
- **Copy-On-Write** only copies "*what is necessary*"; only when a specific area of memory is accessed by the parent do we copy it to the child.

Inter-process Communication

Processes may want to cooperate with each other, and thus need secure, reliable methods to communicate. There are two main methods of IPC: <u>Shared Memory</u> and <u>Message</u> <u>Passing</u>

Shared Memory

This form of IPC uses a shared bit of memory that the processes (in one communication, a *producer* and a *consumer*) can read to/write from.



The OS doesn't mediate this communication so it's up to the processes to get permission to talk to each other. Also, if more than one process is a *consumer*, then there's no necessity to *refer to a specific consumer* - something that Message Passing solves

Message Passing

Message passing is a way of constructing specific messages *directed to a specific process*. These messages reside in temporary **buffers/queues**, coming in three flavours:

- Zero capacity
 - No waiting messages; sender must block until recipient receives the message

- Bounded capacity
 - Finite length of **n** messages can reside in it; if full, sender can continue execution
- Unbounded capacity
 - The queue is infinite; the sender never blocks a message

UNIX pipes are an example of message-passing.

Signals

Using a similar mechanism to <u>Message Passing</u>, signals are an OS mechanism to **notify a process** of something. This is a *one-way* communication that carries no extra information. kill() and raise() are examples of signals

Threads


Owing again to Multi-programming, threads can be thought of as a *unit of CPU utilisation*. This allows threads to be scheduled.


We say the **process** holds the address space, OS resources, etc, but that the **thread** holds the CPU state (program counter, stack pointer, etc).

Threads are mainly utilised in *multi-core* systems where they can run *in parallel*. Just simply adding more threads may not increase speedup if not constructed thoughtfully. **Amdahl's Law** states if we have a system with N processing cores, and a portion S of the application that must be performed serially, our speedup is bounded

$$\text{speedup} \le \frac{1}{S + \frac{(1-S)}{N}}$$

Parallel tasks are not the same as concurrent tasks - where tasks are completed bit-by-bit after each other - as this happens on multiple cores at the same time.





single-threaded process

multithreaded process

Models of multi-threading

There are two types of thread, with different models having different relations to each other. **User threads** are managed above the kernel and **kernel threads** are exclusively managed by the OS directly.

- Many-to-One model
 - Many user threads all map to one kernel thread
- One-to-One model
 - One user thread maps to one kernel thread
- Many-to-many model
 - **Many** user threads are *multiplexed* to a **smaller or equal number** of kernel threads These models may be combined (i.e. many-to-many may also have an instance of one-to-one)

Issues with threading

fork() and exec()

- If a thread in a program calls <code>fork()</code>, should the new process duplicate *all* threads or just the *thread it was called from*?
 - Some UNIX systems have two versions of fork() for each of these possibilities
- If a thread invokes exec(), the program to exec() will replace the entire process including all threads

Handling Signals

When dealing with multi-threading, we focus mainly on *where* (*which thread*) to deliver signals. We can choose to:

- Deliver the signal to the thread to which the signal applies
- Deliver the signal to every thread in the process
- Deliver the signal to certain threads in the process
- Assign a specific thread to receive all signals for the process

Cancelling Threads

There are many situations in which we may want to cancel a thread before completion (e.g. a multi-threaded approach to searching a database may want to terminate once the item has been found). There are two scenarios in which we cancel a (*target*) thread:

- Asynchronous one thread immediately terminates the target thread
- Deferred cancellation the target thread periodically checks for a call to terminate, allowing an opportunity for it to do so in a kind and sensible manner.
 Cancelling a thread asynchronously may not always result in all the resources being freed system-wide.


Thread-Local Storage

There may be examples when each thread may need its own copy of certain data (e.g. a transaction processing system may want its own transaction data in a separate thread). We call this data *thread-local storage* (TLS). This is not the same as local variables, as they are visible across multiple function invocations.


Thread Control Blocks (TCBs)

The <u>Process Control Block (PCB)</u> mentioned earlier now needs to be separated so the thread-specific information is stored in a separate TCB, which is pointed to by the PCB.

When using *user threading*, the kernel is unaware of all the TCBs: they just get mapped to the original PCB. User threading is up to 100 times faster than kernel threads.




All the kernel sees is:



Scheduling


Scheduling is the process of *determining which* <u>process</u> *will* **run next** on the processor. We need to decide how to pick one from the ready queue(s). There are many times we may need to decide based on a scheduler:

- Interrupts (device completion, timer interrupts, etc)
- Syscalls (including voluntary process/thread termination, or yield)
- Exception (including involuntary termination)
 A scheduler will decide which process to switch to based on an <u>algorithm (policy)</u> and then a **dispatcher** switches the task.



Process and Thread Behaviour

Execution of processes/threads consist of either *CPU Execution (CPU Burst)* or *I/O Wait (I/O Burst)*. CPU bursts are *application dependent*, mainly because I/O is unpredictable, and due to this we still want to **maximise CPU utilisation** (don't leave it idle) at all times; when one process is waiting for I/O, another can be running on the CPU.



Goals of Scheduling

Performance

We may want to maximise:

- CPU utilisation
- throughput
 - processes completed per time unit
- turnaround
 - time from submission of task to completion of task and minimise:
- waiting time
 - all periods spent just waiting
- response
 - time from submission of task to response produced
- energy
 - "joules per instruction" (e.g. frames per second for video games)

In most cases, we optimise the **overall metric**, but sometimes minimise the worst case.

Fairness

There isn't really a single definition of "fair". Do we say equal CPU consumption, if so over what timescale? Per user, process, thread? What if one process is CPU bound and another I/O bound?

Sometimes our goal is to be **unfair**, where we explicitly favour some particular class of requests. Ultimately, our scheduler must avoid **starvation** - give everyone at least *some* service.

Classes of Schedulers

Batch

Throughput/utilisation oriented. An example would be *Pixar's* "RenderFarm" process

Interactive

Response time oriented. An example would be a window-based operating system.


Real-time

Deadline driven. Examples would be embedded systems in cars, aeroplanes, etc

Types of Scheduling

Non-preemptive


This type of scheduling lets processes and threads execute until completion or as long as they want. The switch is *voluntary*, only letting the scheduler getting involved at exit or on request



Preemptive

When a process/thread is executing, this executing may be paused to allow another process/thread to resume its execution. The switch is *involuntary*; the scheduler may get

involved at any clock interrupt.



Algorithms

There are many different algorithms schedulers can use to determine which process should be allocated CPU time next.

First-come First-served (FCFS)

We assign processes to the CPU in **the order they request it (arrive)**. A form of Non-preemptive scheduling.

Average response time can be poor as short tasks wait behind big ones (*convoy effect*). It may also lead to poor utilisation of **other resources**, like stopping an I/O intensive job from doing a little bit of computation, which makes the I/O subsystem wait.

Shortest Job First (SJF)

We look at the **length of the CPU time** for a process and then schedule it based on *shortest CPU time first*. There are two variations of SJF:

- Non-preemptive once the CPU is given to the process it cannot be taken away until completion
- <u>Preemptive</u> if a new process arrives with CPU time less than the current remaining time of a current executing process, pre-empt
 - This can only ever really be approximated, and isn't always possible

Round-Robin (RR)

Each process is given a specific time interval (*quantum*) to run in. After this time *has elapsed*, the process is pre-empted, added to the end of the ready queue, and the next process is scheduled. If a process **terminates or blocks for I/O** before this time it is added to the wait queue, and the next process is scheduled.

RR is a good solution for fairness and starvation, and is quite responsive, but due to the context switching time it may add up for *long jobs*.

Priority (PRIO)

We always execute the highest-possible runnable jobs to completion, with each queue (priority tier) processed using <u>FCFS</u>. This can lead to *starvation* if higher priority tasks are always running and block a low priority one from doing so, but it can also result in a **deadlock** - when a low priority task has a lock needed by a high priority task.

Multiple Queues (MQ)

A form of Priority (PRIO) but each queue instead processed with a Round-Robin (RR).

Multilevel Feedback Queue (MLFQ)

Same as <u>Multiple Queues (MQ)</u>, but each queue has a *different time quanta* - shortest for highest priority and vice versa.

Processes start at the highest priority, but when it *exceeds* its quanta it is **moved to the lower priority**. Complementarily, when a process *becomes interactive*, it is **moved to the higher priority**.

Memory

Since we've implemented <u>Scheduling</u>, we need to store these processes in memory; as such, the OS needs to manage this memory. Since we may have variables amounts of memory (e.g. RAM), each process has two special registers for this reason:

The base register holds the smallest legal physical memory address.

• The **limit register** specifies the size of the range. If the base register holds value x and the limit holds y, then the program can access addresses x through to x + y inclusive.

Logical Address Spaces vs. Physical Address Spaces

Each process is given a *Logical Address Space* to basically abstract out the memory space. These always start at 0, for programming ease. The mapping of these logical address to the *actual real physical addresses in physical memory* is done by a separate **Memory-management unit** (MMU); the user program never accesses the real physical addresses.


Dynamic Loading and Dynamically Linked Libraries (DLLs)

To better utilise memory, routines in the program are not loaded into memory *until they are called*. This operation is not handled by the OS and is instead left up to the user programs to handle this themselves.

DLLs delay this even further, leaving even the linking until the routine is invoked.

Contiguous Memory Allocation

This is where each process is brought into (physical) memory that is contiguous (next to) the previous process. This bring a risk of processes accessing memory that it does not own, even if this is partially solved with <u>logical address spaces</u>. Here, the **MMU** is extended to check the **limit register** and trap any bad memory access calls:



One method of contiguous memory allocation is using a *variable partition scheme*. Initially, all memory is available for user processes, considered one large partition, and as it is filled, we see various sized "holes" available. This procedure is an example of a *dynamic storage allocation problem* - how best to satisfy a request of size n from a list of free holes. Commonly used are:


- First-fit: Allocate the first hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough
 - We must search the entire list, unless ordered by size
 - Produces the smallest leftover hole
- Worst-fit: Allocate the largest hole
 - We must search the entire list, unless ordered by size
 - Produces the largest leftover hole

First-fit and **Best-fit** are better than **Worst-fit** in terms of speed and storage utilisation. However, **first-fit** and **best-fit** also suffer from *external fragmentation* - when the free memory space is broken into lots of little pieces. This has knock-on effects to performance.

Paging

An alternative to <u>Contiguous Memory Allocation</u>, *paging* splits the physical memory into fixed-sized blocks (*frames*) and breaks logical memory into same-sized *pages*. Each logical address generated by a CPU and consists of a *page number* p and *page offset* d.

Each process has it's own *page table* of which p indexes. The table contains the base address of each frame in physical memory, so to get the specific physical address we go to address p + d (since d describes the offset from the start).




The size of a page is a power of 2, which makes translating a logical address into a page number easy; if the size of the logical address space is 2^m and a page size is 2^n bits, the high order m-n bits designate the page number and the n low order bits designate the page offset.

The OS keeps a *frame table* indicating whether each frame is free or allocated (and if allocated, to which page of which process(es))

Translation Look-aside Buffer (TLB)

A special piece of hardware cache, the TLB helps us find the actual physical memory. Each TLB entry contains a key(tag) and a value. The TLB essentially acts as a cache for commonly accessed pages.



To protect against bad memory access, the page table also contains a *valid-invalid* bit which indicates whether that page number has an actually useful frame number attached to it.

Benefits of Paging

Shared Pages

Using pages allows us to share common code, such as <u>libraries</u>. We map the (relevant bits of the) address spaces of two processes to this common page in memory.

Read-only code pages


Since pages can be defined as read-only, we can set this parameter on the pages containing code. The OS will not allow anything to overwrite these pages.

Page Table Structures

As modern computer systems support large logical address spaces, the page table grows in size. Recall each program has its own page table: on a 32-bit logical address space machine, each <u>process(!)</u> will need 4MB of physical address space **just for the page table!**

Hierarchical paging

To solve this, we can use a two-level page algorithm in which the page table is also paged. This is done by splitting the *page number* p into two (p_1 and p_2). p_1 serves as an index to the outer page table and p_2 acts a displacement in *that page table* to refer to the *eventual page number* and also the *frame*.




Hashed Page Tables

We store a linked list of hashes for page numbers, known as *virtual page numbers*. We can then check this hash table when given a virtual page number, and if no match, go to the next element. This is still better than a regular implementation, as only page numbers that are actually in use are stored (since we won't be checking anything not in the list).

Inverted Page Tables

With an Inverted Page Table, we only store one page table in the system, where each entry has the address of the page stored in that real memory location, with information about the

process that controls it.



Swapping


We can take processes not in use out of memory through swapping. These are put into a *backing store*. We can also swap <u>Pages</u> in and out of memory too.

Virtual Memory

Eager revisers may have noticed that when using <u>Logical Address Spaces vs. Physical Address Spaces</u>, we are free to assign logical addresses as large as we want them (for example, when using <u>Memory Mapped IO.png</u>). A problem now arises: what to do if a process needs more memory than is **physically** available?

Virtual Memory solves this; the *full address space* is **on disk** (*backing store* in the diagram), and the *main memory* (e.g. RAM) is used **as a cache**.

 This is not the same as CPU cache! That's something much closer, hardwired onto the CPU, and much smaller.



The process of moving pages into memory is known as *demand paging*, as pages are only moved into physical memory when they are *demanded* by the process's execution.

Page Fault

If a process tries attempts to access a page *that is not in main memory* a **page fault** is triggered, which is a trap the OS can act upon. This can occur as the OS has many <u>Page</u> <u>Replacement</u> algorithms, and may indeed have failed to bring the page in memory for this process when it was *demanded*. This trap is detected by the <u>valid-invalid</u> bit in the <u>page</u> <u>table</u>, which states whether a page is actually in physical memory.

Usually, when the OS detects this, it first checks to make sure that the page requested is **valid** - if not, the process is terminated. If it was indeed a valid demand, the OS then finds a free frame (many OSes maintain a *free-frame list*) and <u>swaps</u> the page into that frame, informs the rest of the system by updating the page table, and restarts the instruction that caused the page fault in the first place.

Pure demand paging is the process of relying on this swapping to bring all pages needed for any process into memory. However, this immediately falls apart when a free frame is not found for a valid demand. Additionally, if we have a probability of a page fault p and memory-access time ma, then our effective access time for a program using pure demand paging is

effective access time =
$$(1 - p) \times ma + p \times page$$
 fault time

Basically, page faulting is slower than just reading the page from memory to begin with!

Page Replacement

We will eventually run into a problem where there are no frames left to allocate, and so we will have to swap a page out of main memory and into the backing store. All page replacement algorithms aim to find a page that is not being used and free it, swapping in our desired page.


FIFO Page Replacement

We main a linked list of pages in the order they come into memory. When we need to perform a page replacement, we simply check the list for the *oldest* page, and swap that out, pushing our newly swapped-in page to the end (newest) of the list.

There are as many scenarios when performing this behaviour is good vs. when it is bad. For example, the page may have been used for a system initialisation function, and is no longer needed. But the page may have also been used for a commonly used library *still in use* (if this happens, it would be very quickly page-replaced back into main memory, making the whole operation wasteful).

Belady's Anomaly

We'd assume adding more frames for pages to reside in would reduce the amount of page faults, but *Belady's Anomaly* shows this isn't necessarily always the case.



Optimal Page Replacement

The idea of this algorithm is to *replace the page that will not be used* for the longest period of time. Such an algorithm does not exist, and therefore this is used retrospectively to *benchmark* other (actually implemented) page replacement algorithms.

Least Recently Used (LRU) Page Replacement

Sort of approximating the "page that will not be used" part of the Optimal Page Replacement algorithm, LRU swaps out the page that has not been accessed for the longest period of time.

Accurately recording this takes **substantial hardware assistance** and can add unwanted overhead, so we approximate LRU by

- keeping page table entry bits (maintained in hardware)
- keeping a history/counter for each page (maintained in software)

Second Chance Page Replacement

A <u>FIFO Page Replacement</u> variant that avoids the problem mentioned of *early added* but *commonly referenced* pages being swapped out by simply adding the concept of **references** (usage). We now check the reference bit (and a modify bit* in some implementations) before performing a FIFO operation. When checking the first page in the linked list:

- If the bit has not been referenced it will be removed as usual
- If the bit *has been referenced, it is set to unreferenced (θ) and placed at the end (newest) if the FIFO list

This basically gives the first page a second chance*, so if it was a one-off lucky reference, it will be swapped out the second time. However, if it genuinely gets used all the time, this avoids the overhead of swapping to backing store and then almost immediately swapping it back into the end of the list and into main memory

Enhanced Second Choice

An enhancement of <u>Second Chance Page Replacement</u> that utilises the *modify* bit, and checks the 4 possible permutations of these bits:

Reference	Modify	What to do	
0	0	Best page to replace	
0	1	We'll need to write this page out before replacement - not as good to replace, but decent	
1	0	Probably going to be used soon	
1	1	Will likely be used again soon, and will need writing before eventual replacement	

Counting-Based Page Replacement

We can keep a counter of *how many references have been made to each page*. There are two opposing arguments for how we should handle page replacement based on this count:

• Least Frequently Used (LFU) - the page with the smallest number of references should be removed, because the more actively used pages have more references.

- This does require the counts to be decreased at regular intervals to stop pages waltzing in with a ton of references intitially and then just not doing anything again
- **Most Frequently Used (MFU)** the page with the most references should be removed, because the one with the smallest count is probably just brought in and yet to be used (promise it will be used bro i swear down)

Thrashing

If we have a period of high paging - where a process is spending more time paging than actually executing code - this causes severe performance problems and is called *Thrashing*.

Cause of thrashing

Thrashing is caused by knock-on effects of *frame allocation*. The OS must decide how to allocate the finite number of frames that each process can page to/from. Many of these algorithms incur constant paging, especially with <u>Multi-programming</u>.

Working Set

We can define a working set of pages to be in memory at all times, lest we suffer <u>Thrashing</u>. The working set w(k,t) is defined as

$$w(k,t) = \text{pages referenced in the time interval}(t-k,t)$$

where:

- t is time
- k is the working set window (which can be tuned to control the behaviour of our virtual memory).
 - k is measured in page references

Working Set uses a *local frame replacement algorithm* to ensure the working set for a process only focuses on that process's frames. We then track the working set size and can re-allocate frames among processes dynamically.

This does not solve page faults entirely; in fact we must establish an "acceptable" **page fault** frequency (PFF) to determine our frame allocation rates.

Kernel Memory Allocation

Kernel memory is often allocated from a separate pool from the regular user programs. There are two common strategies for allocating kernel memory.


Buddy System

The kernel requests xKB of memory, and the OS then finds the smallest power of two in which it fits. It then takes a memory segment and splits it into two buddies, and then splits

those until we get to that smallest power, in which that section of memory is given to the kernel.

Slab Allocation

Slab allocation is a form of the original <u>Contiguous Memory Allocation</u> but heavily relies on *caches*.




Secondary Storage

Secondary storage is for anything the computer doesn't immediately need to access. For example, consider starting a *Super Mario* game; in **main memory** we'd need Mario, the current level, and maybe a track of the scores. We wouldn't need Bowser, the fire levels, any fancy mushrooms yet but we will later - these are stored in *Secondary Storage* and will be moved to *main memory* when needed. Secondary storage is also what the *backing store* that Memory/Virtual Memory commonly use to store out of main-mem pages. It is slower to access than main memory (because it is an I/O device and carries the major overhead those devices do), but it can store **lots** more data than main memory could ever dream of. There are two main types of secondary storage (*covered in this course*):

- Hard Disk Drives (HDDs)
- NonVolatile Memory (NVM) devices

Secondary storage devices are connected via a bus, the most common of which being the *Serial Advanced Technology Attachment* (SATA). SATA was traditionally designed for HDDs, but with the wide adoption of NVM drives the *NVM express* (NVMe) interface was created.

Hard Disk Drives (HDDs)



HDDs have several disk *platters* that store the data.

To read/write on the disk, we have a *head* that "flies" above the surface of each platter and accesses data - split into segmented *sectors* on each ring (*track*).

The "speed" of a HDD depends on many aspects (though these are often bundled together into one overall speed, **bandwidth**).

- The platters have a set rotations per minute (RPM)
- The transfer rate is the speed at which data can flow between the drive and the computer
- The random-access time consists of the time necessary to move the arm to the desired cylinder (seek time) and the time necessary for the sector to rotate to the arm's head (rotational latency)

If the head damages the magnetic surface (a **disk crash**), this is usually not replacable (unless using RAID).

HDD Scheduling


When the computer makes a request to a device, this request is placed into a *queue*. The computer can then re-order this queue to reduce the **random-access time**.

FCFS Scheduling

First-come-First-served scheduling simply takes this queue of requests and executes them in that order.

A problem with this approach is needless seeking due to blindly taking orders from the queue. Consider we need to service blocks:


We could dramatically reduce seek time if we went from $122 \to 124$ instead of going to 14 before then.



SSTF Scheduling


Shortest-Seek-Time-First will go to the closest item in the queue to the current seek location. It minimises arm movement (**seek time**) but unfairly favours clustered/middle

blocks, leaving the far-out blocks unserviced for a while.




SCAN Scheduling

Also known as the *elevator algorithm*, **SCAN** starts at *one end of the disk* and moves towards the other end, servicing requests *along the way*. Only where there are no requests in that direction does the *head direction change* and it services requests the other way.



C-SCAN

Providing a *more uniform wait time* than <u>SCAN Scheduling</u>, C-SCAN has one major difference: once it reaches an "end", it *immediately zips back to the other end without servicing any requests along the way*. Because of this, C-SCAN is also known as the *typewriter algorithm*.



Uniform wait times


NonVolatile Memory (NVM) devices

NVMs differ from HDDs in that they store data electronically, not mechanically. They are faster then HDDs due to the lack of **seek time** and **rotational latency** leaves electron path time as the only factor in **random-access time**.

NAND Flash Controller Algorithms

NVMs typically consist of many NAND semiconductors. These conductors have a special quirk that causes issues with our previous Paging techniques: they cannot be *overwritten in a page increment* as the entire NAND *cell must be erased first. These cell blocks* are several pages in size.

The device controller will maintain a *flash translation layer* (FTL) which maps the pages to the NAND blocks.



NVM Scheduling

Due to the lack of moving parts, NVM devices commonly use a simple <u>FCFS Scheduling</u> policy.

Error Detection and Correction

As bits on devices (especially physical devices such as <u>HDDs</u>) can get changed, we need to be able to check for errors.

Parity bits are a form of *checksums* and use modular arithmetic to compare values for fixed-length word. If a bit gets damaged, the checksum won't come out the same and the computer knows an error has occured.

Error-correction codes (ECCs) detect this problem but also correct it. This requires a bit of extra data to store (in practise, this is taken from the message, and so the message gets *less data*), but is very effective (<u>Hamming Codes</u> are one of my favourite examples of this; this isn't part of the course I just think this website is really cool).

Storage Device Management

Formatting

We can't just start writing data on a completely blank slate (which new storage devices come through). For example, NonVolatile Memory (NVM) devices need the FTL to be created. The process of prepping this data for the device controller to work is known as *low-level formatting*, or *physical formatting*.

Partition

The process of splitting the device into one or more groups of blocks/pages. The OS can treat each of these partitions like it's own device. The initial program to run a computer - the bootstrap loader - is often held in it's own **boot partition**.

RAID


Since storage devices are smaller and cheaper, we can connect multiple of them to a computer at once. This can improve reliability (*redundant data stored on multiple drives in case one of them dies*) and also read/write speed (*due to accessing multiple drives in parallel*). Organising drives in such a way is called *redundant arrays of independent disks (RAID)*

• The "i" used to stand for "inexpensive"

RAID Levels

There are different ways to organise RAID - known as *levels* - that have different cost-performance trade-offs. For example, *striping* data is splitting the bits of each byte across multiple drives. This improves data transfer rates (only "one" I/O request made up from 8

different drives).



Filesystem

Files provide the *actual mechanism* of storing data in <u>Secondary Storage</u> on a computer. The OS presents this through a *filesystem* interface.

File

A file is the smallest allotment of *logical* secondary storage. They store different kinds of information e.g.

- · Text file stores text
- Source file stores functions written in a specific language
- Executable files store series of code sections a loader can bring into memory and execute

Files have many different attributes

- Name
- Identifier
 - used by the OS to identify the file in the filesystem. Not human readable, that's the
 Name's job
- Type
- Location
 - Points to a device and the location on that device
- Size
- Protection
 - who can do read/write/exec
- Timestamps, user identification
 - not strictly necessary for core OS, but nice to have for usage and security monitoring purposes

Access Methods

The file's type (and other information) can have implications on the *structure of the data* inside the file, which can optimise how the OS accesses them.

The simplest access method is *sequential access*; read the information in the file in order, one record after the other. This is the most common access method.

Direct Access is the process of splitting the file's records into larger (fixed size) groups of *logical records*, and then accessing data by choosing one of these records. This works better with different file types than others.

Directory

Directories are treated as files too, but can be viewed as a symbol table that translates file names into their file control blocks (these are inodes in Linux from CW3 if any of you remember those). Directories can be **single level** (*only contain files*) or **two level** (*contain files and directories*).

Memory-Mapped files

Using similar techniques to that of <u>Virtual Memory</u>, we can treat this secondary storage file I/O as memory access. This maps a disk block to a page/pages in memory. When the file is

initially accessed, a <u>Page Fault</u> occurs, which will be about as slow (if not a tad slower) than regular file I/O. *However*, subsequent file reads will be accessed using the same page reading mechanisms leading to *major speed improvements*.

However, writing to these files in memory is **not** the same as writing to the secondary storage; at some point actual I/O will have to occur. This point usually occurs once the file is *closed*.

File system structure

The "**block I/O subsystem**" is the most *basic file system* and just issues generic commands to the device drivers to read/write **blocks** on the storage device.

There are modules that then build up from this in *layers*, all the way up to applications that use them.

How <u>directories</u> are actually implemented

Linear list

The simplest method to implement a directory "file" is to produce a linear list of file identifiers, with pointers to the actual data blocks. This is easy to implement but being a binary search is costly to execute, especially on huge directories.


Hash Table

We can hash the file identifiers to point us to the file in a <u>Linear list</u>, which reduces the seek time from our previous binary search. However, choosing a hash size is problematic - if fixed too small, directories have a fixed limit on files. If we dynamically increase this hash size as more files get added to the directory, we will need to periodically update *all* the hash values for *every* file.

Allocating disk space

The file system also determines how we allocate. We basically have two choices - allocate **contigiously** or in a **linked** manner

Contiguous allocation of files



directory				
file	start	length		
count	0	2		
tr	14	3		
mail	19	6		
list	28	4		
f	6	2		

This presents the same dynamic storage allocation problems covered in when we did Contiguous Memory Allocation when dealing with regular Memory.

Linked allocation of files





Figure 14.5 Linked allocation of disk space.

Much easier to allocate, but we also have to consider the space included by adding all these pointers. Also harder to optimise reading patterns, and could lead to fragmentation.

Indexed Allocation of files




Somewhat solves the pointer and fragmenting issue, since we just have to look at the index block. The size of this block then becomes the issue.

Deleting files

When a file is "deleted", the data isn't immediately wiped, but it's blocks are added to a **free space list**. This is implemented frequently as a *bitmap/bit vector*: if blocks 2, 3, 4, 5, 8, 9, 10, 11, 12, 13, 17, 18, 25, 26, and 27 are free and the rest of the blocks are allocated. The free-space bitmap would be

0011110011111110001100000011100000...

A *linked list* can then be made of these positions, and used to write to (if performing a <u>Linked allocation of files</u>)



Recovering files

Filesystems often have **consistency checkers** that compare data stored in *metadata* or the *directory structure*. However, if a directory entry is lost, this can often be disastrous (*the book does not further elaborate on this and such neither will I*).

Synchronisation

As <u>Processes</u> can execute in parallel during <u>Multi-programming</u>, we need methods to *synchronise* the execution of code ideally.

Race Conditions

A race condition is a situation where several processes can manipulate and access the same data concurrently such that the outcome of that data critically depends on the order

the process access takes place in. This is problematic as process schedulers are difficult to reproduce the same results due to the amount of background processes.

Critical Section

A bit of a code that can cause <u>Race Conditions</u> is known as the *critical section*. These need to be synchronised so they occur in an orderly manner.

Preemptive kernel solution

Kernels can *preempt* a process when running in kernel mode. *Non-preemptive kernels* will block other processes from controlling the CPU, effectively freeing itself from race conditions entirely. However, *preemptive kernels* are far more responsive - and if kernel code is written properly to avoid race conditions, then there is no need for the trade-offs of *non-preemptive*!

Hardware support

 We can flag certain instructions typical of a <u>Critical Section</u> as memory barriers and then check execution against a flag, to see if that bit of memory is being accessed

Mutex Locks

Mutual **Ex**clusion locks are used to lock certain memory regions so a process cannot access it if a lock is currently active. Processes must remember to *unlock* the region.

Spinlocks are a form of *mutex* lock. If a process/thread tries to access a locked piece of memory, it will "spin" the core (do nothing processor cycles) until the lock is free, acting on it's critical section once unlocked.

Semaphores

Semaphores take the form of an integer variable S that is accessed only through two atomic operations: wait() and signal:

```
signal(S) {
     S++;
}
```

OSes can distinguish between *binary semaphores* (where S can only be 0 or 1) and *counting semaphores* (which can be a number over any domain)

How to synchronise with semaphores

Say we have a two concurrently running processes P_1 and P_2 , each with their own statement S_1 and S_2 respectfully. We want S_2 to only execute after S_1 has finished execution, adding as little to the process code as possible.

In P_1 , we can put

```
S_1;
signal(synch)
```

and in P_2 we can put

```
wait(synch);
S_2;
```

The value of synch (S) is initialised to 0. Even if P_2 gets ahead first, it will still be stuck on the busy wait of the wait() function, only exiting once S_1 has finished execution.

In practise, instead of just burning cycles, if a process has to wait it will often just suspend itself. The OS adds it to a queue associated with that semaphore, and once it should stop waiting the scheduler adds it to the regular ready queue.

Deadlocks

Deadlocks can occur when two processes are waiting indefinitely for an event which *can* only be caused by another waiting process. Formally, a set of is in a deadlocked state when every process in the set is waiting for an event that can be caused only by another process in the set.

A practical example of this occurring in an OS is when a process of high priority needs to access kernel data being accessed by a low priority process, which depends on the high priority process too. Kernel data is lock protected, which causes a deadlock.

This is typically solved with a *priority-inheritance protocol*; all processes accessing resources needed by a higher priority protocol *inherit* this priority *until they are finished with the resources*.

Safety Algorithm

We can prove if a system is in a safe state by using the following algorithm:

- 1. Let Work and Finish be vectors of length m and n respectively. Initialise Work = Available and Finish[i] = false for i = 0, 1, ..., n 1.
- 2. Find an index i such that
 - Finish[i] == false
 - Need_i \leq Work
 - (If no such i exists goto 6)
- 3. Work = Work + Allocation
- 4. Finish[i] = true
- 5. Goto 2
- 6. If Finish[i] == true for all i, the system is in a **safe** state.

Conditions for a Deadlock

A deadlock situation can arise if the following four conditions *simultaneously hold* in a system. Conversely, a system is **safe** (from deadlocks) if these are not all held.

Mutual Exclusion

 At least one resource must be held in a non-shareable mode (only one thread at a time can use the resource). If a thread requests the resource it must wait until it is released.

Hold and Wait

 A thread must be holding at least one resource and waiting to acquire additional resources currently held by other threads.

No preemption

 A resource can only be released voluntarily by the thread holding it (after that thread has completed its task)

Circular wait

• A set $\{T_0, T_1, \ldots, T_n\}$ of waiting threads must exist so T_0 is waiting on T_1 , T_1 waiting on T_2 , ..., and finally T_n is waiting on T_0

Virtual Machines

Virtualisation is the process of making a *virtual* version of a *physical* object. A *virtual machine* is a *virtualised* computer running inside of a physical computer.

The fundamental idea of virtual machines is abstracting the hardware of a single computer (CPU, <u>Memory</u>, <u>Secondary Storage</u>, <u>Devices</u>, etc) into different execution environments such that each environment runs on it's own private computer.

At the base of a *VM* is the **host** - the underlying hardware system that runs virtual machines. The **virtual machine manger** (VMM) (sometimes called a *hypervisor*) creates/runs VMs by providing an interface that is identical to the host. There are multiple types of virtual machines:

- **Type 0 hypervisors** hardware solutions that provide support for VM creation via *firmware*. Typically found in big servers.
- **Type 1 hypervisors** OS-like software build to provide virtualisation. This is software built into the OS itself.
- **Type 2 hypervisors** *Applications* that run on the OS but provide VMM support to "guest" OSes (e.g. *VirtualBox*).
- An aside of this is application containment; it is not virtualisation but provides similar features by segregating applications from the OS.

Benefits and Features

- VMs are protected from the host and each other. If a virus damages a guest OS, all other guest OSes and the host OS itself are safe.
 - This does make sharing resources between VMs a bit difficult, although using a network connection and allowing a LAN/Wireless connection to handle this would work.
- As VMs are simulated, they can be frozen or suspended. Many VMMs go a step further
 and allow copies and snapshots of a VM to be made, since all required OS variables
 can be read and written to a file.
- Since VMs are software, the load can be distributed on servers far beyond what physical hardware could manage.

Building a VM


VCPU

A *virtual CPU* inside a VM does not execute code; it represents the state of the CPU as the guest OS believes it to be. A VMM maintains multiple VCPUs at once. When the guest is <u>context switched</u> onto the *real* CPU, this information is used to load the right context much like a <u>Process Control Block (PCB)</u>.

VMs executing privileged instructions

When a guest OS kernel attempts to execute a privileged instruction, this causes a *trap* in the VMM. The VMM then "*emulates*" the action that was attempted by the guest OS on the

real kernel. This process is known as trap and emulate.




Another approach is *binary translation*. This is used when *trap-and-emulate* is infeasible - for example, in CPUs without a clear separation of <u>privileged</u> and <u>nonprivileged</u> instructions. *Special instructions* are instructions which *act differently* (**by ignoring certain flags**) *when in user mode vs kernel mode*, which means the *trap* in *trap and emulate* won't ever trigger.

Binary translation follows a simple procedure:

- 1. If the *guest VCPU* is in *user mode* the guest can run its instructions natively on the *physical CPU*.
- 2. If the *guest VCPU* is in *kernel mode*, the guest believes it is running in kernel mode. Now, the VMM examines every instruction and reads ahead for the next few instructions the guest will execute (based on the guest's program counter). If we spot any special instructions, we translate them into *new instruction that would perform the equivalent task* (such as changing flags in the VCPU).

These translated instructions are *cached* to improve performance.



Nested <u>Page Tables</u>

VMMs need to monitor all page tables for guests **and** *its own* **page table**. A common method of performing this is using a *Nested Page Table* (NPT). When the CPU is executing a guest OS's instruction, the VMM points to the correct location in this NPT so the correct

memory addresses can be accessed.

