Interprocess Communication (IPC) Computer Operating Systems BLG 312E 2014-2015 Spring

• between concurrent processes - resource sharing - communication - synchronization

Levels of Interaction

- interaction between processes on three levels
 - processes not aware of each other (competing): using system resources (moderated by operating system)
 - processes indirectly aware of each other (sharing): resource sharing through mutual exclusion and synchronization
 - processes directly aware of each other (communicating)


Resource Sharing

- · mutual exclusion
 - two types of resources
 - can be used by more than one process at a time (e.g. reading from a file)
 - · can be used by only one process at a time
 - due to physical constraints (e.g. some I/O units)
 - if the actions of one process interferes with those of another (e.g. writing to a shared memory location)
- synchronization
 - a process needs to proceed after another process completes some actions

```
Example

2 processes: Observer and Reporter
counter shared variable

observer: reporter:
while TRUE { while TRUE {
   observe; print_counter;
   counter ++; counter=0;
}
```



Example – Possible Errors counter++ LOAD ACC, COUNTER INC ACC SAVE COUNTER, ACC Race: • when processes access a shared variable • outcome depends on order and running speed of processes

· may be different for different runs

P1: k=0 (intial value) while TRUE k=k+1; what about the values of k depending on the order of P1 and P2 executions? P2: while TRUE k=k+1; SOLUTION: mutual exclusion

• two types of sharing: - READ (no need for mutual exclusion) - WRITE (mutual exclusion needed) • for consistency - mutual exclusion - synchronization

Synchronization programs should not be dependent on running order of processes programs working together may need to be synchronized at some points e.g. a program uses output calculated by another program

```
Mutual Exclusion

critical section (CS): Part of code in a process in which operations on shared resources are performed.

mutual exclusion: only one process can execute a CS for a resource at a time
```

```
P1: P2:

while TRUE {
    <non-CS>
    mx_begin
    <CS ops>
    mx_end
    <non-CS>
    )
}


Example

while TRUE {
    <non-CS>
    mx_begin
     <CS ops>
    mx_end
    <non-CS>
}
```

Mutual Exclusion - Possible Problems

- · deadlock
 - more than one process requires the same resources
 - each process does not release the resource required by the other

Example: 3 processes and 3 resources



<u>P1()</u> <u>P2()</u> <u>P3()</u> req(R1); req(R2); req(R3); req(R2); req(R3); req(R1);

Mutual Exclusion

- mx_begin
 - is there a process in its CS which has not yet executed mx end?
 - if NOT
 - · allow process to proceed into CS
 - · leave mark for other processes
- mx end
 - allow any process waiting to go into its CS to proceed
 - if there aren't any, then leave mark (empty)

Mutual Exclusion Implementation

- · only one process may be in its CS
- if a process wants to enter its CS and if there are no others executing their CS, it shouldn't wait
- any process not executing its CS should not prevent another process from entering its own CS
- no assumptions should be made about the order and speed of execution of processes
- · no process should stay in its CS indefinitely
- · no process should wait to enter its own CS indefinitely

Mutual Exclusion Solutions

- · software based solutions
- · hardware based solutions
- · software and hardware based solutions

A Software Based Solution

 use a shared flag that shows whether a process is in its CS or not: busy

 $\begin{aligned} \text{busy} \leftarrow \text{TRUE}: \text{process in CS} \\ \text{busy} \leftarrow \text{FALSE}: \text{no process in CS} \end{aligned}$

• mx_begin: while (busy); busy = TRUE;

- wait until process in CS is finished
- enter CS
- mx end: busy = FALSE;

A Software Based Solution

- · a possible error
 - busy is also a shared variable!
 - Example:
 - P1 checks and finds busy=FALSE
 - P1 interrupted
 - P2 checks and finds busy=FALSE
 - both P1 and P2 enter CS

Solutions Requiring Busy Waiting

Solutions Requiring Busy Waiting

- use up CPU time
- works properly but has limitations:
 - · processes enter their CS in turn
 - · depends on speed of process execution
 - · depends on number of processes

Solutions Requiring Busy Waiting

- first correct solution: Dekker algorithm
- Peterson algorithm (1981)
 - similar approach
 - simpler

Peterson Algorithm

· shared variables:

req_1, req_2: bool and initialized to FALSE turn: integer and initialized to "P1" or "P2"

Peterson Algorithm

- · different scenarios:
 - P1 is active, P2 is passive
 req_1=TRUE and turn=P2
 req_2=FALSE so P1 proceeds after while loop
 - P1 in CS, P2 wants to enter CS
 req_2=TRUE and turn=P1;
 req_1=TRUE so P2 waits in while loop
 P2 continues after P1 executes max_end

Peterson Algorithm

- (different scenarios cntd.):
 - P1 and P2 want to enter CS at the same time

P1: P2:
req_1=TRUE; req_2=TRUE;
turn=P2; turn=P1;

 \Rightarrow order depends on which process assigns value to the turn variable first.

Hardware Based Solutions

- with uninterruptable machine code instructions completed in one machine cycle
 - e.g.: test and set
 - busy waiting used
 - when a process exits CS, no mechanism to determine which other process enters next
 - · indefinite waiting possible
- · disabling interrupts
 - interferes with scheduling algorithm of operating system

Hardware Based Solutions

```
test_and_set(a): cc \leftarrow a
                                  \texttt{a} \; \leftarrow \; \texttt{TRUE}
```

• with one machine instruction, contents of "a" copied into condition code register and "a" is assigned TRUE

```
mx begin: test and set(busy);
           while (cc) {
             test_and_set(busy);
                                  busy: shared variable
mx end:
           busy=FALSE;
                                  cc: local condition code
```

Semaphores

- hardware and software based solution
- · no busy waiting
- does not waste CPU time
- semaphore is a special variable
 - only access through using two special operations
 - special operations cannot be interrupted
 - operating system carries out special operations

Semaphores

- s: semaphore variable
- · special operations:
 - P (wait): when entering CS: mutex_begin
 - V (signal): when leaving CS: mutex end

```
P(s):
                V(s):
if (s > 0)
               if (anyone waiting on s)
 s=s-1;
                  activate_next_in_line;
                else
else
                   s=s+1;
 wait on s;
```

Semaphores

- take on integer values (>=0)
- · created through a special system call
- · assigned an initial value
- binary semaphore:
 - can be 0/1
 - used for CS
- · counting semaphore:
 - can be integers >=0

Example: Observer - Reporter

```
global shared variables:
  counter: integer;
  sem: semaphore;
process P1:
                         process P2:
  observe;
                            P(sem);
  P(sem);
    counter++;
                              print(counter);
  V(sem);
                               counter=0;
                            V(sem);
main_program:
    sem=1; counter=0;
  activate(P1);
  activate(P2);
```

sample run: P1: P(sem) ... sem=0; P2: P(sem) ... sem=0 so P2 is suspended P1: V(sem) ... P2 is waiting for sem; activate P2 P2: V(sem) ... no one waiting; sem=1

Synchronization with Semaphores

- a process may require an event to proceed process is suspended
 - e.g. process waiting for input
- another process detecting the occurence of event wakes up suspended process
- \Rightarrow "suspend wake-up" synchronization

Semaphores

Initial value for semaphore:
• =1 for mutual exclusion

• =0 for synchronization

```
Semaphores
· possible deadlock scenario:
x, y: semaphore;
x=1; y=1;
process 1:
                  process 2:
                                         Pay
                                      attention to
                  P(y);
  P(x);
                                      the order of P and V!
                  P(x);
  P(y);
                  V(y);
  V(x);
                  V(x);
  V(y);
```