
Chart Documentation

1. Chart Types

1.1 Bar Chart



a) Creating new instance of the bar chart

new BarChart(container, nameOfTheHtmlElement, dataModelForTheChart);

• container – the parent java container where the object should be embedded

- nameOfTheHtmlElement name of the html element (div) which will display
 the chart. If you want to embed this chart in special template you will have to
 call in the vtl template \$control.get(nameOfTheHtmlElement) to display the
 chart in your new template. If you don't need to create special template,
 enough will be to create the instance in the java class like presented above.
- dataModelForTheChart data model containing information which will be presented in the chart. In case of BarChart we need to use
 ValueListChartModel, which contains the list of labels (presented on X) and list of ValueListChartDataset which contains the list of datasets. Each of the dataset contains the list of of values (should be in the same size as the list of labels, and gui settings in what way the BarChart should present delivered data (color, size, background, font) other settings for the chart can be found under barChart.getConfiguration() method and can be overwritten every time.

b) Assigning data to the bar chart

Data assignment can be done in two different ways.

- Assigning, updating an removing using methods delivered in ChartModel
 - 1) **addDataToModel** adding defined element in given dataset number under given label
 - 2) **changeDataByModel** change the value of the element defined by dataset which it is located in and given label
 - 3) **removeDataFromModel** removes element from the dataset number defined and label given in the method
- ➤ Changing the whole model using the method **setModel** accessible in the chart instance.

Both ways don't require refreshing the view as it is already done in the implementation.

c) Defining available events for bar chart

At the time there is only one type of event accessible – **actionClick**. In order to add your own implementation for the event it is required to create a class implementing **SelectionListener** and add to the chart using method **chart. addElementSelectedListener**. You can register as many listeners as you want.

d) Bar Chart Configuration


- ➤ **barValueSpacing** Whether the scale should start at zero, or // an order of magnitude down from the lowest value value in pixels
- **barDatasetSpacing** = Spacing between each of the X value sets. Value in pixels

The BarChart provides default configuration which could be changed by

- using the method chart.getConfiguration().set...
- providing new instance of BarChartConfiguration

Additional settings provided in the **BarChartConfiguration** come from the common configuration and are accessible and common for all chart types

1.2 Circle Chart



a) Creating new instance of the circle chart

new CircleChart(container, nameOfTheHtmlElement, dataModelForTheChart);

- **container** the parent java container where the object should be embedded
- nameOfTheHtmlElement name of the html element (div) which will display the chart. If you want to embed this chart in special template you will have to call in the vtl template \$control.get(nameOfTheHtmlElement) to display the chart in your new template. If you don't need to create special template, enough will be to create the instance in the java class like presented above.
- dataModelForTheChart data model containing information which will be presented in the chart. In case of CircleChart we need to use
 SimpleValueChartModel only a list of SimpleValueChartDataset which

contains definition for each value with the label presented in the chart. Behind defining the label and value user needs also to define the color of the segment and the highlight color of the segment for each dataset defined. The difference between **SimpleValueChartDataset** and **ValueListChartDataset** is that each dataset contains only one value and only one value can be assigned to one label.

b) Assigning data to the circle chart

Data assignment can be done in two different ways.

- Assigning, updating an removing using methods delivered in SimpleValueChartModel
 - addDataToModel adding given value with color for the displaying under given new label
 - 2) **changeDataByModel** change the value of the element in given dataset
 - 3) removeDataFromModel removes dataset defined by given label
- Changing the whole model using the method **setModel** accessible in the chart instance.

Both ways don't require refreshing the view as it is already done in the implementation.

c) Defining available events for circle chart

At the time there is only one type of event accessible – **actionClick**. In order to add your own implementation for the event it is required to create a class implementing **SelectionListener** and add to the chart using method **chart. addElementSelectedListener**. You can register as many listeners as you want.

d) Circle Chart Configuration


percentageInnerCutout- Number - The percentage of the chart that we cut out of the

The BarChart provides default configuration which could be changed by

- Using the method chart.getConfiguration().set...
- providing new instance of CircleChartConfiguration

Additional settings provided in the **BarChartConfiguration** come from the common configuration and are accessible and common for all chart types

1.3 Line Chart



a) Creating new instance of the line chart

new LineChart(container, nameOfTheHtmlElement, dataModelForTheChart);

container – the parent java container where the object should be embedded

- nameOfTheHtmlElement name of the html element (div) which will display
 the chart. If you want to embed this chart in special template you will have to
 call in the vtl template \$control.get(nameOfTheHtmlElement) to display the
 chart in your new template. If you don't need to create special template,
 enough will be to create the instance in the java class like presented above.
- dataModelForTheChart data model containing information which will be presented in the chart. In case of LineChart we need to use ValueListChartModel, which contains the list of labels (presented on X) and list of ValueListChartDataset which contains the list of datasets. Each of the dataset contains the list of of values (should be in the same size as the list of labels, and gui settings in what way the LineChart should present delivered data (color, size, background, font) other settings for the chart can be found under lineChart.getConfiguration() method and can be overwritten every time.

b) Assigning data to the line chart

Data assignment can be done in two different ways.

- Assigning, updating an removing using methods delivered in ChartModel
- c) **addDataToModel** adding defined element in given dataset number under given label
- d) **changeDataByModel** change the value of the element defined by dataset which it is located in and given label
- e) **removeDataFromModel** removes element from the dataset number defined and label given in the method
- ➤ Changing the whole model using the method **setModel** accessible in the chart instance.

Both ways don't require refreshing the view as it is already done in the implementation.

c) Defining available events for line chart

At the time there is only one type of event accessible – **actionClick**. In order to add your own implementation for the event it is required to create a class implementing **SelectionListener** and add to the chart using method **chart. addElementSelectedListener**. You can register as many listeners as you want.

d) Line Chart Configuration


- **bezierCurveTension** Number Tension of the bezier curve between points
- **pointDot** Boolean Whether to show a dot for each point
- **bezierCurve** - Boolean Whether the line is curved between points
- **pointDotRadius** Number Radius of each point dot in pixels
- **pointDotStrokeWidth** Number Pixel width of point dot stroke
- pointHitDetectionRadius Number amount extra to add to the radius to cater for hit detection outside the drawn point
- **datasetFill** Boolean Whether to fill the <u>dataset</u> with a <u>colour</u>

The LineChart provides default configuration which could be changed by

- using the method chart.getConfiguration().set...
- providing new instance of LineChartConfiguration

Additional settings provided in the **LineChartConfiguration** come from the common configuration and are accessible and common for all chart types

1.4 Polar Chart



a) Creating new instance of the polar chart

new PolarChart(container, nameOfTheHtmlElement, dataModelForTheChart);

- **container** the parent java container where the object should be embedded
- nameOfTheHtmlElement name of the html element (div) which will display
 the chart. If you want to embed this chart in special template you will have to
 call in the vtl template \$control.get(nameOfTheHtmlElement) to display the
 chart in your new template. If you don't need to create special template,
 enough will be to create the instance in the java class like presented above.
- dataModelForTheChart data model containing information which will be presented in the chart. In case of PolarChart we need to use
 SimpleValueChartModel only a list of SimpleValueChartDataset which contains definition for each value with the label presented in the chart. Behind defining the label and value user needs also to define the color of the segment

and the highlight color of the segment for each dataset defined. The difference between **SimpleValueChartDataset** and **ValueListChartDataset** is that each dataset contains only one value and only one value can be assigned to one label.

b) Assigning data to the polar chart

Data assignment can be done in two different ways.

- Assigning, updating an removing using methods delivered in SimpleValueChartModel
 - a) addDataToModel adding given value with color under given new label
 - **b) changeDataByModel** change the value of the element in given dataset
 - c) removeDataFromModel removes dataset defined by given label
- Changing the whole model using the method **setModel** accessible in the chart instance.

Both ways don't require refreshing the view as it is already done in the implementation.

c) Defining available events for bar chart

At the time there is only one type of event accessible – actionClick. In order to add your own implementation for the event it is required to create a class implementing SelectionListener and add to the chart using method chart. addElementSelectedListener. You can register as many listeners as you want.

d) Polar Chart Configuration

- > scaleShowLine- Boolean Show line for each value in the scale
- scaleBackdropPaddingX Number The backdrop padding to the side of the label in in pixels
- scaleBackdropPaddingY Number The backdrop padding above & below the label in in pixels
- > scaleBackdropColor String The colour of the label backdrop
- > scaleShowLabelBackdrop Boolean Show a backdrop to the scale label


The PolarChart provides default configuration which could be changed by

using the method chart.getConfiguration().set...

providing new instance of PolarChartConfiguration

Additional settings provided in the **PolarChartConfiguration** come from the common configuration and are accessible and common for all chart types

1.5 Radar Chart



a) Creating new instance of the radar chart

new RadarChart(container, nameOfTheHtmlElement, dataModelForTheChart);

- container the parent java container where the object should be embedded
- nameOfTheHtmlElement name of the html element (div) which will display
 the chart. If you want to embed this chart in special template you will have to
 call in the vtl template \$control.get(nameOfTheHtmlElement) to display the

- chart in your new template. If you don't need to create special template, enough will be to create the instance in the java class like presented above.
- dataModelForTheChart data model containing information which will be presented in the chart. In case of RadarChart we need to use RadarChartModel which has the same structure as ValueListChartModel, and contains the list of labels (presented on X) and list of RadarChartDataset (the same structure as ValueListDataset except two additional gui settings which can be provided by displaying the chart). Each of the dataset contains the list of of values (should be in the same size as the list of labels, and gui settings in what way the RadarChart should present delivered data (color, size, background, font) other settings for the chart can be found under radarChart.getConfiguration() method and can be overwritten every time.

b) Assigning data to the radar chart

Data assignment can be done in two different ways.

- Assigning, updating an removing using methods delivered in ChartModel
- c) **addDataToModel** adding defined element in given dataset number under given label
- d) **changeDataByModel** change the value of the element defined by dataset which it is located in and given label
- e) **removeDataFromModel** removes element from the dataset number defined and label given in the method
- ➤ Changing the whole model using the method **setModel** accessible in the chart instance.

Both ways don't require refreshing the view as it is already done in the implementation.

c) Defining available events for radar chart

At the time there is only one type of event accessible – **actionClick**. In order to add your own implementation for the event it is required to create a class implementing **SelectionListener** and add to the chart using method **chart. addElementSelectedListener** . You can register as many listeners as you want.

d) Radar Chart Configuration

- > scaleShowLabelBackdrop- Show a backdrop to the scale label
- > scaleBackdropColor- The colour of the label backdrop
- scaleBackdropPaddingY Number The backdrop padding above & below the label in pixels
- scaleBackdropPaddingX Number The backdrop padding to the side of the label in pixels
- > scaleShowLine Boolean Show line for each value in the scale

The RadarChart provides default configuration which could be changed by

- using the method chart.getConfiguration().set...
- providing new instance of RadarChartConfiguration

Additional settings provided in the RadarChartConfiguration come from the common configuration and are accessible and common for all chart types

2. Common Chart Configuration

Accessible in all chart format types, provided with default values which can be changed each time by using the method **chart.getChartConfiguration().set...(setter method)**

All settings provided for each chart are listed below:

- a) **Width** in pixels height of the chart, only taken under account if chart responsive is set to false. As default is set: 500
- b) **Height** in pixels height of the chart, only taken under account if chart responsive is set to false. As default is set: 500
- c) **Responsive** Boolean whether or not the chart should be responsive and resize when the browser does. As default is set: false
- d) Animation Boolean Whether to animate the chart. As default is set: true
- e) animationSteps Number Number of animation steps. As default is set: 60
- f) **animationEasing** Animation easing effect. Defined as enumeration. As default is set : **EASEINOUTBOUNCE**
- g) showScale Boolean If we should show the scale at all. As default is set : true
- h) **scaleOverride** Boolean If we want to override with a hard coded scale. As default is set: false
- i) scaleLineColor String Color of the scale line. As default is set: rgba(0,0,0,1)
- i) scaleLineWidth Number Pixel width of the scale line. As default is set: 1

- k) **scaleShowLabels** Boolean Whether to show labels on the scale. As default is set : true
- scaleBeginAtZero Whether the scale should start at zero, or an order. As default is set: true
- m) **scaleFontFamily** Scale label font declaration for the scale label. As default is set: Helvetica Neue', 'Helvetica'; 'Arial', sans-serif
- n) scaleFontSize Number Scale label font size in pixels. As default is set: 12
- o) scaleFontStyle Number Scale label font weight style. As default is set : normal
- p) **scaleFontColor** String Scale label font <u>colour</u>. As default is set : #666
- q) maintainAspectRatio Boolean whether to maintain the starting aspect ratio or not when responsive, if set to false, will take up entire container. As default is set: true
- r) **showTooltips** Boolean Determines whether to draw <u>tooltips</u> on the canvas or or not. As default is set: true
- s) **tooltipFillColor** String <u>Tooltip</u> background <u>colour.</u> As default is set : rgba(0,0,0,0.8)
- t) **tooltipFontFamily** String <u>Tooltip</u> label font declaration for the scale label. As default is set: Helvetica Neue', 'Helvetica', 'Arial', sans-serif
- u) tooltipFontSize- Number Tooltip label font size in pixels. As default is set: 14
- v) tooltipFontStyle String Tooltip font weight style. As default is set : normal
- w) tooltipFontColor String Tooltip label font colour. As default is set: #fff
- x) **tooltipTitleFontFamily** String <u>Tooltip</u> title font declaration for the scale label. As default is set: 'Helvetica Neue', 'Helvetica'; 'Arial', sans-serif
- y) tooltipTitleFontSize Number Tooltip title font size in pixels. As default is set: 14
- z) tooltipTitleFontStyle String Tooltip title font weight style. As default is set : bold
- aa) tooltipTitleFontColor String Tooltip title font weight style. As default is set: #fff
- bb) **tooltipYPadding** Number pixel height of padding around <u>tooltip</u> text. As default is set : 6
- cc) **tooltipXPadding** Number pixel width of padding around <u>tooltip</u> text. As default is set: 6
- dd) tooltipCaretSize Number Size of the caret on the tooltip. As default is set: 8
- ee) tooltipCornerRadius Number Pixel radius of the tooltip border. As default is set: 6
- ff) tooltipXOffset Number Pixel offset from point x to <u>tooltip</u> edge. As default is set : 10
- gg) **tooltipTemplate** String Template string for single <u>tooltips</u>. As default is set : <%if (label){%><%=label%>= <%}%><%= value %>
- hh) **legendTemplate** A legend template, format for the legend <u>tooltip</u>. For each of the chart different
- ii) **showStroke** Whether we should show a stroke on each segment. As default is set : true
- jj) strokeColor The colour of each segment stroke. As default is set: rgba(0,0,0,1)

- kk) **segmentStrokeWidth** Number The width of each segment stroke. As default is set : 2
- II) scaleGridLineColor Color of the grid lines. As default is set: rgba(0,0,0,1)
- mm) scaleGridLineWidth Number Width of the grid lines. As default is set: 1
- nn) **scaleShowVerticalLines** Boolean Whether to show vertical lines (except Y axis). As default is set: false
- oo) **scaleShowHorizontalLines** Whether to show horizontal lines (except X axis). As default is set: false