CALCULUS
MADE
EASY
—
THOMPSON


MACMILLAN

Property of

Edward M Sumner

5716 Inadale Ave.

Los Angeles, Calit.





THE MACMILLAN COMPANY
NEW YORK - BOSTON - CHICAGO - DALLAS
ATLANTA - SAN FRANCISCO
MACMILLAN AND CO., LIMITED
LONDON - BOMBAY - CALCUTTA - MADRAS
MELBOURNE

THE MACMILLAN COMPANY
OF CANADA, LIMITED
TORONTO

CALCULUS MADE EASY:

BEING A VERY-SIMPLEST INTRODUCTION TO THOSE BEAUTIFUL METHODS OF RECKONING WHICH ARE GENERALLY CALLED BY THE TERRIFYING NAMES OF THE

DIFFERENTIAL CALCULUS

AND THE

INTEGRAL CALCULUS.

SILVANUS P. THOMPSON, F.R.S.

SECOND EDITION, ENLARGED

New York

THE MACMILLAN COMPANY

All rights reserved

"6-14-43"

What one fool can do, another can.
(Ancient bimian Provera



PREFACE TO THE SECOND EDITION.

The surprising success of this work has led the author to add a considerable number of worked examples and exercises. Advantage has also been taken to enlarge certain parts where experience showed that further explanations would be useful.

The author acknowledges with gratitude many valuable suggestions and letters received from teachers, students, and—critics.

October, 1914.



CONTENTS.

CHAPTER.				PAGE
	Prologue	•	-	хi
I.	To deliver you from the Preliminal	ry T	ER-	
	RORS	-	-	1
II.	On Different Degrees of Smallness	-	-	3
III.	On Relative Growings	-		9
IV.	SIMPLEST CASES			18
V.	NEXT STAGE. WHAT TO DO WITH CONS	TAN	ŗş .	26
VI.	Sums, Differences, Products, and Qu	это	NTS	35
VII.	Successive Differentiation	-	-	49
VIII.	WHEN TIME VARIES	-	-	52
IX.	INTRODUCING A USEFUL DODGE -	-	-	67
X.	GEOMETRICAL MEANING OF DIFFERENTIA	ATION	r -	76
XI.	MAXIMA AND MINIMA	-	-	93
XII.	CURVATURE OF CURVES	-		112
XIII.	OTHER USEFUL DODGES	•	•	121
XIV.	On true Compound Interest and the	Law	OF	
	ORGANIC GROWTH ~		•	134
XV.	How to DEAL WITH SINES AND COSINES	3 -	-	165
XVI.	Partial Differentiation			175
XVII.	Integration	•		182

XVIII.	Integrating as the Reverse of Differentiating	191
XIX.	On Finding Areas by Integrating	206
XX.	Dodges, Pitfalls, and Triumphs	226
XXI.	FINDING SOME SOLUTIONS	234
XXIL	A LITTLE MORE ABOUT CURVATURE OF CURVES -	249
XXIII.	How to Find the Length of an Arc on .	260
	EPILOGUE AND APOLOGUE	283
	Table of Standard Forms	286
	Answers to Exercises	288

PROLOGUE.

Considering how many fools can calculate, it is surprising that it should be thought either a difficult or a tedious task for any other fool to learn how to master the same tricks.

Some calculus-tricks are quite easy. Some are enormously difficult. The fools who write the text-books of advanced mathematics—and they are mostly clever fools—seldom take the trouble to show you how easy the easy calculations are. On the contrary, they seem to desire to impress you with their tremendous cleverness by going about it in the most difficult way.

Being myself a remarkably stupid fellow, I have had to unteach myself the difficulties, and now beg to present to my fellow fools the parts that are not hard. Master these thoroughly, and the rest will follow. What one fool can do, another can.



CHAPTER I.

TO DELIVER YOU FROM THE PRELIMINARY TERRORS.

THE preliminary terror, which chokes off most fifthform boys from even attempting to learn how to calculate, can be abolished once for all by simply stating what is the meaning—in common-sense terms—of the two principal symbols that are used in calculating.

These dreadful symbols are:

(1) d which merely means "a little bit of."

Thus dx means a little bit of x; or du means a little bit of u. Ordinary mathematicians think it more polite to say "an element of," instead of "a little bit of." Just as you please. But you will find that these little bits (or elements) may be considered to be indefinitely small.

(2) \int \text{ which is merely a long S, and may be called (if you like) "the sum of."}

Thus $\int dx$ means the sum of all the little bits of x; or $\int dt$ means the sum of all the little bits of t. Ordinary mathematicians call this symbol "the C.M.E.

integral of." Now any fool can see that if x is considered as made up of a lot of little bits, each of which is called dx, if you add them all up together you get the sum of all the dx's, (which is the same thing as the whole of x). The word "integral" simply means "the whole." If you think of the duration of time for one hour, you may (if you like) think of it as cut up into 3600 little bits called seconds. The whole of the 3600 little bits added up together make one hour.

When you see an expression that begins with this terrifying symbol, you will henceforth know that it is put there merely to give you instructions that you are now to perform the operation (if you can) of totalling up all the little bits that are indicated by the symbols that follow.

That's all.

CHAPTER II.

ON DIFFERENT DEGREES OF SMALLNESS.

WE shall find that in our processes of calculation we have to deal with small quantities of various degrees of smallness.

We shall have also to learn under what circumstances we may consider small quantities to be so minute that we may omit them from consideration. Everything depends upon relative minuteness.

Before we fix any rules let us think of some familiar cases. There are 60 minutes in the hour, 24 hours in the day, 7 days in the week. There are therefore 1440 minutes in the day and 10080 minutes in the week.

Obviously 1 minute is a very small quantity of time compared with a whole week. Indeed, our forefathers considered it small as compared with an hour, and called it "one minute," meaning a minute fraction—namely one sixtieth—of an hour. When they came to require still smaller subdivisions of time, they divided each minute into 60 still smaller parts, which, in Queen Elizabeth's days, they called "second minutes" (i.e., small quantities of the second order of minuteness). Nowadays we call these small quantities

of the second order of smallness "seconds." But few people know why they are so called.

Now if one minute is so small as compared with a whole day, how much smaller by comparison is one second!

Again, think of a farthing as compared with a sovereign: it is worth only a little more than $\frac{1}{1000}$ part. A farthing more or less is of precious little importance compared with a sovereign: it may certainly be regarded as a small quantity. But compare a farthing with £1000: relatively to this greater sum, the farthing is of no more importance than $\frac{1}{1000}$ of a farthing would be to a sovereign. Even a golden sovereign is relatively a negligible quantity in the wealth of a millionaire.

Now if we fix upon any numerical fraction as constituting the proportion which for any purpose we call relatively small, we can easily state other fractions of a higher degree of smallness. Thus if, for the purpose of time, $\frac{1}{60}$ be called a small fraction, then $\frac{1}{60}$ of $\frac{1}{60}$ (being a small fraction of a small fraction) may be regarded as a small quantity of the second order of smallness.*

^{*}The mathematicians talk about the second order of "magnitude" (i.e. greatness) when they really mean second order of smallness. This is very confusing to beginners.

be a small fraction of the third order of smallness, being 1 per cent. of 1 per cent. of 1 per cent.

Lastly, suppose that for some very precise purpose we should regard 1,000,000 as "small." Thus, if a first-rate chronometer is not to lose or gain more than half a minute in a year, it must keep time with an accuracy of 1 part in 1,051,200. Now if, for such a purpose, we regard $\frac{1}{1.000,000}$ (or one millionth) as a small quantity, then $\frac{1}{1,000,000}$ of $\frac{1}{1,000,000}$, that is, 1,000,000,000,000 (or one billionth) will be a small quantity of the second order of smallness, and may be utterly disregarded, by comparison.


Then we see that the smaller a small quantity itself is, the more negligible does the corresponding small quantity of the second order become. Hence we know that in all cases we are justified in neglecting the small quantities of the second-or third (or higher)-orders, if only we take the small quantity of the first order small enough in itself.

But it must be remembered that small quantities, if they occur in our expressions as factors multiplied by some other factor, may become important if the other factor is itself large. Even a farthing becomes important if only it is multiplied by a few hundred.

Now in the calculus we write dx for a little bit of x. These things such as dx, and du, and dy, are called "differentials," the differential of x, or of u, or of y, as the case may be. [You read them as dee-eks, or dee-you, or dee-wy.] If dx be a small bit of x, and relatively small of itself, it does not follow that such quantities as $x \cdot dx$, or $x^2 dx$, or $a^x dx$ are negligible. But $dx \times dx$ would be negligible, being a small quantity of the second order.

A very simple example will serve as illustration.

Let us think of x as a quantity that can grow by a small amount so as to become x+dx, where dx is the small increment added by growth. The square of this is $x^2+2x\cdot dx+(dx)^2$. The second term is not negligible because it is a first-order quantity; while the third term is of the second order of smallness, being a bit of a bit of x. Thus if we took dx to mean numerically, say, $\frac{1}{60}$ of x, then the second term would be $\frac{2}{60}$ of x^2 , whereas the third term would be $\frac{1}{3600}$ of x^2 . This last term is clearly less important than the second. But if we go further and take dx to mean only $\frac{1}{10000}$ of x, then the second term will be $\frac{2}{10000}$ of x^2 , while the third term will be only $\frac{1}{10000000}$ of x^2 .



Geometrically this may be depicted as follows: Draw a square (Fig. 1) the side of which we will take to represent x. Now suppose the square to grow by having a bit dx added to its size each