A Search for the Neutrinoless Double Beta Decay of Xenon-136 with Improved Sensitivity from Waveform Denoising

Clayton G. Davis

April 3, 2014


Outline

 $\beta\beta2\nu$ and $\beta\beta0\nu$ Decay

The EXO-200 Detector

Denoising


What is Double-Beta Decay?



Feynman diagram for $\beta\beta2\nu$ decay. Equivalent to two single- β decays:

$$2n \to 2p + 2e^- + 2\bar{\nu}_e$$

What is Double-Beta Decay?



Feynman diagram for $\beta\beta2\nu$ decay. Equivalent to two single- β decays:


$$2n \rightarrow 2p + 2e^- + 2\bar{\nu}_e$$

Feynman diagram for $\beta\beta0\nu$ decay. Neutrinos annihilate each other:

$$2n \rightarrow 2p + 2e^-$$

 $\beta\beta2\nu$ is allowed in the Standard Model; $\beta\beta0\nu$ is not.

Implications of Double-Beta Decay



► Lepton number changes:

$$\Delta L = +2$$

► Neutrinos can convert to their own antiparticle:


$$\bar{\nu}_R \to \nu_L$$

Neutrinos have mass through a Majorana interaction:

$$-\frac{m_L}{2} \left(\overline{\Psi_L^c} \Psi_L + \overline{\Psi_L} \Psi_L^c \right)$$

$$-\frac{m_R}{2}\left(\overline{\Psi_R^c}\Psi_R+\overline{\Psi_R}\Psi_R^c\right)$$

The A = 136 Isobar




 136 Cs undergoes single- β decay.

 136 Xe cannot, due to energy conservation – but it can $\beta\beta$ decay through 136 Cs to 136 Ba.

The Q-value of $^{136}\text{Xe} \rightarrow ^{136}\text{Ba}$ is 2457.83 ± 0.37 keV, shared between all final products of the decay.


We observe energy in electrons; energy in neutrinos is lost.

Ideal Double-Beta Energy Spectrum




 136 Xe $\beta\beta2\nu$ produces a smooth energy spectrum; "missing" energy carried off by neutrinos.

Ideal Double-Beta Energy Spectrum




 136 Xe $\beta\beta0\nu$ has no neutrinos, so no "missing" energy; mono-energetic peak at Q=2458 keV.

Ideal Double-Beta Energy Spectrum




If the $\beta\beta0\nu$ peak exists, neutrinos have Majorana mass; peak height gives a measurement of that mass.

The EXO-200 Detector




The EXO-200 Detector



To search for rare decays, low background is key:


- Clean (low-radioactivity) materials surrounding TPC.
- Deep underground to avoid cosmogenics.




EXO-200 TPC

110 kg of liquid xenon in active volume, enriched to 80.6% in ¹³⁶Xe, contained in a time projection chamber (TPC).

Xenon continuously circulates through purifiers outside of the cryostat.




EXO-200 TPC




Charge drifts under an electric field and is collected by wires on the anodes. Light is observed by APDs behind the wires.

Energy from Ionization and Scintillation



Energy is independently measured from scintillation and ionization.

They are anticorrelated – better energy resolution from both together than either independently.




Primary Backgrounds: ³⁷Xe. ²³²Th. and ²³⁸U

Energy resolution is measured as σ /mean of a mono-energetic peak at the Q-value. Typically 1.5-2% for EXO-200.

Better resolution gives a sharper $\beta\beta 0\nu$ peak, so less background in that energy window.


¹³⁷Xe spectrum is smooth around *Q*-value; background proportional to energy resolution.



Primary Backgrounds: ³⁷Xe, ²³²Th, and ²³⁸U

Not all backgrounds are smooth. 232 Th has a gamma line at 2615 keV, so resolution reduces background sharply until 2457 and 2615 keV are well-separated around 1.2%.

Beyond that, resolution for ²³²Th is less important (though still helpful).




Primary Backgrounds: ³⁷Xe, ²³²Th, and ²³⁸U


238U has a 2448-keV gamma line, indistinguishable from 2457-keV Q-value except with extremely good resolution.

So, even down to 0.4% energy resolution, most of the ²³⁸U peak at 2448 keV is still within our energy window. ²³⁸U backgrounds aren't significantly reduced by resolution improvements.


Backgrounds vs. Resolution



Time Variation of Resolution




Time Variation of Resolution



APD Noise is Correlated across Channels



APD Noise is Correlated across Channels



Correlated noise \Rightarrow offline denoising of some sort should work!

Three types of noise in the scintillation measurements:

- ► Electronic noise.
- ▶ Photon fluctuations.
- ► Gain fluctuations.

A "denoising" algorithm should minimize all three.

Three types of noise in the scintillation measurements:

- ightharpoonup Electronic noise. \leftarrow Additive; use fewer channels.
- ▶ Photon fluctuations.
- ► Gain fluctuations.

A "denoising" algorithm should minimize all three.

Three types of noise in the scintillation measurements:

ightharpoonup Electronic noise. \leftarrow Additive; use fewer channels.

 \triangleright Photon fluctuations. \leftarrow Poissonian; use more channels.

▶ Gain fluctuations. \leftarrow Poissonian; use more channels.

A "denoising" algorithm should minimize all three.

Three types of noise in the scintillation measurements:

- \triangleright Electronic noise. \leftarrow Additive; use fewer channels.
- ▶ Photon fluctuations. \leftarrow Poissonian; use more channels.
- \triangleright Gain fluctuations. \leftarrow Poissonian; use more channels.

A "denoising" algorithm should minimize all three.

Most denoising algorithms transform an input waveform to an output waveform, with pulses amplified and additive noise reduced.

Here we're trying to reduce the impact of noise which is correlated with pulses. That means traditional denoising won't accomplish what we need.

So, "denoising" for us means producing a noise-tolerant estimate of the scintillation energy.

Types of Denoising

There are also three approaches to reducing the impact of noise:

- ► Frequency weighting.
- ► Channel weighting.
- ► Exploit noise correlations.

On the bottom part (or right side) of the screen I can show three pictures which demonstrate how they'll be used:

- power spectrum of noise vs signal.
- ▶ APD pulse magnitude vs channel (left side of event display for a typical SS Th event).
- ▶ Noise correlation heat plot, per Carter's request.

Waveform Model

When there is one energy deposit in the xenon, the APD waveform $X_i[f]$ (in frequency space) on channel i can be modeled:

$$X_i[f] = M_i Y_i[f] + N_i[f]$$
, where:

- $ightharpoonup Y_i[f]$ is the unit-magnitude template pulse for channel i.
- ▶ M_i is the magnitude of the pulse observed on channel i, including the scintillation energy and Poisson fluctuations in photon statistics and gain.
- ▶ $N_i[f]$ is the additive (electronic) noise on channel i.

To complete our model, we need to understand the distributions of the random variables:

- ▶ How M_i depends on the unknown energy E.
- ▶ How magnitudes M_i and M_j are correlated.
- ▶ How electronic noise $N_i[f]$ and $N_j[f]$ are correlated.

Electronic Noise

To measure the electronic (additive) noise, we need waveforms with no pulse.

Fortunately, EXO-200 is a low-background detector: most of the time all it measures is noise.

So, this is fairly easy: use our noise data to measure all of the pairwise noise correlations.

Explicitly, we measure:

$$\left\langle N_i^R[f]N_j^R[f] \right\rangle, \left\langle N_i^R[f]N_j^I[f] \right\rangle, \text{ and } \left\langle N_i^I[f]N_j^I[f] \right\rangle,$$

where $N_i^R[f]$ and $N_i^I[f]$ are the real and imaginary parts of $N_i[f]$.


Electronic Noise

Main detail: the electronic noise changes over time (mostly in discontinuous steps). Show plot of time windows (but I should really make it show the windows used/recommended, rather than events.

The expected pulse height M_i on a channel i from a deposit at position \vec{x} and time t is described by a lightmap $L_i(\vec{x}, t)$:

$$\langle M_i \rangle = L_i(\vec{x}, t) E.$$

To measure $L_i(\vec{x}, t)$, we need a known-energy deposit for all position and time bins. But we don't have that much data: calibration sources give us good statistics, but aren't near every position.



The expected pulse height M_i on a channel i from a deposit at position \vec{x} and time t is described by a lightmap $L_i(\vec{x}, t)$:

$$\langle M_i \rangle = L_i(\vec{x}, t) E.$$

To reduce the amount of statistics needed, we make an approximation that $L_i(\vec{x},t)$ is separable into spatial and temporal components:

$$L_i(\vec{x},t) = R_i(\vec{x})S_i(t).$$

So, rather than needing one known-energy deposit per position per time, we need one per position during the whole history of EXO-200.

(We do this assuming that APD gain varies over time, but light collection does not, and gain does not depend on the position of the deposit.)

With this simpler form for the lightmap, we can measure $R_i(\vec{x})$ and $S_i(t)$ by combining all thorium source calibration events from the ²⁰⁸Tl 2615-keV gamma line. It is a clean, well-isolated peak:

Show the spectrum, indicating cuts.

Finish convincing people that denoising can work; explain the sources of noise in more detail.

Denoising: An Optimization Problem

So, the waveforms $X_i[f]$ are modeled by:

$$X_i[f] = M_i Y_i[f] + N_i[f],$$

and we have full descriptions of the random variables M_i and $N_i[f]$.

Linear real-valued energy estimators \widehat{E} take the form:

$$\widehat{E} = \sum_{if} A_i[f] X_i^R[f] + B_i[f] X_i^I[f],$$

where $A_i[f]$ and $B_i[f]$ are parameters we can adjust.

Problem: minimize the mean square error, $\left\langle \left(E-\widehat{E}\right)^2\right\rangle$.

Constraint: estimator is unbiased, $\langle E - \widehat{E} \rangle = 0$.

Denoising: An Optimization Problem

The solution is a big matrix equation

Denoising: An Optimization Problem

The solution is a big matrix equation which we write in a compact way:

$$\begin{pmatrix} \mathbf{N} + \mathbf{P} & C^{\top} \\ C & 0 \end{pmatrix} \begin{pmatrix} A \\ \lambda \end{pmatrix} = \begin{pmatrix} 0 \\ 1 \end{pmatrix}.$$


The LHS matrix is a $143,291 \times 143,291$ sparse matrix with roughly twenty million non-zero entries.

We need to solve this system once **for each event**, and there are hundreds of millions of events. Fortunately this is an embarassingly parallel problem, so we can just find a big computing system and do it.

NERSC, at LBNL CHECK THIS, was used for this analysis; we required roughly 50,000 core-hours to do this processing.

Backup Slides

Anticorrelated Scintillation/Charge



Why not the Anscombe transformation?

The Anscombe transformation (and generalizations) are designed to transform Poisson noise into Gaussian noise. However, for this purpose "noise" is defined to mean noise **uncorrelated with pulse**. We, on the other hand, are looking to understand noise which **is** correlated with the pulse, and then minimize its effect.

So, the Anscombe transformation doesn't really help us here.