


**Example 1.** Initially, the upper tank initially contains 200 gallons of salt solution with salt concentration of 0.2 lb/gal, and the lower tank also initially contains 200 gallon of salt solution, but with salt concentration 0.1 lb/gal. As time progresses, water flows between the tanks in the manner indicated, with pure water flowing into the upper tank. Find formulas for the salt contents  $x_1(t)$  and  $x_2(t)$  in the upper and lower tanks, in lbs.

$$\left\{ \begin{array}{l} x_1(0) = 200 \text{ gal} \cdot \frac{0.2 \text{ lbs}}{\text{gal}} = 40 \text{ lbs} \\ x_2(0) = 200 \text{ gal} \cdot \frac{0.1 \text{ lbs}}{\text{gal}} = 20 \text{ lbs} \end{array} \right.$$



Remember, if  $A$  is  $2 \times 2$  with a repeated eigenvalue then we have the shortcut:

$$e^{tA} = e^{ct} (I + tN) \text{ where } N = A - cI$$

$$\text{for us } c = -\frac{1}{40}$$

$$\begin{pmatrix} x_1 \\ x_2 \end{pmatrix}' = \begin{pmatrix} x_1 & x_2 \\ -\frac{1}{40} & 0 \\ 1/40 & -1/40 \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \end{pmatrix} + \begin{pmatrix} 0 \\ 0 \end{pmatrix}$$

$\underbrace{A}_{\text{the rest}}$

$$\begin{pmatrix} x_1 \\ x_2 \end{pmatrix}(0) = \begin{pmatrix} 40 \\ 20 \end{pmatrix}$$

$\underbrace{\det(A - \lambda I) = 0}_{\lambda = -\frac{1}{40}, \text{ repeated}}$

$$(-\frac{1}{40} - \lambda)^2 = 0$$

$\underbrace{\text{shortcut: } e^{tA} = e^{-t/40} \begin{pmatrix} 1 & 0 \\ -1/40 & 1 \end{pmatrix}}$


exp method for homogeneous:  $\vec{x} = e^{tA} \vec{x}_0$

$$\begin{aligned} \vec{x} &= e^{-t/40} \begin{pmatrix} 1 & 0 \\ -1/40 & 1 \end{pmatrix} \begin{pmatrix} 40 \\ 20 \end{pmatrix} \\ &= e^{-t/40} \begin{pmatrix} 40 \\ t+20 \end{pmatrix} \end{aligned}$$

**Example 2.** Find the state-free solution—i.e. with initial values equal 0—for currents  $i_1$  and  $i_2$  in the circuit:

$$\vec{i}(0) = \vec{0}$$

$$\vec{i} = \begin{pmatrix} i_1 \\ i_2 \end{pmatrix}$$




Current law: current in = current out

$$i + i_2 = i_1$$

$$i = i_1 - i_2$$

Voltage law: left loop



$$6e^{-8t} = 8i_1 + 2i_1' + \boxed{4i}$$

↓ rearrange

$$i_1' = -6i_1 + 2i_2 + 3e^{-8t}$$

Voltage law: right loop



↳ corrective neg so counterclockwise

$$0 = \boxed{4(-i)} + \boxed{1i_2'}$$

$$i_2' = 4i_1 - 4i_2$$

$$i_1 \quad i_2$$

$$\left( \begin{pmatrix} i_1 \\ i_2 \end{pmatrix} \right)' = \boxed{\begin{pmatrix} -6 & 2 \\ 4 & -4 \end{pmatrix}} \left( \begin{pmatrix} i_1 \\ i_2 \end{pmatrix} \right) + \boxed{\begin{pmatrix} \frac{1}{8} \\ 3e^{-8t} \end{pmatrix}}$$

state-free:  $\vec{i}(0) = \vec{0}$

Some reminders about electrical circuits.  
The zigzags are resistors and the curlyies are inductors.

Kirkhoff's Current Law:

- at any juncture, the current in equals the current out.

Kirkhoff's Voltage Law:

- directed sum of voltages around any closed loop equals 0

Impeding voltages across components:

- resistor: Ohm's Law  $E_R = RI$
- capacitor: Capacitance Law  $E_C = \frac{Q}{C}$
- inductor: Faraday's Law  $E_L = L \frac{dI}{dt}$

Current is derivative of charge:

$$\bullet I = \frac{dQ}{dt}$$

We apply Kirkhoff's voltage law to the left loop and the right loop.

Example 2 Continued.

You should find:

$$A = \begin{pmatrix} -6 & 2 \\ 4 & -4 \end{pmatrix} \text{ and } f(t) = \begin{pmatrix} 3e^{-8t} \\ 0 \end{pmatrix}$$

in which case it will turn out that:

$$e^{tA} = \frac{1}{3} \begin{pmatrix} e^{-2t} + 2e^{-8t} & e^{-2t} - e^{-8t} \\ 2e^{-2t} - 2e^{-8t} & 2e^{-2t} + e^{-8t} \end{pmatrix}$$

(state-free soln)

$$\vec{z} = e^{tA} * \vec{x}(t)$$

$$= \frac{1}{3} \sum_{u=0}^t \begin{pmatrix} e^{-2u} + 2e^{-8u} & * \\ 2e^{-2u} - 2e^{-8u} & * \end{pmatrix} \begin{pmatrix} 3e^{-8(t-u)} \\ 0 \end{pmatrix} du$$

used this  
pull in front of integral

$$= e^{-8t} \sum_{u=0}^t \begin{pmatrix} e^{6u} + 2 \\ 2e^{6u} - 2 \end{pmatrix} du$$

$$= e^{-8t} \begin{pmatrix} e^{6t} - 1 + 2t \\ 2e^{6t} - 2 - 2t \end{pmatrix}$$

Bonus Formula: If  $A$  is  $2 \times 2$  w/ complex evals  $\lambda = a \pm bi$ , then:

$$e^{tA} = e^{at} \left( \cos(bt) I + \sin(bt) R \right) \text{ where } R = \frac{1}{b} (A - aI)$$

Justification:

Fact.  $A = aI + bR$  where  $R^2 = -I$

$$e^{tA} = e^{atI + btr}$$

$$= e^{atI} e^{btr}$$

$$= e^{at} \left( I + btr + \frac{b^2 t^2 R^2}{2!} + \frac{b^3 t^3 R^3}{3!} + \frac{b^4 t^4 R^4}{4!} + \dots \right)$$

$$= e^{at} \left[ \left( I - \frac{b^2 t^2}{2!} + \frac{b^4 t^4}{4!} + \dots \right) I + \left( bt - \frac{b^3 t^3}{3!} + \frac{b^5 t^5}{5!} + \dots \right) R \right]$$

$$= e^{at} [\cos bt \cdot I + \sin bt \cdot R]$$

not obvious

