example: producer/consumer



shared buffer (queue) of fixed size

one or more producers inserts into queue one or more consumers removes from queue

example: producer/consumer



shared buffer (queue) of fixed size

one or more producers inserts into queue one or more consumers removes from queue

producer(s) and consumer(s) don't work in lockstep (might need to wait for each other to catch up)

example: producer/consumer



shared buffer (queue) of fixed size

one or more producers inserts into queue one or more consumers removes from queue

producer(s) and consumer(s) don't work in lockstep (might need to wait for each other to catch up)

example: C compiler

 $\mathsf{preprocessor} \to \mathsf{compiler} \to \mathsf{assembler} \to \mathsf{linker}$

monitors/condition variables

locks for mutual exclusion

```
condition variables for waiting for event
    operations: wait (for event); signal/broadcast (that event happened)
related data structures
```

a monitor


lock
shared data
condvar 1
condvar 2
•••
operation1()
operation2()


a monitor

lock
shared data
condvar 1
condvar 2

operation1()
operation2()

lock must be acquired before accessing any part of monitor's stuff






condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning


Broadcast(cv) — remove all from condvar queue



condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning


Broadcast(cv) — remove all from condvar queue



condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning


Broadcast(cv) — remove all from condvar queue



condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning


Broadcast(cv) — remove all from condvar queue



condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue



```
// MISSING: init calls, etc.
pthread_mutex_t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread cond_wait(&finished_cv, &lock);
  pthread mutex unlock(&lock);
void Finish() {
  pthread mutex lock(&lock);
  finished = true;
  pthread cond broadcast(&finished cv);
  pthread mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread_mutex_t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
 pthread_mutex_lock(&lock);
 while (!finished) {
    pthread_cond_wait(&finished_cv, &tock);
                                     acquire lock before
 pthread mutex unlock(&lock);
                                     reading or writing finished
void Finish() {
 pthread mutex lock(&lock);
  finished = true;
  pthread cond broadcast(&finished cv);
 pthread mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread_mutex_t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
                                check whether we need to wait at all
  while (!finished) {	━
    pthread_cond_wait(&finishe (why alloop? we'll explain later)
  pthread mutex unlock(&lock);
void Finish() {
  pthread mutex lock(&lock);
  finished = true;
  pthread cond broadcast(&finished cv);
  pthread mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread_mutex_t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread_cond_wait(&finished_cv, &lock);
  pthread mutex unlock(&lock):
                           know we need to wait
                          (finished can't change while we have lock)
void Finish() {
  pthread_mutex_lock(&lockso wait, releasing lock...
  finished = true:
  pthread cond broadcast(&finished cv);
  pthread mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread_mutex_t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread cond_wait(&finished_cv, &lock);
  pthread mutex unlock(&lock);
                                        allow all waiters to proceed
                                         (once we unlock the lock)
void Finish() {
  pthread mutex lock(&lock);
  finished = true;
  pthread cond broadcast(&finished cv);
  pthread mutex_unlock(&lock);
```

WaitForFinish timeline 1

WaitForFinish thread	Finish thread
<pre>mutex_lock(&lock)</pre>	
(thread has lock)	
	<pre>mutex_lock(&lock)</pre>
	(start waiting for lock)
while (!finished)	
<pre>cond_wait(&finished_cv, &lock);</pre>	
(start waiting for cv)	(done waiting for lock)
	finished = true
	<pre>cond_broadcast(&finished_cv)</pre>
(done waiting for cv)	
(start waiting for lock)	
·	<pre>mutex_unlock(&lock)</pre>
(done waiting for lock)	
while (!finished)	
(finished now true, so return)	
mutex_unlock(&lock)	

WaitForFinish timeline 2 WaitForFinish thread Finish thread

WaitForFinish thread	Finish thread
	<pre>mutex_lock(&lock)</pre>
	finished = true
	<pre>cond_broadcast(&finished_cv)</pre>
	<pre>mutex_unlock(&lock)</pre>
<pre>mutex_lock(&lock)</pre>	
while (!finished)	
(finished now true, so return)	
<pre>mutex_unlock(&lock)</pre>	

why the loop

```
while (!finished) {
   pthread_cond_wait(&finished_cv, &lock);
}
we only broadcast if finished is true
so why check finished afterwards?
```

why the loop

```
while (!finished) {
  pthread_cond_wait(&finished_cv, &lock);
we only broadcast if finished is true
so why check finished afterwards?
pthread cond wait manual page:
    "Spurious wakeups ... may occur."
```

spurious wakeup = wait returns even though nothing happened

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread mutex lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread mutex unlock(&lock);
}
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread mutex t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread mutex lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread mutex unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

rule: never touch buffer without acquiring lock
otherwise: what if two threads simulatenously en/dequeue?
(both use same array/linked list entry?)
(both reallocate array?)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedOueue buffer;
Produce(item) {
    pthread mutex lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
                                                 check if empty
}
                                                 if so, dequeue
Consume() {
    pthread_mutex_lock(&lock):
                                                 okay because have lock
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);

    other threads cannot dequeue here


    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread mutex lock(&lock);
                                                wake one Consume thread
    buffer.enqueue(item);
                                                if any are waiting
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

```
Thread 1
                                                                Thread 2
pthread mutex t lock;
                                         Produce()
pthread_cond_t data_ready;
                                         ...lock
UnboundedOueue buffer;
                                         ...enqueue
                                         ...signal
Produce(item) {
                                         ...unlock
    pthread mutex lock(&lock);
                                                            Consume()
    buffer.enqueue(item);
                                                            ...lock
    pthread_cond_signal(&data_ready)
                                                            ...empty? no
    pthread mutex unlock(&lock);
                                                            ...dequeue
                                                            ...unlock
                                                            return
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
         pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
                                      0 iterations: Produce() called before Consume()
    pthread_mutex_unlock(&lock)
                                      1 iteration: Produce() signalled, probably
    return item;
                                      2+ iterations: spurious wakeup or ...?
```

```
Thread 1
                                                                  Thread 2
pthread mutex t lock;
                                                             Consume()
pthread_cond_t data_ready;
                                                             ...lock
UnboundedOueue buffer;
                                                             ...empty? yes
                                                             ...unlock/start wait
Produce(item) {
                                                 Produce()
                                                                  waiting for
    pthread mutex lock(&lock);
                                                  ...lock
    buffer.enqueue(item);
                                                                  data ready
    pthread_cond_signal(&data_ready);
                                                  ...enqueue
                                                  ...signal
                                                             stop wait
    pthread mutex unlock(&lock);
                                                  ...unlock
                                                             lock
                                                             ...empty? no
                                                             ...dequeue
Consume() {
    pthread_mutex_lock(&lock);
                                                             ...unlock
    while (buffer.empty()) {
                                                             return
         pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
                                      0 iterations: Produce() called before Consume()
    pthread_mutex_unlock(&lock)
                                       1 iteration: Produce() signalled, probably
    return item;
                                       2+ iterations: spurious wakeup or ...?
```

```
Thread 1
                                                       Thread 2
                                                                        Thread 3
pthread mutex t lock;
                                                   Consume()
pthread_cond_t data_ready;
                                                   …lock
UnboundedQueue buffer;
                                                   ...empty? yes
                                                   ...unlock/start wait
Produce(item) {
                                       Produce()
                                                        waiting for
    pthread mutex lock(&lock);
                                       ...lock
                                                                       Consume()
    buffer.enqueue(item);
                                                       data ready
                                       ...enqueue
    pthread_cond_signal(&data_rea
                                                                        waiting for
    pthread_mutex_unlock(&lock);
                                       ...signal
                                                   stop wait
                                                                           lock
                                       ...unlock
                                                                       lock
                                                        waiting for
                                                                       ...empty? no
                                                           lock
                                                                       ...dequeue
Consume() {
    pthread_mutex_lock(&lock);
                                                                       ...unlock
    while (buffer.empty()) {
                                                   ...lock
                                                                       return
         pthread_cond_wait(&data_r
                                                   ...empty? yes
                                                   ...unlock/start wait
    item = buffer.dequeue();
                                       0 iterations: Produce() called before Consume()
    pthread_mutex_unlock(&lock)
                                       1 iteration: Produce() signalled, probably
    return item;
                                       2+ iterations: spurious wakeup or ...?
```



Hoare versus Mesa monitors

```
Hoare-style monitors signal 'hands off' lock to awoken thread
```

```
Mesa-style monitors

any eligible thread gets lock next

(maybe some other idea of priority?)
```

every current threading library I know of does Mesa-style

```
pthread_mutex_t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    while (buffer.full()) { pthread cond wait(&space ready, &lock); }
    buffer.enqueue(item);
    pthread cond signal(&data ready);
    pthread mutex unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.enqueue(item);
    pthread cond signal(&data ready);
    pthread mutex unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
   pthread_mutex_lock(&lock);
   while (buffer.full()) { pthread cond wait(&space ready, &lock); }
    buffer.engueue(item);
    pthread cond signal(&data ready);
   pthread mutex unlock(&lock).
      correct (but slow?) to replace with:
Consum pthread cond broadcast(&space ready);
      (just more "spurious wakeups")
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
    return item;
```

return item;

```
pthread_mutex_t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.enqueue(item);
                                               correct but slow to replace
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
                                               data ready and space ready
                                               with 'combined' condvar ready
                                               and use broadcast.
Consume() {
    pthread_mutex_lock(&lock);
                                               (just more "spurious wakeups")
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
```

monitor pattern

```
pthread mutex lock(&lock);
while (!condition A) {
    pthread_cond_wait(&condvar_for_A, &lock);
... /* manipulate shared data, changing other conditions */
if (set condition A) {
    pthread_cond_broadcast(&condvar_for_A);
   /* or signal, if only one thread cares */
if (set condition B) {
    pthread cond broadcast(&condvar for B);
    /* or signal, if only one thread cares */
pthread_mutex_unlock(&lock)
```

monitors rules of thumb

never touch shared data without holding the lock

keep lock held for entire operation:

verifying condition (e.g. buffer not full) up to and including manipulating data (e.g. adding to buffer)

create condvar for every kind of scenario waited for

always write loop calling cond_wait to wait for condition X

broadcast/signal condition variable every time you change X

monitors rules of thumb

never touch shared data without holding the lock

keep lock held for entire operation:

verifying condition (e.g. buffer not full) up to and including manipulating data (e.g. adding to buffer)

create condvar for every kind of scenario waited for

always write loop calling cond_wait to wait for condition X

broadcast/signal condition variable every time you change X

correct but slow to...

broadcast when just signal would work broadcast or signal when nothing changed use one condvar for multiple conditions

mutex/cond var init/destroy

```
pthread_mutex_t mutex;
pthread cond t cv;
pthread_mutex_init(&mutex, NULL);
pthread_cond_init(&cv, NULL);
// --OR--
pthread_mutex_t mutex = PTHREAD_MUTEX_INITIALIZER;
pthread cond t cv = PTHREAD COND INITIALIZER;
// and when done:
pthread cond destroy(&cv);
pthread mutex destroy(&mutex);
```

wait for both finished

```
// MISSING: init calls, etc.
pthread_mutex_t lock;
bool finished[2];
pthread_cond_t both_finished_cv;
void WaitForBothFinished() {
 pthread_mutex_lock(&lock);
 while (_____) {
   pthread_cond_wait(&both_finished_cv, &lock);
 pthread mutex unlock(&lock);
void Finish(int index) {
 pthread mutex lock(&lock);
  finished[index] = true;
 pthread mutex unlock(&lock);
```

wait for both finished

```
A. finished[0] && finished[1]
// MISSING: init calls, etc.
                               B. finished[0] || finished[1]
pthread_mutex_t lock;
                               C. !finished[0] || !finished[1]
bool finished[2];
                               D. finished[0] != finished[1]
pthread cond t both finished cv
                               E. something else
void WaitForBothFinished() {
 pthread_mutex_lock(&lock);
 while (______
   pthread cond wait(&both finished cv, &lock);
 pthread mutex unlock(&lock);
void Finish(int index) {
 pthread mutex lock(&lock);
  finished[index] = true;
 pthread mutex unlock(&lock);
```

wait for both finished

```
// MISSING: init calls, etc.
pthread_mutex_t lock;
                          A. pthread cond signal(&both finished cv)
bool finished[2];
                          B. pthread_cond_broadcast(&both_finished_cv)
pthread cond t both fin
                          C. if (finished[1-index])
                                  pthread cond singal(&both finished cv);
void WaitForBothFinishe D. if (finished[1-index])
                                  pthread_cond_broadcast(&both_finished_cv);
  pthread_mutex_lock(&l
                          E. something else
  while (
    pthread cond wait(&both finished cv, &lock);
  pthread mutex unlock(&lock);
void Finish(int index) {
  pthread mutex lock(&lock);
  finished[index] = true;
  pthread mutex unlock(&lock);
```

monitor exercise: barrier

suppose we want to implement a one-use barrier; fill in blanks: struct BarrierInfo { pthread mutex t lock; int total_threads; // initially total # of threads int number_reached; // initially 0 **}**; void BarrierWait(BarrierInfo *b) { pthread mutex lock(&b->lock); ++b->number reached; if (b->number reached == b->total threads) { } else { pthread mutex unlock(&b->lock);

monitor exercise: ConsumeTwo

suppose we want producer/consumer, but...

but change Consume() to ConsumeTwo() which returns a pair of values

and don't want two calls to ConsumeTwo() to wait... with each getting one item

what should we change below?

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
}

Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    }
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
}
```

monitor exercise: ordering

suppose we want producer/consumer, but...

but want to ensure first call to Consume() always returns first

(no matter what ordering cond_signal/cond_broadcast use)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
}

Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
        item = buffer.dequeue();
        pthread_mutex_unlock(&lock);
        return item;
}
```

producer/consumer signal?

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.engueue(item);
    /* GOOD CODE: pthread_cond_signal(&data_ready); */
    /* BAD CODE: */
    if (buffer.size() == 1)
        pthread_cond_signal(&item);
    pthread_mutex_unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

bad case (setup)

thread 0	1	2	3
Consume():			
lock			
empty? wait on cv	Consume():		'
	lock		
	empty? wait on cv		
		Produce(): lock	
		lock	Produce():

bad case

thread 0	1	2	3
Consume():			
lock empty? wait on cv	Consume():		
empty: wait on cv	lock		
	empty? wait on cv		
		Produce():	
		lock	Produce():
			wait for lock
wait for lock		enqueue	
Walt for lock		size = 1? signal unlock	gets lock
		dillock	enqueue
			$size \neq 1$: don't signal
			unlock
gets lock			
dequeue	ctill waiting		
	still waiting		

generalizing locks: semaphores

semaphore has a non-negative integer value and two operations:

P() or **down** or **wait**: wait for semaphore to become positive (> 0), then decerement by 1

V() or **up** or **signal** or **post**: increment semaphore by 1 (waking up thread if needed)

P, V from Dutch: proberen (test), verhogen (increment)

semaphores are kinda integers

semaphore like an integer, but...

cannot read/write directly

down/up operaion only way to access (typically) exception: initialization

never negative — wait instead

down operation wants to make negative? thread waits

reserving books


```
suppose tracking copies of library book...
Semaphore free_copies = Semaphore(3);
void ReserveBook() {
    // wait for copy to be free
    free_copies.down();
    ... // ... then take reserved copy
void ReturnBook() {
    ... // return reserved copy
    free copies.up();
    // ... then wakekup waiting thread
```

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book

Copy 1	
Copy 2	
Сору 3	


free copies 3

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book






suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book




free copies 2 after calling down to reserve

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book



free copies 0 after calling down three times to reserve all copies


suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book





reserve book call down again start waiting...

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book



implementing mutexes with semaphores

```
struct Mutex {
    Semaphore s; /* with inital value 1 */
   /* value = 1 --> mutex if free */
    /* value = 0 --> mutex is busy */
MutexLock(Mutex *m) {
   m->s.down();
MutexUnlock(Mutex *m) {
    m->s.up();
```

implementing join with semaphores

```
struct Thread {
    Semaphore finish_semaphore; /* with initial value 0 */
   /* value = 0: either thread not finished OR already joined */
    /* value = 1: thread finished AND not joined */
};
thread join(Thread *t) {
    t->finish semaphore->down();
  assume called when thread finishes */
thread exit(Thread *t) {
    t->finish semaphore->up();
   /* tricky part: deallocating struct Thread safely? */
```

POSIX semaphores

```
#include <semaphore.h>
...
sem_t my_semaphore;
int process_shared = /* 1 if sharing between processes */;
sem_init(&my_semaphore, process_shared, initial_value);
...
sem_wait(&my_semaphore); /* down */
sem_post(&my_semaphore); /* up */
...
sem_destroy(&my_semaphore);
```

semaphore exercise

```
int value; sem t empty, ready; // with some initial values
void PutValue(int argument) {
    sem_wait(&empty);
    value = argument;
                        What goes in the blanks?
    sem_post(&ready);
                        A: sem_post(&empty) / sem_wait(&ready)
                        B: sem_wait(&ready) / sem_post(&empty)
                        C: sem_post(&ready) / sem_wait(&empty)
int GetValue() {
                        D: sem_post(&ready) / sem_post(&empty)
    int result:
                        E: sem_wait(&empty) / sem_post(&ready)
    result = value;
                        F: something else
    return result;
```

PutValue().
PutValue() waits for prior GetValue(), places value, then allows next GetValue().

GetValue() waits for PutValue() to happen, retrieves value, then allows next

semaphore intuition

```
What do you need to wait for?
     critical section to be finished
     queue to be non-empty
     array to have space for new items
what can you count that will be 0 when you need to wait?
     # of threads that can start critical section now
     # of threads that can join another thread without waiting
     # of items in queue
     # of empty spaces in array
```

use up/down operations to maintain count

producer/consumer constraints

consumer waits for producer(s) if buffer is empty producer waits for consumer(s) if buffer is full any thread waits while a thread is manipulating the buffer

producer/consumer constraints

```
consumer waits for producer(s) if buffer is empty producer waits for consumer(s) if buffer is full any thread waits while a thread is manipulating the buffer
```

one semaphore per constraint:

```
sem_t full_slots; // consumer waits if empty
sem_t empty_slots; // producer waits if full
sem_t mutex; // either waits if anyone changing buffer
FixedSizedQueue buffer;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set size(BUFFER CAPACITY);
Produce(item) {
    sem wait(&empty slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem wait(&full slots); // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem init(\&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set size(BUFFER CAPACITY);
Produce(item) {
    sem wait(&empty slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem wait(&full slots); // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem init(\&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set size(BUFFER CAPACITY);
Produce(item) {
    sem wait(&empty slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem wait(&full slots); // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set size(BUFFER CAPACITY);
Produce(item) {
   sem wait(&empty slots); // wait until free slot, reserve it
   sem wait(&mutex);
                            Can we do
   buffer.enqueue(item);
                              sem_wait(&mutex);
   sem_post(&mutex);
                              sem_wait(&empty_slots); re data
   sem_post(&full_slots);
                            instead?
Consume() {
   sem wait(&full slots); // wait until queued item, reserve it
   sem_wait(&mutex);
   item = buffer.dequeue();
   sem_post(&mutex);
   sem_post(&empty_slots); // let producer reuse item slot
   return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY);
Produce(item) {
   sem wait(&empty slots); // wait until free slot, reserve it
   sem wait(&mutex);
                           Can we do
   buffer.enqueue(item);
                             sem_wait(&mutex);
   sem_post(&mutex);
                             sem_post(&full_slots);
                           instead?
                           No. Consumer waits on sem_wait(&mutex)
Consume() {
   sem_wait(&full_slots);
                           so can't sem post(&empty slots)
   sem_wait(&mutex);
   item = buffer.dequeue() (result: producer waits forever
   sem_post(&mutex);
                          problem called deadlock)
   sem_post(&empty_slots);
   return item;
                                                                  36
```

producer/consumer: cannot reorder mutex/empty

```
ProducerReordered() {
    // BROKEN: WRONG ORDER
    sem_wait(&mutex);
    sem_wait(&empty_slots);
    ...
    sem_post(&mutex);
```

```
Consumer() {
   sem_wait(&full_slots);

// can't finish until
   // Producer's sem_post(&mutex):
   sem_wait(&mutex);

...

// so this is not reached
   sem_post(&full_slots);
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem init(\&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set size(BUFFER CAPACITY);
Produce(item) {
    sem_wait(&empty_slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
   sem_post(&full_slots Can we do
                                                     s more data
                           sem_post(&full_slots);
                           sem post(&mutex);
Consume() {
    sem_wait(&full_slots instead?
                                                       reserve it
   item = buffer.dequeu Yes — post never waits
    sem_wait(&mutex);
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

producer/consumer summary

```
producer: wait (down) empty_slots, post (up) full_slots consumer: wait (down) full_slots, post (up) empty_slots
```

two producers or consumers? still works!

binary semaphores

binary semaphores — semaphores that are only zero or one

as powerful as normal semaphores

exercise: simulate counting semaphores with binary semaphores (more than one) and an integer

gate intuition/pattern

```
pattern to allow one thread at a time:
sem_t gate; // 0 = closed; 1 = open
ReleasingThread() {
    ... // finish what the other thread is waiting for
   while (another thread is waiting and can go) {
        sem_post(&gate) // allow EXACTLY ONE thread
        ... // other bookkeeping
WaitingThread() {
    ... // indicate that we're waiting
    sem_wait(&gate) // wait for gate to be open
    ... // indicate that we're not waiting
```

backup slides

backup slides

recall: pthread mutex


```
#include <pthread.h>
pthread_mutex_t some_lock;
pthread mutex init(&some lock, NULL);
// or: pthread_mutex_t some_lock = PTHREAD_MUTEX_INITIALIZER;
pthread mutex lock(&some lock);
pthread mutex unlock(&some lock);
pthread_mutex_destroy(&some_lock);
```

life homework even/odd

```
naive way has an operation that needs locking:
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    ... compute to grid ...
    swap(from grid, to grid);
but this alternative needs less locking:
Grid grids[2];
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    from grid = &grids[time % 2];
    to_grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
```

life homework even/odd

```
naive way has an operation that needs locking:
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    ... compute to grid ...
    swap(from grid, to grid);
but this alternative needs less locking:
Grid grids[2];
for (int time = 0; time < MAX_ITERATIONS; ++time) {</pre>
    from grid = &grids[time % 2];
    to_grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
```



lock variable in shared memory: the_lock

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax
                           // %eax <- 1
    lock xchg %eax, the_lock // swap %eax and the_lock
                                    // sets the_lock to 1 (taken)
                                    // sets %eax to prior val. of t
                              // if the lock wasn't 0 before:
    test %eax, %eax
    ine acquire
                              // try again
    ret
release:
    mfence
                              // for memory order reasons
                              // then, set the_lock to 0 (not taker
    movl $0, the lock
    ret
```

lock variable in shared memory: the_lock

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax
    lock xchg %eax, the_lock // swap %eax and the_lock
                                           // sets the_lock to 1 (taken)
                                   // sets %eax to prior val. of t

// if set lock variable to 1 (taken) read old value
    test %eax, %eax
    ine acquire
    ret
release:
    mfence
                                   // for memory order reasons
                                   // then, set the_lock to 0 (not taker
    movl $0, the lock
    ret
```

ret

lock variable in shared memory: the lock if 1: someone has the lock; if 0: lock is free to take acquire: movl \$1, %eax lock xchg %eax, the_lock // swap %eax and the lock // sets the_lock to 1 (taken) <u>// sets %eax to prior val</u> of t test %eax, %eax if lock was already locked retry ine acquire "spin" until lock is released elsewhere ret release: mfence // for memory order reasons // then, set the_lock to 0 (not taker movl \$0, the lock

lock variable in shared memory: ${\tt the_lock}$

```
if 1: someone has the lock; if 0: lock is free to take
acquire:
    movl $1, %eax
    lock xchg %eax, the_lock // swap %eax and the lock
                                      // sets the_lock to 1 (taken)
                                          sets %eax to prior val of t
                          release lock by setting it to 0 (not taken)
    test %eax, %eax
    ine acquire
                          allows looping acquire to finish
    ret
release:
```

```
release:

mfence
// for memory order reasons

movl $0, the_lock
// then, set the_lock to 0 (not taken)
ret
```

release:

mfence

ret

movl \$0, the lock

lock variable in shared memory: the lock if 1: someone has the lock; if 0: lock is free to take acquire: movl \$1, %eax lock xchg %eax, the_lock // swap %eax and the lock // sets the_lock to 1 (taken) Intel's manual says: test %eax, %eax no reordering of loads/stores across a lock ine acquire ret or mfence instruction

// for memory order reasons

// then, set the_lock to 0 (not taker

```
48
```

exercise: spin wait

consider implementing 'waiting' functionality of pthread_join

```
thread calls ThreadFinish() when done
```

ThreadWaitForFinish:

```
lock xchg %eax, finished cmp $0, %eax
____ ThreadWaitForFinish ret
```

A. mfence; mov \$1, finished C. mov \$0, %eax E. je B. mov \$1, finished; mfence D. mov \$1, %eax F. jne

spinlock problems

lock abstraction is not powerful enough
lock/unlock operations don't handle "wait for event"
common thing we want to do with threads
solution: other synchronization abstractions

spinlocks waste CPU time more than needed want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks

spinlock problems

lock abstraction is not powerful enough
lock/unlock operations don't handle "wait for event"
common thing we want to do with threads
solution: other synchronization abstractions

spinlocks waste CPU time more than needed

want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks

mutexes: intelligent waiting

want: locks that wait better example: POSIX mutexes

instead of running infinite loop, give away CPU

lock = go to sleep, add self to list sleep = scheduler runs something else

unlock = wake up sleeping thread

mutexes: intelligent waiting

want: locks that wait better example: POSIX mutexes

instead of running infinite loop, give away CPU

lock = go to sleep, add self to list
sleep = scheduler runs something else

unlock = wake up sleeping thread

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock

unlock = use spinlock to remove item from list

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock unlock = use spinlock to remove item from list

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

spinlock protecting lock_taken and wait_queue
only held for very short amount of time (compared to mutex itself)

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

tracks whether any thread has locked and not unlocked

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

list of threads that discovered lock is taken and are waiting for it be free these threads are not runnable

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                               LockSpinlock(&m->guard_spinlock);
 if (m->lock_taken) {
                                               if (m->wait_queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock taken = true:
                                              UnlockSpinlock(&m->guard_spinlock);
   UnlockSpinlock(&m->guard_spinlock);
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

instead of setting lock_taken to false choose thread to hand-off lock to

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                               LockSpinlock(&m->guard_spinlock);
 if (m->lock_taken) {
                                               if (m->wait_queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock taken = true:
                                              UnlockSpinlock(&m->guard_spinlock);
   UnlockSpinlock(&m->guard_spinlock);
```

```
struct Mutex {
     SpinLock guard_spinlock;
     bool lock taken = false;
     WaitQueue wait queue;
};
subtly: if UnlockMutex runs here on another core
need to make sure scheduler on the other core doesn't switch to thread
while it is still running (would 'clone' thread/mess up registers)
                                            UnlockMutex(Mutex *m) {
LockMutex(Mutex ^m) {
  LockSpinlock(&m->guard_spinlock);
                                              LockSpinlock(&m->guard_spinlock);
  if (m->lock_taken) {
                                              if (m->wait_queue not empty) {
                                                remove a thread from m->wait_queue
    put current thread on m->wait_queue
    mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
    UnlockSpinlock(&m->guard_spinlock);
                                              } else {
    run scheduler (context switch)
                                                 m->lock_taken = false;
  } else {
    m->lock taken = true:
                                              UnlockSpinlock(&m->guard_spinlock);
    UnlockSpinlock(&m->guard_spinlock);
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                              LockSpinlock(&m->guard_spinlock);
 if (m->lock_taken) {
                                              if (m->wait_queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock_taken = true;
                                              UnlockSpinlock(&m->guard_spinlock);
   UnlockSpinlock(&m->guard_spinlock);
```

mutex and scheduler subtly

core 0 (thread A)	core 1 (thread B)	
start LockMutex		
acquire spinlock		
discover lock taken		
enqueue thread A		
thread A set not runnable		
release spinlock	start UnlockMutex	
·	thread A set runnable	
	finish UnlockMutex	
	run scheduler	
	scheduler switches to A	
	with old verison of registers	
thread A runs scheduler		l
finally saving registers		
IIII aliy saving ICEIstor	1	

Linux soln.: track 'thread running' separately from 'thread runnable'

xy6 coln: hold schodular lock until throad A cayos registers

mutex and scheduler subtly

core 0 (thread A)	core 1 (thread B)	
start LockMutex		
acquire spinlock		
discover lock taken		
enqueue thread A		
thread A set not runnable		
release spinlock	start UnlockMutex	
•	thread A set runnable	
	finish UnlockMutex	
	run scheduler	
	scheduler switches to A	
	with old verison of registers	
thread A runs scheduler		
finally saving registers		

Linux soln.: track 'thread running' separately from 'thread runnable'

xy6 coln: hold schodular lock until throad A cayos registers

mutex efficiency

'normal' mutex **uncontended** case:

lock: acquire + release spinlock, see lock is free

unlock: acquire + release spinlock, see queue is empty

not much slower than spinlock

implementing locks: single core

intuition: context switch only happens on interrupt timer expiration, I/O, etc. causes OS to run

solution: disable them reenable on unlock

implementing locks: single core

intuition: context switch only happens on interrupt timer expiration, I/O, etc. causes OS to run

solution: disable them reenable on unlock

x86 instructions:

cli — disable interrupts
sti — enable interrupts

naive interrupt enable/disable (1)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}

problem: user can hang the system:
    Lock(some_lock);
    while (true) {}
```

```
Lock() {
                             Unlock() {
    disable interrupts
                                  enable interrupts
problem: user can hang the system:
            Lock(some lock);
            while (true) {}
problem: can't do I/O within lock
            Lock(some lock);
             read from disk
                 /* waits forever for (disabled) interrupt
                    from disk IO finishing */
```

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Unlock() {
Lock() {
    disable interrupts
                                 enable interrupts
problem: nested locks
        Lock(milk lock);
        if (no milk) {
            Lock(store lock);
            buy milk
            Unlock(store lock);
            /* interrupts enabled here?? */
        Unlock(milk lock);
```

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented?

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented?

dynamically allocated array
reallocated on size changes

C++ containers and locking

can you use a vector from multiple threads?

```
...question: how is it implemented?
dynamically allocated array
reallocated on size changes
```

can access from multiple threads ...as long as not append/erase/etc.?

assuming it's implemented like we expect...

but can we really depend on that? e.g. could shrink internal array after a while with no expansion save memory?

C++ standard rules for containers

multiple threads can read anything at the same time can only read element if no other thread is modifying it

can safely add/remove elements if no other threads are accessing container

(sometimes can safely add/remove in extra cases)

exception: vectors of bools — can't safely read and write at same time

might be implemented by putting multiple bools in one int

GCC: preventing reordering example (1)

```
void Alice() {
    int one = 1;
    __atomic_store(&note_from_alice, &one, __ATOMIC_SEQ_CST);
    do {
    } while (__atomic_load_n(&note_from_bob, __ATOMIC_SEQ_CST));
    if (no milk) {++milk:}
Alice:
  movl $1, note from alice
  mfence
.L2:
  movl note from bob, %eax
  testl %eax, %eax
  ine .L2
```

GCC: preventing reordering example (2)

```
void Alice() {
    note from alice = 1;
    do {
        __atomic_thread_fence(__ATOMIC_SEQ_CST);
    } while (note from bob);
    if (no milk) {++milk;}
Alice:
  movl $1, note_from_alice // note_from_alice <- 1</pre>
.L3:
 mfence // make sure store is visible to other cores before
          // on x86: not needed on second+ iteration of loop
  cmpl $0, note from bob // if (note from bob == 0) repeat for
  ine .L3
  cmpl $0, no_milk
```

exercise: fetch-and-add with compare-and-swap

exercise: implement fetch-and-add with compare-and-swap

```
compare_and_swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true; // x86: set ZF flag
    } else {
        return false; // x86: clear ZF flag
    }
}
```

solution

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
 while(xchg(&lk->locked, 1) != 0)
 // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  sync synchronize();
  . . .
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
  while(xchg(&lk->locked, 1) != 0)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
    don't let us be interrupted after while have the lock
    problem: interruption might try to do something with the lock
    ...but that can never succeed until we release the lock
    ...but we won't release the lock until interruption finishes
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
 while(xchg(&lk->locked, 1) != 0)
 // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  sync synchronize();
  . . .
```

xchg wraps the lock xchg instruction same loop as before

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
  while(xchg(&lk->locked, 1) != 0)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
    svnc svnchronize():
  ··· avoid load store reordering (including by compiler)
     on x86, xchg alone is enough to avoid processor's reordering
     (but compiler may need more hints)
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; __sync_synchronize() tells them both not to.
  sync synchronize();
 // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
 popcli();
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
 sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
  popcli turns into instruction to tell processor not to reorder
         plus tells compiler not to reorder
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; sync synchronize() tells them both not to.
  sync synchronize();
 // Release the lock, equivalent to lk->locked = 0.
 // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
  popcli();
          turns into mov of constant 0 into lk->locked
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; sync synchronize() tells them both not to.
  sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
 popcli().
        reenable interrupts (taking nested locks into account)
```

fetch-and-add with CAS (1)

```
compare-and-swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true;
    } else {
        return false;
long my_fetch_and_add(long *pointer, long amount) { ... }
implementation sketch:
    fetch value from pointer old
    compute in temporary value result of addition new
    try to change value at pointer from old to new
    [compare-and-swap]
    if not successful, repeat
```

fetch-and-add with CAS (2)

```
long my_fetch_and_add(long *p, long amount) {
    long old_value;
    do {
        old_value = *p;
    } while (!compare_and_swap(p, old_value, old_value + amount);
    return old_value;
}
```

exercise: append to singly-linked list

ListNode is a singly-linked list assume: threads *only* append to list (no deletions, reordering) use compare-and-swap(pointer, old, new): atomically change *pointer from old to new return true if successful return false (and change nothing) if *pointer is not old void append to list(ListNode *head, ListNode *new last node) {

some common atomic operations (1)

```
// x86: emulate with exchange
test and set(address) {
    old_value = memory[address];
    memory[address] = 1;
    return old value != 0; // e.g. set ZF flag
// x86: xchq REGISTER, (ADDRESS)
exchange(register, address) {
    temp = memory[address];
    memory[address] = register;
    register = temp;
```

some common atomic operations (2)

```
// x86: mov OLD_VALUE, %eax; lock cmpxchq NEW_VALUE, (ADDRESS)
compare—and—swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true; // x86: set ZF flag
    } else {
        return false; // x86: clear ZF flag
// x86: lock xaddl REGISTER, (ADDRESS)
fetch-and-add(address, register) {
    old value = memory[address];
    memory[address] += register;
    register = old value;
```

common atomic operation pattern

```
try to do operation, ...

detect if it failed

if so, repeat
```

atomic operation does "try and see if it failed" part

cache coherency states

extra information for each cache block overlaps with/replaces valid, dirty bits

stored in each cache

update states based on reads, writes and heard messages on bus

different caches may have different states for same block

MSI state summary

Modified value may be different than memory and I am the only one who has it

Shared value is the same as memory

Invalid I don't have the value; I will need to ask for it

MSI scheme

from state	hear read	hear write	read	write		
Invalid			to Shared	to Modified		
Shared		to Invalid		to Modified		
Modified	to Shared	to Invalid		_		
blue, transition requires conding response on bus						

blue: transition requires sending message on bus

MSI scheme

```
from state hear read hear write read write

Invalid — to Shared to Modified
Shared — to Invalid — to Modified
Modified to Shared to Invalid — —

blue: transition requires sending message on bus
```

example: write while Shared must send write — inform others with Shared state then change to Modified

MSI scheme

from state	hear read	hear write	read	write		
Invalid			to Shared	to Modified		
Shared		to Invalid		to Modified		
Modified	to Shared	to Invalid	_			
blue: transition requires sending message on bus						

example: write while Shared

must send write — inform others with Shared state then change to Modified


example: hear write while Shared

change to Invalid


can send read later to get value from writer

example: write while Modified nothing to do — no other CPU can have a copy

MSI example




MSI example




79

MSI example




CPU1 writes 102 to 0xA300

MSI example




CPU2 reads 0xA300

MSI example



MSI example



MSI: update memory

to write value (enter modified state), need to invalidate others can avoid sending actual value (shorter message/faster)

"I am writing address X" versus "I am writing Y to address X"

MSI: on cache replacement/writeback

still happens — e.g. want to store something else

changes state to invalid

requires writeback if modified (= dirty bit)

cache coherency exercise

```
modified/shared/invalid; all initially invalid; 32B blocks, 8B
read/writes
     CPU 1: read 0x1000
     CPU 2: read 0x1000
     CPU 1: write 0x1000
     CPU 1: read 0x2000
     CPU 2: read 0x1000
     CPU 2: write 0x2008
     CPU 3: read 0x1008
Q1: final state of 0x1000 in caches?
     Modified/Shared/Invalid for CPU 1/2/3
```

Q2: final state of 0x2000 in caches? Modified/Shared/Invalid for CPU 1/2/3

CPU 1:

Modified/Shared/Invalid for CPU 1/2/3 CPU 1: CPU 2:

CPU 2:

CPU 3:

CPU 3:

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

C++: preventing reordering

to help implementing things like pthread_mutex_lock

C++ 2011 standard: *atomic* header, *std::atomic* class prevent CPU reordering *and* prevent compiler reordering also provide other tools for implementing locks (more later)

could also hand-write assembly code compiler can't know what assembly code is doing

C++: preventing reordering example

```
#include <atomic>
void Alice() {
    note_from_alice = 1;
    do {
        std::atomic thread fence(std::memory order seg cst);
    } while (note from bob);
    if (no milk) {++milk;}
Alice:
  movl $1, note_from_alice // note_from alice <- 1</pre>
.L2:
  mfence // make sure store visible on/from other cores
  cmpl $0, note from bob // if (note from bob == 0) repeat fence
  jne .L2
  cmpl $0, no milk
```

C++ atomics: no reordering

```
std::atomic<int> note_from_alice, note_from_bob;
void Alice() {
    note_from_alice.store(1);
    do {
    } while (note from bob.load());
    if (no milk) {++milk;}
Alice:
  movl $1, note_from alice
  mfence
.L2:
  movl note from bob, %eax
  testl %eax, %eax
  ine .L2
```

GCC: built-in atomic functions

used to implement std::atomic, etc.

predate std::atomic

builtin functions starting with __sync and __atomic

these are what xv6 uses

aside: some x86 reordering rules

```
each core sees its own loads/stores in order (if a core stores something, it can always load it back)
```

stores from other cores appear in a consistent order (but a core might observe its own stores too early)

causality:

```
if a core reads X=a and (after reading X=a) writes Y=b, then a core that reads Y=b cannot later read X=older value than a
```

how do you do anything with this?

difficult to reason about what modern CPU's reordering rules do typically: don't depend on details, instead:

special instructions with stronger (and simpler) ordering rules often same instructions that help with implementing locks in other ways

special instructions that restrict ordering of instructions around them ("fences")


loads/stores can't cross the fence


spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads solution: other synchronization abstractions


spinlocks waste CPU time more than needed want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks







CPU2 read-modify-writes lock (to see it is still locked)



CPU3 read-modify-writes lock (to see it is still locked)




CPU2 read-modify-writes lock (to see it is still locked)



CPU3 read-modify-writes lock (to see it is still locked)

"I want to modify lock" CPU1 CPU₂ CPU3 MEM1 address value state address value state address value state lock unlocked Modified lock Invalid lock Invalid

CPU1 sets lock to unlocked



some CPU (this example: CPU2) acquires lock

test-and-set problem: cache block "ping-pongs" between caches each waiting processor reserves block to modify could maybe wait until it determines modification needed — but not typical implementation

each transfer of block sends messages on bus


...so bus can't be used for real work like what the processor with the lock is doing


test-and-test-and-set (pseudo-C)

```
acquire(int *the_lock) {
    do {
        while (ATOMIC-READ(the_lock) == 0) { /* try again */ }
    } while (ATOMIC-TEST-AND-SET(the_lock) == ALREADY_SET);
}
```


test-and-test-and-set (assembly)

```
acquire:
   cmp $0, the_lock  // test the lock non-atomically
          // unlike lock xchg --- keeps lock in Shared state!
   ine acquire
               // try again (still locked)
   // lock possibly free
   // but another processor might lock
   // before we get a chance to
   // ... so try wtih atomic swap:
   movl $1, %eax <- 1
   lock xchg %eax, the lock // swap %eax and the lock
         // sets the lock to 1
         // sets %eax to prior value of the lock
   test %eax, %eax // if the lock wasn't 0 (someone else
                     // try again
   jne acquire
   ret
```







CPU2 reads lock (to see it is still locked)



CPU1 writes back lock value, then CPU2 reads it



CPU3 reads lock (to see it is still locked)




CPU2, CPU3 continue to read lock from cache no messages on the bus

"I want to modify lock" CPU2 CPU3 CPU1 MEN address value state address value state address value state lock unlocked Modified lock Invalid lock Invalid

CPU1 sets lock to unlocked

"I want to modify lock"



some CPU (this example: CPU2) acquires lock (CPU1 writes back value, then CPU2 reads + modifies it)

couldn't the read-modify-write instruction...

notice that the value of the lock isn't changing...

and keep it in the shared state

maybe — but extra step in "common" case (swapping different values)

more room for improvement?

can still have a lot of attempts to modify locks after unlocked there other spinlock designs that avoid this ticket locks

MCS locks

...

MSI extensions

real cache coherency protocols sometimes more complex:

separate tracking modifications from whether other caches have copy

send values directly between caches (maybe skip write to memory) send messages only to cores which might care (no shared bus)

too much milk

roommates Alice and Bob want to keep fridge stocked with milk:

time	Alice	Bob
3:00	look in fridge. no milk	
3:05	leave for store	
3:10	arrive at store	look in fridge. no milk
3:15	buy milk	leave for store
3:20	return home, put milk in fridge	arrive at store
3:25		buy milk
3:30		return home, put milk in fridge

how can Alice and Bob coordinate better?

too much milk "solution" 1 (algorithm)

```
leave a note: "I am buying milk"
     place before buying, remove after buying
    don't try buying if there's a note
\approx setting/checking a variable (e.g. "note = 1")
    with atomic load/store of variable
if (no milk) {
     if (no note) {
          leave note;
          buy milk;
          remove note;
```

```
leave a note: "I am buying milk"
     place before buying, remove after buying
    don't try buying if there's a note
\approx setting/checking a variable (e.g. "note = 1")
    with atomic load/store of variable
if (no milk) {
     if (no note) {
          leave note;
          buy milk;
          remove note;
exercise: why doesn't this work?
```

too much milk "solution" 1 (timeline)

```
Alice
                                    Bob
if (no milk) {
    if (no note) {
                            if (no milk) {
                                if (no note) {
        leave note;
        buy milk;
        remove note;
                                    leave note;
                                    buy milk;
                                    remove note;
```

intuition: leave note when buying or checking if need to buy

```
leave note;
if (no milk) {
    if (no note) {
       buy milk;
    }
}
remove note;
```

too much milk: "solution" 2 (timeline)

```
Alice
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

too much milk: "solution" 2 (timeline)

```
Alice
leave note;
if (no milk) {
   if (no note) { ← but there's always a note buy milk;
   }
}
remove note;
```

too much milk: "solution" 2 (timeline)

"solution" 3: algorithm

```
intuition: label notes so Alice knows which is hers (and vice-versa)
    computer equivalent: separate noteFromAlice and noteFromBob
    variables
            Alice
                                                      Bob
                                       leave note from Bob;
leave note from Alice;
                                       if (no milk) {
if (no milk) {
    if (no note from Bob) {
                                            if (no note from Alice
         buy milk
                                                buy milk
remove note from Alice;
                                       remove note from Bob;
```

too much milk: "solution" 3 (timeline)

```
Alice
                                      Bob
leave note from Alice
if (no milk) {
                              leave note from Bob
    if (no note from Bob) {
                              if (no milk) {
                                  if (no note from Alice) {
                              remove note from Bob
```

remove note from Alice

too much milk: is it possible

is there a solutions with writing/reading notes? \approx loading/storing from shared memory

yes, but it's not very elegant

```
Alice
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

```
Bob
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
     }
}
remove note from Bob
```

```
Alice
                                             Bob
leave note from Alice
                                 leave note from Bob
while (note from Bob) {
                                 if (no note from Alice) {
    do nothing
                                     if (no milk) {
                                          buy milk
   (no milk) {
    buy milk
                                 remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
```

```
Alice
                                             Bob
leave note from Alice
                                 leave note from Bob
while (note from Bob) {
                                 if (no note from Alice) {
    do nothing
                                     if (no milk) {
                                          buy milk
   (no milk) {
    buy milk
                                 remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
```

```
Alice
                                             Bob
leave note from Alice
                                  leave note from Bob
while (note from Bob) {
                                  if (no note from Alice) {
    do nothing
                                      if (no milk) {
                                          buy milk
   (no milk) {
    buy milk
                                  remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
exercise (hard): extend to three people
```

Peterson's algorithm

general version of solution

see, e.g., Wikipedia

we'll use special hardware support instead

mfence

x86 instruction mfence

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

mfence

x86 instruction mfence

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

aside: this instruction is did not exist in the original x86 so xv6 uses something older that's equivalent

modifying cache blocks in parallel

cache coherency works on cache blocks

but typical memory access — less than cache block e.g. one 4-byte array element in 64-byte cache block

what if two processors modify different parts same cache block?

4-byte writes to 64-byte cache block


cache coherency — write instructions happen one at a time: processor 'locks' 64-byte cache block, fetching latest version processor updates 4 bytes of 64-byte cache block later, processor might give up cache block

modifying things in parallel (code)

```
void *sum_up(void *raw_dest) {
    int *dest = (int *) raw_dest;
    for (int i = 0; i < 64 \times 1024 \times 1024; ++i) {
        *dest += data[i];
attribute ((aligned(4096)))
int array[1024]; /* aligned = address is mult. of 4096 */
void sum twice(int distance) {
    pthread t threads[2];
    pthread_create(&threads[0], NULL, sum_up, &array[0]);
    pthread_create(&threads[1], NULL, sum_up, &array[distance]);
    pthread_join(threads[0], NULL);
    pthread join(threads[1], NULL);
```

performance v. array element gap

(assuming sum_up compiled to not omit memory accesses)



false sharing

synchronizing to access two independent things

two parts of same cache block

solution: separate them

exercise (1)

```
int values[1024];
int results[2];
void *sum_front(void *ignored_argument) {
    results[0] = 0;
    for (int i = 0; i < 512; ++i)
        results[0] += values[i];
    return NULL;
}
void *sum_back(void *ignored_argument) {
    results[1] = 0;
    for (int i = 512; i < 1024; ++i)
        results[1] += values[i];
    return NULL:
int sum_all() {
    pthread_t sum_front_thread, sum_back_thread;
    pthread create(&sum front thread, NULL, sum front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL);
    pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
}
```

Where is false sharing likely to occur? How to fix?

exercise (2)

```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        my_info->result += my_info->values[i];
    return NULL;
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
}
```


Where is false sharing likely to occur?

connecting CPUs and memory

multiple processors, common memory

how do processors communicate with memory?

shared bus



one possible design

we'll revisit later when we talk about I/O

tagged messages — everyone gets everything, filters

contention if multiple communicators some hardware enforces only one at a time

shared buses and scaling

shared buses perform poorly with "too many" CPUs

so, there are other designs

we'll gloss over these for now

shared buses and caches


remember caches?

memory is pretty slow


each CPU wants to keep local copies of memory

what happens when multiple CPUs cache same memory?

the cache coherency problem



the cache coherency problem



CPU1 writes 101 to 0xA300?

Anderson-Dahlin and semaphores

Anderson/Dahlin complains about semaphores

"Our view is that programming with locks and condition variables is superior to programming with semaphores."

argument 1: clearer to have separate constructs for waiting for condition to be come true, and allowing only one thread to manipulate a thing at a time

arugment 2: tricky to verify thread calls up exactly once for every down

alternatives allow one to be sloppier (in a sense)

monitors with semaphores: locks

```
sem_t semaphore; // initial value 1

Lock() {
    sem_wait(&semaphore);
}

Unlock() {
    sem_post(&semaphore);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
problem: signal wakes up non-waiting threads (in the far future)
```

monitors with semaphores: cvs (better)

start with only wait/signal:

```
sem t private lock; // initially 1
int num_waiters;
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
                                           Signal() {
  sem_wait(&private_lock);
                                             sem_wait(&private_lock);
                                             if (num waiters > 0) {
  ++num waiters;
  sem_post(&private_lock);
                                               sem_post(&threads_to_wakeup);
  lock.Unlock();
                                               --num_waiters;
  sem_wait(&threads_to_wakeup);
  lock.Lock();
                                             sem_post(&private_lock);
```

monitors with semaphores: broadcast

now allows broadcast:

```
sem_t private_lock; // initially 1
int num waiters;
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
                                          Broadcast() {
  sem_wait(&private_lock);
                                             sem_wait(&private_lock);
  ++num waiters;
                                             while (num_waiters > 0) {
  sem_post(&private_lock);
                                               sem_post(&threads_to_wakeup);
  lock.Unlock();
                                               --num waiters;
  sem_wait(&threads_to_wakeup);
  lock.Lock();
                                             sem_post(&private_lock);
```

pthread_mutex_t lock;

lock to protect shared state

```
pthread_mutex_t lock;
unsigned int count;
```

lock to protect shared state

shared state: semaphore tracks a count

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 *,
pthread_cond_t count_is_positive_cv;
```

lock to protect shared state shared state: semaphore tracks a count

add cond var for each reason we wait semaphore: wait for count to become positive (for down)

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
void down() {
    pthread_mutex_lock(&lock);
   while (!(count > 0)) {
        pthread_cond_wait(
            &count_is_positive_cv,
            &lock);
    count -= 1;
    pthread mutex unlock(&lock);
```

lock to protect shared state shared state: semaphore tracks a count

add cond var for each reason we wait semaphore: wait for count to become positive (for down)

wait using condvar; broadcast/signal when condition changes

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
void down() {
                                        void up() {
    pthread_mutex_lock(&lock);
                                            pthread_mutex_lock(&lock);
   while (!(count > 0)) {
                                            count += 1;
        pthread_cond_wait(
                                            /* count must now be
            &count_is_positive_cv,
                                               positive, and at most
            &lock);
                                               one thread can go per
                                               call to Up() */
                                            pthread_cond_signal(
    count -= 1:
    pthread_mutex_unlock(&lock);
                                                &count is positive cv
                                            pthread_mutex_unlock(&lock);
lock to protect shared state
```

add cond var for each reason we wait semaphore: wait for count to become positive (for down)

shared state: semaphore tracks a count

wait using condvar; broadcast/signal when condition changes

counting semaphores with binary semaphores

via Hemmendinger, "Comments on 'A correct and unrestrictive implementation of general semaphores' " (1989); Barz, "Implementing semaphores by binary semaphores" (1983) // assuming initialValue > 0 BinarySemaphore mutex(1); int value = initialValue ; BinarvSemaphore gate(1 /* if initialValue >= 1 */); /* gate = # threads that can Down() now */ void Down() { void Up() { gate.Down(); mutex.Down(); // wait, if needed value += 1; mutex.Down(); **if** (value == 1) { value -= 1; gate.Up(); **if** (value > 0) { // because down should finish now gate.Up(); // but could not before // because next down should finish // now (but not marked to before) mutex.Up(); mutex.Up();

backup slides