Engineering Journal

CIT167 Chaz Davis

> BCTC Spring 2020

March 19, 2020

Contents

U	Useful Commands: Basics		
U	Useful Bits: Basics		
1	Configuring Basic Router	9	
2	Documenting The Network	15	
3	Configuring IPv4 and IPv6	19	
U	Useful Commands: Static Routing		
U	seful Bits: Static Routing	30	
4	Troubleshooting Static Routes	32	
5	Configuring IPv6 Static Routes	35	
6	Configuring IPv4 Static	40	
U	seful Commands: Dynamic Routing	47	
U	seful Bits: Dynamic Routing	49	
7	Configuring RIPv2	53	
8	Configuring Basic RIPv2	56	
U	Useful Bits: SSH and Port Security		
U	seful Commands: SSH and Port Security	63	
9	Basic Switch Configuration	66	
10	Configuring Switch Security	73	
U	seful Commands: Configuring VLANs	77	
11	Troubleshooting Vlan	80	
12	Troubleshooting Vlans Scenario 2	83	
13	Configuring Vlans and Trunks	89	

Chaz Davis	March 19, 2020
14 Legacy InterVlan Implementation	92
15 Router on a Stick	96

Basic Commands

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

Basic Router Commands

Router Config Commands

```
Router#
Router# configure terminal Router# show ?
Router# show running-config
Router# copy running-config startup-config
Router# ping 192.168.1.100
Router# traceroute 192.168.1.100
Router# ssh 192.168.1.100
Router# telnet 192.168.1.100
Router# debug ?
Router# clock set 07:14:00 October 15 2019
Router# reload
Router(conf)#
Router(conf)# hostname R1
Router(conf)# banner motd "No unauthorized access allowed!"
Router(conf)# enable password class
Router(conf)# enable secret class
Router(conf)# service password-encryption
Router(config)# line vty 0 15
Router(config)# line console 0
Router(config)# interface gigabitEthernet 0/0/0
Router(config-line)#
Router(config-line)# password cisco
Router(config-line)# login
Router(config-line)# transport input all (line vty)
Router(config-if)# interface gigabitEthernet 0/0/0 Router(config-if)# int g0/0 //command abbreviation
Router(config-if)# ip address 192.168.1.1 255.255.255.0
Router(config-if)# no shutdown
```

Basic Switch Commands

```
Switch> ---User EXEC mode exit
Switch> enable
Switch# ---Privileged EXEC mode disable, exit
Switch# configure terminal
Switch(config)# ---Global Config mode exit, end, Ctrl+c, Ctrl+z
Switch(config)# line vty 0 15
Switch(config)# line console 0
Switch(config-line)# ---Line configuration mode exit, end, Ctrl+c, Ctrl+z
Switch(config)# interface vlan 1
\begin{tabular}{lll} \textbf{Switch}(\textbf{config-if}) \textbf{\#} & \textbf{---Interface configuration mode exit, end, Ctrl+z, Ctrl+z} \\ \end{tabular}
Switch#
Switch# configure terminal
Switch# show ?
Switch# show running-config
Switch# copy running-config startup-config
Switch# ping 192.168.1.100
Switch# traceroute 192.168.1.100
Switch# ssh 192.168.1.100
Switch# telnet 192.168.1.100
Switch# debug ?
Switch# clock set 07:14:00 October 15 2019
Switch# reload
Switch(conf)#
Switch(conf)# hostname R1
Switch(conf)# banner motd "No unauthorized access allowed!"
Switch(conf)# enable password class
Switch(conf)# enable secret class
Switch(conf)# service password-encryption
Switch(config)# line vty 0 15
Switch(config)# line console 0
Switch(config)# interface vlan 1
Switch(config-line)#
Switch(config-line)# password cisco
Switch(config-line)# login
Switch(config-line)# transport input all (line vty)
Switch(config-if)#
Switch(config-if)# interface vlan 1
Switch(config-if)# ip address 192.168.1.2 255.255.255.0
Switch(config-if)# no shutdown
Switch(config-if)# exit
Switch(config)# ip default-gateway 192.168.1.1
```

Extra helpful commands:

```
Router(conf)# no ip domain-lookup //prevents miss-typed commands from being "translated..."
Router(conf-line)# logging synchronous //prevents logging output from interrupting your command input
```

Useful Bits: Basics

2020

Packet Tracer Labs
Spring 2020
Chaz Davis

```
User can interact with a shell with a CLI or a GUI.
Cisco IOS is used for cisco devices
The most common way to configure a HOME router is with a web broswer
Methods to access the CLI environment:
-Console : Physical management port that provides out of band access,
       works even without connectivity
-SSH : Secure CLI connection, requires active networking services -Telnet: Like SSH but insecure because everything is sent in cleartext
Some devices also support a legacy AUX port used to establish remote CLI session using a modem.
It works similarly to console connection.
Some useful terminal emulators via SSH/Telnet:
-PuTTY
-Tera term
-OS X terminal
-SecureCRT
For security Cisco IOS separates management access into two modes:  \\
-User EXEC mode: Limited capabilities but useful for basic operations and monitoring,
    {\tt Doesn't\ allow\ change\ to\ configurations}
    CLI prompt ends with a >
    referred as 'view-only' mode
-Privileged EXEC mode: Higher configuration modes can only be accessed this mode
                           CLI prompt ends with a #
To configure the device the user must enter {\tt Global} configuration mode:
 - it is identified by a command prompt that ends with (config)#
- changes here affect the device as a whole % \left\{ 1\right\} =\left\{ 1\right\}
- from here you can access more specifi sub-configuration mode for specific function of the IOS device:
Two common subs are:
 -Line configuration Mode: (config-line)#
-Interface configuration Mode: (config-if)#
If you type 'enable' on command line you go from user EXEC to privileged EXEC mode
If you type 'disable' on command line you return to the user EXEC mode
From privileged EXEC mode if i type 'configure terminal' i go to Global configuration mode
To return to privileged EXEC mode type 'exit'
```

```
From Global configuration mode if i type 'interface <interface-name> <interface-number'
  i get to the specific interface configuration
for the specified interface, the same for line 'line <line-name' <line-number'.
You don't need to return to global configuration mode to switch between sub-configurations.
To return to Global Configuration mode (from sub-configuration) type 'exit'.
To return directly to Privileged exec mode type 'end' or press 'Ctrl+Z'
The general command syntax is the command followed by keywords and arguments:
-Keyword : a specific parameter defined in the operating system
-Argument: not predefined, a variable or value user-defined.
boldface: commands and literals that you enter as shown
italics: arguments for which you suplly values
[x] : Optional element
{x} : Required element
[x \{y \mid z\}]: Required choice within an optional argument
IOS helps:
-Context-sensitive help:
Helps you find quickly which command are available in each command mode
To access it type '?' at the CLI
It can even be used to check what parameters a particular command accept
or to finish the name of a command.
Command syntax check:
If a command is entered wrong, the CLI provides the user a feedback about what is wrong.
```

```
Cisco IOS shortcuts
{\tt IMPORTANT\ SHORTCUTS\ :\ Ctrl-Shift-6\ To\ abort\ a\ command\ mid-stream}
  (Useful for mistyped commands and cisco IOS attempting translate it with DNS)
     Ctrl+R refresh last command (example if an output of a interface down/up
    shows in the middle of typing a command)
Hostnames:
-Case sensitive
-to change hostname use the command 'hostname <hostname>' in Global Config Mode
-to reset default hostname use the command 'no hostname' in Global Config Mode
-use 'enable secret <password>' in Global Config Mode to set password for Privileged Exec Mode
-to set a password in user EXEC mode, type 'password password>' in line console configuration mode
('line console 0' global config command)
next enable user login with the 'login' command
-to set a password for VTY (Virtual terminal) lines used for SSH and Telnet enter line VTY config mode
with 'line vty 0 15' (if 16 vty lines)
next set password with 'password <password>' and enable login with 'login'
-To encrypt passwords:
Use command 'service password-encryption', this applies only to configuration files
To check the config for encryption run 'show running-config'
To add a banner message of the day use 'banner motd # the message of the day # '
There are two types of config:
-startup config ,stored in NVRAM, to view it use 'show startup-config'
-running config ,stored in RAM
To save changes made to the running config in the startup config do 'copy running-config startup-config'
To restore the startup config run in privileged EXEC mode 'reload'
If unwanted changes were made to the startup config file it is
      possible to remove it by using 'erase startup-config'
```

```
Types of network media include twisted-pair copper cables,
   fiber-optic cables,
   coaxial cables,
   or wireless as shown in the figure.

Difference between them:

Distance the media can successfully carry a signal

Environment in which the media is to be installed

Amount of data and the speed at which it must be transmitted

Cost of the media and installation
```

```
Cisco IOS Layer 2 switches have physical ports for devices to connect.
These ports do not support Layer 3 IP addresses.
Therefore, switches have one or more switch virtual interfaces (SVIs)

IP address information can be added:
--manually
--using DHCP

To configure SVI use 'interface vlan 1' in global config mode.
Assign an ip address using 'ip address <ip-address> <subnet-mask>'
Enable the inteface using 'no shutdown'

To see a brief interface ip screen : 'show ip inteface brief'

To test the connectivity of a device on a network or of a website use the command 'ping <ip-address>'
```

Lab 1

Configuring Basic Router Settings

Jan 23, 2020

CIT 167

Packet Tracer Lab 1 Spring 2020 Chaz Davis

- Important Commands for the Lab
 - no ip domain lookup suppresses all DNS-lookups from the router to the configured DNS seves allows for sloppy typing keeps from doing a lookup everytime better practice configure ip name-server then disable automatic telnetting to "hostnames"" transport prefferred none and set that for con, aux, and vty
 - exec-timeout 5 0

configure the inactive session timeout on console port parameter passed in is minutes if two nubers passed the second is seconds

· logging synchronous

for when long commands are interrupted by console message tells the router to hold messages until it detects no input from the keyboard

• service password-encryption

normally all passwords, except enable secret, are stored in clear-text stores all passwords in an encrypted form stores them using an MD5 hashing algorithm

- ? allows you to look up help from command line similar to -help on linux

if no help available, returns <CR>

- Important Concepts
 - Understand the process of setting up new schemes
 - Logging in over ssh and telnet from the commandline
 - · Finding info through the long lines of output

Part 1:Set Up the Topology

i) Cable the Network

I started off by placing the the router (1941), the switch (2960), and 2 windows 7 pcs on the the canvas.



Figure 1.1: View of the Network Topology

ii) Wiring up the routers

Next I used straight copper wiring to connect the router the switch and the two pcs and renamed the accordingly. See Fig 1.2.



Figure 1.2: Configuring the Network

Part 2: Configure Devices and Verify connectivity

I started off by configuring the ipaddress, subnet mask, and default gateways on PC-A and PC-B

i) Configuring the PCs

I started off by configuring the IPs for the PC's. See Fig 1.3.



Figure 1.3: Configuring the IPs

ii) Configuring the router

Next I logged into the router went to the commandline, and escalated to priveledged exec mode.

1

Name and passwords

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#no ip domain lookup
R1(config)#no ip domain-lookup
R1(config)#security passwords min-length 10
R1(config)#enable secret cisco12345
R1(config)#line con 0
R1(config-line)#password coscoconpass
R1(config-line)#exec-timeout 5 0
R1(config-line)#login
R1(config-line)#logging synchronous
R1(config-line)#exit
R1(config)#line vty 0 4
R1(config-line)#password ciscovtypass
R1(config-line)#exec-timeout 5 0
R1(config-line)#login
R1(config-line)#logging synchronous
R1(config-line)# exit
R1(config)#service password-encryption
R1(config)#banner motd #Unauthorized access prohibited!#
```

$\mathbf{2}$

Connections

```
R1(config)#int g0/0
R1(config-if)\#description Connection to PC-B
R1(config-if)#ip address 192.168.0.1 255.255.255.0
R1(config-if)#no shut
R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0,
changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface
GigabitEthernet0/0, changed state to up
R1(config-if)#exit
R1(config)#exit
%SYS-5-CONFIG_I: Configured from console by console
R1#clock set 10:00:00 28 Jan 2020
R1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
```

I then did the same for PC-A

```
R1(config)#int g 0/1
R1(config-if)#description Connection to S1
R1(config-if)#ip address 192.168..1.1 255.255.255.0

% Invalid input detected at '^' marker.

R1(config-if)#ip address 192.168.

% Invalid input detected at '^' marker.

R1(config-if)#ip address 192.168.1.1 255.255.255.0
R1(config-if)#no shut


R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up


R1(config-if)#
```

3

Verifying network connectivity







(b) Pingin PC-B from PC-A

(c) Telnet PC-A to R1

Figure 1.4: Verifying the Network Connectivity

Part 3: Display Router Information

i) important hardware and software info

While logged in with telnet I ran the following commands

```
R1>show version
Cisco IOS Software, C1900 Software (C1900-UNIVERSALK9-M),
Version 15.1(4)M4, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 23-Feb-11 14:19 by pt_team
ROM: System Bootstrap, Version 15.1(4)M4, RELEASE SOFTWARE (fc1)
cisco1941 uptime is 1 hours, 19 minutes, 11 seconds
System returned to ROM by power-on
System image file is "flash0:c1900-universalk9-mz.SPA.151-1.M4.bin"
Last reload type: Normal Reload
This product contains cryptographic features
and is subject to United States and local country
laws governing import, export, transfer and
use. Delivery of Cisco cryptographic products does not imply
third-party authority to import, export,
distribute or use encryption. Importers, exporters,
distributors and users are responsible for
compliance with U.S. and local country laws
By using this product you agree to comply with
applicable laws and regulations. If you are unable to
comply with U.S. and local laws,
return this product immediately.
A summary of U.S. laws governing Cisco
```

```
cryptographic products may be found at:
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html
```

We can see that the IOS image on the router is Cisco IOS Software,

```
C1900 Software (C1900-UNIVERSALK9-M), Version 15.1(4)M4, RELEASE SOFTWARE (fc2)
```

We can also see that the NVRAM by using show flash:

```
R1#show flash

System flash directory:
File Length Name/status
3 33591768 c1900-universalk9-mz.SPA.151-4.M4.bin
2 28282 sigdef-category.xml
1 227537 sigdef-default.xml
[33847587 bytes used, 221896413 available, 255744000 total]
249856K bytes of processor board System flash (Read/Write)
```

ii) Display Startup Info

```
R1#show startup-config
Using 959 bytes
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
security passwords min-length 10
hostname R1
enable secret 5 $1$mERr$WvpWOn5HghRrqnrwXCUUl.
ip cef
no ipv6 cef
license udi pid CISCO1941/K9 sn FTX1524C630-
no ip domain-lookup
spanning-tree mode pvst
interface GigabitEthernet0/0
description Connection to PC-B
 ip address 192.168.0.1 255.255.255.0
 duplex auto
 speed auto
interface GigabitEthernet0/1
 no ip address
 duplex auto
 speed auto
shutdown
interface Vlan1
no ip address
 shutdown
ip classless
ip flow-export version 9
banner motd ^CUnauthorized access prohibited!^C
line con 0
exec-timeout 5 0
password 7 0822435D0A1606181C1B0D1739
 logging synchronous
login
line aux 0
line vty 0 4
 exec-timeout 5 0
 password 7 0822455D0A1613030B1B0D1739
```

```
logging synchronous
login
!
end
```

From this we can see that the passwords are encrypted

I used show startup-config | begin vty

It did not like that command wouldnt show any info

iii) Display the routing table on the router

I ran show ip route

```
R1#show ip route
Codes:
L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2, E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2,
ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
  192.168.0.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.0.0/24 is directly connected, GigabitEthernet0/0 L 192.168.0.1/32 is directly connected, GigabitEthernet0/0
  192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.1.0/24 is directly connected, GigabitEthernet0/1
L 192.168.1.1/32 is directly connected, GigabitEthernet0/1
R1#
```

There are two entries with a C encoding

iv) Display a summary list

Display a summary list of the interfaces on the router

I ran the show ip interface brief command:

```
show ip interface brief
Interface IP-Address OK? Method Status Protocol
GigabitEthernetO/0 192.168.0.1 YES manual up up
GigabitEthernetO/1 192.168.1.1 YES manual up up
Vlan1 unassigned YES unset administratively down down
```

when we gave the command 'no shut' that changed the gig ethernet ports from down to up.

Lab 2

Documenting The Network

Jan 26, 2020

Packet Tracer Lab 2
Spring 2020
Chaz Davis

```
- Important Commands for the Lab
```

 $\bullet~$ show interface displays the status of the router's interfaces

interface status up/down

Protocol status on the device

Utilization

Errors

MTU

MTU

• show ip interface (brief) tons of useful info:

IP protocol status

all its services

all of its interfaces and their protocols and status'

Ip address

Layer 2 status

layer 3 status

it is the config thats in the routers memory.

sh run this is not updated upon changes. but upon running the command copy running-configuration startup-configuration $\frac{1}{2}$

• show ip route

lists all networks that the router can reach

their metric - the routers preference for them and how to get there

• show version gives the routers config register (firmware settings)

the last time it was booted

the version of the IOS

the model of router

the amount of ram and Flash

Part 1: filling in the table

i) R2

I logged into R2 and ran the following commands i ran show ip config

```
IP-Address
                                      OK? Method Status Protocol
                      10.255.255.245 YES manual up
GigabitEthernet0/0
GigabitEthernet0/1
                      10.255.255.249 YES manual up
                                                          up
GigabitEthernet0/2
                      10.10.10.1
                                      YES manual up
Serial0/0/0
                      64.100.100.1
                                     YES manual up
Serial0/0/1
                      unassigned
                                      YES unset up
                      64.100.200.2
Serial0/0/1.1
                                     YES manual up
Vlan1
                      unassigned
                                     YES unset
administratively down down
```

I then ran show interfaces

```
GigabitEthernetO/O is up, line protocol is up (connected)
Hardware is CN Gigabit Ethernet, address is
0001.969a.1d01 (bia 0001.969a.1d01)
Internet address is 10.255.255.245/30
MTU 1500 bytes, BW 1000000 Kbit, DLY 10 usec,
reliability 255/255, txload 1/255, rxload 1/255
Encapsulation ARPA, loopback not set
Keepalive set (10 sec)
Full-duplex, 100Mb/s, media type is RJ45
output flow-control is unsupported, input flow-control is unsupported
ARP type: ARPA, ARP Timeout 04:00:00,
Last input 00:00:08, output 00:00:05, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0 (size/max/drops); Total output drops: 0
Queueing strategy: fifo
Output queue :0/40 (size/max)
5 minute input rate 63 bits/sec, 0 packets/sec
5 minute output rate 65 bits/sec, 0 packets/sec
241 packets input, 16664 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort 0 watchdog, 1017 multicast, 0 pause input
O input packets with dribble condition detected
```

I then ran show running-config

```
Building configuration...
Current configuration : 2258 bytes
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
hostname R2
enable secret 5 $1$mERr$9cTjUIEqNGurQiFU.ZeCi1
ip cef
no ipv6 cef
username Tier3a password 0 cisco
username administrator password 0 cisco
license udi pid CISCO2911/K9 sn FTX15249169
ip ssh version 2
ip domain-name Central
ip host R1 10.255.255.254 10.255.255.246 10.2.0.1
ip host R3 10.255.255.253 10.255.255.250 10.3.0.1
spanning-tree mode pvst
interface GigabitEthernet0/0
 ip address 10.255.255.245 255.255.252
 ip ospf priority 255
 duplex auto
 speed auto
interface GigabitEthernet0/1
 ip address 10.255.255.249 255.255.255.252
 ip ospf priority 255
 duplex auto
 speed auto
```

```
interface GigabitEthernet0/2
 ip address 10.10.10.1 255.255.255.0
 duplex auto
 speed auto
interface Serial0/0/0
ip address 64.100.100.1 255.255.255.252
 encapsulation ppp
ppp authentication pap
ppp pap sent-username R2 password 0 cisco interface Serial0/0/1
no ip address
 encapsulation frame-relay
 clock rate 2000000
interface Serial0/0/1.1 point-to-point ip address 64.100.200.2 255.255.255.252
 frame-relay interface-dlci 202
 clock rate 2000000
interface Vlan1
no ip address
shutdown
router ospf 1
log-adjacency-changes
 {\tt passive-interface \ Serial0/0/0}
 passive-interface Serial0/0/1
 network 10.255.255.244 0.0.0.3 area 0
network 10.255.255.248 0.0.0.3 area 0
 network 10.10.10.0 0.0.0.255 area 0
 network 64.100.100.0 0.0.0.3 area 0
 {\tt default-information\ originate}
ip classless
ip route 0.0.0.0 0.0.0.0 64.100.100.2
ip route 0.0.0.0 0.0.0.0 64.100.200.1 200
ip flow-export version 9
ip access-list extended PERMIT_LOCAL
permit udp any any eq domain
 permit tcp any any eq domain
 permit ip 64.100.200.0 0.0.0.3 any
 permit ip 64.104.223.0 0.0.0.3 any
 permit icmp 64.100.200.0 0.0.0.3 any
 permit icmp 64.104.223.0 0.0.0.3 any
 permit icmp any any echo-reply
 deny ip any any
banner login Username: administrator
Password: cisco Enable: class
banner motd Username:administrator
Password:cisco Enable:class
line con 0
line aux 0
line vty 0
login local
 transport input ssh
line vty 1 4
no login
```

ii) Filling in part of the table

We now have enough information to fill in pieces of the table

R2			connecting	device
interface	address	subnetmask	name	interface
G0/0	10.255.255.245	255.255.255.252	D1	Gi 0/1
G0/1	10.255.255.249	255.255.255.252	D2	G 0/1
G0/2	10.10.10.1	255.255.255.0	S3	G 0/1

Part 2: S3

i) Gathering data

I continued to do the same for the rest of the switches and interfaces

ii) full table

Here is the completed table

R2			connecting	device
interface	address	subnetmask	name	interface
G0/0	10.255.255.245	255.255.255.252	D1	Gi 0/1
$\dot{G0/1}$	10.255.255.249	255.255.255.252	D2	$\frac{\dot{G}}{0/1}$
G0/2	10.10.10.1	255.255.255.0	S3	$\frac{1}{1}$
		255.255.255.252	Internet	N/A
s0/0/1.1	64.100.200.2	255.255.255.252	Intranet	N/A
S3				
$VLAN\ 1$	10.10.10.254	255.255.255.0	N/A	N/A
F0/1	N/A	N/A	Cent. Srvr	NIC
G0/1	N/A	N/A	R2	G0/2
C. Srvr				
NIC	10.10.10.2	255.255.255.0	S3	F0/1
D1				
VLAN2	10.2.0.1	255.255.255.0	N/A	N/A
G0/1	10.255.255.246	255.255.255.252	R2	G0/0
G0/2	10.255.255.254	255.255.255.252	D2	G0/2
F0/23	N/A	N/A	S2	F0/23
F0/24	N/A	N/A	S1	G0/1
S1				
VLAN2	10.2.0.2	255.255.255.0	N/A	N/A
F0/23	N/A	N/A	D2	F0/23
G0/1	N/A	N/A	D1	F0/24
D2				
F0/23		N/A	S1	F0/23
F0/24	10.3.0.1	255.255.255.0	S3	G0/1
G0/1	10.255.255.250	255.255.255.252	R2	G0/1
G0/2	10.255.255.253	255.255.255.252	D1	G0/2
S2				
VLAN1	10.3.0.1	255.255.255.0	N/A	N/A
F0/23	N/A	N/A	D1	F0/23
G0/1	N/A	N/A	D2	F0/24

Lab 3

Configuring IPv4 and IPv6

Jan 28, 2020

Packet Tracer Lab 3 Spring 2020 CIT 167 Chaz Davis

- Important Commands for the Lab
 - config start off in user mode

enable moves you from user to priveledged mode config terminal you can change the global parameters interface router

router from global you can go into router settings instead of interface routerprotocol

- $\bullet~$ ip address... followed by the ip address and the subnet mask of the pc to be cofigured
- no shutdown this enables the interface or 'brings it up' must be in interface configuration mode
- interface... Followed by the name of the interface to be configured ie.

 ${\bf GigabitEthernet0/0}$

 ${\bf FastEthernet0...}$

can be shortened to int g0/0or int Fa $0\,$

- Important Concepts
 - Difference between IPv6 and IPv4
 - How to ping from the commandline




Figure 3.1: Assigning IPv4 addressing

Part 1: Configuring IPv4

i) Assign IPv4 addressing

I opened up PC1 and clicked on the desktop. I then opened the IPconfiguration box and entered the Information from the table. See Fig 3.1a.

I opened up PC2 and clicked on desktop and opened the ipconfiguration box and entered the information from the table. See Fig 3.1b.

I opened up R1 and and used the commandline tool to enter the information according to the chart. See Fig 3.2a.

We can now see that PC1 PC2 and R1 are all connected to each other. See Fig 3.2b.





Figure 3.2: Network Connectivity


ii) Verify connectivity

I opened PC1 went the command line and successfully pinged the Dual stack server and then successfully pinged PC2. See Fig 3.3a

I opened PC2 went the command line and successfully pinged the Dual stack server and then successfully pinged PC1 See Fig 3.3b







(b) PC2 successfully pinging the server and PC1 $\,$

Figure 3.3: Network Verification

Part 2: configuring IPv6




Figure 3.4: IPv6 Configuration

i) Assign IPv6 addressing and verify connectivity

I opened up PC3 and clicked on desktop and opened the ipconfiguration box and entered the information from the table. See Fig 3.4a.

I opened up PC4 and clicked on desktop and opened the ipconfiguration box and entered the information from the table. See Fig 3.4b

I opened up R2 and and used the commandline tool to enter the information according to the chart. See Fig 3.4c.

We can now see in Fig 3.4d that PC3 PC4 and R2 are all connected to each other.

ii) Verify connectivity

I opened PC3 went the command line and successfully pinged the Dual stack server and then successfully pinged PC4

```
C:\>ping 2001:DB8:100:1::A

Pinging 2001:DB8:100:1::A with 32 bytes of data:


Reply from 2001:DB8:100:1::A: bytes=32 time=1ms TTL=126
Reply from 2001:DB8:100:1::A: bytes=32 time=1ms TTL=126
Reply from 2001:DB8:100:1::A: bytes=32 time=1ms TTL=126
Reply from 2001:DB8:100:1::A: bytes=32 time=3ms TTL=126
Ping statistics for 2001:DB8:100:1::A:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 3ms, Average = 1ms

C:\>ping 2001:DB8:C0DE:13::A

Pinging 2001:DB8:C0DE:13::A with 32 bytes of data:


Reply from 2001:DB8:C0DE:13::A: bytes=32 time=15ms TTL=127
Reply from 2001:DB8:C0DE:13::A: bytes=32 time<1ms TTL=127
Reply from 2001:DB8:C0DE:13::A: bytes=32 time<1ms TTL=127
Ping statistics for 2001:DB8:C0DE:13::A:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 15ms, Average = 4ms
```



(a) Pinging the Server and PC4 from PC3 $\,$


(b) Pinging the Server and PC3 from PC4



(c) Topology of the Completed Network

Figure 3.5: Verifying Connectivity of the Network


I opened PC4 went the command line and successfully pinged the Dual stack server and then successfully pinged PC3 $\,$



Part 3: Wrap Up

i) Success

Clicked the Check results button 100% success



Configuring Static Routes

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

Configuring Static Routes

- There are two common types of static routes in the routing table:
 - Static route to a specific network
 - Default static route

IPv4 Routing

ip route <network-address> <subnet-mask> { next-hop-ip | exit-intf }

- Next-hop-ip: IP-address of the connecting router to use for forwarding.
- Exit-intf: the outgoing interface to use to forward the packet to the next hop.

Configure a IPv4 Default Static Route

ip route 0.0.0.0 0.0.0.0 { exit-intf | next-hop-ip }

The distance parameter is used to create a floating static route by setting an administrative distance that is higher than a dynamically learned route.

Configure an IPv4 Floating Static Route

- Given an example where R1 is attached to R2 (172.16.2.2) and R3 (10.10.10.2), the following would create a default static route to R2, and a floating static route to R3:

- Default route to R2 has no administrative distance specified, so would default to 1. This is the preferred route..
- Floating default route to R3 has administrative distance 5. Since this value is greater that of the default route, this route "floats" it is not present in the routing table unless the preferred route fails.

Default Administrative Distances

```
0
Connected
Static
EIGRP summary route
                            5
External BGP
                            20
Internal EIGRP
                            90
IGRP
                            100
OSPF
                            110
IS-IS
                            115
RTP
                            120
External EIGRP
                            170
Internal BGP
```

Verify a Static Route

```
show ip route
show ip route static  # Displays contents of static routes
show ip route static | begin Gateway
show ip route <network>

show running-config | section ip route

# displays the routes that packets will actually take when traveling to their
destination
traceroute <ip-address>
trace <destination>

#displays detailed info about neighboring devices descovered using Cisco Discovery
Protocol
show cdp neighbors
show cdp neighbors detail
```

Command Sequence

```
enable
configure terminal

ip route 192.168.3.0 255.255.255.0 192.168.2.2
exit

show ip route
ping 192.168.3.1
trace 192.168.3.1
exit
```

IPv6 Routing

```
ipv6 route <ipv6-prefix>/<prefixlength> {ipv6-address | exit-intf}
```

Displaying and Testing IPv6 Routes

```
show ipv6 route
show ipv6 route static
show ipv6 route <network>
show running-config | section ipv6 route

ping ipv6 <ipv6-address>
traceroute
```

Configure a Directly Connected Static IPv6 Route

```
ipv6 route <ipv6-address>/<network-prefix> <interface>
ipv6 route 2001:db8:acad:2::/64 s0/0/0
```

Configure a Fully Specified Static IPv6 Route

ipv6 route <ipv6-address>/<network-prefix> <interface> <next-hop ipv6-address>
ipv6 route 2001:db8:acad:2::/64 s0/0/0 fe80::2

Configure a Default IPv6 Static Route

```
ipv6 route ::/0 {ipv6-address | exit-intf}
ipv6 route ::/ 2001:db8:acad:4::2
```

Configure an IPv6 Floating Static Route

```
ipv6 route ::/0 <ipv6-address> <administrative-distance>
ipv6 route ::/0 2001:db8:aad:4::2
ipv6 route ::/0 2001:db8:aad:6::2 5
```

Common IOS Troubleshooting Commands

```
ping
ping <ip-address> source <source_ip>
traceroute <ip-address>
show ip route | begin Gateway
show ip interface brief
show cdp neighbors detail
```

Static Routing

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

Important Concepts for Static Routing

- Routing is the process of selecting paths in a network along which to send network traffic
- Static routing involves manual updating of routing tables with fixed paths to destination networks.
- Static routing uses include:

Defining an exit point from a router when no other routes are available or necessary.

Small networks that require only one or two routes.

To provide a failsafe backup in the event that a dynamic route is unavailable.

To help transfer routing information from one routing protocol to another.

• Static routing disadvantages include:

Potential for human error

Lack of fault tolerance

Default prioritization over dynamic routing

Administrative overhead

- To display the current state of the routing table use the show ip route command in user EXEC or privileged EXEC mode.
- To display the entries in the Address Resolution Protocol (ARP) table use the show arp command in user EXEC or privileged EXEC mode.
- To establish static routes use the ip route command in global configuration mode. To remove static routes, use the no form of this command.
- To discover the routes that packets will actually take when traveling to their destination, use the trace / traceroute privileged EXEC command.
- To display detailed information about neighboring devices discovered using Cisco Discovery Protocol (CDP), use the show cdp neighbors privileged EXEC command.

Important Terms to know

• ARP table

A table of IP and hardware addresses resolved using the Address Resolution Protocol.

• Cisco Express Forwarding (CEF)

An advanced layer 3 switching technology used mainly in large core networks or the Internet to enhance the overall network performance.

• Internet Control Message Protocol (ICMP)

Used by network devices to send error messages on an IP network.

· Layer 3 switch

A device capable of both routing and switching operations using dedicated application-specific integrated circuit (ASIC) hardware.

• next-hop router

The next router in the path between source and destination.[20]

• outgoing interface

The local network interface used to connect to a next-hop router.

• routing table

A data table stored in a router or a networked computer that lists the routes to particular network destinations, and in some cases, metrics (distances) associated with those routes.

· static route

A manually-configured routing entry.

summary route

A route containing the highest-order bits that match all addresses for a given collection of destination networks.

• traceroute

A computer network diagnostic tool for displaying the route (path) and measuring transit delays of packets across an Internet Protocol (IP) network.

Lab 4

Troubleshooting Static Routes

Feb 4, 2020

Packet Tracer Lab 4 Spring 2020 CIT 167 Chaz Davis

- Important Commands for the Lab
 - show ip route [ip-address] to display the current state of the routing table command can be used in EXEC or privileged EXEC mode
 - no ip route To remove static routes, use this command in global configuration no ip route prefix mask <ip address | interface-type interface-number> [permanent]
 - ip route To establish static routes, use this command in global configuration

 ip route prefix mask <ip address | interface-type interface-number> [permanent]

 ip route 192.168.3.0 255.255.255.0 192.168.2.2

Part 1: Locate The Problem

Based on the output of the commands I've run, from PC1 and from R1 and R2 and R3.

It appears that R2 is incorrectly configured and it has R1 as the wrong ip addresses in its routing table. See Fig.

It also appears that R3 is incorrectly configured and has no route for pc1 in its tables.

```
2#show ip route
odes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, 0 - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
          candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route
Sateway of last resort is not set
    172.31.0.0/16 is variably subnetted, 8 subnets, 5 masks
       172.31.0.0/24 is directly connected, GigabitEthernet0/0
       172.31.0.1/32 is directly connected, GigabitEthernet0/0
       172.31.1.0/25 [1/0] via 172.31.1.198
       172.31.1.128/26 [1/0] via 172.31.1.194
       172.31.1.192/30 is directly connected, Serial0/0/0
       172.31.1.193/32 is directly connected, Serial0/0/0
       172.31.1.196/30 is directly connected, Serial0/0/1
       172.31.1.197/32 is directly connected, Serial0/0/1
                     (a) R2 misconfiguration of static Route
```

Figure 4.1: Network Misconfigured: R2 - not set up for R1

Part 2: Determine the solution

I believe the solution is going to be statically configuring the routes for router 2 and 3, making sure that all are connected.

Part 3: Implement the solution

I went to R2 first, and configured the network settings. First, by removing the incorrect routing tables by running the

commands no ip route 172.31.1.0 255.255.255.128 172.31.1.198 and no ip route 172.31.1.128 255.255.255.192 172.31.1.194 Then,


I repopulated the table by running the commands ip route 172.31.1.0 255.255.255.128 172.31.1.194 and ip route 172.31.1.128 255.255.255.128 I then went to R3 and cofigured it for PC1 by running ip route 172.31.1.0 255.255.255.128 serial 0/0/1

Part 4: Verify that the issue is resolved

Finally I verified that the network is now working properly. Table on Pg. 34

As you can see in FIg. 4.2a I was successfully able to ping the server from PC1.

I then opened the web browser on PC1 Fig. 4.2b and PC2 Fig. 4.2c and entered the servers address and got the congratulations message.



(a) Successful Ping of the server from PC1



Troubleshooting Static Routes

Congratulations, you have completed this activity.

(b) Successful Webpage Login PC1

(c) Successful Webpage Login from PC2

Figure 4.2: Successful Verification

Lab 5

Configuring IPv6 Static Routes

Feb 6, 2020

Packet Tracer Lab 5 Spring 2020 CIT 167 Chaz Davis

- Important Commands for the Lab
 - ipv6 unicast-routing
 - ipv6 route
 - show ipv6 interface brief
- Important notes about IPv6

IPv6 uses a new mechanism for mapping IP addresses to link layer addresses (MAC addresses), because it does not support the broadcast addressing method, on which the functionality of the Address Resolution Protocol (ARP) in IPv4 is based. IPv6 implements the Neighbor Discovery Protocol (NDP, ND) in the link layer, which relies on ICMPv6 and multicast transmission. IPv6 hosts verify the uniqueness of their IPv6 addresses in a local area network (LAN) by sending a neighbor solicitation message asking for the link layer address of the IP address. If any other host in the LAN is using that address, it responds.

Part 1:Examine the Network

i) a

There are 5 networks connected in the current topology




Figure 5.1: Topology of the Network

ii) b

In Fig 5.1 we can see the R1 and R3 each have two connected networks, and that R2 has three connected networks.

iii) c

Ipv6 route then we specify [the network, and prefix] then we specify either [next hop address or exit interface]

Part 2: Configure IPv6 static and default routes

i) Enabling the Routers

I logged into Each of the routers ena, conf t, and then typed in ipv6 unicast-routing into each terminal as seen in Fig 5.2.




Figure 5.2: Enabling IPv6

ii) Configuring the routers

Next I went to the three routers and manually entered the info for the network configuring each destination and each hop on the network. See Fig 5.3.

```
RZ=ena
RZ=conf t
Enter configuration commands, one per line. End with CNTL/Z.
RZ(config)#ipv6 route 2001:DB8:1:1::1/64 0/0/0
R1>ena
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ipv6 route 2001:DB8:1:2::/64
% Incomplete command.
R1(config)#ipv6 route 2001:DB8:1:2::/64 2001:DB8:1:A001::2
R1(config)#ipv6 route 2001:DB8:1:A002::/64 2001:DB8:1:A001::2
R1(config)#ipv6 route 2001:DB8:1:3::/64
                                                                                                                                    % Invalid input detected at '^' marker.
                                                                                                                                   R2(config)#ipv6 route 2001:DB8:1:1::1/64 serial 0/0/0
R2(config)#ipv6 route 2001:DB8:1:3::1/64 serial 0/0/1
R2(config)#ipv6 route 2001:DB8:1:3::1/64 serial 0/0/1 2001:DB8:1:A002::2/64
% Incomplete command.
R1(config)#ipv6 route 2001:DB8:1:3::/64
                                                                                                                                    % Invalid input detected at '^' marker.
 % Incomplete command.
                                                                                                                                   R2(config)#
R2(config)#ipv6 route 2001:DB8:1:3::1/64 serial 0/0/1 2001:DB8:1:A002/64
 R1(config)#ipv6 route 2001:DB8:1:3::/64 2001:DB8:1:2::1/64
 % Invalid input detected at '^' marker.
                                                                                                                                    % Invalid input detected at '^' marker.
                                                                                                                                   R2(config)#ipv6 route 2001:DB8:1:3::1/64 serial 0/0/1 2001:DB8:1:A002::2
 R1(config)#ipv6 route 2001:DB8:1:3::/64 2001:DB8:1:A001::2
            (a) Manually entering the network info on R1
                                                                                                                                                       (b) Manually entering the network info on R2
                                                                  R3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
                                                                  R3(config)#ipv6 route ::/0
% Incomplete command.
                                                                   R3(config)#ipv6 route ::/0 2001:DB8:1:A002::1
                                                                  R3(config)#
                                                                                     (c) Manually entering the network info on R3
```

Figure 5.3: Manually Configuring the Destination IPv6 address, as well as the next hop address and Exit address

iii) Verifying Static Route Configurations

```
RCMSNOW IPV6 TOUTE

IPV6 ROULING Table - 6 entries

Codes: C - Connected, L - Local, S - Static, R - RIP, B - BGP

U - Per-user Static route, M - MIPV6

I1 - ISIS L1, I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary

O - OSPF intra, OI - OSPF inter, OEI - OSPF ext 1, OE2 - OSPF ext 2

ON1 - OSPF NSSA ext 1, ON2 - OSPF NSSA ext 2

D - EIGRP, EX - EIGRP external

S::/0 [1/0]

via 2001:DB8:1:3::/04 [0/0]

via GigabitEthernet0/0, directly connected

L 2001:DB8:1:3::1/128 [0/0]

via GigabitEthernet0/0, receive

C 2001:DB8:1:3::1/128 [0/0]
R3#show ipv6 interface brief
GigabitEthernet0/0
                                                                      [up/up]
         FE80::3
          2001:DB8:1:3::1
GigabitEthernet0/1
                                                                      [administratively down/down]
         unassigned
Serial0/0/0
                                                                      [administratively down/down]
         unassigned
                                                                                                                                                                                                               via uigabilEthernet8/0, receive
2001:D88:1-A002::/64 [6/0]
via Serial8/0/1, directly connected
2001:D88:1-A002::/2/128 [6/0]
via Serial8/0/1, receive
FF00::/8 [6/0]
via Null0, receive
Serial0/0/1
                                                                      [up/up]
         FE80::3
          2001:DB8:1:A002::2
Vlan1
                                                                      [administratively down/down]
         unassigned
                                                     (b) IPv6 Interface brief
                                                                                                                                                                                                                                                                 (c) show ipv6 route
```

Figure 5.4: Verifying the Network

a

PC command

From the command prompt in the PC terminals, I entered the command ipv6 config for information on the network See Fig 5.4a

b

routing address


From the routers terminals I entered show ipv6 interface brief to display the configured addresses. See Fig 5.4b

 \mathbf{c}

Routing Table

Finally, I entered show ipv6 route into each of the prompts to display the routing tables. See Fig 5.4c

Part 3: Success



Lab 6

Configuring IPv4 Static Routes

Feb 8, 2020

Packet Tracer Lab 6 Spring 2020 CIT 167 Chaz Davis

- Important Concepts for the Lab
 - Recursive static route

a route whose next hop and destination network are covered by another learned route in the Routing Information Database (RIB).

Such static routes cannot be installed in the RIB because they are considered redundant routes.

- Directly Connected Static Route
 - A directly connected static route is one that uses the exit interface to forward traffic to the intended destination.

This is in contrast to the recursive static route which used the next hop IP address of the router along the path to the destination

- \bullet Loopback
 - A loopback interface is a logical, virtual interface in a cisco router.
 - A loopback interface is not a physical interface like Fast Ethernet or Gigabit Ethernet interface.
- A loopback interface has many uses


Loopback interface's IP Address determines a routers OSPF Router ID. $\,$

A loopback interface is always up and allows Border Gateway Protocol (BGP) neighborship between two routers to stay up even if one of the outbound physical interfaces is down.

Part 1: Setting up the topology

i) Cabling the Network

I've configured the network with two routers, 2 switches, and 2 pcs as seen in Fig. 6.1a.



(a) Cabling the topology

ii) Initialization

I flipped the switches and restarted the routers and switches.

Part 2: Configuring Basic Device Settings

i) Configuring the PC Interfaces


I configured the PCs according to the table. As you can see in Fig. 6.2a and Fig. 6.2b on Pg. 42.


ii) Verify the LANs

Next, I ran commands on the routers to configure the device names, setup DNS lookup, added passwords, and then ran the configuration and startup styles.

iii) Configuring IP settings on the routers

Finally, I configured the ip addresses on the routers and set up the static routing tables for the addresses. See Fig. 6.2d and Fig. 6.2e on Pg. 42.





(c) The network now

```
Router>ena Router#conf t Enter configuration commands, one per line. End with CNTL/Z. Router(configuration commands, one per line. End with CNTL/Z. Router(configu-ff)#ip address 1e.1.1.2 255.255.255.252 Router(configu-ff)# address 1e.1.1.2 255.255.255.255 Router(configu-ff)#configuration for the configuration of the confi
%LINK-5-CHANGED: Interface Serialo/0/0, changed state to down Router(config-if)mexit Router(config)-sinterface % Incomplete command. Router(config)-sinterface loopback 0
    Router(config-if)#
%LINK-5-CHANGED: Interface Loopbackθ, changed state to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up

Router(config-if)#ip address 209.165.200.225 255.255.255.224 Router(config-if)#no shut Router(config-if)#exit interface loopback 1

% Invalid input detected at '^' marker.

Router(config-if)#exit Router(config)#interface loopback 1

Router(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1, changed state to up

Router(config-if)#ipaddress 198.133.219.1 255.255.255.0

% Invalid input detected at '^' marker.

Router(config-if)#ip address 198.133.219.1 255.255.255.08
Router(config-if)#mo shut
Router(config-if)#minterface gigabitEthernet 0/1
Router(config-if)#ip address 192.108.1.1 255.255.255.0
Router(config-if)#no shut

Router(config-if)# %LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up (d) Router 3 config

Souter>ena
Souter/econft
Enter configuration commands, one per line. End with CNTL/Z.
Souter(config)#interface serial 0/0/1
Souter(config-if)#ipaddress 10.1.1.1 255.255.255.252 Invalid input detected at '^' marker. Router(config-if)#ip address 10.1.1.1 255.255.255.252 Router(config-if)#no shut Router(config-if)# %LINK-5-CHANGED: Interface Serial0/0/1, changed state to up outer(config-if)#exit Outer(config)#interface gig Outer(config)#interface gigabitEthernet 0/ KLINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up l Router(config-if)#interface gigabitEthernet 0/1 Router(config-if)#ip address 192.168.0.1 255.255.255.0 Router(config-if)#noshut Invalid input detected at '^' marker. outer(config-if)#no shut Router(config-if)# #LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up *LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

(e) router 1 config

Figure 6.2: Configuring the network interfaces

iv) Verify Connectivity of LANs

I tested conectivity by pinging from each PC. I was able to ping from PC to router but from PC-A I was ubnable to reach PC-C or either loopback. See Fig. 6.3a. and Fig. 6.3b on Pg. 43.

```
Packet Tracer PC Command Line 1.0
C:\>ping 192.168.0.1

Pinging 192.168.0.1 with 32 bytes of data:

Reply from 192.168.0.1: bytes=32 time=78ms TTL=255
Reply from 192.168.0.1: bytes=32 time<1ms TTL=255
Reply from 192.168.0.1: bytes=32 time=12ms TTL=255
Reply from 192.168.0.1: bytes=32 time<1ms TTL=255

Ping statistics for 192.168.0.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 78ms, Average = 22ms

C:\>
```

(a) Pinging the default gateway from PC-A Pinging PC-C, Lo0, and Lo1 from PC-A

```
Packet Tracer PC Command Line 1.0

C:\>ping 192.168.1.1 with 32 bytes of data:

Reply from 192.168.1.1: bytes=32 time=1ms TTL=255
Reply from 192.168.1.1: bytes=32 time<1ms TTL=255
Ping statistics for 192.168.1.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>
```

(b) Pinging the default gateway from PC-C

```
Router#ping 10.1.1.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.1.1.2, timeout is 2 seconds:

[!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/4/15 ms

Router#
```

(c) Pinging S0/0/0 and R3 from R1

Figure 6.3: Verifying Connections between devices on the network

Part 3: Configure Static Routes

i) Configure recursive static route

I went to R1 and entered the command ip route 192.168.1.0 255.255.255.0 10.1.1.2 in to the command line.

The new show ip route shows us the static routing configuration.

In the last line we see s 192.168.1.0/24 [1/0] via 10.1.1.2.

ii) Configure directly connected static route

I went to $\mathrm{R}3$ and entered ip route 192.168.0.0 255.255.255.0 serial 0/0/0.

When I run the show ip route command from R3 we can now see the static exit interface in the line s 192.168.0.0/24 is directly command.

iii) Configure Static Route

I went to R1 and ran ip route 198.133.219.0 255.255.255.0 serial 0/0/1.

iv) Remove static Routes for Loopback

I went to R1 and ran ip route 209.165.200.224 255.255.255.224 10.1.1.2 and now we can see with the lines:

```
S 198.133.219.0/24 is directly connected, Serial0/0/1 209.165.200.0/27 is subnetted, 1 subnets S 209.165.200.224/27 [1/0] via 10.1.1.2
```

That we are correctly configured.

Part 4: Configure and verify the default route

I went to R1 and entered ip route 0.0.0.0 0.0.0.0.
I the went to PC-A and Pinged 209.165.200.225 see Fig. 6.4a Lastly, I pinged 198.133.219.1 from PC-A. See Fig. 6.4b

```
C:\>ping 209.165.200.225

Pinging 209.165.200.225 with 32 bytes of data:

Reply from 209.165.200.225: bytes=32 time=1ms TTL=254

Ping statistics for 209.165.200.225:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 1ms, Maximum = 1ms, Average = 1ms
```

(a) Pinging PC-C from PC- A

```
Pinging 198.133.219.1 with 32 bytes of data:

Reply from 198.133.219.1: bytes=32 time=2ms TTL=254
Reply from 198.133.219.1: bytes=32 time=1ms TTL=254
Reply from 198.133.219.1: bytes=32 time=2ms TTL=254
Reply from 198.133.219.1: bytes=32 time=1ms TTL=254
Ping statistics for 198.133.219.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 1ms, Maximum = 2ms, Average = 1ms
```

(b) Pinging R1 from PC-A

Figure 6.4: Verifying the default routes

Reflection

If we added a new network we could run

ip route 192.168.3.0 255.255.255.0 s0/0/0

ip route 192.168.3.0 255.255.255.0 10.1.1.1 from ${
m R3}$

With a recursive static route perform lookups in the routing table before forwarding the packets. With a directly connected static route, the exit-interface parameter is specified, which allows the route to resolve a forwarding decision in one lookup.

A default gateway tells the device to contact the next hop of the default route if they don't have a more specific route. Without a default route, a router will drop a request for a network that is not in its routing table and send ICMP Destination unreachable.

Configuring Dynamic Routing

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

Access RIP configuration mode

router rip

- Prompt will show up as Router(config-router)#
- When enabling RIP, the default version is RIPv1.
- To disable and eliminate RIP, use the 'no router rip' global configuration command. This command stops the RIP process and erases all existing RIP configurations.
- $\bullet \quad \text{Upon enabling, need to advertise networks with `network < network-address}>`$

Enable and Verify RIPv2

By default, when a RIP process is configured on a Cisco router, it is running RIPv1, as shown in Figure 1. However, even though the router only sends RIPv1 messages, it can interpret both RIPv1 and RIPv2 messages. A RIPv1 router ignores the RIPv2 fields in the route entry.

Use the 'version 2' router configuration mode command to enable RIPv2, as shown in Figure 2. Notice how the 'show ip protocols' command verifies that R2 is now configured to send and receive version 2 messages only. The RIP process now includes the subnet mask in all updates, making RIPv2 a classless routing protocol.

Note: Configuring 'version 1' enables RIPv1 only, while configuring 'no version' returns the router to the default setting of sending version 1 updates but listening for version 1 and version 2 updates.

Propogate a Default Route

The `default-information originate` router configuration command. This instructs R1 to originate default information, by propagating the static default route in RIP updates.

RIP Routing Configuration Mode Commands $\mbox{\tt\#}$ Enables RIP on all interfaces on that network. network <network-address> version 2 # Enables RIPv2 version 1 # Enables RIPv1 only no version # Returns to default setting: send v1, listen v1+v2 no auto-summary # Disables default automatic summarization (RIPv2) passive-interface <interface> # Prevent transmission of routing updates out interface # However, still allows network to be advertised passive-interface g0/0 # Makes all interfaces passive # Re-enables passive transmission of routing updates passive-interface default no passive-interface <intf>

```
Verify RIP Routing

show ip protocols
show ip route
```

```
Propogate a Default Route

To propagate a default route in RIP, the edge router must be configured with a default static route using the `ip route 0.0.0.0 0.0.0.0 `command:

ip route 0.0.0.0 0.0.0.0 <exit-interface> <next-hop IP>

Next configure router to propogate the static default route in RIP updates:

router rip default-information originate
```

Useful Bits Dynamic Routing

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

RIP Overview

The Routing Information Protocol (RIP) uses broadcast UDP data packets to exchange routing information. Cisco software sends routing information updates every 30 seconds, which is termed advertising. If a device does not receive an update from another device for 180 seconds or more, the receiving device marks the routes served by the nonupdating device as unusable. If there is still no update after 240 seconds, the device removes all routing table entries for the nonupdating device.

A device that is running RIP can receive a default network via an update from another device that is running RIP, or the device can source the default network using RIP. In both cases, the default network is advertised through RIP to other RIP neighbors.

The Cisco implementation of RIP Version 2 (RIPv2) supports plain text and message digest algorithm 5 (MD5) authentication, route summarization, classless interdomain routing (CIDR), and variable-length subnet masks (VLSMs).

RIP Routing Updates

The Routing Information Protocol (RIP) sends routing-update messages at regular intervals and when the network topology changes. When a device receives a RIP routing update that includes changes to an entry, the device updates its routing table to reflect the new route. The metric value for the path is increased by 1, and the sender is indicated as the next hop. RIP devices maintain only the best route (the route with the lowest metric value) to a destination. After updating its routing table, the device immediately begins transmitting RIP routing updates to inform other network devices of the change. These updates are sent independently of the regularly scheduled updates that RIP devices send.

RIP Routing Metric

The Routing Information Protocol (RIP) uses a single routing metric to measure the distance between the source and the destination network. Each hop in a path from the source to the destination is assigned a hop-count value, which is typically 1. When a device receives a routing update that contains a new or changed destination network entry, the device adds 1 to the metric value indicated in the update and enters the network in the routing table. The IP address of the sender is used as the next hop. If an interface network is not specified in the routing table, it will not be advertised in any RIP update.

Authentication in RIP

The Cisco implementation of the Routing Information Protocol (RIP) Version 2 (RIPv2) supports authentication, key management, route summarization, classless interdomain routing (CIDR), and variable-length subnet masks (VLSMs).

By default, the software receives RIP Version 1 (RIPv1) and RIPv2 packets, but sends only RIPv1 packets. You can configure the software to receive and send only RIPv1 packets. Alternatively, you can configure the software to receive and send only RIPv2 packets. To override the default behavior, you can configure the RIP version that an interface sends. Similarly, you can also control how packets received from an interface are processed.

RIPv1 does not support authentication. If you are sending and receiving RIP v2 packets, you can enable RIP authentication on an interface.

The key chain determines the set of keys that can be used on the interface. Authentication, including default authentication, is performed on that interface only if a key chain is configured. For more information on key chains and their configuration, see the "Managing Authentication Keys" section in the "Configuring IP Routing Protocol-Independent Features" chapter in the Cisco IOS IP Routing: Protocol-Independent Configuration Guide.

Cisco supports two modes of authentication on an interface on which RIP is enabled: plain-text authentication and message digest algorithm 5 (MD5) authentication. Plain-text authentication is the default authentication in every RIPv2 packet.

Note

Do not use plain text authentication in RIP packets for security purposes, because the unencrypted authentication key is sent in every RIPv2 packet. Use plain-text authentication when security is not an issue; for example, you can use plain-text authentication to ensure that misconfigured hosts do not participate in routing.

Exchange of Routing Information

Routing Information Protocol (RIP) is normally a broadcast protocol, and for RIP routing updates to reach nonbroadcast networks, you must configure the Cisco software to permit this exchange of routing information.

To control the set of interfaces with which you want to exchange routing updates, you can disable the sending of routing updates on specified interfaces by configuring the passive-interface router configuration command.

You can use an offset list to increase increasing incoming and outgoing metrics to routes learned via RIP. Optionally, you can limit the offset list with either an access list or an interface.

Routing protocols use several timers that determine variables such as the frequency of routing updates, the length of time before a route becomes invalid, and other parameters. You can adjust these timers to tune routing protocol performance to better suit your internetwork needs. You can make the following timer adjustments:

The rate (time, in seconds, between updates) at which routing updates are sent The interval of time, in seconds, after which a route is declared invalid The interval, in seconds, during which routing information about better paths is suppressed The amount of time, in seconds, that must pass before a route is removed from the routing table The amount of time for which routing updates will be postponed You can adjust the IP routing support in the Cisco software to enable faster convergence of various IP routing algorithms, and hence, cause quicker fallback to redundant devices. The total effect is to minimize disruptions to end users of the network in situations where quick recovery is essential

In addition, an address family can have timers that explicitly apply to that address family (or Virtual Routing and Forwarding [VRF]) instance). The timers-basic command must be specified for an address family or the system defaults for the timers-basic command are used regardless of the timer that is configured for RIP routing. The VRF does not inherit the timer values from the base RIP configuration. The VRF will always use the system default timers unless the timers are explicitly changed using the timers-basic command.

RIP Route Summarization

Summarizing routes in RIP Version 2 improves scalability and efficiency in large networks. Summarizing IP addresses means that there is no entry for child routes (routes that are created for any combination of the individual IP addresses contained within a summary address) in the RIP routing table, reducing the size of the table and allowing the router to handle more routes.

Summary IP address functions more efficiently than multiple individually advertised IP routes for the following reasons: The summarized routes in the RIP database are processed first. Any associated child routes that are included in a summarized route are skipped as RIP looks through the routing database, reducing the processing time required. Cisco routers can summarize routes in two ways: Automatically, by summarizing subprefixes to the classful network boundary when crossing classful network boundaries (automatic summary).

Note

Automatic summary is enabled by default.

As specifically configured, advertising a summarized local IP address pool on the specified interface (on a network access server) so that the address pool can be provided to dialup clients. When RIP determines that a summary address is required in the RIP database, a summary entry is created in the RIP routing database. As long as there are child routes for a summary address, the address remains in the routing database. When the last child route is removed, the summary entry also is removed from the database. This method of handling database entries reduces the number of entries in the database because each child route is not listed in an entry, and the aggregate entry itself is removed when there are no longer any valid child routes for it.

RIP Version 2 route summarization requires that the lowest metric of the "best route" of an aggregated entry, or the lowest metric of all current child routes, be advertised. The best metric for aggregated summarized routes is calculated at route initialization or when there are metric modifications of specific routes at advertisement time, and not at the time the aggregated routes are advertised.

The ip summary-address rip router configuration command causes the router to summarize a given set of routes learned via RIP Version 2 or redistributed into RIP Version 2. Host routes are especially applicable for summarization.

See the "Route Summarization Example" section at the end of this chapter for examples of using split horizon.

You can verify which routes are summarized for an interface using the show ip protocols EXEC command. You can check summary address entries in the RIP database. These entries will appear in the database only if relevant child routes are being summarized. To display summary address entries in the RIP routing database entries if there are relevant routes being summarized based upon a summary address, use the show ip rip database command in EXEC mode. When the last child route for a summary address becomes invalid, the summary address is also removed from the routing table.

Lab 7

Configuring RIPv2

Jan 31, 2020

Packet Tracer Lab 7
Spring 2020
Chaz Davis

- Important Commands for the Lab
 - router rip
 - version 2
 - no auto-summary
 - network
 - for when long commands are interrupted by console message
 - passive-interface

Part 1: Configure RIPv2

i) Configure RIPv2 on R1

I configured the Router for default rute all internet traffic through serial 0/0/1

```
Ri>ena
Ri#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Ri(config)#ip route 0.0.0.0.0.0.0.0 serial 0/0/1
WDefault route without gateway, if not a point-to-point interface, may impact performance
Ri(config)#
```

Next I, configured the router to use rip protocol, then to use version 2, and then passed it the no auto-summary command

```
Ri>ena
Ri#conft
Enter configuration commands, one per line. End with CNTL/Z.
Ri(config)#ip route 0.0.0.0 0.0.0.0 serial 0/0/1
MDefault route without gateway, if not a point-to-point interface, may impact performance
Ri(config)#router rip
Ri(config-router)#version 2
Ri(config-router)#no auto-summary
Ri(config-router)#
```

I set the networks on R1, and then Used the passive interface command to setup the LAN port, and then default-information originate to advertise the routes that I've configured see: 7.1a.

Lastly, I stepped out of config router mode and ran the command: copy-running config startup-config to save my work see:7.1b

```
| Second | S
```

Figure 7.1: Configuring R1 for RIPv2

ii) Configure RIPv2 on R2 and R3 Next I configured R2 and R3 for their networks

```
Second 1

Second 1

Second 1

Second 2

Second 3

Second 4

Second
```

Figure 7.2: Configuring the Routers for RIPv2

Part 2: Verify Configurations

i) View Routing Tables of R1, R2, and R3

```
CATABOR AT NURSE

Codes: L. Local, C. - connected, S. - static, R. - RIP, M. - mobile, B. - B8P

D. - EIGRP, EX. - EIGRP external, 0 - 0.05PF, IA - 05PF inter area

N1 - 05PF NSA external type 1, B2 - 05PF NSAS external type 2

E1 - 05PF external type 1, E2 - 05PF external type 2, E - E6P

I - ISI-15, L1 - ISI-15 level-1, L2 - ISI-15 level-2, Ja - ISI-15 inter area

- candidate default, 0 - per-user static route, 0 - 00R

P. periodic downloaded static route

Gateway of last resort is 0.0.0.0 to network 0.0.0.0

102.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

C. 102.168.1.0/24 is directly connected, GigabitEtherneto/0

L. 102.168.1.0/24 is directly connected, GigabitEtherneto/0

L. 102.168.2.0/24 is variably subnetted, 2 subnets, 2 masks

C. 102.168.2.0/24 is variably subnetted, 2 subnets, 2 masks

C. 102.168.2.0/24 is variably subnetted, 2 subnets, 2 masks

C. 102.168.3.0/24 [120/1] via 102.168.2.2, 00:00:22, Serialo/0/0

R. 102.168.5.0/24 [102/1] via 102.168.2.2, 00:00:22, Serialo/0/0

R. 102.168.5.0/24 [102/1] via 102.168.2.2, 00:00:22, Serialo/0/0

200.165.200.0/24 is variably subnetted, 2 subnets, 2 masks

C. 200.165.200.2/24/0 is directly connected, Serialo/0/1

L. 200.165.200.2/24/0 is directly connected, Serialo/0/1

L. 200.165.200.2/24/0 is directly connected, Serialo/0/1

E15P
```

```
R2>show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, R2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - Is-Is, IL - Is-Is level-1, L2 - Is-Is level-2, ia - Is-Is inter area
* candiate default, U - per-user static route
P - periodic downloaded static route
Gateway of last resort is 192.168.2.1 to network 0.0.0
R 192.168.1.0/24 [120/1] Via 192.168.2.1, 00:00:28, Serial0/0
192.168.2.0/24 is variably submetted, 2 submets, 2 masks
C 192.168.2.0/24 is variably submetted, 2 submets, 2 masks
C 192.168.3.0/24 is variably submetted, 2 subnets, 2 masks
C 192.168.3.0/24 is variably submetted, 2 subnets, 2 masks
C 192.168.3.0/24 is variably submetted, 2 subnets, 2 masks
C 192.168.3.0/24 is variably submetted, 2 subnets, 2 masks
C 192.168.4.0/24 is variably submetted, 61.051Ethernet0/0
192.168.5.0/24 [120/1] via 192.168.4.1, 00:00:26, Serial0/0/0
R* 0.0.0.0/0 [120/1] via 192.168.2.1, 00:00:28, Serial0/0/0
```


(a) Routing Tables for R2

```
R3#show ip route
Codes: L - local, C - connected, S - static, R - RIP, N - mobile, B - BBP
D - EigRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
1 - IS-SSA external type 1, N2 - OSPF NSSA external type 2
1 - IS-SSA external type 1, N2 - OSPF NSSA external type 2
1 - IS-SSA external type 3
1 - IS-SSA
```

(b) Routing Tables for R3

Figure 7.3: IP Routing Tables for the Routers

ii) Success



(b) All components cleared

Figure 7.4: Successful Completion

Lab 8

Configuring Basic RIPv2

Jan 31, 2020

Packet Tracer Lab 8 Spring 2020 CIT 167 Chaz Davis

```
- Important Commands for the Lab

enable
configure terminal
```

router rip network 192.168.0.0 version 2 exit exit show ip route

ping 192.168.3.1 trace 192.168.3.1

exit

- Important Concepts
 - Dynamic or adaptive routing involves automatic updating of the routing tables based on information carried by routing protocols.
 - Link-state protocols require that a router inform all the nodes in a network of topology changes. Each node shares info regarding the nodes it can connect to with the entire network so that each node can build its own network map and determine for itself the least cost path to any given node.
 - RIP is a distance vector routing protocol which employs the hop count as a routing metric. RIP uses UDP as its transport protocol, and is assigned the reserved port number 520.
 - auto summarization a feature which allows RIP to summarize its routes to their classful networks automatically.

Part 1: Build the Network and Configure Basic Device Settings

I did as the Lab specified, I placed three 1941 routers, making sure to turn them off and add on the Serial ports, turning them back on when finished. I then placed two 2960 switches, and then three end user PCs as instructed.

i) Cable The Network

I ran the cabling between as shown in the diagram Fig 8.1, connecting the correct ports and interfaces.

ii) Initialize the Router and Switch and Configure basic settings for each

I configured each of the routers and then their serial interfaces, i then configured the switches

iii) Configure PC IP Addressing

I went to the desktop of each pc and set it up according to the addressing table. See Fig 8.2.







Figure 8.1: Cabling the Network



(a) Configuring PC A



(b) Configuring PC B



(c) Configuring PC C

Figure 8.2: Setting up the PC's according to the addressing Table

iv) Test Connectivity

To test connectivity I went to the command prompt on each of the PCs and pinged their routers. See Fig 8.3.

```
C:\pling 172.30.10.1 with 32 bytes of data:

Reply from 172.30.10.1 bytes=32 time=lms TTL=265

Reply from 172.30.10.1 bytes=32 time=lms TTL=265

Reply from 172.30.10.1 bytes=32 time=ms TTL=265

Reply from 172.30.10.1 bytes=32 time=2ms TTL=265

Reply from 172.30.10.1 bytes=32 time=lms TTL=265

Ping statistics for 172.30.10.1:

Apackets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 2ms, Average = 1ms
```

(a)

Packet Tracer PC Command Line 1.0

2:\oping 200.165.201.1

Pinging 200.165.201.1 with 32 bytes of data:

Reply from 200.165.201.1: bytes=32 time=1ms TTL=255

Reply from 200.165.201.1: bytes=32 time=1ms TTL=255

Reply from 200.165.201.1: bytes=32 time=1ms TTL=255

Reply from 200.165.201.1: bytes=32 time<1ms TTL=255

Pring statistics for 200.165.201.1:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms

 $$^{\rm (c)}$$ Figure 8.3: Testing Connectivity

Packet Tracer PC Command Line 1.0
2:\Sping 172.30.30.1 with 32 bytes of data:
Pinging 172.30.30.1 with 32 bytes of data:
Reply from 172.30.30.1: bytes=32 time=1ms TTL=255
Reply from 172.30.30.1: bytes=32 time<1ms TTL=255
Reply from 172.30.30.1: bytes=32 time<1ms TTL=255
Reply from 172.30.30.1: bytes=32 time<1ms TTL=255
Ping statistics for 172.30.30.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 1ms, Average = 0ms

(b)

Part 2: Configure and Verify RIPv2 Routing

i) Confingure RIPv2 routing

I ran the commands for setting up router rip version two on each router see Fig 8.4a.

ii) Examine the current state of the network

I ran show ip interface brief from router 2. See Fig 8.4b.

iii) Disable automatic summarization

I ran No auto-summary from each of the routers, cleared the ip routing tables

iv) Configure and redistribute a default route for internet access

I went to R2 set the default route and then gave the command to distribute the table amongst the network

v) Verify the routing configuration

I went to R1 and typed show ip route to verify the network configurations as you can see in Fig 8.5a.

I then Pinged PC-B from PC-A's interface. See Fig 8.5b.

Finally, I pinged PC-C from PC-B. Fig 8.5c.

```
Eleshow ip route

Dodes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF MSAB external type 1, R - OSPF MSAB external type 2

E1 - OSPF external type 1, E - OSPF external type 2

E1 - OSPF external type 1, E - OSPF external type 2, E - EGP

i - IS-IS, LI - IS-IS level-1, L - IS-IS level-2, ia - IS-IS inter area

" - candidate default, U - per-user static route, O - OOR

P - periodic downloaded static route

aateway of last resort is not set

10.0.0/8 is variably subnetted, 2 subnets, 2 masks

10.1.1.0/30 is directly connected, Serial0/6/6

12.30.0.0/2 list directly connected, Serial0/6/6

12.30.0.0/2 list directly connected, Serial0/6/6

12.30.10.1/22 is directly connected, 3 subnets, 1 masks

12.30.10.1/22 is directly connected, 3 subnets, 1 masks
```

(a) Setting Up RIPv2 on Each Router

```
RZ#show ip interface brief
Interface
IP-Address OK7 Method Status Protocol
sigabitEthernet0/0 209.185.201.1 YES manual up up
sigabitEthernet0/1 unassigned YES unset administratively down down
serial0/0/1 10.1.1.2 YES manual up up
serial0/0/1 10.2.2.2 YES manual up up
Vlan1 unassigned YES unset administratively down down
RZ#
```

(b) show ip interface brief ran from router 2

Figure 8.4: Configuring RIPv2 on the network

```
Risshow ip route

Dodes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIDFF, EX - EIGRP external, 0 - OSFF, IA - OSFF inter area

N1 - OSFF MSSA external type 1, 22 - OSFF MSSA external type 2

E1 - OSFF external type 1, E2 - OSFF external type 2, E -
```

(a) Running show ip route from R1

```
Pinging 209.165.201.2 with 32 bytes of data:

Reply from 209.165.201.2: bytes=32 time=2ms TTL=126
Reply from 209.165.201.2: bytes=32 time=1ms TTL=126
Reproximate round trip times in milli-seconds:
Minimum = 1ms, Maximum = 2ms, Average = 1ms
Reproximate round trip times in milli-seconds:
```

(b) Pinging PC-B from PC-A

```
C:(>ping 172.30.30.3

Pinging 172.30.30.3 with 32 bytes of data:

Reply from 172.30.30.3: bytes=32 time=2ms TTL=125

Reply from 172.30.30.3: bytes=32 time=2ms TTL=125

Reply from 172.30.30.3: bytes=32 time=5ms TTL=125

Reply from 172.30.30.3: bytes=32 time=5ms TTL=125

Ping statistics for 172.30.30.3:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 2ms, Maximum = 5ms, Average = 2ms
```

(c) Pinging PC-C from PC-A

Figure 8.5: Verifying connectivity

Part 3: Reflection

i) Why would you turn off auto-summary?

Route summarization reduces the amount of routing information in the routing tables. If you are using RIP Version 2, you can turn off automatic summarization by specifying no auto-summary. Disable automatic summarization if you must perform routing between disconnected subnets. When automatic summarization is off, subnets are advertised.

ii) How did R1 and R3 learn the pathway to the internet?

They are using rip routing updates from the router default config. RIPv2 multicasts the entire routing table to all adjacent routers at the address

SSH and Port Security

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

Configuring SSH

- All switch ports (interfaces) should be secured before the switch is deployed for production use.
 - Specify a single MAC address or a group of valid MAC addresses allowed on a port.
 - Specify that a port automatically shuts down if unauthorized MAC addresses are detected.
- Sticky secure MAC addresses
 - MAC addresses that can be dynamically learned or manually configured, then
 - stored in the address table and added to the running configuration by stick learning:
- $\bullet~$ If the sticky secure MAC addresses are saved to the startup configuration file
 - then when the switch restarts or the interface shuts down, the interface does not need to relearn the addresses.
 - If the sticky secure addresses are not saved, they will be lost.
- If sticky learning is disabled by using the no switchport port-security mac-address sticky interface configuration mode command
 - the sticky secure MAC addresses remain part of the address table, but are removed from the running configuration.

Characteristics of sticky secure MAC addresses:

- · Learned dynamically, converted to sticky secure MAC addresses stored in the running-config.
- Removed from the running-config if port security is disabled.
- $\bullet~$ Lost when the switch reboots (power cycled).
- Saving sticky secure MAC addresses in the startup-config makes them permanent and the switch retains them after a reboot.
- Disabling sticky learning converts sticky MAC addresses to dynamic secure addresses and removes them from the running-config.

Note: The port security feature will not work until port security is enabled on the interface using the switchport port-security command.

Port Security: Violation Modes

- Protect When the number of secure MAC addresses reaches the limit allowed on the port, packets with unknown source addresses are dropped until a sufficient number of secure MAC addresses are removed, or the number of maximum allowable addresses is increased. There is no notification that a security violation has occurred.
- Restrict When the number of secure MAC addresses reaches the limit allowed on the port, packets with unknown source addresses are dropped until a sufficient number of secure MAC addresses are removed, or the number of maximum allowable addresses is increased. In this mode, there is a *notification that a security violation has occurred*.
- Shutdown In this (default) mode, a port security violation causes the

interface to immediately become error-disabled and turns off the port LED. It increments the violation counter.

When a secure port is in the error-disabled state, it can be brought out of this state by entering the shutdown interface configuration mode command followed by the no shutdown command.

Port Security: Configuring

Default Port Security on a Cisco Catalyst Switch

- · Port security and Sticky address learning: Disabled
- Max number of secure MAC addresses: 1
- Violation mode: Shutdown (Port shuts down when max number of secure MAC addresses exceeded).

Ports in Error Disabled State

- When a port is error disabled, it is effectively shut down and no traffic is sent or received on that port.
- Port protocol and link status is changed to down; port LED will turn off; port goes into the error disabled stated.
- · show interfaces identifies port status as err-disabled
- $\bullet\,$ show port-security interface shows port status as secure-shutdown

The administrator should determine what caused the security violation before re-enabling the port. If an unauthorized device is connected to a secure port, the port should not be re-enabled until the security threat is eliminated. To re-enable the port, use the shutdown interface configuration mode command (Figure 3). Then, use the no shutdown interface configuration command to make the port operational.

SSH and Port Security

2020

Packet Tracer Labs Spring 2020

CIT 167 Chaz Davis

Configuring SSH

SSH configuration

show ip ssh

Verify that switch supports SSH, shows version

ip domain-name <domain-name> ip ssh version 2

Device must be minimally configured with a hostname # Recommended to only enable version 2 (more secure)

crypto key generate rsa username <username> privilege <level> secret <password>

Enable SSH protocol on VTY lines

line vty 0 15

transport input ssh

login local

Require local authentication from local username database

To delete a RSA key pair

crypto key zeroize rsa

SSH automatically disabled when key pair is deleted.

Port Security

 ${\bf Disable\ Unused\ Ports}\ \hbox{-}\ {\bf Good\ practice\ to\ disable\ unused\ ports};\ {\bf can\ configure\ range};$

interface range <type module>/<first number>-<last number> shutdown

Port Security: Operation Static Secure MAC Address:

```
interface <interface-id>
switchport port-security mac-address <mac-address>
```

Sticky secure MAC addresses - MAC addresses that can be dynamically learned or manually configured, then stored in the address table and added to the running configuration by stick learning:

switchport port-security mac-address sticky

(Intf-config)

- *All sticky secure MAC addresses are added to the address table and to the running configuration*.
- Sticky secure MAC addresses can also be manually defined (also added to running-config):

switchport port-security mac-address sticky <mac-address>

Port Security: Violation Modes

```
To change the violation mode on a switch port:

switchport port-security violation {protect | restrict | shutdown}
```

Port Security: Configuring

```
Configure Port Security on an Interface
```

```
interface <interface_id>
switchport mode access
switchport port-security
switchport port-security maximum 10
switchport port-security mac-address sticky

# Sets interface mode to access
# Enables port security on the interface
# Max number of secure addresses allowed
# Enables sticky learning
```

- Violation mode is set to shutdown by default.

Port Security: Verifying

Verify Port Security Settings:

show port-security interface <interface_id>

Verify Secure MAC Addresses:

show port-security address

Lab 9

Basic Switch Configuration

February 21, 2020

Packet Tracer Lab 09 Spring 2020 CIT 167 Chaz Davis

Steps to Configure Switches

- Step 1 Connect to the device via console
- Step ${\bf 2}$ Setup a hostname for the particular Helps distiguish it within the network
- Step 3 Configure an admin password enable secret password
- Step 4 configure a password for the Telnet and Console access
- ${f Step~5}$ Define IP adresses allowed to acces Telnet
- Step 6 Assign IP address to the switch $\label{eq:condition} \text{Used for management}$
- Step 8 Disable unneeded ports on the switch
- ${\bf Step~9}$ Configure L2 Vlans and assign them ports
- Step 10 Save the configuration

Part 1: Cable the Network and Verify the Default Switch Configuration

i) Cable the Network

I set up the network according to the topography, see Fig. 9.1a on Pg.Pg. 68. I went to the flash memory on the switch, and there was no vlan.dat configuration. So I proceeded to the next step.

ii) Verify the default switch Configuration

а

I ran the enable command to log into priviledged exec mode and ran the following commands:

h

We can see in Fig. 9.1b on Pg. 68 that the switch has 24 fast ethernet ports and that the switch has 2 gigabit ethernet ports. We can also see that the vty lines have the values 0 4 and 5 15.

c

In Fig. 9.2a on Pg. 69 that we do indeed get the response startup-config is not present, this is because we have not configured any settings, and have in fact reset the switch.

d

From the output of Fig. 9.2b on Pg. 69 that that there is no ip address assigned yet, because we have not set it up yet, and that the mac address is 00e0.f9bd.263e.

e and f

You can see in Fig. 9.2 c on Pg. 69 that protocols are down and vlan 1 is not set up yet. It's showing multicast and fifo settings after hookup.

 \mathbf{g}

You can see in Fig. 9.3 a on Pg. 69 that the Cisco IOS version on the switch is 12.2(25)FX, and the system image filename C2960-LANBASE-M, and the mac address is 00e0.f9bd.263e.

h

You can see in Fig. 9.3 b on Pg. 69 that the interface is up because we connected it to the PC. mac address is 00e0.b037.9co6. The speed of the switch is 100mb/s and it is full duplex.

i

You can see in Fig. 9.3 c on Pg. 69 that the name of vlan 1 is default, currently all ports on on vlan 1, the default type is ethernet.




Figure 9.1: Configuring and verifying the switch Pt 1

```
Switch#Snow run
Building configuration...
  Current configuration : 1080 bytes
!
version 12.2
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
  nostname Switch
   panning-tree mode pvst
panning-tree extend system-id
  nterface FastEthernet0/1
  nterface FastEthernet0/2
 :
interface FastEthernet0/3
 :
interface FastEthernet0/4
  nterface FastEthernet0/5
 .
interface FastEthernet0/6
 :
interface FastEthernet0/7
 :
interface FastEthernet0/8
  interface FastEthernet0/9
  nterface FastEthernet0/10
 :
interface FastEthernet0/11
 !
interface FastEthernet0/12
 interface FastEthernet0/13
 :
interface FastEthernet0/15
 :
interface FastEthernet0/16
 .
interface FastEthernet0/17
 .
interface FastEthernet0/19
 !
interface FastEthernet0/21
  Interface FastEthernet0/22
 interface FastEthernet0/23
 :
interface GigabitEthernet0/1
  nterface GigabitEthernet0/2
 !
interface Vlan1
no ip address
shutdown
line vty 0 4
login
line vty 5 15
login
```

(b) show running config output

Switch# Switch#show startup-config startup-config is not present Switch#

(a) show startup config

SWITCH#Show interrace vian 1
Vlan1 is administratively down, line protocol is down
Hardware is CPU Interface, address is 00e0.f0bd.263e (bia 00e0.f0bd.
203e)
MTU 1500 bytes, BW 100000 Kbit, DLY 10000000 usec,
 reliability 255/255, txload 1/255, rxload 1/255
Encapsulation ARPA, loopback not set
ARP type: ARPA, ARP Timeout 04:00:00
Last input 21:40:21, output never, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
queueing strategy: fifo
Output queue: 0/40 (size/max/drops/flushes); Total output drops: 0
Timute input rate 0 bits/sec, 0 packets/sec
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
1082 packets input, 530005 bytes, 0 no buffer
Received 0 broadcasts (0 IP multicast)
0 runts, 0 qiants, 0 throttles
0 input errors, 0 cRC, 0 frame, 0 overrun, 0 ignored
503809 packets output, 0 bytes, 0 underruns
0 output errors, 23 interface resets
0 output buffer failures, 0 output buffers swapped out

(b) show interface vlan1

Switch#show ip interface vlan 1 Vlan1 is administratively down, line protocol is down Internet protocol processing disabled

(c) show ip interface vlan1 after connecting the ethernet cable

Figure 9.2: Configuring and Verifying the switch Pt 2

```
LAN Name
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 Status Ports
SMITCHSHOW VERSION

Lisco IOS SOFTWARE, (2008 SOftware (C2000-LANBASE-M), Version 12.2(25)FX,

EXELBASE SOFTWARE (fc.)

copyright (c) 1986-2009 by Cisco Systems, Inc.

compiled wed 12-0cr-05 22:05 by pt_team
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              active Fa0/1, Fa0/2, Fa0/3,
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               Fa0/5, Fa0/6, Fa0/7,
 ROM: C2960 Boot Loader (C2960-HBOOT-M) Version 12.2(25r)FX, RELEASE
SOFTWARE (fc4)
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               Fa0/9, Fa0/10, Fa0/11,
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     a0/12
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               Fa0/13, Fa0/14, Fa0/15,
                                                                                                                                                                                                                                                                                     Fa9/16
 cisco W3-C2960-24TT (RC32300) processor (revision C0) with 21039K bytes of memory.
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               Fa0/17, Fa0/18, Fa0/19,
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   Fa0/20
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  Fa0/21, Fa0/22, Fa0/23,
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  Fa9/24
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  Gig0/1, Gig0/2
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 1002 fddi-default
1003 token-ring-default
1004 fddinet-default
1005 trnet-default
     Gagant Ethernet/IEEE 802.3 Intertace(s)

AGRK bytes of Tabhs.shuntace non-volatile configuration men
ase ethernet Mc Address
see ethernet See ethernet See ethernet Mc Address
see ethernet See ethernet See ethernet Mc Address
see ethernet See 
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           MTU Parent RingNo BridgeNo Stp BrdgMode Trans1
                   code Number
are Board Revision Number
              1 26 WS-C2960-24TT
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     rimary Secondary Type
     onfiguration register is 0xF
                                                        (a) show version output
                                                                                                                                                                                                                                                                                                                                                            (b) show interface f0/6
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       (c) show vlan
                                                                                                                                                                                                                                                       SWITCH#SHOW YLASH
```

```
SWITCHMSHOW YIASH
Directory of flash:/

1 -rw- 4414921 <no date> c2960-lanbase-mz.

122-25.FX.bin
64016384 bytes total (59601463 bytes free)

(d) show flash
```

Figure 9.3: Configuring and Verifying the switch Pt 3

Part 2: Configure Basic Network Device Settings

i) Configure basic switch settings

I ran pasted the commands as shown by you. I ran the commands to setup the ip address and default ip address. I set up the console and setup the vty. The login command is required because it logs in the first time and makes us use the password afterwards.

ii) Configure IP address on PC-A

I logged into PC-A and configured the ip configuration according to the table

Part 3: Verify and Test Network Connectivity

i) Display the switch configuration

You can see in Fig. 9.4 a on Pg. 71 and Fig. 9.4b on Pg. 71 that the bandwidth is 100,000 bytes, its state is up and its protocol is up.

ii) Test end-to-end connectivity with ping

I ran ping from PC-A to PC-A as seen in Fig. 9.4c on Pg. 71.

I then, Pinged S1 from PC-A, the first ping was lost due to address resolution, as you can see in Fig. 9.4d on Pg. 71.

iii) Test and Verify Remote management of S1

From PC-A I remotely logged into S1 via telnet. See Fig. 9.4e on Pg. 71.

iv) Saving the Switch Running Configuration File

I saved the switches configuration file.

51#show in int vian 99

MTU is 1500 bytes Helper address is not set

Proxy ARP is enabled

'lan99 is up, line protocol is up Internet address is 192.168.1.2/24 Broadcast address is 255.255.255.255 Address determined by setup command

Outgoing access list is not set Inbound access list is not set

Directed broadcast forwarding is disabled

```
Local Proxy ARP is disabled
                                                                                Security level is default
                                                                                Split horizon is enabled
                                                                                ICMP redirects are always sent
                                                                                ICMP unreachables are always sent
                                                                                ICMP mask replies are never sent
                                                                                IP fast switching is disabled
                                                                                IP fast switching on the same interface is disabled
S1#show vlan brief
                                                                                IP Null turbo vector
VLAN Name
                                Status
                                        Ports
                                                                                IP multicast fast switching is disabled
                                                                                IP multicast distributed fast switching is disabled
                                                                                IP route-cache flags are None
                                active Fa0/1, Fa0/2, Fa0/3,
99 VLAN0099
Fa0/4
                                                                                Router Discovery is disabled
                                                                                IP output packet accounting is disabled
                                         Fa0/5, Fa0/6, Fa0/7,
Fa0/8
                                                                                IP access violation accounting is disabled
                                         Fa0/9, Fa0/10, Fa0/11,
                                                                                TCP/IP header compression is disabled
Fa0/12
                                         Fa0/13, Fa0/14, Fa0/15,
                                                                                RTP/IP header compression is disabled
Fa0/16
                                                                                Probe proxy name replies are disabled
                                         Fa0/17, Fa0/18, Fa0/19,
Fa0/20
                                                                                Policy routing is disabled
                                         Fa0/21, Fa0/22, Fa0/23,
                                                                                Network address translation is disable
Fa0/24
                                         Gig0/1, Gig0/2
                                                                                WCCP Redirect outbound is disabled
1002 fddi-default
1003 token-ring-default
1004 fddinet-default
                                active
                                                                                WCCP Redirect inbound is disabled
                                active
                                                                                WCCP Redirect exclude is disabled
                                active
1005 trnet-default
                                 active
                                                                                BGP Policy Mapping is disabled
                         (a) show run
                                                                                                  (b) show interface vlan 99
                                         acket Tracer PC Command Line 1.0
                                         :\>ping 192.168.1.10
                                       Pinging 192.168.1.10 with 32 bytes of data:
                                        Reply from 192.168.1.10: bytes=32 time=5ms TTL=128
                                       Reply from 192.168.1.10: bytes=32 time=1ms TTL=128
Reply from 192.168.1.10: bytes=32 time=2ms TTL=128
                                        Reply from 192.168.1.10: bytes=32 time=2ms TTL=128
                                        ing statistics for 192.168.1.10:
                                           Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
                                        pproximate round trip times in milli-seconds:
Minimum = 1ms, Maximum = 5ms, Average = 2ms
                                                            (c) PC-A pinging PC-A
                                                                                 \>telnet 192.168.1.2
                                                                               Trying 192.168.1.2 ...Open
  \>ping 192.168.1.2
                                                                              Unauthorized access is strictly prohibited
Pinging 192.168.1.2 with 32 bytes of data:
 Request timed out.
                                                                              User Access Verification
Reply from 192.168.1.2: bytes=32 time<1ms TTL=255
Reply from 192.168.1.2: bytes=32 time<1ms TTL=255
                                                                               Password:
 eply from 192.168.1.2: bytes=32 time<1ms TTL=255
                                                                              S1>enable
                                                                               assword:
 ing statistics for 192.168.1.2:
   Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
                                                                               S1#exit
  proximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
                                                                               [Connection to 192.168.1.2 closed by foreign host]
                      (d) PC-A pinging S1
                                                                                                    (e) PC-A telnet to S1
```

Figure 9.4: Verifying and Testing Network Connectivity

Part 4: Manage the MAC Address table

i) Record the MAC address of the host

There were none listed in the table. zero in total.

ii) Determine the MAC Addresses that the switch has learned

There are three options for Mac addressing dynamic, interfaces, or static.

iii) List the show mac address-table options

There are three options, dynamic, interfaces, or static.

iv) Set up a static MAC address

I ran the commands as shown and set up the mac address, statically.

Reflection

i) Why should you configure the vty password for the switch?

To protect it from unwanted usage where someone could set up a way into the network and where they would have root access to the network.

ii) Why change the default VLAN 1 to a different VLAN number?

Harder to find from cursory looks at the network.

iii) How can you prevent passwords from being sent in plain text? set encryption

iv) Why configure a static MAC address on a port interface?

So that it stays the same and doesnt try to ask the DNS to resolve it and risk losing it and resetting the main ports of the network.

Configuring Switch Security Features February 26, 2020

Packet Tracer Lab 10 Spring 2020 CIT 167 Chaz Davis

Port security features

- Port security is disabled by default.
 - switchport port-security command is used to enabled it.
- Port security feature does not work on three types of ports.
 - Trunk ports
 - Ether channel ports
 - Switch port analyzer ports

Part 1: The Lab

i) Cable the Network

I created and cabled the network according to the diagram.

ii) Initialize and reload the router and switch

I went into router configuration, and checked the flash.

iii) Configure an IP address on PC-A

I then went to PC-A and setup the IP configuration.

iv) Configure basic settings on R1

I went into R1 and entered the commands and then copied the running and startup configs.

v) Configure basic settings on S1

I ran the commands from the diagram, setting up basic settings and then creatings and configuring vlan 99. When I issued the show vlan command it shows vlan 99 as active.

When I ran the command show ip interface brief the status was ok and protocol was down.

It shows as down because its not connected to a network.

After assigning f0/5 and f0/6 to vlan 99 no when running the show ip int brief command we can see vlan 99 as up.

vi) Verify Connectivity between Devices

As you can see in Fig. 10.1 All of the pings were successful.

```
Packet Tracer PC Command Line 1.0
C:\>ping 172.16.99.1
Pinging 172.16.99.1 with 32 bytes of data:
Reply from 172.16.99.1: bytes=32 time=87ms TTL=255
Reply from 172.16.99.1: bytes=32 time<1ms TTL=255
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Reproximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 87ms, Average = 21ms
```

```
C:\>ping 172.16.99.11

Pinging 172.16.99.11 with 32 bytes of data:

Request timed out.

Reply from 172.16.99.11: bytes=32 time<1ms TTL=255

Reply from 172.16.99.11: bytes=32 time<1ms TTL=255

Reply from 172.16.99.11: bytes=32 time<1ms TTL=255

Ping statistics for 172.16.99.11:

Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

```
(a) PC-A pinging R1

SI#ping 172.16.99.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.99.1, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms

(c) S1 pinging R1
```

Figure 10.1: Successful pings on the network

vii) Configure SSH access on S1

The ssh-version is 1.99

SSH will allow 3 retries

The default timeout is 120 secs

viii) Modify the SSH configuration on S1

It will now allow 2 retries, so a total of 3 attempts.

The timeout would be 75 seconds. So, 1 minute and 15 seconds.

a

It was successful, and the prompt said unauthorized access is strictly prohibited, and the gave the S1 prompt with the octothorpe signifying the admin account.

ix) Configure general security features on S1

b

```
Si#config t
Enter configuration commands, one per line. End with CNTL/Z.
Si(config)#banner motd #
Enter TEXT message. End with the character '#'.
Unauthorized access is strictly prohibited. Violators will be prosecuted to the full extent of the law. #
Si(config)#exit
```

Figure 10.2: Banner MOTD update

c

The physical ports that are open are $\mathrm{Fa0/5}$ and $\mathrm{Fa0/6}$

c & d

I ran the commands the output of show ip int brief gives us:

S1#show ip int brief						
Interface	IP-Address	OK?	Method	Status		Protocol
FastEthernet0/1	unassigned	YES	manual	administratively	down	down
FastEthernet0/2	unassigned	YES	manual	administratively	down	down
FastEthernet0/3	unassigned	YES	manual	administratively	down	down
FastEthernet0/4	unassigned	YES	manual	administratively	down	down
FastEthernet0/5	unassigned	YES	manual	up		up
FastEthernet0/6	unassigned	YES	manual	up		up
FastEthernet0/7	unassigned			administratively		
FastEthernet0/8	unassigned	YES	manual	administratively	down	down
FastEthernet0/9	unassigned	YES	manual	administratively	down	down
FastEthernet0/10	unassigned	YES	manual	administratively	down	down
FastEthernet0/11	unassigned	YES	manual	administratively	down	down
FastEthernet0/12	unassigned	YES	manual	administratively	down	down
FastEthernet0/13	unassigned	YES	manual	administratively	down	down
FastEthernet0/14	unassigned			administratively		
FastEthernet0/15	unassigned			administratively		
FastEthernet0/16	unassigned			administratively		
FastEthernet0/17	unassigned	YES	manual	administratively	down	down
FastEthernet0/18	unassigned	YES	manual	administratively	down	down
FastEthernet0/19	unassigned	YES	manual	administratively	down	down
FastEthernet0/20	unassigned	YES	manual	administratively	down	down
FastEthernet0/21	unassigned	YES	manual	administratively	down	down
FastEthernet0/22	unassigned	YES	manual	administratively	down	down
FastEthernet0/23	unassigned			administratively		
FastEthernet0/24	unassigned			administratively	down	
GigabitEthernet0/1	unassigned		manual			down
GigabitEthernet0/2	unassigned	YES	manual	down		down
Vlan1	unassigned	YES	manual	administratively	down	down
Vlan99	172.16.99.11	YES	manual	up		up
S1#						

Figure 10.3: Output of show ip int brief

x) Configure and verify port security on S1

a
The macaddress is 0004.9a08.6602
b
fa0/5 has a mac address of 0004.9a08.6602 and fa0/6 doesnt show on the table.
c & d
The port status is secure-up.
e
From R1 I pinged PC-A as seen in Fig. 10.4a.
l
The ping from R1 to PC-A was not successful.
m
See Fig. 10.4b for the output of show int f0/5.

This time the ping was successful again. See Fig. 10.4c

RI#ping 172.16.99.3

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.99.3, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms

(a) With a MAC-address

RI#ping 172.16.99.3

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.99.3, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5)
RI#

(b) With no mac-address

RI#ping 172.16.99.3

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.99.3, timeout is 2 seconds:
Sending 5, 100-byte ICMP Echos to 172.16.99.3, timeout is 2 seconds:

Figure 10.4: Ping from R1 to PC-A

Success rate is 80 percent (4/5), round-trip min/avg/max = $\theta/\theta/\theta$ ms (c) With S1 back on

Reflection

i) Why would you enable port security on a switch?

To prevent unauthorized users to gain access to the LAN.

ii) Why should unused ports on a switch be disabled?

Any enabled port not in use could allow someone to come in and plug into your network and gain access. So, it's best practice to disable any unused ports.

Configuring VLANs

2020

Packet Tracer Labs Spring 2020 CIT 167 Chaz Davis

Configuring VLANs

SSH configuration

- Configurations are stored in the `flash:vlan.dat` file.

Display/Verify VLANs

```
show vlan
show vlan brief
show vlan summary
show vlan id <vlan-id>
show vlan name <vlan-name>
show interfaces vlan <vlan-id>
show interfaces <interface-id> switchport
```

```
Create a VLAN
```

vlan <vlan-id>
name <vlan-name>
exit

vlan 100,102, 105-107 # Creates multiple VLANs

Assigning Ports to VLANs

interface <interface-id>
switchport mode access
switchport access vlan <vlan-id>

interface range <interfaces> can be used to configure multipe interfaces.

Changing VLAN Port Membership

interface <interface-id>
no switchport access vlan # Removes vlan;
not necessary if want to replace

Deleting VLANs

no vlan <vlan-id># Delete single VLAN

delete flash:vlan.dat # Deletes entire vlan.dat file

- Note: before deleting a VLAN, reassign all member ports to a different VLAN first. Any ports that are not moved to an active VLAN are unable to communicate with other hosts after the VLAN is deleted and until they are assigned to an active VLAN.

Restore switch to factory defaults

erase startup-config delete vlan.dat reload

Configuring VLAN Trunks

```
interface <interface-id>
switchport mode trunk
switchport trunk native vlan <vlan-id>
switchport trunk allowed vlan <vlan-list>
exit
```

Resetting the Trunk to Default State

```
interface <interface-id>
no switchport trunk allowed vlan
no switchport trunk native vlan
and
```

Troubleshooting VLANs

```
show vlan
show mac address-table
show interfaces
show interfaces switchport
show interface <interface-id> switchport
```

- Each VLAN must correspond to a unique IP subnet; check IP addressing.
- Check that ports belongs to expected VLANs and are active.
- Check if inactive VLAN is assigned to a port: 'show interfaces switchport'

Troubleshooting Trunks

show interfaces trunk

- Check whether local and peer native VLANs match (VLAN leaking occurs with mismatch).
- Check whether trunk has been established. Cisco Catalyst switch ports use DTP by default; statically configure trunk links whenever possible.
- Check status of trunk ports for incorrect port modes
- Common configuration errors:
- Native VLAN mismatches: inter-VLAN routing issues; security risk.
- Trunk mode mismatches: trunk link will not work.
- $\bullet\,\,$ Allowed VLANs on trunks: unexpected or no traffic.

Troubleshooting Vlans Scenario 1 February 29, 2020

Netlab Lab 11 Spring 2020 Chaz Davis

Common General Switch Issues

- Physical Interface/Connectivity Issues.
- Physical Interface Speed/Duplex Issues.
- VLAN-specific Issues.
- VLAN trunking issues.
- $\bullet~$ Inter-VLAN Routing Issues.
- 802.1D Spanning Tree Issues.
- no ip authentication mode eigrp 100 md5.

Part 1: Test Connectivity between PCs on the Same VLAN

i) Can PC1 ping PC4

Attempt to ping PC4 from PC1 was unsuccessful. See Fig. 11.1 a.

ii) Can pc2 ping pc5

Attempt to ping PC5 from PC2 was unsuccessful. See Fig. 11.1 b.

iii) Can pc3 ping pc6

Attempt to ping PC6 from PC3 was unsuccessful. See Fig. 11.1 c.

```
C:\>ping 172.17.10.24

Pinging 172.17.10.24 with 32 bytes of data:

Request timed out.

Request timed out.

Request timed out.

Request timed out.

Ping statistics for 172.17.10.24:

Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

(a) PC1 pinging PC4

C:\>ping 172.17.20.25

Pinging 172.17.20.25 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 172.17.20.25:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>

C:\>ping 172.17.30.26

Pinging 172.17.30.26 with 32 bytes of data:

Request timed out.

Request timed out.

Request timed out.

Request timed out.

Ping statistics for 172.17.30.26:

Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>

(c) PC3 Pinging PC6

Figure 11.1: Testing Connections on the same networks

Part 2: Investigate Connectivity Problems by Gathering Data

i) Verify Configurations on the PCs

(b) PC2 pinging PC5

I checked configurations for IP address and subnetmasks on all pcs. PC5 had an incorrect IP address.

ii& 3) Verify Configs on the Switches

On switch 2 vlan for subnet 30 had the 10 and 30 subnets attached to it, so I moved the Fa0/11 interface to 10 faculty/staff. Also on S2, G0/1 was not setup as a trunk.

PC5 appears to be connected on port Fa0/17 when it should be Fa0/18.

Switch3, vlan 20 and vlan 30 are switched on their connections.

Part 3: Implement the Solution and Test Connectivity

On S2 I ran int fa 0/11 and then switchport access vlan 10to correct the first issue. Then I ran, int g0/1 and then switchport mode trunk.

On S1, I ran int g0/1 and then switchport mode trunk.

On S3, I ran int f0/18 and then switchport access vlan 20. I then ran int f0/6 and then switchport access vlan 30. I'll now attempt to ping each of the connected networks. All pings were successful. See Fig. 11.2.

```
C:\>ping 172.17.10.24

Pinging 172.17.10.24 with 32 bytes of data:

Reply from 172.17.10.24: bytes=32 time=12ms TTL=128

Reply from 172.17.10.24: bytes=32 time<1ms TTL=128

Reply from 172.17.10.24: bytes=32 time<1ms TTL=128

Reply from 172.17.10.24: bytes=32 time<1ms TTL=128

Ping statistics for 172.17.10.24:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 12ms, Average = 3ms
```

(a) PC1 pinging PC4

```
C:\>ping 172.17.20.25

Pinging 172.17.20.25 with 32 bytes of data:

Reply from 172.17.20.25: bytes=32 time=24ms TTL=128

Reply from 172.17.20.25: bytes=32 time<1ms TTL=128

Reply from 172.17.20.25: bytes=32 time<1ms TTL=128

Reply from 172.17.20.25: bytes=32 time<1ms TTL=128


Ping statistics for 172.17.20.25:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 24ms, Average = 6ms
```

(b) PC2 pinging PC5



(c) PC3 pinging PC6

Figure 11.2: Network connections are now all successfull




Figure 11.3: Successful Completion of the Activity $\,$

Troubleshooting Vlans Scenario 2 March 2, 2020

Packet Tracer Lab 12
Spring 2020
Chaz Davis

The following CLI commands are used to display VLAN information:

- show system internal private-vlan info
- show system internal private-vlan event-history errors
- show system internal private-vlan event-history traces
- show vlan id vlan-id
- $\bullet \quad \text{show vlan private-vlan}$
- show vlan all-ports
- show vlan private-vlan type
- show vlan internal bd-info vlan-to-bd 1
- show vlan internal errors
- show vlan internal info
- ullet show vlan internal event-history errors

Part 1: Discover and Documentation Issues in the Network

i) Verifying PC conectivity

You can see in Fig. 12.1 on Pg. 84, I checked the setup for ip configuration on all six PCs on the network. All of the PCs had the correct configurations for their IP addresses, subnet masks, and their default gateways.

You can see in Fig. 12.2 on Pg. 84, none of the PCs were able to talk to their network counterparts.




Figure 12.1: IP config for PC on the network

```
Packet Tracer PC Command Line 1.0
C:\>ping 192.168.10.24

Pinging 192.168.10.24 with 32 bytes of data:

Request timed out.

Request timed out.

Request timed out.

Request timed out.

Ping statistics for 192.168.10.24:

Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>
```

```
Packet Tracer PC Command Line 1.0
C:\>ping 192.168.20.25

Pinging 192.168.20.25 with 32 bytes of data:

Request timed out.
Requ
```

Figure 12.2: Pingin PCs on Joined Networks - Unsuccessfully

ii) Verifying Switch Configuration

(b) Vlan Brief on Switch 1

In order to discover More about the switch configurations, and why the three networks weren't able to communicate amongst themselves, I ran both show ip int brief, see Fig. 12.3 on Pg. 85. I then ran show vlan brief on each of the switches, see Fig. 12.4 on Pg. 85.




Figure 12.4: Running show vlan brief on each switch

(c) Vlan Brief on Switch 3

iii) Documenting the Problems and Solutions

As you can see in Fig. 12.1 I have found the errors and will fix them and then retest all of the connections.

Table 12.1: Documentation

Problems	Solutions
S1 not configured with any vlan	Configure Vlans
S1 Native vlan 56	set Native VLAN 56
S2 g0/1 is an access port not a trunk port	Implement switchport mode# trunk command
s3 ports are not assigned to a VLAN	Implement switchport access vlan# command
	based on the Port assignment table

Part 2: Implement Solutions and Test Connectivity

i) Setting up Switch 1

For switch 1, I ran the following commands:

```
en
conf t
vlan 56
name Management&Native
vlan 30
name Guest(Default)
vlan 10
name Faculty/Staff
vlan 20
name Students
int range g0/1 - 2
switchport trunk native vlan 56
```

Once I ran those commands, I got the following in my tables:

astEthernet0/1	unassigned	YES manual	down	down			
astEthernet0/2	unassigned	YES manual	down	down			
astEthernet0/3	unassigned	YES manual	down	down			
astEthernet0/4	unassigned	YES manual	down	down			
astEthernet0/5	unassigned	YES manual	down	down			
astEthernet0/6	unassigned	YES manual	down	down			
stEthernet0/7	unassigned	YES manual	down	down			
astEthernet0/8	unassigned	YES manual	down	down			
astEthernet0/9	unassigned	YES manual	down	down			
astEthernet0/10	unassigned	YES manual	down	down	61#show vlan brief		
astEthernet0/11	unassigned	YES manual	down	down			
astEthernet0/12	unassigned	YES manual	down	down	/LAN Name	Status	Ports
astEthernet0/13	unassigned	YES manual	down	down			
istEthernet0/14	unassigned	YES manual	down	down	1 default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4
stEthernet0/15	unassigned	YES manual	down	down			Fa0/5, Fa0/6, Fa0/7, Fa0/8
stEthernet0/16	unassigned	YES manual	down	down			Fa0/9, Fa0/10, Fa0/11, Fa0/1
stEthernet0/17	unassigned	YES manual	down	down			Fa0/13, Fa0/14, Fa0/15, Fa0/
stEthernet0/18	unassigned	YES manual	down	down			
stEthernet0/19	unassigned	YES manual	down	down			Fa0/17, Fa0/18, Fa0/19, Fa0/
istEthernet0/20	unassigned	YES manual	down	down			Fa0/21, Fa0/22, Fa0/23, Fa0/
istEthernet0/21	unassigned	YES manual	down	down	<pre>10 Faculty/Staff</pre>	active	
istEthernet0/22	unassigned	YES manual	down	down	20 Students	active	
istEthernet0/23	unassigned	YES manual	down	down	30 Guest(Default)	active	
astEthernet0/24	unassigned	YES manual	down	down	56 Management&Native	active	
igabitEthernet0/1	unassigned	YES manual	up	up	1002 fddi-default	active	
gabitEthernet0/2	unassigned	YES manual	up	up	1003 token-ring-default	active	
an1	unassigned	YES manual	administratively down	down	1004 fddinet-default	active	
lan56	192.168.56.11	YES manual	up	up			
#					1005 trnet-default	active	

Figure 12.5: S1 after configuration

ii) Setting Up Switch 2

For Switch 2, I ran the following commands:

en

conf t
int g0/1
switchport mode trunk

After running those commands, I got the following output:

Interface IP-Address	S2#show ip int brief						
FastEthernet0/2 unassigned YES manual down down FastEthernet0/3 unassigned YES manual down down FastEthernet0/3 unassigned YES manual down down FastEthernet0/4 unassigned YES manual down down FastEthernet0/5 unassigned YES manual down down FastEthernet0/6 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/11 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down		IP-Address	OK? Method Status	Protocol			
FastEthernet0/2 unassigned YES manual down down FastEthernet0/3 unassigned YES manual down down FastEthernet0/4 unassigned YES manual down down FastEthernet0/5 unassigned YES manual down down FastEthernet0/6 unassigned YES manual down down FastEthernet0/6 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/8 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down 1 default active Gig0/2 FastEthernet0/1 unassigned YES manual down down 20 Students active Fa0/1, Fa0/1, Fa0/1, Fa0/19, Fa0/2, Fa0/12, Fa0/2, Fa0/23, Fa0/24 Fa5tEthernet0/2 unassigned YES manual down down 30 Guest(Default) active Fa0/1, Fa0/2, Fa0/3, Fa0/6 Fa5tEthernet0/2 unassigned YES manual down down 50 Management&Native active Fa0/1, Fa0/2, Fa0/3, Fa0/6 Fa0/10 Fa0/2, Fa0/2, Fa0/3, Fa0/6 Fa0/10 Fa0/2 Fa0/20 Fa0/20 Fa0/20 Fa0/20 Fa0/20 Fa0/20 Fa0/2							
FastEthernet0/3 unassigned YES manual down down FastEthernet0/4 unassigned YES manual down down FastEthernet0/5 unassigned YES manual down down FastEthernet0/6 unassigned YES manual up up FastEthernet0/7 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/11 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/13 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down							
FastEthernet0/5 unassigned YES manual down down FastEthernet0/5 unassigned YES manual down down FastEthernet0/6 unassigned YES manual up up FastEthernet0/6 unassigned YES manual up up FastEthernet0/7 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down Dup FastEthernet0/2 unassigned YES manual down down Dup Fa			YES manual down				
FastEthernet0/5 unassigned YES manual down down FastEthernet0/6 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/7 unassigned YES manual down down FastEthernet0/8 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/11 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/13 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual dow	FastEthernet0/4						
FastEthernet0/6 unassigned YES manual up up FastEthernet0/7 unassigned YES manual down down FastEthernet0/8 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down WLAN Name Status Ports FastEthernet0/1 unassigned YES manual down down Unassigned YES manual down down AssEthernet0/1 unassigned YES manual down down Deathernet0/1 unassigned YES manual down down I default active Gig0/2 FastEthernet0/1 unassigned YES manual down down I fastEthernet0/1 unassigned YES manual down down PastEthernet0/1 unassigned YES manual down down I fastEthernet0/1 unassigned YES manual down down I fastEthernet0/1 unassigned YES manual down down 2 Students active Fa0/11, Fa0/12, Fa0/13, Fa0/16, Fa0/16, Fa0/16, Fa0/16, Fa0/16, Fa0/17, Fa0/18, Fa0/16, Fa0/17, Fa0/18, Fa0/18, Fa0/19, Fa0/28, Fa0/23, Fa0/24, Fa0/23, Fa0/24, Fa0/23, Fa0/24, Fa0/23, Fa0/24, Fa0/23, Fa0/24, Fa0/23, Fa0/24, Fa0/24	FastEthernet0/5		YES manual down	down			
FastEthernet0/7 unassigned YES manual down down FastEthernet0/8 unassigned YES manual down down FastEthernet0/9 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/11 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/13 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual d	FastEthernet0/6		YES manual up				
FastEthernete/9 unassigned YES manual down down FastEthernete/9 unassigned YES manual down down FastEthernete/10 unassigned YES manual down down FastEthernete/11 unassigned YES manual down down FastEthernete/12 unassigned YES manual down down FastEthernete/12 unassigned YES manual down down FastEthernete/13 unassigned YES manual down down FastEthernete/14 unassigned YES manual down down FastEthernete/15 unassigned YES manual down down FastEthernete/16 unassigned YES manual down down FastEthernete/16 unassigned YES manual down down FastEthernete/17 unassigned YES manual down down FastEthernete/19 unassigned YES manual down down FastEthernete/19 unassigned YES manual down down FastEthernete/20 unassigned YES manual down down fastItyley down FastEthernete/20 unassigned YES manual down down fastItyley down fastItyley down FastEthernete/20 unassigned YES manual d	FastEthernet0/7						
FastEthernet0/9 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/11 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/21 unassigned YES manual down down FastEthernet0/20 unassigned YES manual							
FastEthernet0/19 unassigned YES manual down down FastEthernet0/11 unassigned YES manual down down FastEthernet0/12 unassigned YES manual down down FastEthernet0/13 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down 20 Students active Fa0/11, Fa0/12, Fa0/13, Fa0/16, Fa0/1	FastEthernet0/9		YES manual down				
FastEthernete/11 unassigned YES manual Up up Assigned YES manual down down PastEthernete/12 unassigned YES manual down down AssEthernete/14 unassigned YES manual down down AssEthernete/15 unassigned YES manual down down YLAN Name Status Ports PastEthernete/16 unassigned YES manual down down 1 default active Gigb/2 FastEthernete/17 unassigned YES manual down down 1 default active Gigb/2 FastEthernete/17 unassigned YES manual down down 1 default active Gigb/2 FastEthernete/19 unassigned YES manual down down 1 default active Fab/11, Fab/12, Fab/13, Fab/14, Fab/14, Fab/15, Fab/16, Fab/16, Fab/16, Fab/16, Fab/17, Fab/18, Fab/16, Fab/17, Fab/18, Fab/18, Fab/18, Fab/19, Fab/19							
FastEthernete/12 unassigned YES manual down down FastEthernete/13 unassigned YES manual down down FastEthernete/14 unassigned YES manual down down FastEthernete/15 unassigned YES manual down down FastEthernete/16 unassigned YES manual down down FastEthernete/16 unassigned YES manual down down FastEthernete/17 unassigned YES manual down down FastEthernete/17 unassigned YES manual down down FastEthernete/18 unassigned YES manual down down FastEthernete/19 unassigned YES manual down down FastEthernete/19 unassigned YES manual down down FastEthernete/20 unassigned YES manual down down FastEthernete/21 unassigned YES manual down down FastEthernete/22 unassigned YES manual down down FastEthernete/23 unassigned YES manual down down FastEthernete/24 unassigned YES manual down down FastEthernete/25 unassigned YES manual down down FastEthernete/26 unassigned YES manual down down FastEthernete/27 unassigned YES manual down down FastEthernete/28 unassigned YES manual down down FastEthernete/29 unassigned YES manual down down FastEthernete/20 unassigned YES manual down down FastEthernete/21 unassigned YES manual down down FastEthernete/24 unassigned YES manual down down FastEthernete/25 unassigned YES manual down down FastEthernete/24 unassigned YES manual down down FastEthernete/25 unassigned YES manual down down FastEthernete/25 unassigned YES manual down down FastEthernete/25 unassigned YES manual down down FastEthernete/26 unassigned YES manual down down fast factive down down FastEthernete/26 unassigned YES manual down down fast factive down fast factive factive fast factive factive fast factive fast factive fast factive fast factive fast fa							
FastEthernet0/12 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/21 unassigned YES manual down down FastEthernet0/22 unassigned YES manual down down FastEthernet0/24 unassigned YES manual down down FastEthernet0/25 unassigned YES manual down down FastEthernet0/26 unassigned YES manual down down FastEthernet0/27 unassigned YES manual down down FastEthernet0/28 unassigned YES manual down down FastEthernet0/29 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down down FastEthernet0/20 unassigned YES manual down down down FastEthernet0/20 unassigned							
FastEthernet0/14 unassigned YES manual down down FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/18 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/21 unassigned YES manual down down FastEthernet0/2 unassigned YES manual down down FastEthernet0/10 unassigned YES manual down down FastEthernet0/2 unassigned YES manual down down FastEthernet0/2 unassigned YES manual down down FastEthernet0/2 unassigned YES manual down down FastEthernet0/1 unassigned YES manual down down FastEthernet0/2 unassigned YES manual up up FastEthernet0/2 unassigned Y					S2#SNOW Vian prier		
FastEthernet0/15 unassigned YES manual down down FastEthernet0/16 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/17 unassigned YES manual down down FastEthernet0/19 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down FastEthernet0/21 unassigned YES manual down down FastEthernet0/21 unassigned YES manual down down FastEthernet0/22 unassigned YES manual down down FastEthernet0/24 unassigned YES manual down down FastEthernet0/25 unassigned YES manual down down FastEthernet0/26 unassigned YES manual down down FastEthernet0/27 unassigned YES manual down down FastEthernet0/28 unassigned YES manual down down FastEthernet0/29 unassigned YES manual down down FastEthernet0/20 unassigned YES manual down down down FastEthernet0/20 unassigned YES manual down down down down down down down down	FastEthernet0/14		YES manual down	down			
FastEthernet0/17 unassigned VES manual down down 1 default active 6ig0/2 FastEthernet0/18 unassigned VES manual up up 10 FastEthernet0/18 unassigned VES manual down down 20 Students active Fa0/15, Fa0/16, Fa0/17, Fa0/18, Fa0/18, Fa0/18, Fa0/18, Fa0/18, Fa0/18, Fa0/18, Fa0/18, Fa0/18, Fa0/19, Fa0/18, Fa0/18, Fa0/19, Fa0/18, Fa0/19, F	FastEthernet0/15				VLAN Name	Status	Ports
FastEthernet0/17 unassigned VES manual down down 1 default active 6ig0/2 FastEthernet0/18 unassigned VES manual up up 10 Faculty/Staff active Fa0/15, Fa0/12, Fa0/13, Fa0/12, Fa0/13, Fa0/12, Fa0/13, Fa0/12, Fa0/13,	FastEthernet0/16	unassigned	YES manual down	down			
FastEthernet0/18 unassigned VES manual up up 10 Faculty/Staff active Fa0/11, Fa0/12, Fa0/12, Fa0/13, FastEthernet0/19 unassigned VES manual down down PastEthernet0/20 unassigned VES manual down down PastEthernet0/20 unassigned VES manual down down PastEthernet0/21 unassigned VES manual down down PastEthernet0/21 unassigned VES manual down down PastEthernet0/22 unassigned VES manual down down PastEthernet0/22 unassigned VES manual down down PastEthernet0/23 unassigned VES manual down down PastEthernet0/24 unassigned VES manual down down 1002 fddi-default active VES manual down Land down 1003 fddi-default active VES manual down Land down 1004 fddi-default active VES manual down Land down 1004 fddi-default active VES manual down Land Land Land Land down Land Land Land Land Land Land Land Lan	FastEthernet0/17		YES manual down	down	1 default	active	Gig0/2
FastEthernet0/19 unassigned VES manual down down 20 Students active Fa0/15, Fa0/16, Fa0/17 Fa0/16, Fa0/18, Fa0/19, Fa0/20, Fa0/22, Fa0/22, Fa0/22, Fa0/22, Fa0/22, Fa0/22, Fa0/22, Fa0/22, Fa0/22, Fa0/23, Fa0/24 Unassigned VES manual down down Fa0/20 VES manual down down Fa0/20 VES manual down down Fa0/20 VES manual down down Some Pa0/20 VES manual down down Some Pa0/20 VES manual down down Some Pa0/20 VES manual Up Up Some Pa0/20 VES manual Up Up Some Pa0/20 VES manual down down Some Pa0/20 VES manual Up Up Up Up Up Some Pa0/20 VES Manual Up Up Up Up Up	FastEthernet0/18		YES manual up	up			Fa0/11, Fa0/12, Fa0/13, Fa
FastEthernet6/2 unassigned VES manual down down down PS EastEthernet6/21 unassigned VES manual down down PS EastEthernet6/21 unassigned VES manual down down PastEthernet6/22 unassigned VES manual down down PastEthernet6/22 unassigned VES manual down down PastEthernet6/23 unassigned VES manual down down PastEthernet6/24 unassigned VES manual down down PastEthernet6/24 unassigned VES manual down down down down down PS EastEthernet6/24 unassigned VES manual down down down down down down performed PS EastEthernet6/2 unassigned VES manual down down 1002 fddi-default active Vlani unassigned VES manual down down 1003 fddi-default active Vlani unassigned VES manual down down 1003 fddi-default active Vlani 102.108.50.12 VES manual up up 1004 fddi-default active Vlani 1005 trnet-default active VES manual down up 1005 ftmet-default active VES manual down up 1005 ftmet-defaul	FastEthernet0/19	unassigned	YES manual down	down			
FastEthernet0/21 unassigned VES manual down down down 4 Fa8/22, Fa8/23, Fa8/24 FastEthernet0/22 unassigned VES manual down down 4 FastEthernet0/22 unassigned VES manual down down 4 FastEthernet0/24 unassigned VES manual down down 4 FastEthernet0/24 unassigned VES manual up up 6 Fa8/19 Fa8/5 Fa8/5 Fa8/5 Fa8/5 Fa8/5 Fa8/6 Fa8/7, Fa8/8, Fa8/6 Fa8/7, Fa8/8, Fa8/9 Fa8/19 Fa8/	FastEthernet0/20	unassigned	YES manual down	down	20 Students	active	Fa0/18, Fa0/19, Fa0/20, Fa
FastEthernet0/22 unassigned YES manual down down down PE Fab/6, Fab/7, Fab/8, Fab Fab/1, Fab/8, Fab Fab/1, Fab/8, Fab Fab/1, Fab/1, Fab/8, Fab Fab/1, Fab/2, Fab/3, Fab/1, Fab/1, Fab/2, Fab/3, Fab/1, Fab/1, Fab/2, Fab/3, Fab/3, Fab/3, Fab/1, Fab/2, Fab/3,	FastEthernet0/21	unassigned	YES manual down	down		401270	
FastEthernet0/23 unassigned VES manual down down FastEthernet0/24 unassigned VES manual down down GigabitEthernet0/2 unassigned VES manual up up VES manual up VES manual up Up 1602 fddi-default active VES manual down down 1802 fddi-default active VIAN1 unassigned VES manual up VIAN1 unassigned VES manual up VES manual up UNAN5 192.108.50.12 VES manual up up 1004 fddinet-default active 1005 trnet-default active 1005 trnet-default 1006 trnet-default 1007 trnet-default 1008 trnet-default 1009 trnet-default 1009 trnet-default	FastEthernet0/22		YES manual down	down	30 Guest(Default)	active	Fa0/6, Fa0/7, Fa0/8, Fa0/9
FastEthernet0/24 unassigned YES manual down down 56 Management&Native active Fa0/1, Fa0/2, Fa0/3, Fa0 fagabitEthernet0/1 unassigned YES manual up up fa0/2 fa0/2 fa0/3, Fa	FastEthernet0/23	unassigned	YES manual down	down		401210	
GigabitEthernete/1 unassigned YES manual up up Fa0/5 GigabitEthernete/2 unassigned YES manual down down 1002 fddi-default active Vlan1 unassigned YES manual administratively down down 1003 token-ring-default active Vlan56 192.168.56.12 YES manual up up 1004 fddinet-default active S2#	FastEthernet0/24	unassigned	YES manual down	down	56 Management&Native	active	
GigabitEthernete/2 unassigned VES manual down down 1802 fddi-default active Vlan1 unassigned VFS manual administratively down down 1803 token-ring-default active Vlan56 192.168.56.12 VES manual up up 1804 fddinet-default active 182# 182# 182# 1805 trnet-default active	GigabitEthernet0/1	unassigned	YES manual up	up	- Indiagonofftanative	active	
Vlan1 unassigned YES manual administratively down down 1003 token-ring-default active Vlan56 192.168.56.12 YES manual up up 1604 fddinet-default active 1605 trnet-default active	GigabitEthernet0/2		YES manual down		1882 fddi-default	active	14070
Vlan56 192.168.56.12 YES manual up up 1004 fddinet-default active S2# 1005 trnet-default active	Vlan1	unassigned	YES manual administratively down	down			
1005 trnet-default active	/lan56	192.168.56.12	YES manual up	up			
Page fuller-delants and active	S2#		*	•			
(a) show in int byief on S2					Taga timer-delanti	active	
		(a) show i	ip int brief on S2		(b) show vlan brie	ef on S2

Figure 12.6: S2 after configuration


ii) Setting up Switch 3

For switch 3, i ran the following commands:

```
en
conf t
int range fa0/1 - 5
switchport access vlan 56
int range fa0/6 - 10
switchport access vlan 30
int range fa0/11 - 17
switchport access vlan 10
int range fa0/18 - 24
switchport access vlan 20
```

Part 4: Conclusion

I was able to Ping each of the PCs within their connected networks, and I got 70/70 on the Scoring Rubric.



```
3#show vian briet
 /I AN Name
                                                                        Status
                                                                                            Ports
                                                                                           Gige/1
Fa9/11, Fa9/12, Fa9/13, Fa9/14
Fa9/15, Fa9/16, Fa9/17
Fa9/18, Fa9/19, Fa9/20, Fa9/21
Fa9/22, Fa9/23, Fa9/24
Fa9/6, Fa9/7, Fa9/8, Fa9/9
        Students
                                                                        active
        Guest(Default)
                                                                        active
        Management&Native
                                                                        active
                                                                                            Fa0/1, Fa0/2, Fa0/3, Fa0/4
Fa0/5
1002 fddi-default
1003 token-ring-default
1004 fddinet-default
1005 trnet-default
                                                                        active
active
active
                                                                         active
```

(a) show ip int brief on S3

(b) show vlan brief on S3

>ping 192,168,20,25

Figure 12.7: Switch 3 after configuration

```
C:\>ping 192.168.10.24
                                                                            inging 192.168.20.25 with 32 bytes of data:
Pinging 192.168.10.24 with 32 bytes of data:
                                                                            teply from 192.168.20.25: bytes=32 time=1ms TTL=128
Reply from 192.168.10.24: bytes=32 time<1ms TTL=128
                                                                            Reply from 192.168.20.25: bytes=32 time<1ms TTL=128
Reply from 192.168.10.24: bytes=32 time<1ms TTL=128
                                                                            Reply from 192.168.20.25: bytes=32 time<1ms TTL=128
Reply from 192.168.10.24: bytes=32 time<1ms TTL=128
                                                                            eply from 192.168.20.25: bytes=32 time<1ms TTL=128
Reply from 192.168.10.24: bytes=32 time<1ms TTL=128
                                                                            ing statistics for 192.168.20.25:
Ping statistics for 192.168.10.24:
 Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
                                                                               Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
                                                                             pproximate round trip times in milli-seconds:
                                                                                Minimum = 0ms, Maximum = 1ms, Average = 0ms
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
                     (a) PC1 pingin PC4
                                                                                                  (b) PC2 pingin PC5
                                        >ping 192.168.30.26
                                      inging 192.168.30.26 with 32 bytes of data:
                                      eply from 192.168.30.26: bytes=32 time=13ms TTL=128
```

eply from 192.168.30.26: bytes=32 time<1ms TTL=128 eply from 192.168.30.26: bytes=32 time<1ms TTL=128 eply from 192.168.30.26: bytes=32 time=1ms TTL=128 ing statistics for 192.168.30.26: Packets: Sent = 4, Received = 4, Lost = 0 (0% loss), proximate round trip times in milli-seconds: Minimum = 0ms, Maximum = 13ms, Average = 3ms (c) PC3 pingin PC6 Completion: 70/70 1/1 (d) Final Score

Figure 12.8: Pinging Networks and Final Score

Configuring Vlans and Trunks

March 4, 2020

Packet Tracer Lab 13 Spring 2020 CIT 167 Chaz Davis

vlans and trunks

- · configure terminal
- interface interface-id
- switchport mode dynamic auto \mid desirable \mid trunk
- $\bullet~$ switch port access vlan vlan-id
- $\bullet\;$ switchport trunk native vlan vlan-id end
- show interfaces interface-id switchport
- show interfaces interface-id trunk
- $\bullet \quad {\rm copy} \ {\rm running\text{-}config} \ {\rm startup\text{-}config}$

Part 1: Configuration

I set up the configurations for each pc on the network.




Figure 13.1: PC configurations

I then copied and pasted the commands from the handout for each of the switches: The network is all up and running, We can now ping from PC3 to PC6 across the same network.

Switch#show ip int b	rief		
Interface	IP-Address	OK? Method State	us Protocol
astEthernet0/1	unassigned	YES manual up	up
astEthernet0/2	unassigned	YES manual down	down
astEthernet0/3	unassigned	YES manual down	down
astEthernet0/4	unassigned	YES manual down	down
astEthernet0/5	unassigned	YES manual down	down
astEthernet0/6	unassigned	YES manual up	up
astEthernet0/7	unassigned	YES manual down	down
astEthernet0/8	unassigned	YES manual down	down
astEthernet0/9	unassigned	YES manual down	down
astEthernet0/10	unassigned	YES manual down	down
astEthernet0/11	unassigned	YES manual down	down
astEthernet0/12	unassigned	YES manual down	down
astEthernet0/13	unassigned	YES manual down	down
astEthernet0/14	unassigned	YES manual down	down
astEthernet0/15	unassigned	YES manual down	down
astEthernet0/16	unassigned	YES manual down	down
astEthernet0/17	unassigned	YES manual down	down
astEthernet0/18	unassigned	YES manual down	down
astEthernet0/19	unassigned	YES manual down	down
astEthernet0/20	unassigned	YES manual down	down
astEthernet0/21	unassigned	YES manual down	down
astEthernet0/22	unassigned	YES manual down	down
astEthernet0/23	unassigned	YES manual down	down
astEthernet0/24	unassigned	YES manual down	down
SigabitEthernet0/1	unassigned	YES manual down	down
SigabitEthernet0/2	unassigned	YES manual down	down
/lan1	unassigned	YES manual admi	nistratively down down

(a) sł	iow	ip	$_{ m int}$	brief	$_{ m on}$	Switch	2
----	------	-----	----	-------------	-------	------------	--------	---

and the state of the state of	1 1 6	_			_	
Switch#show ip int						
Interface	IP-Address		Method			Protocol
FastEthernet0/1	unassigned		manual			up
FastEthernet0/2	unassigned		manual			down
FastEthernet0/3	unassigned		manual			down
FastEthernet0/4	unassigned		manual			down
FastEthernet0/5	unassigned	YES	manual	down		down
FastEthernet0/6	unassigned	YES	manual	up		up
FastEthernet0/7	unassigned		manual			down
FastEthernet0/8	unassigned	YES	manual	down		down
FastEthernet0/9	unassigned	YES	manual	down		down
FastEthernet0/10	unassigned	YES	manual	down		down
FastEthernet0/11	unassigned	YES	manual	up		up
FastEthernet0/12	unassigned	YES	manual	down		down
FastEthernet0/13	unassigned	YES	manual	down		down
FastEthernet0/14	unassigned	YES	manual	down		down
FastEthernet0/15	unassigned	YES	manual	down		down
FastEthernet0/16	unassigned	YES	manual	down		down
FastEthernet0/17	unassigned	YES	manual	down		down
FastEthernet0/18	unassigned	YES	manual	down		down
FastEthernet0/19	unassigned	YES	manual	down		down
FastEthernet0/20	unassigned	YES	manual	down		down
FastEthernet0/21	unassigned	YES	manual	down		down
FastEthernet0/22	unassigned	YES	manual	down		down
FastEthernet0/23	unassigned	YES	manual	down		down
FastEthernet0/24	unassigned	YES	manual	down		down
GigabitEthernet0/1	unassigned	YES	manual	down		down
GigabitEthernet0/2	unassigned	YES	manual	down		down
Vlan1	unassigned	YES	manual	administratively of	iown	down
Switch#	-					

(c) show ip int brief on Switch 3

Swite	ch#show vian brief		
VLAN	Name	Status	Ports
1	default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/5 Fa0/7, Fa0/8, Fa0/9, Fa0/10 Fa0/11, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/21, Fa0/22 Fa0/23, Fa0/24, Gig0/1, Gig0/2
10	student	active	
30	faculty	active	Fa0/6
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005	trnet-default	active	

(b) show vlan brief on Switch 2

Swite	ch#show vlan brief		
VLAN	Name	Status	Ports
1	default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/5 Fa0/7, Fa0/8, Fa0/9, Fa0/10 Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23 Fa0/24, Gig0/1, Gig0/2
10	student	active	Fa0/11
30	faculty	active	Fa0/6
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005	trnet-default	active	
Swite	ch#		


(d) show vlan brief on Switch 3

Figure 13.2: Switch Configurations

```
c:\>ping 172.17.30.26

singing 172.17.30.26 with 32 bytes of data:
seply from 172.17.30.26: bytes=32 time=2ms TTL=128
seply from 172.17.30.26: bytes=32 time=1ms TTL=128
seply from 172.17.30.26: bytes=32 time<1ms TTL=128
seply from 172.17.30.26: bytes=32 time<1ms TTL=128
sing statistics for 172.17.30.26:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
sepproximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 2ms, Average = 0ms</pre>
```

(a) PC3 pinging PC6



(b) Layout of the Network

Figure 13.3: The Network Connected

Legacy InterVlan Implementation

March 5, 2020

Packet Tracer Lab 14 Spring 2020 CIT 167 Chaz Davis

```
Inter Vlan Routing
    • router is usually connected to the switch using multiple interfaces.

    One for each VLAN.

    • The interfaces on the router are configured as the default gateways

    for the VLANs configured on the switch.

    • In this form of inter-VLAN routing
          - router must have as many LAN interfaces as the number of VLANs
Scenario: - R1 connected to switch ports: G0/0 -> F0/4 (VLAN 10), G0/1 -> F05 (VLAN 30) - S1 switch ports F0/4
and F0/11 belong to VLAN 10; F0/5 and F0/6 belong to VLAN 30. Configure the switch:
vlan 10 # Create VLAN 10
vlan 30 # Create VLAN 30
interface f0/11
 switchport access vlan 10
interface f0/4
 switchport access vlan 10
interface f0/6
 switchport access vlan 30
interface f0/5
  switchport access vlan 30
Configure the router:
interface g0/0
  ip address <default gateway of VLAN10> <subnet-mask>
 no shutdown
interface g0/1
  ip address <default gateway of VLAN 30> <subnet-mask>
Check routing table with:
show ip route
```

Part 1: Configuring and verifying the network

i) Configuring The Pcs

I setup the Configuration according to the handout. I then, configured the IP address, default gateways, and subnet masks on each of the PCs.

IP Address	172.17.10.21
Subnet Mask	255.255.255.0
Default Gateway	0.0.0.0
DNS Server	0.0.0.0

 IP Address
 172.17.30.23

 Subnet Mask
 255.255.255.0

 Default Gateway
 0.0.0.0

 DNS Server
 0.0.0.0

(a) IP config on PC1

(b) IP Config on PC3

Figure 14.1: IP Configurations

ii) Configuring The Router and Switch

I Next ran the commands on R1, You can see in Fig. 14.2 a on Pg. 94, the results of show ip int brief. And then the commands on S1, as you can see in Fig. 14.2b and Fig. 14.2c on Pg. 94, the results of show ip int brief and show vlan brief on switch 1.

I had to go back and run int g0/1 no shut on R1. As You can see in Fig. 14.2d, the output of the show ip int brief and the output of show vlan brief on S3 in Fig. 14.2e on Pg. 94.




Figure 14.2: Configuration of R1 and S1

iii) Checking the Connections

After that I was able to successfully ping from PC1 to PC3.

```
Pinging 172.17.30.23 with 32 bytes of data:

Request timed out.

Reply from 172.17.30.23: bytes=32 time<1ms TTL=127

Reply from 172.17.30.23: bytes=32 time<1ms TTL=127


Reply from 172.17.30.23: bytes=32 time<1ms TTL=127

Ping statistics for 172.17.30.23:

Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms
```



(b) Successful network architecture

Figure 14.3: Successful Lab layout

Router On a Stick

March 8, 2020

Packet Tracer Lab 15 Spring 2020 CIT 167 Chaz Davis

Router on a stick

- a term frequently used to describe a setup up that consists of a router and switch connected using one Ethernet link configured as an 802.1q trunk link.
- \bullet In this setup, the switch is configured with multiple VLANs and the router performs all routing between the different networks/VLANs.
- Use the interface type number.subint command in global configuration mode
 - create a unique subinterface for each VLAN to be routed.
- Use the encapsulation dot1q vlan_id command to enable 802.1Q trunking
 - associate each VLAN with the subinterface.
- Use the ip address address mask command to configure the IP settings.

Scenario:

- R1 is connected to switch S1 on trunk port F0/5
- VLANs 10 and 30 are added to switch S1
- Two subinterfaces are configured
 - $-\,$ using the 'interface <code><interface-id>.<subinterface-id>'</code>
 - $-\ \, \mathrm{G0/0.10:}\ \, 172.17.10.1/24\ \, \mathrm{G0/0.30:}\ \, 172.17.30.1/24$

Configure the switch:

```
vlan 10
vlan 30
interface f0/5
switchport mode trunk
end
```

Configure the router:

```
interface g0/0.10
encapsulation dot1q 10
ip address 172.17.10.1 255.255.255.0
interface g0/0.30
encapsulation dot1q 30
ip address 172.17.30.1 255.255.255.0
interface g0/0
no shutdown
```

- To set the IEEE 802.1Q native VLAN
 - use the 'native' keyword option;
 - $-\,$ by default, the native VLAN is VLAN 1.
- ullet If the physical interface is disabled,
 - all subinterfaces are disabled.

Verify Subinterfaces:

```
show vlan show ip route
```

Verify routing:

ping <ip-address>
traceroute <ip-address># UNIX
tracert <ip-address># Windows

Part 1: Configuring and verifying the Network

i) Configuring PCs on the Network

I First set up the network according to the diagram. I then, Configured the Ip address, subnet masks, and default gateways for the PCs according the chart.

172.17.30.10

255.255.255.0

172.17.30.1

0.0.0.0




Figure 15.1: IP configuration of the PCs on the network

ii) Configuring the Switch and Router

I then, configured the Switch and router according to the handout.

Switch#show vlan brief				
/LAN Name	Status	Ports		
1 default	active	Fa8/1, Fa8/2, Fa8/3, Fa8/4 Fa8/5, Fa8/7, Fa8/8, Fa8/9 Fa8/18, Fa8/12, Fa8/13, Fa8/14 Fa8/15, Fa8/16, Fa8/17, Fa8/18 Fa8/19, Fa8/26, Fa8/21, Fa8/22 Fa8/23, Fa8/24, Gig9/2		Qouter#show ip int brief
10 VLAN0010 30 VLAN0030 1002 fddi-default 1003 token-ring-default 1004 fddinet-default 1005 trnet-default	active active active active active active	Fa0/11		Interface IP-Address OK? Method Status Protoc: sigabitethernete/0 unassigned YES unset administratively down down sigabitethernete/0.10 172.17.10.1 Sigabitethernete/0 unassigned YES unset administratively down down sigabitethernet/1 unassigned YES unset administratively down down Vlan1 unassigned YES unset administratively down down Vlan2 unassigned YES unset administratively down down VES unset administratively down down
(a) sho	w ip int bri			(b) show vlan brief on R1
		Switch#show vlan brief VLAN Name	Status	Ports
		1 default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/21, Fa0/22 Fa0/23, Fa0/24, Giq0/1, Giq0/2
		10 VLAN0010 30 VLAN0030 1002 fddi-default 1003 Token-ring-default 1004 fddinet-default 1005 trnet-default	active active active active active active	Fa9/11 Fa9/6
		(c) show vlan br	ief on S1	after trunk config

Figure 15.2: Switch and Router configuration

iii) Verifying the Network

Successfully able to ping PC3 from PC1.

```
C:\>ping 172.17.30.10

Pinging 172.17.30.10 with 32 bytes of data:

Reply from 172.17.30.10: bytes=32 time=1ms TTL=127

Reply from 172.17.30.10: bytes=32 time<1ms TTL=127

Reply from 172.17.30.10: bytes=32 time<1ms TTL=127

Reply from 172.17.30.10: bytes=32 time<1ms TTL=127


Ping statistics for 172.17.30.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms
```

(a) Pinging PC3 from PC1



(b) Successful Network Configuration

Figure 15.3: Successful network setup