

Cloud Volumes ONTAP 9.10.1 Release Notes

Cloud Volumes ONTAP 9.10.1 release notes

NetApp April 06, 2022

This PDF was generated from https://docs.netapp.com/us-en/cloud-volumes-ontap-relnotes/index.html on April 06, 2022. Always check docs.netapp.com for the latest.

Table of Contents

Cloud Volumes ONTAP 9.10.1 Release Notes	1
What's new in Cloud Volumes ONTAP 9.10.1	2
Licensing update (9 Feb 2022)	2
9.10.1 GA (31 Jan 2022)	2
Support for more VM types (2 Jan 2021)	2
9.10.1 RC1 (28 Nov 2021)	3
Required version of the Cloud Manager Connector	4
Upgrade notes	4
Licensing for Cloud Volumes ONTAP	5
Licensing overview	5
Freemium offering	5
Capacity-based licensing packages	6
Keystone Flex Subscription	8
Node-based licensing	8
License conversions.	9
Max number of systems	9
Supported configurations	. 10
Supported configurations in AWS	. 10
Supported configurations in Azure	. 13
Supported configurations in Google Cloud	. 16
Storage limits	. 19
Storage limits in AWS	. 19
Storage limits in Azure	. 26
Storage limits in Google Cloud.	. 33
Known issues	. 37
Known limitations	. 38
Limitations in all cloud providers	. 38
Known limitations in AWS	. 40
Known limitations in Azure	. 40
Known limitations in Google Cloud	. 41
Cloud provider integrations	. 42
Collaborative support best practices	. 42
Azure maintenance events	. 42
Legal notices	. 43
Copyright	. 43
Trademarks	. 43
Patents	. 43
Privacy policy	. 43
Open source	43



What's new in Cloud Volumes ONTAP 9.10.1

Cloud Volumes ONTAP 9.10.1 includes several new features and enhancements.

Additional features and enhancements are also introduced in the latest versions of Cloud Manager. See the Cloud Manager Release Notes for details.

Licensing update (9 Feb 2022)

We have introduced the following marketplace changes for Cloud Volumes ONTAP:

• The Essentials package and Professional package are now available in the AWS and Google Cloud Marketplaces.

These by-capacity charging methods enable you to pay by the hour or to purchase an annual contract directly from your cloud provider. You still have the option to purchase a by-capacity license directly from NetApp.

If you have an existing subscription in a cloud marketplace, you're automatically subscribed to these new offerings as well. You can choose by-capacity charging when you deploy a new Cloud Volumes ONTAP working environment.

If you're a new customer, Cloud Manager will prompt you to subscribe when you create a new working environment.

 By-node licensing via the AWS and Google Cloud Marketplaces is deprecated and no longer available for new subscribers. This includes annual contracts and hourly subscriptions (Explore, Standard, and Premium).

This charging method is still available for existing customers who have an active subscription.

Learn more about the licensing options for Cloud Volumes ONTAP.

9.10.1 GA (31 Jan 2022)

The General Availability (GA) release of Cloud Volumes ONTAP 9.10.1 is now available. The GA release includes bug fixes.

Cloud Manager will prompt you to upgrade existing systems that are running any of the following versions: 9.10.1 RC1, 9.10.0, or 9.9.1.

Support for more VM types (2 Jan 2021)

As part of the Cloud Manager 3.9.14 release, Cloud Volumes ONTAP is now supported with the following VM types in Microsoft Azure, starting with the 9.10.1 release:

- E4ds v4
- E8ds v4
- E32ds v4
- E48ds v4

Go to the supported configurations page for more details.

9.10.1 RC1 (28 Nov 2021)

Cloud Volumes ONTAP 9.10.1 Release Candidate 1 is now available in AWS, Azure, and Google Cloud. This release includes the following new features and enhancements.

HA enhancements in Microsoft Azure

- We reduced the unplanned failover time for Cloud Volumes ONTAP HA pairs running in Microsoft Azure.
- NFSv4 is now supported.

To make these enhancements available to Cloud Volumes ONTAP, you need to enable a feature on your Azure subscription. An Azure user who has "Owner" privileges can enable the feature from the Azure CLI:

```
az account set -s AZURE_SUBSCRIPTION_NAME_OR_ID
az feature register --name EnableHighAvailabilityMode --namespace
Microsoft.Network
az provider register -n Microsoft.Network
```

Cloud Manager will prompt you with these details in an Action Required message for Cloud Volumes ONTAP 9.10.1 systems where the feature needs to be enabled on an Azure subscription.

Note the following:

- There are no problems with the high availability of your Cloud Volumes ONTAP HA pair. This Azure feature works in concert with ONTAP to reduce the client observed application outage time for NFS protocols that result from unplanned failover events.
- Enabling this feature is non-disruptive to Cloud Volumes ONTAP HA pairs.
- Enabling this feature on your Azure subscription won't cause issues to other VMs.

Security enhancements

We enhanced the security of ONTAP image creation and the security of the Cloud Volumes ONTAP boot disk.

Support for Keystone Flex Subscriptions

As part of the Cloud Manager 3.9.13 release, you can now use a Keystone Flex Subscription with Cloud Volumes ONTAP HA pairs. A Keystone Flex Subscription is a pay-as-you-grow subscription-based service that delivers a seamless hybrid cloud experience for those preferring OpEx consumption models to upfront CapEx or leasing.

A Keystone Flex Subscription is supported with all new versions of Cloud Volumes ONTAP that you can deploy from Cloud Manager.

Encryption key management

The ONTAP 9.10.1 release includes an enhancement that enables you to use Azure Key Vault (AKV) or the Google Cloud Key Management Service to protect ONTAP encryption keys.

Required version of the Cloud Manager Connector

The Cloud Manager Connector must be running version 3.9.13 or later to deploy new Cloud Volumes ONTAP 9.10.1 systems and to upgrade existing systems to 9.10.1.



Automatic upgrades of the Connector are enabled by default so you should be running the latest version.

Upgrade notes

- Upgrades of Cloud Volumes ONTAP must be completed from Cloud Manager. You should not upgrade Cloud Volumes ONTAP by using System Manager or the CLI. Doing so can impact system stability.
- You can upgrade to Cloud Volumes ONTAP 9.10.1 from the 9.10.0 release and from the 9.9.1 release. Cloud Manager will prompt you to upgrade eligible Cloud Volumes ONTAP systems to the 9.10.1 release.

Learn how to upgrade when Cloud Manager notifies you.

- The upgrade of a single node system takes the system offline for up to 25 minutes, during which I/O is interrupted.
- Upgrading an HA pair is nondisruptive and I/O is uninterrupted. During this nondisruptive upgrade process, each node is upgraded in tandem to continue serving I/O to clients.

c4, m4, and r4 instance types

Starting with the 9.8 release, c4, m4, and r4 instance types aren't supported with new Cloud Volumes ONTAP systems. If you have an existing Cloud Volumes ONTAP system that's running on a c4, m4, or r4 instance type, you can still upgrade to this release.

We recommend changing to an instance type in the c5, m5, or r5 instance family.

DS3_v2

Starting with the 9.9.1 release, the DS3_v2 VM type is no longer supported with new and existing Cloud Volumes ONTAP systems. If you have an existing system running on this VM type, you'll need to change VM types before you upgrade to 9.10.1.

Licensing for Cloud Volumes ONTAP

Several licensing options are available for Cloud Volumes ONTAP. Each option enables you to choose a consumption model that meets your needs.

Licensing overview

The following licensing options are available for new customers.

Freemium offering

Free of charge up to 500 GiB of provisioned capacity without purchasing a license or contract. Includes limited support.

Essentials package

Pay by capacity for Cloud Volumes ONTAP in a number of different configurations.

Professional package

Pay by capacity for any type of Cloud Volumes ONTAP configuration. Includes unlimited backups with Cloud Backup.

Keystone Flex Subscription

A pay-as-you-grow subscription-based service that delivers a seamless hybrid cloud experience for HA pairs.

The previous by-node licensing model remains available for existing customers who have already purchased a license or who have an active marketplace subscription.

The following sections provide more details about each of these options.

Freemium offering

Provides all Cloud Volumes ONTAP features free of charge from NetApp (cloud provider charges still apply).

- · No license or contract is needed.
- Support from NetApp is not included.
- You're limited to 500 GiB of provisioned capacity per Cloud Volumes ONTAP system.
- You can use up to 10 Cloud Volumes ONTAP systems with the Freemium offering per NetApp account.
- If the provisioned capacity for a Cloud Volumes ONTAP system exceeds 500 GiB, Cloud Manager converts the system to the Essentials package (capacity-based licensing).

Any other systems that have less than 500 GiB of provisioned capacity stay on Freemium (as long as they were deployed using the Freemium offering).

To get started with the Freemium offering, create a new Cloud Volumes ONTAP working environment and select **Freemium** when prompted to choose a charging method.

- Launching Cloud Volumes ONTAP in AWS
- Launching Cloud Volumes ONTAP in Azure

Capacity-based licensing packages

Capacity-based licensing enables you to pay for Cloud Volumes ONTAP per TiB of capacity. The license is associated with your NetApp account and enables you to charge multiple systems against the license, as long as enough capacity is available through the license.

For example, you could purchase a single 20 TiB license, deploy four Cloud Volumes ONTAP systems, and then allocate a 5 TiB volume to each system, for a total of 20 TiB. The capacity is available to the volumes on each Cloud Volumes ONTAP system deployed in that account.

Capacity-based licensing is available in the form of a *package*. When you deploy a Cloud Volumes ONTAP system, you can choose the *Essentials* package or the *Professional* package.

Essentials package

- Choose your Cloud Volumes ONTAP configuration:
 - A single node or HA system
 - File and block storage or secondary data for disaster recovery (DR)
- Add on any of NetApp's cloud data services at extra cost

Professional package

- Provides licensing for any Cloud Volumes ONTAP configuration (single node or HA with any storage type)
- Includes volume backups using Cloud Backup (only for volumes charged against this license)
- Add on any of NetApp's cloud data services at extra cost

Consumption models

The Essentials and Professional packages are available with the following consumption models:

- A license (BYOL) purchased from NetApp
- An annual contract from your cloud provider's marketplace (AWS and Google Cloud only)
- · An hourly subscription (PAYGO) from your cloud provider's marketplace

Note the following:

• If you purchase a license from NetApp (BYOL), you also need to subscribe to the PAYGO offering from your cloud provider's marketplace.

Your license is always charged first, but you'll be charged from the hourly rate in the marketplace in these cases:

- If you exceed your licensed capacity
- If the term of your license expires
- If you have an annual contract from a marketplace, *all* Cloud Volumes ONTAP systems that you deploy are charged against that contract. You can't mix and match an annual marketplace contract with BYOL.

Pricing

For details about pricing, go to NetApp Cloud Central.

Free trials

A 30-day free trial is available from the pay-as-you-go subscription in your cloud provider's marketplace. The free trial includes Cloud Volumes ONTAP and Cloud Backup and starts at the time that you subscribe to the marketplace listing.

There are no hourly software license charges for the instance, but infrastructure charges from your cloud provider still apply.

A free trial automatically converts to a paid hourly subscription when it expires. If you terminate the instance within the time limit, the next instance that you deploy is not part of the free trial (even if it's deployed within those 30 days).

You can start a 30-day free trial of Cloud Volumes ONTAP from Cloud Manager by creating your first Cloud Volumes ONTAP system in a payer's account.

Pay-as-you-go trials are awarded through a cloud provider and are not extendable by any means.

Supported configurations

Capacity-based licensing packages are available with Cloud Volumes ONTAP 9.7 and later.

Capacity limit

With this licensing model, each individual Cloud Volumes ONTAP system supports up to 2 PiB of capacity through disks and tiering to object storage.

There is no maximum capacity limitation when it comes to the license itself.

Notes about charging

- If you exceed your BYOL capacity or if your license expires, you'll be charged for overages at the hourly rate based on your marketplace subscription.
- For each package, there is a minimum 4 TiB capacity charge. Any Cloud Volumes ONTAP instance that has less than 4 TiB of capacity will be charged at a rate of 4 TiB.
- There are no extra licensing costs for additional data-serving storage VMs (SVMs), but there is a 4 TiB minimum capacity charge per data-serving SVM.
- Disaster recovery SVMs are charged according to the provisioned capacity.
- For HA pairs, you're only charged for the provisioned capacity on a node. You aren't charged for data that is synchronously mirrored to the partner node.
- You won't be charged for the capacity used by FlexClone volumes.
- Source and destination FlexCache volumes are considered primary data and charged according to the provisioned space.

How to get started

- 1. Contact NetApp Sales to obtain a license.
- Add your license to Cloud Manager.
- Select the capacity-based BYOL charging method when you create a Cloud Volumes ONTAP system.
 - Launching Cloud Volumes ONTAP in AWS
 - Launching Cloud Volumes ONTAP in Azure
 - · Launching Cloud Volumes ONTAP in Google Cloud

Keystone Flex Subscription

A pay-as-you-grow subscription-based service that delivers a seamless hybrid cloud experience for those preferring OpEx consumption models to upfront CapEx or leasing.

Charging is based on the size of your committed capacity for one or more Cloud Volumes ONTAP HA pairs in your Keystone Flex Subscription.

The provisioned capacity for each volume is aggregated and compared to the committed capacity on your Keystone Flex Subscription periodically, and any overages are charged as burst on your Keystone Flex Subscription.

Learn more about Keystone Flex Subscriptions.

Supported configurations

Keystone Flex Subscriptions are supported with HA pairs. This licensing option isn't supported with single node systems at this time.

Capacity limit

Each individual Cloud Volumes ONTAP system supports up to 2 PiB of capacity through disks and tiering to object storage.

How to get started

- 1. If you don't have a subscription yet, contact NetApp.
- Contact NetApp to authorize your Cloud Manager user account with one or more Keystone Flex Subscriptions.
- 3. After NetApp authorizes your account, link your subscriptions for use with Cloud Volumes ONTAP
- 4. Select the Keystone Flex Subscription charging method when you create a Cloud Volumes ONTAP system.
 - Launching Cloud Volumes ONTAP in AWS
 - Launching Cloud Volumes ONTAP in Azure
 - Launching Cloud Volumes ONTAP in Google Cloud

Node-based licensing

Node-based licensing is the previous generation licensing model that enabled you to license Cloud Volumes ONTAP by node. This licensing model is not available for new customers and no free trials are available. By-

node charging has been replaced with the by-capacity charging methods described above.

Node-based licensing is still available for existing customers:

- · If you have an active license, BYOL is available for license renewals only.
- If you have an active marketplace subscription, charging is still available through that subscription.

License conversions

Converting an existing Cloud Volumes ONTAP system to another licensing method isn't supported. The three current licensing methods are capacity-based licensing, Keystone Flex Subscriptions, and node-based licensing. For example, you can't convert a system from node-based licensing to capacity-based licensing (and vice versa).

If you want to transition to another licensing method, you can purchase a license, deploy a new Cloud Volumes ONTAP system using that license, and then replicate the data to that new system.

Max number of systems

The maximum number of Cloud Volumes ONTAP systems is limited to 20 per NetApp account, regardless of the licensing model in use.

A *system* is either an HA pair or a single node system. For example, if you have two Cloud Volumes ONTAP HA pairs and two single node systems, you'd have a total of 4 systems, with room for 16 additional systems in your account.

If you have questions, reach out to your account rep or sales team.

Learn more about NetApp accounts.

Supported configurations

Supported configurations in AWS

Several Cloud Volumes ONTAP configurations are supported in AWS.

Supported number of nodes

Cloud Volumes ONTAP is available in AWS as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair is not supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

Supported storage

Cloud Volumes ONTAP supports several types of EBS disks, and S3 object storage for data tiering. The maximum storage capacity is determined by the license that you choose.

Storage support by license

Each license supports a different maximum system capacity. The maximum system capacity includes disk-based storage plus object storage used for data tiering. NetApp doesn't support exceeding this limit.

	Freemium	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based license	Capacity- based license
Maximum system capacity (disks + object storage) ¹	500 GiB	2 TiB	10 TiB	368 TiB ²	368 TiB per license ²	2 PiB ²
Supported disk types	 General Purpose SSD (gp3 and gp2) ³ Provisioned IOPS SSD (io1) ³ Throughput Optimized HDD (st1) ⁴ 					
Cold data tiering to S3	Supported	Not supported	Supported			

- 1. For an HA pair, the capacity limit is for the entire HA pair. It's not per node. For example, if you use the Premium license, you can have up to 368 TiB of capacity between both nodes.
- For some configurations, disk limits prevent you from reaching the capacity limit by using disks alone. In those cases, you can reach the capacity limit by tiering inactive data to object storage. For information about disk limits, refer to storage limits.
- Enhanced write performance is enabled when using SSDs with all Cloud Volumes ONTAP configurations, except for PAYGO Explore.

4. Tiering data to object storage is not recommended when using Throughput Optimized HDDs (st1).

Supported disk sizes

In AWS, an aggregate can contain up to 6 disks that are all the same type and size.

General Purpose SSDs (gp3 and gp2)	Provisioned IOPS SSDs (io1)	Throughput Optimized HDDs (st1)
• 100 GiB	• 100 GiB	• 500 GiB
• 500 GiB	• 500 GiB	• 1 TiB
• 1 TiB	• 1 TiB	• 2 TiB
• 2 TiB	• 2 TiB	• 4 TiB
• 4 TiB	• 4 TiB	• 6 TiB
• 6 TiB	• 6 TiB	• 8 TiB
• 8 TiB	• 8 TiB	• 16 TiB
• 16 TiB	• 16 TiB	

Supported EC2 compute

Each Cloud Volumes ONTAP license supports different EC2 instance types. For your convenience, the table below shows the vCPU, RAM, and bandwidth for each supported instance type. You should refer to AWS for the latest and complete details about EC2 instance types.

The bandwidths shown in the table below match the documented AWS limits for each instance type. These limits don't completely align with what Cloud Volumes ONTAP can provide. For the expected performance, refer to NetApp Technical Report 4383: Performance Characterization of Cloud Volumes ONTAP in Amazon Web Services with Application Workloads.

License	Supported instance	vCPU	RAM	Flash Cache ¹	Network bandwidth (Gbps)	EBS bandwidth (Mbps)	High write speed ²
Explore or any other license	m5.xlarge	4	16	Not supported	Up to 10	Up to 4,750	Supported (single node only)
Standard or any other license	r5.xlarge	4	32	Not supported	Up to 10	Up to 4,750	Supported (single node only)
	m5a.2xlarge	8	32	Not supported	Up to 10	Up to 2,880	Supported
	m5.2xlarge	8	32	Not supported	Up to 10	Up to 4,750	Supported

License	Supported instance	vCPU	RAM	Flash Cache ¹	Network bandwidth (Gbps)	EBS bandwidth (Mbps)	High write speed ²
any other	m5n.2xlarge	8	32	Not supported	Up to 25	Up to 4,750	Supported
license	r5.2xlarge	8	64	Not supported	Up to 10	Up to 4,750	Supported
	r5d.2xlarge	8	64	Supported	Up to 10	Up to 4,750	Supported
	c5d.4xlarge	16	32	Supported	Up to 10	4,570	Supported
	m5.4xlarge	16	64	Not supported	Up to 10	4,750	Supported
	m5d.8xlarge	32	128	Supported	10	6,800	Supported
	r5.8xlarge	32	256	Not supported	10	6,800	Supported
	c5.9xlarge	36	72	Not supported	10	9,500	Supported
	c5d.9xlarge	36	72	Supported	10	9,500	Supported
	c5n.9xlarge	36	96	Not supported	50	9,500	Supported
	c5a.12xlarg e	48 4	96	Not supported	12	4,750	Supported
	c5.18xlarge	48 4	144	Not supported	25	19,000	Supported
	c5d.18xlarg e	48 4	144	Supported	25	19,000	Supported
	m5d.12xlarg e	48	192	Supported	12	9,500	Supported
	c5n.18xlarg e	48 4	192	Not supported	100	19,000	Supported
	m5a.16xlarg e	48 4	256	Not supported	12	9,500	Supported
	m5.16xlarge	48 4	256	Not supported	20	13,600	Supported
	r5.12xlarge ³	48	384	Not supported	10	9,500	Supported
	m5dn.24xlar ge	48 4	384	Supported	100	19,000	Supported

^{1.} Some instance types include local NVMe storage, which Cloud Volumes ONTAP uses as Flash Cache. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It's effective for random read-intensive workloads, including databases, email, and file services. Compression must be disabled on all volumes to take advantage of the Flash Cache performance improvements. Learn more about Flash Cache.

- Cloud Volumes ONTAP supports high write speed with most instance types when using an HA pair. High write speed is supported with all instance types when using a single node system. Learn more about choosing a write speed.
- 3. The r5.12xlarge instance type has a known limitation with supportability. If a node unexpectedly reboots due to a panic, the system might not collect core files used to troubleshoot and root cause the problem. The customer accepts the risks and limited support terms and bears all support responsibility if this condition occurs. This limitation affects newly deployed HA pairs and HA pairs upgraded from 9.8. The limitation does not affect newly deployed single node systems.
- While these EC2 instance types support more than 48 vCPUs, Cloud Volumes ONTAP supports up to 48 vCPUs.
- 5. When you choose an EC2 instance type, you can specify whether it is a shared instance or a dedicated instance.
- 6. Cloud Volumes ONTAP can run on either a Reserved or On-demand EC2 instance. Solutions that use other instance types aren't supported.

Supported regions

For AWS region support, see Cloud Volumes Global Regions.

Supported configurations in Azure

Several Cloud Volumes ONTAP configurations are supported in Azure.

Supported configurations by license

Cloud Volumes ONTAP is available in Azure as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair is not supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

Single node systems

You can choose from the following configurations when deploying Cloud Volumes ONTAP as a single-node system in Azure:

	Freemium	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based license	Capacity- based license
Maximum system capacity (disks + object storage)	500 GiB	2 TiB ¹	10 TiB	368 TiB	368 TiB per license	2 PiB

	Freemium	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based license	Capacity- based license
Supported	• DS4_v2	• E4s_v3	• DS4_v2	• DS5_v2	• DS4_v2	• DS4_v2
virtual machine	• DS5_v2	• E4ds_v4 ³	• DS13_v2	• DS14_v2	• DS5_v2	• DS5_v2
types	• DS13_v2		• E8s_v3	• DS15_v2	• DS13_v2	• DS13_v2
	• DS14_v2		• E8ds_v4 ³	• E32s_v3 ³	• DS14_v2	• DS14_v2
	• DS15_v2			• E48s_v3 ³	• DS15_v2	• DS15_v2
	• L8s_v2 ²			• E64is_v3 ³	• L8s_v2 ²	• L8s_v2 ²
	• E4s_v3			• <u>F</u> 32ds_v4	• E4s_v3	• E4s_v3
	• E8s_v3			• Ę48ds_v4	• E8s_v3	• E8s_v3
	• E32s_v3 ³			3	• E32s_v3 ³	• E32s_v3 ³
	• E48s_v3 ³			• E80ids_v4	• E48s_v3 ³	• E48s_v3 ³
	• E64is_v3 ³				• E64is_v3 ³	• E64is_v3 ³
	• E4ds_v4 ³				• E4ds_v4 ³	• E4ds_v4 ³
	• E8ds_v4 ³				• E8ds_v4 ³	• E8ds_v4 ³
	• F32ds_v4				•	• <u>F</u> 32ds_v4
	• <u>F</u> 48ds_v4				• <u>F</u> 48ds_v4	• <u>E</u> 48ds_v4
	• E80ids_v4				• E80ids_v4	• E80ids_v4
Supported disk types ⁴	Standard HDD Disks	Managed Disks	, Standard SSD	Managed Disks	s, and Premium	SSD Managed

Notes:

- 1. Data tiering to Azure Blob storage isn't supported with PAYGO Explore.
- 2. This VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as Flash Cache. Flash Cache speeds access to data through real-time intelligent caching of recently read user data and NetApp metadata. It is effective for random read-intensive workloads, including databases, email, and file services. Compression must be disabled on all volumes to take advantage of the Flash Cache performance improvements. Learn more.
- 3. These VM types use an Ultra SSD for VNVRAM, which provides better write performance.

If you choose any of these VM types when you deploy a new Cloud Volumes ONTAP system, you can't change to another VM type that *doesn't* use an Ultra SSD for VNVRAM. For example, you can't change from E8ds_v4 to E8s_v3, but you can change from E8ds_v4 to E32ds_v4 because both of those VM types use Ultra SSDs.

Conversely, if you deployed Cloud Volumes ONTAP using any other VM type, you won't be able to change to a VM type that uses an Ultra SSD for VNVRAM. For example, you can't change from E8s_v3 to E8ds v4.

4. Enhanced write performance is enabled when using SSDs.

- 5. For Azure region support, see Cloud Volumes Global Regions.
- 6. Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

HA pairs

You can choose from the following configurations when deploying Cloud Volumes ONTAP as an HA pair in Azure.

	Freemium	PAYGO Standard	PAYGO Premium	Node-based license	Capacity-based license
Maximum system capacity (disks + object storage)	500 GiB	10 TiB	368 TiB	368 TiB per license	2 PiB
Supported virtual machine	• DS4_v2	• DS4_v2	• DS5_v2 ¹	• DS4_v2	• DS4_v2
types	• DS5_v2 1	• DS13_v2	• DS14_v2 ¹	• DS5_v2 1	• DS5_v2 ¹
	• DS13_v2	• E8ds_v4 ¹	• DS15_v2 1	• DS13_v2	• DS13_v2
	• DS14_v2 ¹		• E8s_v3	• DS14_v2 ¹	• DS14_v2 1
	• DS15_v2 ¹		• E48s_v3 ¹	• DS15_v2 ¹	• DS15_v2 1
	• E8s_v3		• E32ds_v4 ¹	• E8s_v3	• E8s_v3
	• E48s_v3 ¹		• E48ds_v4 ¹	• E48s_v3 ¹	• E48s_v3 ¹
	• E8ds_v4 ¹		• E80ids_v4 ²	• E8ds_v4 ¹	• E8ds_v4 ¹
	• E32ds_v4 ¹			• E32ds_v4 ¹	• E32ds_v4 ¹
	• E48ds_v4 ¹			• E48ds_v4 ¹	• E48ds_v4 ¹
	• E80ids_v4 ²			• E80ids_v4 ²	• E80ids_v4 ²
Supported disk types	Premium page blo	obs			

Notes:

- Cloud Volumes ONTAP supports high write speed with these VM types when using an HA pair. High write speed is supported with all instance types when using a single node system. Learn more about choosing a write speed.
- 2. This VM is recommended only when Azure maintenance control is needed. It's not recommended for any other use case due to the higher pricing.
- 3. PAYGO Explore isn't supported with HA pairs in Azure.
- 4. For Azure region support, see Cloud Volumes Global Regions.
- 5. Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

Supported disk sizes

In Azure, an aggregate can contain up to 12 disks that are all the same type and size.

Single node systems

Single node systems use Azure Managed Disks. The following disk sizes are supported:

Premium SSD	Standard SSD	Standard HDD
• 500 GiB	• 100 GiB	• 100 GiB
• 1 TiB	• 500 GiB	• 500 GiB
• 2 TiB	• 1 TiB	• 1 TiB
• 4 TiB	• 2 TiB	• 2 TiB
• 8 TiB	• 4 TiB	• 4 TiB
• 16 TiB	• 8 TiB	• 8 TiB
• 32 TiB	• 16 TiB	• 16 TiB
	• 32 TiB	• 32 TiB

HA pairs

HA pairs use Premium page blobs. The following disk sizes are supported:

- 500 GiB
- 1 TiB
- 2 TiB
- 4 TiB
- 8 TiB

Supported configurations in Google Cloud

Several Cloud Volumes ONTAP configurations are supported in Google Cloud.

Supported configurations by license

Cloud Volumes ONTAP is available in Google Cloud Platform as a single node system and as a high-availability (HA) pair of nodes for fault tolerance and nondisruptive operations.

Upgrading a single node system to an HA pair isn't supported. If you want to switch between a single node system and an HA pair, then you need to deploy a new system and replicate data from the existing system to the new system.

	Freemium	PAYGO Explore	PAYGO Standard	PAYGO Premium	Node-based license	Capacity- based license
Maximum system capacity (disks + object storage) ¹	500 GB	2 TB ²	10 TB	368 TB	368 TB per license	2 PiB
Supported machine types ³	 n1- standard- 8 n1- standard- 32 n2- standard- 4 n2- standard- 8 n2- standard- 32 	• n2- standard- 4	 n1- standard- 8 n2- standard- 8 	 n1- standard- 32 n2- standard- 32 	 n1- standard- 8 n1- standard- 32 n2- standard- 4 n2- standard- 8 n2- standard- 32 	 n1- standard- 8 n1- standard- 32 n2- standard- 4 n2- standard- 8 n2- standard- 32
Supported disk types 4	Zonal persister	nt disks (SSD, ba	alanced, and sta	andard)		

Notes:

1. Disk limits can prevent you from reaching the maximum system capacity limit by using disks alone. You can reach the capacity limit by tiering inactive data to object storage.

Learn more about disk limits in Google Cloud.

- 2. Data tiering to Google Cloud Storage isn't supported with PAYGO Explore.
- 3. The custom-4-16384 machine type is no longer supported with new Cloud Volumes ONTAP systems.

If you have an existing system running on this machine type, you can keep using it, but we recommend switching to the n2-standard-4 machine type.

- 4. Enhanced write performance is enabled when using SSDs.
- 5. The Cloud Manager interface shows an additional supported machine type for Standard and BYOL: n1-highmem-4. However, this machine type isn't meant for production environments. We've made it available for a specific lab environment only.
- 6. For Google Cloud Platform region support, see Cloud Volumes Global Regions.
- 7. Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Solutions that use other VM instance types aren't supported.

Supported disk sizes

In Google Cloud, an aggregate can contain up to 6 disks that are all the same type and size. The following disk sizes are supported:

- 100 GB
- 500 GB
- 1 TB
- 2 TB
- 4 TB
- 8 TB
- 16 TB
- 64 TB

Storage limits

Storage limits in AWS

Cloud Volumes ONTAP has storage configuration limits to provide reliable operations. For best performance, do not configure your system at the maximum values.

Maximum system capacity by license

The maximum system capacity for a Cloud Volumes ONTAP system is determined by its license. The maximum system capacity includes disk-based storage plus object storage used for data tiering.

NetApp doesn't support exceeding the system capacity limit. If you reach the licensed capacity limit, Cloud Manager displays an action required message and no longer allows you to add additional disks.

For some configurations, disk limits prevent you from reaching the capacity limit by using disks alone. In those cases, you can reach the capacity limit by tiering inactive data to object storage. Refer to capacity and disk limits below for more details.

License	Maximum system capacity (disks + object storage)
Freemium	500 GiB
PAYGO Explore	2 TiB (data tiering is not supported with Explore)
PAYGO Standard	10 TiB
PAYGO Premium	368 TiB
Node-based license	368 TiB per license
Capacity-based license	2 PiB

For HA, is the license capacity limit per node or for the entire HA pair?

The capacity limit is for the entire HA pair. It is not per node. For example, if you use the Premium license, you can have up to 368 TiB of capacity between both nodes.

For an HA system in AWS, does mirrored data count against the capacity limit?

No, it doesn't. Data in an AWS HA pair is synchronously mirrored between the nodes so that the data is available in the event of failure. For example, if you purchase an 8 TiB disk on node A, Cloud Manager also allocates an 8 TiB disk on node B that is used for mirrored data. While 16 TiB of capacity was provisioned, only 8 TiB counts against the license limit.

Disk and tiering limits by EC2 instance

Cloud Volumes ONTAP uses EBS volumes as disks, with a maximum disk size of 16 TiB. The sections below show disk and tiering limits by EC2 instance family because many EC2 instance types have different disk

limits. Disk limits are also different between single node systems and HA pairs.

Note the following:

- c4, m4, and r4 instance types are not supported with new Cloud Volumes ONTAP 9.10.0 systems. However, we're still showing disk limits for these instance types because you can upgrade a system to the 9.10.0 release when running on one of these instance types.
- The disk limits below are specific to disks that contain user data. The limits do not include the boot disk and root disk.
- You can now purchase multiple node-based licenses for a Cloud Volumes ONTAP BYOL system to allocate
 more than 368 TiB of capacity. The number of licenses that you can purchase for a single node system or
 HA pair is unlimited. Be aware that disk limits can prevent you from reaching the capacity limit by using
 disks alone. You can go beyond the disk limit by tiering inactive data to object storage. Learn how to add
 additional system licenses to Cloud Volumes ONTAP.

Single node with a Premium license

Instance	Max disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
c5, m5, and r5 instances	21 1	336 TiB	368 TiB
m5dn.24xlarge	19 ²	304 TiB	368 TiB
c4, m4, and r4 instances	34	368 TiB	368 TiB

- 1. 21 data disks is the limit for *new* deployments of Cloud Volumes ONTAP. If you upgrade a system that was created with version 9.7 or earlier, then the system continues to support 22 disks. One less data disk is supported on new systems that use these instance types because of the addition of a core disk starting with the 9.8 release.
- This instance type has more local NVMe disks than other instance types, which means a smaller number of data disks are supported.

Single node with node-based licensing

Instance	Max disks per node	Max system capacity with one license		Max system capacity with multiple licenses	
		Disks alone	Disks + data tiering	Disks alone	Disks + data tiering
c5, m5, and r5 instances	21 1	336 TiB	368 TiB	336 TiB	368 TiB x each license
m5dn.24xlarge	19 ²	304 TiB	368 TiB	304 TiB	368 TiB x each license
c4, m4, and r4 instances	34	368 TiB	368 TiB	544 TiB	368 TiB x each license

1. 21 data disks is the limit for *new* deployments of Cloud Volumes ONTAP. If you upgrade a system that was created with version 9.7 or earlier, then the system continues to support 22 disks. One less data disk is supported on new systems that use these instance types because of the addition of a core disk starting

- with the 9.8 release.
- 2. This instance type has more local NVMe disks than other instance types, which means a smaller number of data disks are supported.

Single node with capacity-based licensing

Instance	Max disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
c5, m5, and r5 instances	21	336 TiB	2 PiB
m5dn.24xlarge	19 ¹	304 TiB	2 PiB

1. This instance type has more local NVMe disks than other instance types, which means a smaller number of data disks are supported.

HA pairs with a Premium license

Instance	Max disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
c5, m5, and r5 instances	18 ¹	288 TiB	368 TiB
m5dn.24xlarge	16 ²	256 TiB	368 TiB
c4, m4, and r4 instances	31	368 TiB	368 TiB

- 1. 18 data disks is the limit for *new* deployments of Cloud Volumes ONTAP. If you upgrade a system that was created with version 9.7 or earlier, then the system continues to support 19 disks. One less data disk is supported on new systems that use these instance types because of the addition of a core disk starting with the 9.8 release.
- This instance type has more local NVMe disks than other instance types, which means a smaller number of data disks are supported.

HA pairs with node-based licensing

Instance	Max disks per node	Max system capacity with one license		Max system capacity with multiple licenses	
		Disks alone	Disks + data tiering	Disks alone	Disks + data tiering
c5, m5, and r5 instances	18 ¹	288 TiB	368 TiB	288 TiB	368 TiB x each license
m5dn.24xlarge	16 ²	256 TiB	368 TiB	256 TiB	368 TiB x each license
c4, m4, and r4 instances	31	368 TiB	368 TiB	496 TiB	368 TiB x each license

1. 18 data disks is the limit for *new* deployments of Cloud Volumes ONTAP. If you upgrade a system that was created with version 9.7 or earlier, then the system continues to support 19 disks. One less data disk is

- supported on new systems that use these instance types because of the addition of a core disk starting with the 9.8 release.
- 2. This instance type has more local NVMe disks than other instance types, which means a smaller number of data disks are supported.

HA pairs with capacity-based licensing

Instance	Max disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
c5, m5, and r5 instances	18	288 TiB	2 PiB
m5dn.24xlarge	16 ¹	256 TiB	2 PiB

^{1.} This instance type has more local NVMe disks than other instance types, which means a smaller number of data disks are supported.

Aggregate limits

Cloud Volumes ONTAP uses AWS volumes as disks and groups them into *aggregates*. Aggregates provide storage to volumes.

Parameter	Limit
Maximum number of aggregates	Single node: Same as the disk limit HA pairs: 18 in a node ¹
Maximum aggregate size	96 TiB of raw capacity ²
Disks per aggregate	1-6 ³
Maximum number of RAID groups per aggregate	1

Notes:

- 1. It's not possible to create 18 aggregates on both nodes in an HA pair because doing so would exceed the data disk limit.
- 2. The aggregate capacity limit is based on the disks that comprise the aggregate. The limit does not include object storage used for data tiering.
- 3. All disks in an aggregate must be the same size.

Storage VM limits

Some configurations enable you to create additional storage VMs (SVMs) for Cloud Volumes ONTAP.

Learn how to create additional storage VMs.

License type	Instance family	Storage VM limit
PAYGO	c4, m4, and r4	1 storage VM for serving data1 storage VM for disaster recovery
	c5, m5, and r5	1 storage VM for serving data1 storage VM for disaster recovery
Freemium	c5, m5, and r5	24 storage VMs total ^{1,2}
Capacity-based license 3	c5, m5, and r5	24 storage VMs total ^{1,2}
Node-based BYOL ⁴	c4, m4, and r4	1 storage VM for serving data1 storage VM for disaster recovery
	c5, m5, and r5	24 storage VMs total ^{1,2}

- 1. The limit can be lower, depending on the EC2 instance type that you use. The limits per instance are listed in the section below.
- 2. These 24 storage VMs can serve data or be configured for disaster recovery (DR).
- 3. For capacity-based licensing, there are no extra licensing costs for additional storage VMs, but there is a 4 TiB minimum capacity charge per storage VM. For example, if you create two storage VMs and each has 2 TiB of provisioned capacity, you'll be charged a total of 8 TiB.
- 4. For node-based BYOL, an add-on license is required for each additional *data-serving* storage VM beyond the first storage VM that comes with Cloud Volumes ONTAP by default. Contact your account team to obtain a storage VM add-on license.

Storage VMs that you configure for disaster recovery (DR) don't require an add-on license (they are free of charge), but they do count against the storage VM limit. For example, if you have 12 data-serving storage VMs and 12 storage VMs configured for disaster recovery, then you've reached the limit and can't create any additional storage VMs.

Storage VM limit by EC2 instance type

When you create an additional storage VM, you need to allocate private IP addresses to port e0a. The table below identifies the maximum number of private IPs per interface, as well as the number of IP addresses that are available on port e0a after Cloud Volumes ONTAP has been deployed. The number of available IP addresses directly affects the maximum number of storage VMs for that configuration.

The instances listed below are for the c5, m5, and r5 instance families.

Configuration	Instance type	Max private IPs per interface	IPs remaining after deployment ¹	Max storage VMs without a mgmt LIF ^{2,3}	Max storage VMs with a mgmt LIF ^{2,3}
Single node	*.xlarge	15	9	10	5
	*.2xlarge	15	9	10	5
	*.4xlarge	30	24	24	12
	*.8xlarge	30	24	24	12
	*.9xlarge	30	24	24	12
	*.12xlarge	30	24	24	12
	*.16xlarge	50	44	24	12
	*.18xlarge	50	44	24	12
	*.24xlarge	50	44	24	12
HA pair in	*.xlarge	15	10	11	5
single AZ	*.2xlarge	15	10	11	5
	*.4xlarge	30	25	24	12
	*.8xlarge	30	25	24	12
	*.9xlarge	30	25	24	12
	*.12xlarge	30	25	24	12
	*.16xlarge	50	45	24	12
	*.18xlarge	50	45	24	12
	*.24xlarge	50	44	24	12
HA pair in multi	*.xlarge	15	12	13	13
AZs	*.2xlarge	15	12	13	13
	*.4xlarge	30	27	24	24
	*.8xlarge	30	27	24	24
	*.9xlarge	30	27	24	24
	*.12xlarge	30	27	24	24
	*.16xlarge	50	47	24	24
	*.18xlarge	50	47	24	24
	*.24xlarge	50	44	24	12

- 1. This number indicates how many *remaining* private IP addresses are available on port e0a after Cloud Volumes ONTAP is deployed and set up. For example, a *.2xlarge system supports a maximum of 15 IP addresses per network interface. When an HA pair is deployed in a single AZ, 5 private IP addresses are allocated to port e0a. As a result, an HA pair that uses a *.2xlarge instance type has 10 private IP addresses remaining for additional storage VMs.
- 2. The number listed in these columns includes the initial storage VM that Cloud Manager creates by default. For example, if 24 is listed in this column, it means that you can create 23 additional storage VMs for a total

of 24.

3. A management LIF for the storage VM is optional. A management LIF provides a connection to management tools like SnapCenter.

Because it requires a private IP address, it will limit the number of additional storage VMs that you can create. The only exception is an HA pair in multiple AZs. In that case, the IP address for the management LIF is a *floating* IP address so it doesn't count against the *private* IP limit.

File and volume limits

Logical storage	Parameter	Limit
Files	Maximum size	16 TiB
	Maximum per volume	Volume size dependent, up to 2 billion
FlexClone volumes	Hierarchical clone depth ¹	499
FlexVol volumes	Maximum per node	500
	Minimum size	20 MB
	Maximum size	100 TiB
Qtrees	Maximum per FlexVol volume	4,995
Snapshot copies	Maximum per FlexVol volume	1,023

1. Hierarchical clone depth is the maximum depth of a nested hierarchy of FlexClone volumes that can be created from a single FlexVol volume.

iSCSI storage limits

iSCSI storage	Parameter	Limit
LUNs	Maximum per node	1,024
	Maximum number of LUN maps	1,024
	Maximum size	16 TiB
	Maximum per volume	512
igroups	Maximum per node	256
Initiators	Maximum per node	512
	Maximum per igroup	128
iSCSI sessions	Maximum per node	1,024
LIFs	Maximum per port	32
	Maximum per portset	32
Portsets	Maximum per node	256

Storage limits in Azure

Cloud Volumes ONTAP has storage configuration limits to provide reliable operations. For best performance, do not configure your system at the maximum values.

Maximum system capacity by license

The maximum system capacity for a Cloud Volumes ONTAP system is determined by its license. The maximum system capacity includes disk-based storage plus object storage used for data tiering.

NetApp doesn't support exceeding the system capacity limit. If you reach the licensed capacity limit, Cloud Manager displays an action required message and no longer allows you to add additional disks.

License	Maximum system capacity (disks + object storage)
Freemium	500 GiB
PAYGO Explore	2 TiB (data tiering is not supported with Explore)
PAYGO Standard	10 TiB
PAYGO Premium	368 TiB
Node-based license	368 TiB per license
Capacity-based license	2 PiB

For HA, is the license capacity limit per node or for the entire HA pair?

The capacity limit is for the entire HA pair. It is not per node. For example, if you use the Premium license, you can have up to 368 TiB of capacity between both nodes.

Disk and tiering limits by VM size

The disk limits below are specific to disks that contain user data. The limits do not include the root disk, core disk, and VNVRAM.

The tables below show the maximum system capacity by VM size with disks alone, and with disks and cold data tiering to object storage.

- Single node systems can use Standard HDD Managed Disks, Standard SSD Managed Disks, and Premium SSD Managed Disks, with up to 32 TiB per disk. The number of supported disks varies by VM size.
- HA systems use Premium page blobs as disks, with up to 8 TiB per page blob. The number of supported disks varies by VM size.



You can purchase multiple node-based licenses for a Cloud Volumes ONTAP BYOL system to allocate more than 368 TiB of capacity. The number of licenses that you can purchase for a single node system or HA pair is unlimited. Be aware that disk limits can prevent you from reaching the capacity limit by using disks alone. You can go beyond the disk limit by tiering inactive data to object storage. Learn how to add additional system licenses to Cloud Volumes ONTAP.

Single node with a Premium license

VM size	Max data disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
DS5_v2	61	368 TiB	368 TiB
DS14_v2	61	368 TiB	368 TiB
DS15_v2	61	368 TiB	368 TiB
E32s_v3	29	368 TiB	368 TiB
E48s_v3	29	368 TiB	368 TiB
E64is_v3	29	368 TiB	368 TiB
E32ds_v 4	29	368 TiB	368 TiB
E48ds_v 4	29	368 TiB	368 TiB
E80ids_v 4	61	368 TiB	368 TiB

Single node with node-based licensing



For some VM types, you'll need several BYOL licenses to reach the max system capacity listed below. For example, you'd need 6 BYOL licenses to reach 1.95 PiB with DS5_v2.

VM size	Max data disks per node	Max system capacity with one license		Max system capacity with multip licenses	
		Disks alone	Disks + data tiering	Disks alone	Disks + data tiering
DS4_v2	29	368 TiB	368 TiB	928 TiB	368 TiB x each license
DS5_v2	61	368 TiB	368 TiB	1.95 PiB	368 TiB x each license
DS13_v2	29	368 TiB	368 TiB	928 TiB	368 TiB x each license
DS14_v2	61	368 TiB	368 TiB	1.95 PiB	368 TiB x each license

VM size	Max data disks per node	Max system capacity with one license				Max system capa	city with multiple
DS15_v2	61	368 TiB	368 TiB	1.95 PiB	368 TiB x each license		
L8s_v2	13	368 TiB	368 TiB	416 TiB	368 TiB x each license		
E4s_v3	5	160 TiB	368 TiB	160 TiB	368 TiB x each license		
E8s_v3	13	368 TiB	368 TiB	416 TiB	368 TiB x each license		
E32s_v3	29	368 TiB	368 TiB	928 TiB	368 TiB x each license		
E48s_v3	29	368 TiB	368 TiB	928 TiB	368 TiB x each license		
E64is_v3	29	368 TiB	368 TiB	928 TiB	368 TiB x each license		
E4ds_v4	5	160 TiB	368 TiB	160 TiB	368 TiB x each license		
E8ds_v4	13	368 TiB	368 TiB	416 TiB	368 TiB x each license		
E32ds_v 4	29	368 TiB	368 TiB	928 TiB	368 TiB x each license		
E48ds_v 4	29	368 TiB	368 TiB	928 TiB	368 TiB x each license		
E80ids_v 4	61	368 TiB	368 TiB	1.95 PiB	368 TiB x each license		

Single node with capacity-based licensing

VM size	Max data disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
DS4_v2	29	928 TiB	2 PiB
DS5_v2	61	1.95 PiB	2 PiB
DS13_v2	29	928 TiB	2 PiB
DS14_v2	61	1.95 PiB	2 PiB
DS15_v2	61	1.95 PiB	2 PiB
L8s_v2	13	416 TiB	2 PiB
E4s_v3	5	160 TiB	2 PiB
E8s_v3	13	416 TiB	2 PiB
E32s_v3	29	928 TiB	2 PiB

VM size	Max data disks per node	Max system capacity with disks alone	Max system capacity with disks and data tiering
E48s_v3	29	928 TiB	2 PiB
E64is_v3	29	928 TiB	2 PiB
E4ds_v4	5	160 TiB	2 PiB
E8ds_v4	13	416 TiB	2 PiB
E32ds_v 4	29	928 TiB	2 PiB
E48ds_v 4	29	928 TiB	2 PiB
E80ids_v 4	61	1.95 PiB	2 PiB

HA pairs with a Premium license

VM size	Max data disks for an HA pair	Max system capacity with disks alone	Max system capacity with disks and data tiering
DS5_v2	61	368 TiB	368 TiB
DS14_v2	61	368 TiB	368 TiB
DS15_v2	61	368 TiB	368 TiB
E8s_v3	13	104 TiB	368 TiB
E48s_v3	29	232 TiB	368 TiB
E32ds_v 4	29	232 TiB	368 TiB
E48ds_v 4	29	232 TiB	368 TiB
E80ids_v 4	61	368 TiB	368 TiB

HA pairs with node-based licensing

VM size	Max data disks for an HA pair	Max system capacity with one license		Max system ca licenses	pacity with multiple
		Disks alone	Disks + data tiering	Disks alone	Disks + data tiering
DS4_v2	29	232 TiB	368 TiB	232 TiB	368 TiB x each license
DS5_v2	61	368 TiB	368 TiB	488 TiB	368 TiB x each license

VM size	Max data disks for an HA pair license		city with one	Max system capa licenses	city with multiple
DS13_v2	29	232 TiB	368 TiB	232 TiB	368 TiB x each license
DS14_v2	61	368 TiB	368 TiB	488 TiB	368 TiB x each license
DS15_v2	61	368 TiB	368 TiB	488 TiB	368 TiB x each license
E8s_v3	13	104 TiB	368 TiB	104 TiB	368 TiB x each license
E48s_v3	29	232 TiB	368 TiB	232 TiB	368 TiB x each license
E8ds_v4	13	104 TiB	368 TiB	104 TiB	368 TiB x each license
E32ds_v 4	29	232 TiB	368 TiB	232 TiB	368 TiB x each license
E48ds_v 4	29	232 TiB	368 TiB	232 TiB	368 TiB x each license
E80ids_v 4	61	368 TiB	368 TiB	488 TiB	368 TiB x each license

HA pairs with capacity-based licensing

VM size	Max data disks for an HA pair	Max system capacity with disks alone	Max system capacity with disks and data tiering
DS4_v2	29	232 TiB	2 PiB
DS5_v2	61	488 TiB	2 PiB
DS13_v2	29	232 TiB	2 PiB
DS14_v2	61	488 TiB	2 PiB
DS15_v2	61	488 TiB	2 PiB
E8s_v3	13	104 TiB	2 PiB
E48s_v3	29	232 TiB	2 PiB
E8ds_v4	13	104 TiB	2 PiB
E32ds_v 4	29	232 TiB	2 PiB
E48ds_v 4	29	232 TiB	2 PiB
E80ids_v 4	61	488 TiB	2 PiB

Aggregate limits

Cloud Volumes ONTAP uses Azure storage as disks and groups them into *aggregates*. Aggregates provide storage to volumes.

Parameter	Limit	
Maximum number of aggregates	Same as the disk limit	
Maximum aggregate size ¹	384 TiB of raw capacity for single node ² 352 TiB of raw capacity for single node with PAYGO 96 TiB of raw capacity for HA pairs	
Disks per aggregate	1-12 ³	
Maximum number of RAID groups per aggregate	1	

Notes:

- 1. The aggregate capacity limit is based on the disks that comprise the aggregate. The limit does not include object storage used for data tiering.
- 2. If using node-based licensing, two BYOL licenses are required to reach 384 TiB.
- 3. All disks in an aggregate must be the same size.

Storage VM limits

Some configurations enable you to create additional storage VMs (SVMs) for Cloud Volumes ONTAP.

These are the tested limits. While it is theoretically possible to configure additional storage VMs, it's not supported.

Learn how to create additional storage VMs.

License type	Storage VM limit
PAYGO	1 storage VM for serving data1 storage VM for disaster recovery
Freemium	24 storage VMs total ^{1,2}
Capacity-based license ³	24 storage VMs total ^{1,2}
Node-based BYOL ⁴	24 storage VMs total ^{1,2}

- 1. These 24 storage VMs can serve data or be configured for disaster recovery (DR).
- 2. Each storage VM can have up to three LIFs where two are data LIFs and one is an SVM management LIF.
- 3. For capacity-based licensing, there are no extra licensing costs for additional storage VMs, but there is a 4 TiB minimum capacity charge per storage VM. For example, if you create two storage VMs and each has 2 TiB of provisioned capacity, you'll be charged a total of 8 TiB.

4. For node-based BYOL, an add-on license is required for each additional *data-serving* storage VM beyond the first storage VM that comes with Cloud Volumes ONTAP by default. Contact your account team to obtain a storage VM add-on license.

Storage VMs that you configure for disaster recovery (DR) don't require an add-on license (they are free of charge), but they do count against the storage VM limit. For example, if you have 12 data-serving storage VMs and 12 storage VMs configured for disaster recovery, then you've reached the limit and can't create any additional storage VMs.

File and volume limits

Logical storage	Parameter	Limit
Files	Maximum size	16 TiB
	Maximum per volume	Volume size dependent, up to 2 billion
FlexClone volumes	Hierarchical clone depth ²	499
FlexVol volumes	Maximum per node	500
	Minimum size	20 MB
	Maximum size	100 TiB
Qtrees	Maximum per FlexVol volume	4,995
Snapshot copies	Maximum per FlexVol volume	1,023

Notes:

- Cloud Manager does not provide any setup or orchestration support for SVM disaster recovery. It also does
 not support storage-related tasks on an additional SVM. You must use System Manager or the CLI for SVM
 disaster recovery.
 - SVM Disaster Recovery Preparation Express Guide
 - SVM Disaster Recovery Express Guide
- 2. Hierarchical clone depth is the maximum depth of a nested hierarchy of FlexClone volumes that can be created from a single FlexVol volume.

iSCSI storage limits

iSCSI storage	Parameter	Limit
LUNs	Maximum per node	1,024
	Maximum number of LUN maps	1,024
	Maximum size	16 TiB
	Maximum per volume	512
igroups	Maximum per node	256

iSCSI storage	Parameter	Limit
Initiators	Maximum per node	512
	Maximum per igroup	128
iSCSI sessions	Maximum per node	1,024
LIFs	Maximum per port	32
	Maximum per portset	32
Portsets	Maximum per node	256

Storage limits in Google Cloud

Cloud Volumes ONTAP has storage configuration limits to provide reliable operations. For best performance, do not configure your system at the maximum values.

Maximum system capacity by license

The maximum system capacity for a Cloud Volumes ONTAP system is determined by its license. The maximum system capacity includes disk-based storage plus object storage used for data tiering.

NetApp doesn't support exceeding the system capacity limit. If you reach the licensed capacity limit, Cloud Manager displays an action required message and no longer allows you to add additional disks.

For some configurations, disk limits prevent you from reaching the capacity limit by using disks alone. You can reach the capacity limit by tiering inactive data to object storage. Refer to the disk limits below for more details.

License	Maximum system capacity (disks + object storage)
Freemium	500 GB
PAYGO Explore	2 TB (data tiering is not supported with Explore)
PAYGO Standard	10 TB
PAYGO Premium	368 TB
Node-based license	368 TB per license
Capacity-based license	2 PiB

For an HA pair, is the licensed capacity limit per node or for the entire HA pair?

The capacity limit is for the entire HA pair. It is not per node. For example, if you use the Premium license, you can have up to 368 TB of capacity between both nodes.

For an HA pair, does mirrored data count against the licensed capacity limit?

No, it doesn't. Data in an HA pair is synchronously mirrored between the nodes so that the data is available in

the event of failure in Google Cloud. For example, if you purchase an 8 TB disk on node A, Cloud Manager also allocates an 8 TB disk on node B that is used for mirrored data. While 16 TB of capacity was provisioned, only 8 TB counts against the license limit.

Disk and tiering limits

The table below shows the maximum system capacity with disks alone, and with disks and cold data tiering to object storage. The disk limits are specific to disks that contain user data. The limits do not include the boot disk and root disk.

Parameter	Limit
Maximum data disks	124 for single node systems123 per node for HA pairs
Maximum disk size	64 TB
Maximum system capacity with disks alone	256 TB ¹
Maximum system capacity with disks and cold data tiering to a Google Cloud Storage bucket	Depends on the license. See the table above.

¹ This limit is defined by virtual machine limits in Google Cloud Platform.

Aggregate limits

Cloud Volumes ONTAP groups Google Cloud Platform disks into *aggregates*. Aggregates provide storage to volumes.

Parameter	Limit
Maximum number of data aggregates ¹	99 for single node64 for an entire HA pair
Maximum aggregate size	256 TB of raw capacity ²
Disks per aggregate	1-6 ³
Maximum number of RAID groups per aggregate	1

Notes:

- 1. The maximum number of data aggregates doesn't include the root aggregate.
- 2. The aggregate capacity limit is based on the disks that comprise the aggregate. The limit does not include object storage used for data tiering.
- 3. All disks in an aggregate must be the same size.

Logical storage limits

Logical storage	Parameter	Limit
Storage virtual machines (SVMs)	Maximum number for Cloud Volumes ONTAP (HA pair or single node)	One data-serving SVM and one destination SVM used for disaster recovery. You can activate the destination SVM for data access if there's an outage on the source SVM. ¹ The one data-serving SVM spans the entire Cloud Volumes ONTAP system (HA pair or single node).
Files	Maximum size	16 TB
	Maximum per volume	Volume size dependent, up to 2 billion
FlexClone volumes	Hierarchical clone depth ²	499
FlexVol volumes	Maximum per node	500
	Minimum size	20 MB
	Maximum size	100 TB
Qtrees	Maximum per FlexVol volume	4,995
Snapshot copies	Maximum per FlexVol volume	1,023

Notes:

- Cloud Manager does not provide any setup or orchestration support for SVM disaster recovery. It also does
 not support storage-related tasks on an additional SVM. You must use System Manager or the CLI for SVM
 disaster recovery.
 - SVM Disaster Recovery Preparation Express Guide
 - SVM Disaster Recovery Express Guide
- 2. Hierarchical clone depth is the maximum depth of a nested hierarchy of FlexClone volumes that can be created from a single FlexVol volume.

iSCSI storage limits

iSCSI storage	Parameter	Limit
LUNs	Maximum per node	1,024
	Maximum number of LUN maps	1,024
	Maximum size	16 TB
	Maximum per volume	512
igroups	Maximum per node	256
Initiators	Maximum per node	512
	Maximum per igroup	128
iSCSI sessions	Maximum per node	1,024

iSCSI storage	Parameter	Limit
LIFs	Maximum per port	1
	Maximum per portset	32
Portsets	Maximum per node	256

Known issues

Known issues identify problems that might prevent you from using this release of the product successfully.

There are no known issues in this release specific to Cloud Volumes ONTAP.

You can find known issues for ONTAP software in the ONTAP Release Notes.

Known limitations

Limitations in all cloud providers

Known limitations identify platforms, devices, or functions that are not supported by this release of the product, or that do not interoperate correctly with it. Review these limitations carefully.

The following limitations apply to Cloud Volumes ONTAP in all cloud providers: AWS, Azure, and Google Cloud.

Maximum concurrent replication operations

The maximum number of concurrent SnapMirror or SnapVault transfers for Cloud Volumes ONTAP is 100 per node, regardless of the instance type or machine type.

Cloud provider snapshots must not be used for your backup and recovery plans

You shouldn't use your cloud provider's snapshots as part of your backup and recovery plan for Cloud Volumes ONTAP data. You should always use ONTAP Snapshot copies or third-party backup solutions to back up and restore data hosted on Cloud Volumes ONTAP.

Learn how to use the Cloud Backup service to back up and restore ONTAP data.



ONTAP consistency points in the WAFL file system determine data consistency. Only ONTAP can quiesce the WAFL file system to make a crash-consistent backup.

Support in China regions

Cloud Volumes ONTAP is supported in China regions as follows.

- Cloud Volumes ONTAP 9.6 is supported in AWS China regions.
- · Single node systems are supported.
- Licenses purchased directly from NetApp are supported.

All other locations, versions, configurations, and licenses aren't supported.

Cloud Volumes ONTAP supports Reserved and On-demand VM instances

Cloud Volumes ONTAP can run on either a Reserved or On-demand VM instance from your cloud provider. Other types of VM instances aren't supported.

Automatic application resource management solutions shouldn't be used

Automatic application resource management solutions should not manage Cloud Volumes ONTAP systems. Doing so can result in a change to an unsupported configuration. For example, the solution might change Cloud Volumes ONTAP to an unsupported VM instance type.

Software updates must be completed by Cloud Manager

Upgrades of Cloud Volumes ONTAP must be completed from Cloud Manager. You should not upgrade Cloud Volumes ONTAP by using System Manager or the CLI. Doing so can impact system stability.

Cloud Volumes ONTAP deployment must not be modified from your cloud provider's console

Changes to a Cloud Volumes ONTAP configuration from your cloud provider's console results in an unsupported configuration. Any changes to the Cloud Volumes ONTAP resources that Cloud Manager creates and manages can impact system stability and Cloud Manager's ability to manage the system.

Disks and aggregates must be managed from Cloud Manager

All disks and aggregates must be created and deleted directly from Cloud Manager. You should not perform these actions from another management tool. Doing so can impact system stability, hamper the ability to add disks in the future, and potentially generate redundant cloud provider fees.

SnapManager licensing limitation

SnapManager per-server licenses are supported with Cloud Volumes ONTAP. Per-storage system (SnapManager suite) licenses are not supported.

Unsupported ONTAP features

The following features are not supported with Cloud Volumes ONTAP:

- Aggregate-level inline deduplication
- · Aggregate-level background deduplication
- · Disk maintenance center
- Disk sanitization
- · FabricPool mirroring
- Fibre Channel (FC)
- Flash Pools
- · Infinite Volumes
- Interface groups
- · Intranode LIF failover
- MetroCluster
- ONTAP S3 in AWS and Google Cloud (the S3 protocol is supported in Azure)
- RAID4, RAID-DP, RAID-TEC (RAID0 is supported)
- Service Processor
- SnapLock Compliance and Enterprise modes (only Cloud WORM is supported)
- SnapMirror Synchronous
- VLANs

Known limitations in AWS

The following known limitations are specific to Cloud Volumes ONTAP in Amazon Web Services. Be sure to also review Limitations for Cloud Volumes ONTAP in all cloud providers.

AWS Outpost limitations

If you have an AWS Outpost, you can deploy Cloud Volumes ONTAP in that Outpost by selecting the Outpost VPC in the Working Environment wizard. The experience is the same as any other VPC that resides in AWS. Note that you will need to first deploy a Connector in your AWS Outpost.

There are a few limitations to point out:

- Only single node Cloud Volumes ONTAP systems are supported at this time
- The EC2 instances that you can use with Cloud Volumes ONTAP are limited to what's available in your Outpost
- · Only General Purpose SSDs (gp2) are supported at this time

Flash Cache limitations

C5D and R5D instance types include local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Note the following limitations:

• Compression must be disabled on all volumes to take advantage of the Flash Cache performance improvements.

You can choose no storage efficiency when creating a volume from Cloud Manager, or you can create a volume and then disable data compression by using the CLI.

Cache rewarming after a reboot is not supported with Cloud Volumes ONTAP.

False alarms reported by Amazon CloudWatch

Cloud Volumes ONTAP does not release CPUs when idle, so Amazon CloudWatch can report a high CPU warning for the EC2 instance because it sees 100% usage. You can ignore this alarm. The ONTAP statistics command displays the true usage of the CPUs.

Cloud Volumes ONTAP HA pairs do not support immediate storage giveback

After a node reboots, the partner must sync data before it can return the storage. The time that it takes to resync data depends on the amount of data written by clients while the node was down and the data write speed during the time of giveback.

Learn how storage works in a Cloud Volumes ONTAP HA pair running in AWS.

Known limitations in Azure

The following known limitations are specific to Cloud Volumes ONTAP in Microsoft Azure. Be sure to also review Limitations for Cloud Volumes ONTAP in all cloud providers.

Flash Cache limitations

The Standard_L8s_v2 VM type includes local NVMe storage, which Cloud Volumes ONTAP uses as *Flash Cache*. Note the following limitations for Flash Cache:

 Compression must be disabled on all volumes to take advantage of the Flash Cache performance improvements.

You can choose no storage efficiency when creating a volume from Cloud Manager, or you can create a volume and then disable data compression by using the CLI.

Cache rewarming after a reboot is not supported with Cloud Volumes ONTAP.

HA limitations

HA pairs aren't supported in some regions.

View the list of supported Azure regions.

Pay-as-you-go not available for CSP partners

If you are a Microsoft Cloud Solution Provider (CSP) partner, you cannot deploy Cloud Volumes ONTAP Explore, Standard, or Premium because pay-as-you-go subscriptions are not available for CSP partners. You must purchase a license and deploy Cloud Volumes ONTAP BYOL.

Known limitations in Google Cloud

The following known limitations are specific to Cloud Volumes ONTAP in Google Cloud Platform. Be sure to also review Limitations for Cloud Volumes ONTAP in all cloud providers.

Limitation with packet mirroring

Packet mirroring must be disabled in the Google Cloud VPC in which you deploy Cloud Volumes ONTAP.

Cloud Volumes ONTAP can't operate properly if packet mirroring is enabled.

Google Private Service Connect limitations

If you leverage Google Private Service Connect within the VPC that you are deploying Cloud Volumes ONTAP into, you will need to implement DNS records that forward traffic to the required Cloud Manager API Endpoints.

Tiering data from Cloud Volumes ONTAP into a Google Cloud Storage bucket is not currently supported with Private Service Connect.

Cloud provider integrations

This page describes how NetApp works with cloud providers to resolve issues that might arise.

Collaborative support best practices

NetApp is committed to provide support to Licensee and will use commercially reasonable efforts to resolve technical support issues for Cloud Volumes ONTAP when reported by the Licensee. NetApp and the applicable cloud provider don't have any direct support obligations to each other's licensed software or infrastructure.

NetApp has implemented tools aimed to connect with applicable cloud providers on customer technical issues that may be a result of the applicable cloud provider services. However, the best way to maintain a seamless support flow is for customers to (i) maintain a current support contract with both NetApp and the applicable cloud provider and (ii) coordinate joint escalation meetings with both NetApp and the applicable cloud provider when technical issues arise and the customer needs clarity on which products or services are causing those technical issues.

Azure maintenance events

Microsoft schedules and programmatically announces maintenance events on its Azure virtual machine (VM) infrastructure that may affect Cloud Volumes ONTAP VMs. These events are announced 15 minutes prior to the maintenance window.

Special handling of the maintenance events is supported for Cloud Volumes ONTAP high availability (HA) pairs. To maintain application health, we perform a preventive takeover to prioritize stability, as any loss of connectivity of more than 15 seconds will disable failover capabilities.

When the maintenance window is announced, the partner node of the targeted node will perform a takeover. When the maintenance is complete, a giveback will be initiated. After the giveback, the HA pair is expected to return to a healthy state. If this doesn't occur, contact NetApp Support for assistance. Note that maintenance events are targeted at one of the VMs in an HA pair at a time, and typically both nodes are targeted in a relatively short period of time.

CIFS/SMB clients that use Cloud Volumes ONTAP non-continuously available CIFS shares will experience a loss of session both when a takeover occurs, and when the aggregate that the session is using is given back to the aggregate's home node. This is a limitation imposed by the CIFS/SMB protocol itself. Customers may wish to use third-party products to avoid issues that may arise from takeover and giveback. For further assistance, contact NetApp Support.

Legal notices

Legal notices provide access to copyright statements, trademarks, patents, and more.

Copyright

http://www.netapp.com/us/legal/copyright.aspx

Trademarks

NETAPP, the NETAPP logo, and the marks listed on the NetApp Trademarks page are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.

http://www.netapp.com/us/legal/netapptmlist.aspx

Patents

A current list of NetApp owned patents can be found at:

https://www.netapp.com/us/media/patents-page.pdf

Privacy policy

https://www.netapp.com/us/legal/privacypolicy/index.aspx

Open source

Notice files provide information about third-party copyright and licenses used in NetApp software.

- Notice for Cloud Volumes ONTAP 9.10.1 Mediator in AWS
- Notice for Cloud Volumes ONTAP 9.10.1 Mediator in Google Cloud

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.