ParPyDTK2 Documentation

Release 1.0.0

Qiao Chen

CONTENTS:

1	Introduction				
	1.1	Background & Motivation	1		
	1.2	About Me			
2	Installation				
	2.1	Install MOAB	3		
	2.2	Install DTK2	4		
	2.3	Install ParPyDTK2	5		
	2.4	Using our Docker container	6		
3	Somo	e Details	7		
	3.1	Global IDs/Handles	7		
	3.2	Treatment of Empty Partitions	7		
4	A De	emo	8		
5	API		11		
	5.1	ParPyDTK2 Python API	11		
	5.2	ParPyDTK2 C++ API	21		
6	Indic	ces and tables	35		
Python Module Index					
Index					

CHAPTER

ONE

INTRODUCTION

1.1 Background & Motivation

Multi-physics coupling problems have been one of the popular topics. People try to put different models together and simulate the behaviors in a coupled fashion. With the popularity of *partitioned approach*, i.e. solve different domains with different solvers and couple the interface conditions as those solvers boundary conditions, a robust and accurate interface solution remapping operator is needed. The solution transfer problem on its own is not an easy task, since it involves the following research aspects:

- 1. **numerical method**, i.e. consistent, conservative, high-order convergence.
- 2. **geometry and data structure, i.e. efficient and robust treatments of** *mesh association* of two (potentially more) general surfaces that come from different discretization methods (*FEM*, *FVM*, *FDM*, etc.) thus having different resolutions.
- 3. parallel rendezvous & HPC, i.e. handling migrating meshes that have different parallel partitions.

Data Transfer Kit-2.0 (DTK2) is a package that is developed at the Oak Ridge National Laboratory. DTK2 provides parallel solution transfer services with *meshless* (a.k.a. *mesh-free*) methods, which are relatively easy to implement and computational efficient. Particularly, we are interested in its *modified moving least square*¹ method that is an improvement of traditional MLS fitting in terms of robustness on featured geometries.

Mesh-Oriented datABase is an array-based general purpose mesh library with MPI support. Array-based mesh data structure is more efficient in both computational cost and memory usage compared to traditional pointer-based data structures. MOAB has been adapted in DTK2, so we choose to use it as our mesh database for this work.

In multi-physics coupling, a flexible software framework is must. The fact is: the physics solvers may be implemented in different programming languages or shipped as executable binaries (typically commercial codes), this makes using static languages difficult. Python, on the other hand, can easily glue different languages together and drive executable binaries smoothly. Its built-in reference counting, garbage collection, and pass-by-reference make it as one of the best choices for developing multi-physics coupling frameworks. In addition, MPI is well supported through the mpi4py package. This is the core motivation of this project!

1.2 About Me

I am a Ph.D. candidate who work with Dr. Jim Jiao on high-order numerical methods. This work is for testing our software framework of multi-physics coupling in general, *conjugate heat transfer* (CHT) in particular.

¹ Slattery, S. Hamilton, T. Evans, "A Modified Moving Least Square Algorithm for Solution Transfer on a Spacer Grid Surface", ANS MC2015 - Joint International Conference on Mathematics and Computation (M&C), Supercomputing in Nuclear Applications (SNA) and the Monte Carlo (MC) Method, Nashville, Tennessee ⋅ April 19−23, 2015, on CD-ROM, American Nuclear Society, LaGrange Park, IL (2015).

Note: Please be aware that I may not have time to maintain this package.

1.2. About Me 2

CHAPTER

TWO

INSTALLATION

Installing this package is not a trivial task due to the heavy dependencies. ParPyDTK2 has the following installation requirements:

- 1. C++11 compiler
- 2. MPI
- 3. MOAB
- 4. DTK2 and Trilinos
- 5. Python >= 3.5
- 6. mpi4py
- 7. NumPy
- 8. setuptools

And both MOAB and DTK2 have their own dependencies.

In addition, to build the documentation, the following packages are needed:

- 1. Sphinx
- 2. Doxygen
- 3. breathe
- 4. numpydoc

The good news is you can install these easily through pip.

2.1 Install MOAB

The MOAB official README has a very clear description of the installation process. Here we take an excerpt from our MOAB Docker image build:

(continues on next page)

(continued from previous page)

```
F77=mpif77 \
   --enable-optimize \
   --enable-shared=yes \
   --with-blas=-lopenblas \
    --with-lapack=-lopenblas \
    --with-scotch=/usr/lib \
    --with-metis=/usr/lib/x86_64-linux-gnu \
    --with-eigen3=/usr/include/eigen3 \
    --with-x \
   --with-cgns \
   --with-netcdf \
   --with-hdf5=/usr/lib/hdf5-openmpi \
   --with-hdf5-ldflags="-L/usr/lib/hdf5-openmpi/lib" \
   --enable-ahf=yes \
   --enable-tools=ves
$ make && sudo make install
```

Notice that this is for system installation. Install to your preferred locations if you don't have root access. Also, turn off those optional packages if you don't have them, the only MPI and HDF5 are necessary.

```
Warning: You must build it into a shared object!
```

Note: If you use Ubuntu >= 17.10, all these packages are officially supported.

2.2 Install DTK2

DTK2 is shipped as a sub-module of Trilinos, so installing Trilinos is needed. For people who are not familiar with Trilinos, this can be tricky. The following is an excerpt from our DTK2 Docker image build:

```
$ export TRILINOS_VERSION=12-12-1
$ git clone --depth 1 --branch trilinos-release-${TRILINOS_VERSION}
$ cd Trilinos
$ git clone --depth 1 --branch dtk-2.0 \
   https://github.com/unifem/DataTransferKit.git
$ mkdir build && cd build
$ cmake \
   -DCMAKE_INSTALL_PREFIX:PATH=/usr/local \
   -DCMAKE_BUILD_TYPE:STRING=RELEASE \
   -DCMAKE_VERBOSE_MAKEFILE:BOOL=OFF \
    -DCMAKE_SHARED_LIBS:BOOL=ON \
    -DTPL_ENABLE_MPI:BOOL=ON \
   -DTPL ENABLE Boost:BOOL=ON \
   -DBoost_INCLUDE_DIRS:PATH=/usr/include/boost \
   -DTPL_ENABLE_Libmesh:BOOL=OFF \
   -DTPL_ENABLE_MOAB:BOOL=ON \
   -DMOAB_INCLUDE_DIRS=$MOAB_ROOT/include \
   -DMOAB_LIBRARY_DIRS=$MOAB_ROOT/lib \
   -DTPL_ENABLE_Netcdf:BOOL=ON \
   -DTPL_ENABLE_BinUtils:BOOL=OFF \
    -DTrilinos_ENABLE_ALL_OPTIONAL_PACKAGES:BOOL=OFF \
```

(continues on next page)

2.2. Install DTK2 4

(continued from previous page)

```
-DTrilinos_ENABLE_ALL_PACKAGES=OFF \
    -DTrilinos_EXTRA_REPOSITORIES="DataTransferKit" \
    -DTrilinos_ENABLE_EXPLICIT_INSTANTIATION:BOOL=ON \
    -DTrilinos_ASSERT_MISSING_PACKAGES:BOOL=OFF \
    -DTrilinos_ENABLE_TESTS:BOOL=OFF \
    -DTrilinos_ENABLE_EXAMPLES:BOOL=OFF
    -DTrilinos_ENABLE_CXX11:BOOL=ON \
    -DTrilinos_ENABLE_Tpetra:BOOL=ON \
    -DTpetra_INST_INT_UNSIGNED_LONG:BOOL=ON \
   -DTPL_ENABLE_BLAS:BOOL=ON \
   -DTPL_BLAS_LIBRARIES=/usr/lib/x86_64-linux-gnu/libopenblas.so \
   -DTPL_ENABLE_LAPACK:BOOL=ON \
   -DTPL_LAPACK_LIBRARIES=/usr/lib/x86_64-linux-qnu/libopenblas.so
   -DTPL_ENABLE_Eigen:BOOL=ON \
   -DTPL_Eigen_INCLUDE_DIRS=/usr/include/eigen3 \
   -DTrilinos_ENABLE_DataTransferKit=ON \
   -DDataTransferKit_ENABLE_DBC=ON \
    -DDataTransferKit_ENABLE_TESTS=ON \
    -DDataTransferKit_ENABLE_EXAMPLES=OFF \
    -DDataTransferKit_ENABLE_ClangFormat=OFF \
    -DTPL_ENABLE_BoostLib:BOOL=OFF \
    -DBUILD_SHARED_LIBS:BOOL=ON
$ make && sudo make install
```

Again, this assumes root access, adjust this based on your situation. DTK2 needs to lie in the root directory of Trilinos and be turned on through switches DTrilinos_EXTRA_REPOSITORIES and DTrilinos_ENABLE_DataTransferKit. The environment var MOAB_ROOT is where you install MOAB.

Note: We recommend that install DTK2 from our unifem forked repo or my personal forked repo since we may add/modify the source codes to make DTK2 more advanced.

2.3 Install ParPyDTK2

Once you have the dependencies setup, installing ParPyDTK2 can be very easy. The easiest way is through PyPI:

```
$ sudo pip3 install parpydtk2
```

However, this assumes that ParPyDTK2 can find MOAB and DTK2 on the system. Automatically, with different specifications of install command, ParPyDTK2 can add different paths in order to locate MOAB and DTK2.

```
$ pip3 install parpydtk2 --user
```

will assume MOAB and DTK2 can be found in USER_BASE/{include,lib}.

```
$ pip3 install parpydtk2 --prefix=...
```

will allow ParPyDTK2 to search MOAB and DTK2 under the prefix directory.

The preferred way is to define the environment variables PARPYDTK2_MOAB_ROOT and PARPYDTK2_DTK_ROOT before you do pip install. For instance,

```
$ export PARPYDTK2_MOAB_ROOT=/path/to/moab/root
$ export PARPYDTK2_DTK_ROOT=/path/to/dtk/root
$ pip3 install parpydtk2 --user
```

Warning: We don't mark mpi4py as installation dependency, so you need to install it manually before you install ParPyDTK2. pip3 install mpi4py is just fine.

Of course, you can install from source, which can be obtained here. Just make sure you have all Python *dependencies* installed.

```
$ git clone -b parallel https://github.com/chiao45/parpydtk2.git
$ cd parpydtk2
$ python3 setup.py install --user
```

2.4 Using our Docker container

You can try the package through our pre-built Docker container. Two driver scripts are provided in order to easily use the container:

- 1. parpydtk2_desktop.py
- 2. parpydtk2_jupyter.py

The former will launch a desktop environment through VNC, while the latter will run the container as a Jupyter server.

CHAPTER

THREE

SOME DETAILS

3.1 Global IDs/Handles

MOAB uses global IDs in parallel as well as DTK2. Therefore, ParPyDTK2 expects the user to provide this information. For most applications, this can be obtained offline.

The global IDs are unique handles of the vertices in a point cloud. For instance, if you want to distribute two triangles, then each of them has local IDs from 0 to 2, but a unique global ID that ranges from 1 to 4.

Note: ParPyDTK2 uses 1-based indexing for global IDs

3.2 Treatment of Empty Partitions

Both MOAB and DTK2 don't support empty partitions, which occur pretty frequently in practice. For instance, couple a serial solver with a parallel solver, or couple a commercial code with an open-sourced one through socket and the incoming data from the commercial code probably doesn't align with the open-sourced side.

To support empty partitions, we duplicate the first node in the master process to the processes that are empty. However, this is not complete yet, because the user is not aware of this, so that the values between the duplicated nodes are not synchronized. Of course, we don't want to let the user to explicitly handle this extra layer of communication. To resolve this, a member function, called <code>resolve_empty_partitions()</code>, is added to class <code>IMeshDB</code> and must be called **collectively** whenever the user updates the field values.

CHAPTER

FOUR

A DEMO

Here, we show a demo for transferring solutions between two meshes of the unit square. We let the blue mesh participant run in parallel with two cores, while the green side is treated as serial mesh.

```
import numpy as np
from mpi4py import MPI
from parpydtk2 import *

comm = MPI.COMM_WORLD

blue = IMeshDB(comm)
green = IMeshDB(comm)
assert comm.size == 2
rank = comm.rank
```

For demo purpose, we assign the meshes globally.

```
# create blue meshes on all processes
12
   cob = np.empty(shape=(16, 3), dtype=float, order='C')
13
   index = 0
15
  x = 0.0
16
   for i in range(4):
17
      y = 0.0
18
       for j in range (4):
19
           cob[index] = np.asarray([x, y, 0.0])
20
           index += 1
21
           y += dh
22
       x += dh
23
24
   # global IDs, one based
25
  bgids = np.arange(16, dtype='int32')
26
  bgids += 1
```

The blue side has 16 nodes, the following is for the green side:

```
# create green meshes on all processes
29
   cog = np.empty(shape=(36, 3), dtype=float, order='C')
30
   dh = 0.2
31
   index = 0
32
   x = 0.0
33
   for i in range(6):
34
       y = 0.0
35
       for j in range(6):
36
            cog[index] = np.asarray([x, y, 0.0])
```

(continues on next page)

(continued from previous page)

```
index += 1
    y += dh
    x += dh

// ggids = np.arange(36, dtype='int32')
// ggids += 1
```

The green participant has 36 nodes. The next step is to put the data in the two mesh databases.

```
# creating the mesh database
   blue.begin_create()
47
   # local vertices and global IDs
48
   lcob = cob[8 * rank:8 * (rank + 1), :].copy()
49
   lbgids = bgids[8 * rank:8 * (rank + 1)].copy()
   blue.create_vertices(lcob)
52
   blue.assign_gids(lbgids)
   blue.create_field('b')
53
54
   # do not use trivial global ID strategy
55
   blue.finish_create(False)
```

As we can see, we equally distributed the mesh into the two cores as well as the corresponding global IDs. In line 56, the False flag indicates that the mesh database should use the user-provided global Ids.

Warning: Creating vertices and fields, and assigning global IDs must be called within $begin_create()$ and $finish_create()$! Otherwise, exceptions are thrown.

Here is the treatment for the "serial" participant:

```
# NOTE that green is assumed to be serial mesh
green.begin_create()
# only create on master rank
if not rank:
    green.create_vertices(cog)
green.create_field('g')
# since green is serial, we just use the trivial global IDs
green.finish_create() # empty partition is resolve here

assert green.has_empty()
```

As we can see, only the master process has data.

Note: The *duplicated* node is handled inside *finish* create()

With the two participants ready, we can now create our Mapper.

```
# create our analytical model, i.e. 10+sin(x) *cos(y)

bf = 10.0 + np.sin(lcob[:, 0]) * np.cos(lcob[:, 1])

gf = np.sin(cog[:, 0]) * np.cos(cog[:, 1]) + 10.0

# Construct our mapper

mapper = Mapper(blue=blue, green=green)
```

(continues on next page)

(continued from previous page)

```
75
   # using mmls, blue radius 1.0 green radius 0.6
76
   mapper.method = MMLS
77
   mapper.radius_b = 1.0
   mapper.radius_g = 0.6
   mapper.dimension = 2
80
81
   # Mapper initialization region
82
   mapper.begin_initialization()
83
   mapper.register_coupling_fields(bf='b', gf='g', direct=B2G)
   mapper.register_coupling_fields(bf='b', gf='g', direct=G2B)
   mapper.end_initialization()
```

Line 69-70 just create an analytic model for error analysis. Line 77-80 are for parameters, for this case, we use MMLS (default) with blue side radius 1.0 and green side radius 0.6 for searching.

The important part is from line 83 to 86. Particularly speaking, the function $register_coupling_fields()$. It takes three parameters, where the first two are string tokens that represents the data fields in blue and green. The direct is to indicate the transfer direction, e.g. B2G stands for blue to green.

Warning: register_coupling_fields() must be called within begin_initialization() and end_initialization().

```
# NOTE that the following only runs on green master mesh

if not rank:

green.assign_field('g', gf)

# Since green is serial and has empty partition, we must call this to

# resolve asynchronous values

green.resolve_empty_partitions('g')
```

The above section is to assign values on the green participant. Notice that it is a "serial" mesh, so we only assign values on the master process. But resolve the *duplicated* node is needed, this is done in line 93.

Finally, the solution transfer part is pretty straightforward:

```
# solution transfer region
   mapper.begin_transfer()
   mapper.transfer_data(bf='b', qf='q', direct=G2B)
   err b = (bf - blue.extract field('b'))/10
   mapper.transfer_data(bf='b', qf='q', direct=B2G)
   err_g = (gf - green.extract_field('g'))/10
   mapper.end_transfer()
100
   comm.barrier()
102
103
   print(rank, 'blue L2-error=%.3e' % (np.linalg.norm(err_b)/np.sqrt(err_b.size)))
104
   if rank == 0:
105
       print(0, 'green L2-error=%.3e' % (np.linalg.norm(err_g)/np.sqrt(err_g.size)))
```

This code can be obtained here parallel2serial.py.

CHAPTER

FIVE

API

5.1 ParPyDTK2 Python API

Get the abs include path

5.1.1 Default

```
Main module interface of ParPyDTK2
parpydtk2.B2G
     bool – boolean flag of True denotes transferring direction from blue to green
parpydtk2.G2B
     bool – boolean flag of False denotes transferring direction from green to blue
parpydtk2.MMLS
     int – flag (0) represents using modified moving least square method
parpydtk2.SPLINE
     int – flag (1) represents using spline interpolation method
parpydtk2.N2N
     int – flag (2) represents using nearest node projection method
parpydtk2.WENDLAND2
     int – flag (0) represents using Wendland 2nd-order RBF weights
parpydtk2.WENDLAND4
     int - flag (1) represents using Wendland 4th-order RBF weights
parpydtk2.WENDLAND6
     int - flag (2) represents using Wendland 6th-order RBF weights
parpydtk2.WU2
     int – flag (3) represents using Wu 2nd-order RBF weights
parpydtk2.WU4
     int – flag (4) represents using Wu 4th-order RBF weights
parpydtk2.WU6
     int – flag (5) represents using Wu 6th-order RBF weights
parpydtk2.BUHMANN3
     int - flag (6) represents using Buhmann 3rd-order RBF weights
parpydtk2.get_include()
```

5.1.2 Error Handling

The error handler module

```
parpydtk2.error_handle.ERROR_CODE

int – set this to nonzero values one exceptions have been raised
```

Examples

```
>>> import parpydtk2 as dtk
>>> try:
...  # your programs here
... except Expection:
...  dtk.error.ERROR_CODE = 1
... raise
```

5.1.3 Interface Mesh & Mapper

```
class parpydtk2.IMeshDB(comm=None)
    Interface mesh database
```

ParPyDTK2 utilizes MOAB as the underlying mesh database. MOAB is an array based mesh library that is adapted by DTK2. With array based mesh library, the memory usage and computational cost are lower than typical pointer based data structure. The mesh concept in this work is simple since only meshless methods are ultilized, the only additional attribute one needs is the *global IDs/handles*, which are used by both MOAB and DTK2. For most applications, the global IDs can be computed offline.

One thing is not directly supported by IMeshDB is I/O. However, since this is a Python module and only points clouds are needed, one can easily uses a tool (e.g. meshio) to load the mesh.

```
comm
```

MPI.Comm – MPI communicator

ranks

int – size of comm

rank

int - rank of comm

size

int – point cloud size, i.e. number of vertices

bbox

np.ndarray – local bounding box array of shape (2,3)

gbbox

np.ndarray – global bounding box array of shape (2,3)

Constructor

Parameters comm (MPI. Comm (optional)) - if no communicator or None is passed in, then MPI_COMM_WORLD will be used

Examples

```
>>> # implicit communciator
>>> import parpydtk2 as dtk
>>> mdb = dtk.IMeshDB()
```

```
>>> # explicit communicator
>>> from mpi4py import MPI
>>> import parpydtk2 as dtk
>>> mdb = dtk.IMeshDB(MPI.COMM_WOLRD)
```

assign_field(self, unicode field_name, ndarray values)

Assign values to a field

Note: values size must be at least size*dim

Parameters

- **field_name** (str) name of the field
- values (np.ndarray) input source values

See also:

```
extract_field() extract value from a field
size check the size of a mesh set
```

```
assign_gids (self, __Pyx_memviewslice gids)
    Assign global IDs
```

Internally, both DTK and MOAB use so-called global IDs/handles communications. Each node has its own local IDs/handles and a unique global ID.

Parameters gids (np.ndarray) - global IDs

See also:

```
create_vertices() create vertices
extract_gids() extract global IDs
```

bbox

np.ndarray – local bounding box

The bounding box is stored simply in a 2x3 array, where the first row stores the maximum bounds while minimum bounds for the second row.

```
Warning: Bounding box is valid only after finish_create().
```

See also:

gbbox global bounding box

begin_create(self)

Begin to create/manupilate the mesh

This function must be called in order to let the mesh databse be aware that you will create meshes.

See also:

```
finish create() finish creating mesh
```

comm

MPI.Comm - communicator

```
create_field (self, unicode field_name, int dim=1)
```

Create a data field for solution transfer

This is the core function to register a field so that you can then transfer its values to other domains. The dim parameter determines the data type of the field. By default, it's 1, i.e. scalar fields. For each node, a tensor of (1x''dim'') can be registered. For instance, to transfer forces and displacements in FSI applications, dim is 3 (for 3D problems).

Parameters

- **field_name** (str) name of the field
- dim (int) dimension of the field, i.e. scalar, vector, tensor

Examples

```
>>> from parpydtk2 import *
>>> mdb1 = IMeshDB()
>>> mdb1.begin_create()
>>> mdb1.create_field('heat flux')
```

create_vertices (self, __Pyx_memviewslice coords)

Create a set of coordinates

Note: The coords must be C-ordering with ndim=2!

Parameters coords (np.ndarray) - nx3 coordinates in double precision

See also:

```
assign_gids() assign global IDs
extract_vertices() extract vertex coordinates
```

Examples

```
>>> from parpydtk2 import *
>>> import numpy as np
>>> mdb1 = IMeshDB()
>>> mdb1.begin_create()
>>> verts = np.zeros((2,3)) # two nodes
```

(continues on next page)

(continued from previous page)

```
>>> verts[1][0] = 1.0
>>> mdb1.create_vertices(verts)
```

empty (self)

Check if this is an empty partition

extract_field(self, unicode field_name, __Pyx_memviewslice buffer=None, reshape=False)
Extact the values from a field

Warning: if buffer is passed in, it must be 1D

Parameters

- **field_name** (str) name of the field
- buffer (np.ndarray) 1D buffer
- **reshape** (bool) *True* if we reshape the output, only for vectors/tensors

Returns field data values

Return type np.ndarray

extract_gids (self)

Extract global IDs/handles

Warning: This function should be called once you have finished assign_gids().

Returns array of size that stores the integer IDs

Return type np.ndarray

extract_vertices(self)

Extract coordinate

Warning: This function should be called once you have finished <code>create_vertices()</code>.

Returns (nx3) array that stores the coordinate values

Return type np.ndarray

See also:

size get the mesh size

field_dim(self, unicode field_name)

Check the field data dimension

Parameters field_name (str) – name of the field

Returns data field dimension of *field_name*

Return type int

finish_create (self, trivial_gid=True)

finish mesh creation

This method finalizes the interface mesh database by communicating the bounding boxes and empty partitions. Also, setting up the DTK managers happens here.

Warning: You must call this function once you have done with manupilating the mesh, i.e. vertices and global IDs.

Parameters trivial_gid (bool) - True if we use MOAB trivial global ID computation

Notes

By trivial_gid, it means simply assigning the global IDs based on the size of the mesh. This is useful in serial settings or transferring solutions from a serial solver to a partitioned one.

gbbox

np.ndarray – global bounding box

The bounding box is stored simply in a 2x3 array, where the first row stores the maximum bounds while minimum bounds for the second row.

Warning: Bounding box is valid only after finish_create().

See also:

bbox local bounding box

$has_empty(self)$

Check if an empty partition exists

has_field(self, unicode field_name)

Check if a field exists

Parameters field_name (str) – name of the field

Returns *True* if this meshdb has *field_name*

Return type bool

rank

int – get the rank

ranks

int - Get the communicator size

resolve_empty_partitions (self, unicode field_name)

Resolve asynchronous values on empty partitions

ParPyDTK2 doesn't expect <code>assign_field()</code> should be called collectively. Therefore, a collective call must be made for resolving empty partitions.

Warning: This must be called collectively even on empty partitions

Note: You should call this function following assignment

Parameters field_name (str) - name of the field

Examples

```
>>> if rank == 0:
...    mdb.assign_field('flux', values)
>>> mdb.resolve_empty_partitions('flux')
```

Notes

This API is not available in C++ level, therefore, one needs to implement this if he/she wants to use the C++ API.

size

int – Get the size of a set

The meshless methods in DTK2, including *modified moving least square*, *spline interpolation* and *nearest node projection* methods are wrapped within this class. The most advanced method is the MMLS fitting, which is my personal recommendataion.

blue_mesh

IMeshDB – blue mesh participant

green_mesh

IMeshDB - green mesh participant

comm

MPI.Comm - MPI communicator

ranks

int – size of comm

rank

int - rank of comm

dimension

int – spatial dimension

method

int - method flag, either MMLS, SPLINE, or N2N

basis

int - flag of basis function for weighting schemes used by MMLS and SPLINE

knn b

int - k-nearest neighborhood for searching on blue_mesh

knn_g

int - k-nearest neighborhood for searching on green_mesh

radius b

float – radius used for searching on blue_mesh

radius_g

float – radius used for searching on green_mesh

Constructor

Parameters

- blue_mesh (IMeshDB) blue mesh participant
- green_mesh (IMeshDB) green mesh participant
- profiling (bool (optional)) whether or not do timing report, default is True.

Examples

```
>>> from parpydtk2 import *
>>> blue, green = IMeshDB(), IMeshDB()
>>> # initialize blue and green
>>> mapper = Mapper(blue=blue,green=green)
>>> # do work with mapper
```

basis

int – Get the basis function flag

See also:

method get the method tag

begin_initialization(self)

Initialization starter

This is a must-call function in order to indicate mapper that you are about to initialize/register coupling fields

See also:

```
register_coupling_fields() register coupled fields
end_initialization() finish initialization
```

begin_transfer(self)

Transfer starter

This is a must-call function to inidate the beginning of a transferring block

See also:

```
end_transfer() transfer closer
```

tranfer_data() transfer a coupled data fields

blue mesh

IMeshDB - blue mesh

comm

MPI.Comm – Get the communicator

See also:

```
ranks get the total communicator size
     rank "my" rank
dimension
     int – Get the problem dimension
     Note: this is the spacial dimension
end_initialization(self)
     Initialization closer
     This is a must-call function in order to tell the mapper we are ready
     See also:
     begin_initialization() initialization starter
end transfer(self)
     Transfer closer
     This is a must-call function to indicate we have finished a sequence of transferring requests
     See also:
     begin_transfer() transfer starter
green_mesh
     IMeshDB - green mesh
has_coupling_fields (self, unicode bf, unicode gf, bool direct)
     Check if a coupled fields exists
         Returns True if (bf,gf) exists in the direct direction
         Return type bool
knn_b
     int - KNN of blue mesh
     Note: if blue does not use KNN, then -1 returned
     See also:
     knn_g green knn
knn_g
     int - KNN of green mesh
     Note: if green does not use KNN, then -1 returned
     See also:
     knn b blue knn
```

method

int – Get the method tag

See also:

basis the basis function and order attribute

radius b

float – physical domain radius support for blue mesh

Note: if blue does not use RBF-search, then -1.0 returned

See also:

radius_g green radius

radius_g

float – physical domain radius support for green mesh

Note: if green does not use RBF-search, then -1.0 returned

See also:

radius_b blue radius

rank

int - Check "my" rank

See also:

ranks get the total communicator size

comm MPI communicator

ranks

int - Check the total process number

See also:

rank "my" rank

register_coupling_fields (self, unicode bf, unicode gf, bool direct)

register a coupled fields

Note: we use boolean to indicate direction

Parameters

- **bf** (str) blue mesh field name
- **gf** (str) green mesh field name
- **direct** (bool) *True* for blue->green, *False* for the opposite

See also:

transfer_data() transfer a coupled data fields

set_matching_flag_n2n (self, bool matching)

Set the matching flag for N2N

Note: this function will not throw even if you dont use n2n

Parameters matching (bool) – *True* if the interfaces are matching

transfer_data (self, unicode bf, unicode gf, bool direct)

Transfer (bf, gf) in the direct direction

Parameters

- **bf** (str) blue mesh field name
- **gf** (str) green mesh field name
- direct (bool) True for blue->green, False for the opposite

See also:

register_coupling_fields() register coupled fields

5.2 ParPyDTK2 C++ API

5.2.1 Common Definitions

group common

Defines

```
handle_moab_error (__ret)
    macro to handle moab error

throw_error (__msg)
    throw runtime_error exception

throw_error_if (__cond, __msg)
    conditionally error throw

throw_noimpl (__what)
    throw not implemented feature error

throw_noimpl_if (__cond, __what)
    throw not implemented feature error with condition

show_warning (__msg)
    log warning message in stderr

show_warning_if (__cond, __msg)
```

log warning with condition

```
show_experimental(__msg)
          log experimental warning in stderr
     show_experimental_if(__cond, __msg)
          log experimental warning in stderr with condition
     show_info(__msg, __rank)
          show information in parallel
     show_info_master(__msg, __rank)
          show information only on master rank
     streamer(__rank)
          streaming message with specific rank
     streamer_master(__rank)
          streaming messages only on the master process
     Typedefs
     typedef entity_t
          MOAB entity handle.
     Enums
     enum [anonymous]
          root set
          Values:
          root set = 0
5.2.2 Field Variables
class FieldData
     a representation of MOAB tag for field data
     Public Functions
     FieldData (moab::Core &mdb, const std::string &field_name, int dim = 1)
          constructor with moab instance
          Note set is not the same as mesh set in MOAB
          Parameters
                • mdb: moab instance
                • field_name: field name
                • dim: field dimension
     void assign (const moab::Range &range, const double *values)
          assign values
```

Parameters

- range: entity ranges, for this work, it should be vertices
- values: data values, for vector/tensor, C order is expected

void assign_1st (const moab::Range & range, const double *values) assign to first node

This function is used by Python for handling empty partitions

Parameters

- range: entity ranges
- values: values for the first node, at least size of dim

void extract (const moab::Range &range, double *values) const
extract values

Parameters

- range: entity ranges, for this work, it should be vertices
- values: data values, for vector/tensor, C order is expected

void extract_1st (const moab::Range &range, double *values) const
extract the value from the first node

Parameters

- range: entity ranges
- values: values for the first node, at least size of dim

```
operator const std::string&() const
```

brief implicitly cast to string

```
int dim() const
```

check the dimension

```
int set () const
```

check the set ID

```
const moab::Tag &tag() const
  get MOAB tag
```

Protected Attributes

```
moab::Core &mdb_
reference to moab instance
std::string fn_
field name
int set_
set count
```

```
int dim
          field dimension
     moab::Tag tag_
          moab tag
class FieldDataSet
     a set of field data
     Public Types
     typedef base_t::iterator iterator
          interator type
     typedef base_t::const_iterator const_iterator
          constant iterator
     Public Functions
     virtual ~FieldDataSet()
          destructor
     bool has_field(const std::string &fn) const
          check if a field exist
          Parameters
                • fn: field name
     void create (moab::Core &mdb, const std::string &field_name, int dim = 1)
          create an data field
          Note set is not the same as mesh set in MOAB
          Parameters
                • mdb: moab data base
                • field name: field name
                • dim: field dimension
     FieldData &operator[] (const std::string &fn)
          get a reference to a field data
          Note this overloads the base operator[]
          Parameters
                • fn: field name
     const FieldData &operator[] (const std::string &fn) const
          get a const reference to a field data
          Parameters
```

5.2. ParPyDTK2 C++ API

• fn: field name

```
iterator begin()
          get the first iterator
     iterator end()
          get the end iterator
     const_iterator begin() const
          get the constant iterator
     const_iterator end() const
          get the constant end iterator
     const_iterator cbegin() const
          get the constant iterator
     const_iterator cend() const
          get the constant end iterator
     Protected Attributes
     base tfs
          fields
     Private Types
     typedef std::unordered_map<std::string, FieldData *> base_t
          data structure
5.2.3 Interface Mesh Database
class IMeshDB
     interface mesh database, build on top of MOAB
     imesh_py_interface
     void begin_create()
          begin to create mesh
     void create_vset()
          create a new vertex set
     void create_vertices (int nv, const double *coords)
          create vertices
          Parameters
                • nv: number of vertices
                • coords: coords values
     void extract_vertices (double *coords) const
          extract assigned coordinates
```

Note coords must be at least n*3 where n is the size of the mesh

Parameters

• coords: coordinates

```
void assign_gids (int nv, const int *gids) assign global IDs
```

Note gids should be one-based indices

Parameters

- nv: number of local vertices
- gids: global IDs

void extract_gids (int *gids) const

extract global IDs

Parameters

• gids: global IDs

```
void finish_create (bool trivial_gid = true)
```

finish manupilating the mesh

NOTE that if your input mesh is element-based partition and the vertices you create are mesh nodes, then you have to specify the correct global IDs in parallel. However, if the coordinates are face centres, then the global IDs can be trivially computed by MOAB since there are no shared entities cross different processes.

Parameters

• trivial_gid: true if we let MOAB to compute the GID

bool empty() const

check if empty partition

bool has_empty() const

check if any of the process has an empty partition

```
const std::vector<int> &_m2s() const
get a reference to the m2s pattern
```

Note This is used in Python level as "private" thus having ""

```
int size() const
```

check mesh size

void get_bbox (double *v) const

get bounding box

Parameters

• v: values

$void \ \mathbf{get_gbbox}\ (double\ ^*v)\ \mathbf{const}$

get global bounding box

Parameters

• v: values

```
void create_field (const std::string &field_name, int dim = 1)
    create a field
```

Parameters

- field name: field name
- dim: field dimension

bool has_field(const std::string &field_name) const

check if we have a field

Parameters

• field_name: field name

int field_dim(const std::string &field_name) const

check field dimension

Parameters

• field name: field name

void assign_field(const std::string &field_name, const double *values)

assign a value to a field

Parameters

- field_name: field name
- values: field data values

void _assign_1st (const std::string &field_name, const double *values) assign to the first node

This function is used by Python to resolve the issues when empty empty partitions happen. Therefore, this function has an "_" prefix to indicate "private" usage!

Parameters

- field name: field name
- values: field data values, at least size of field dimension

void extract_field(const std::string &field_name, double *values) const
extract value

Parameters

• field_name: field name

• values: field data values

```
void _extract_1st (const std::string &field_name, double *values) const
extract first value
```

This function is used by Python to resolve the issues when empty empty partitions happen. Therefore, this function has an "_" prefix to indicate "private" usage!

Parameters

field_name: field namevalues: field data values

Public Functions

```
IMeshDB (MPI_Comm comm = MPI_COMM_WORLD) constructor with communicator
```

Parameters

• comm: communicator

```
int ranks() const
    get total ranks

int rank() const
    get my rank

MPI_Comm comm() const
    get the communicator

Teuchos::RCP<moab::ParallelComm> pcomm() const
    get mesh

std::vector<DataTransferKit::MoabManager> &mangers()
    get the manger

void set_dimension(int dim)
    set geometry dimension

Parameters
    • dim: dimension
```

```
bool ready() const
     check if ready

dtk_field_t &dtk_fields()
     get the dtk fields
```

Protected Types

typedef std::unordered_map<std::string, std::pair<int, Teuchos::RCP<Tpetra::MultiVector<double, int, DataTransferKit::Suphandy typedef

Protected Attributes

```
moab::Core mdb_
     moab instance
Teuchos::RCP<moab::ParallelComm> par_
     moab parallel interface
std::vector<entity_t> vsets_
     vertex sets
std::vector<moab::Range>locals_
     local vertex range
std::vector<std::array<double, 6>> bboxes_
     bounding boxes
std::vector<std::array<double, 6>> gbboxes_
     global bounding boxes
FieldDataSet fields_
     field data set
bool created_
     flag to indicate whether users are done with creating mesh
moab::Tag gidtag_
     global ID tag
moab::Tag parttag_
     partition tag
bool usergid_
     flag to indicate if we have user computed global ID
std::vector<DataTransferKit::MoabManager> mngrs_
     DTK MOAB manager.
dtk_field_t dtkfields_
     DTK multi vector for MOAB tags.
bool empty_
     check empty partition
bool has_empty_
     check if any process is empty
std::vector<int> m2s_
     comm pattern for master2slaves for handling empty partitions
Private Functions
void init_ (bool del = false)
     helper for clean up mesh
```

Parameters

• del: whether or not delete mesh

```
void reset_vecs_()
          handle all vectors
     void init\_bbox\_(int i = -1)
          initialize empty bounding boxes
          Parameters
                • i: index if < 0 then init all
     void cmpt_bboxes_()
          compute all bounding box
5.2.4 Solution Mapper
class Mapper
     the mapper interface for interface solution transfer
     mapper_py_interface
     int ranks () const
          get the ranks
     int rank() const
          get my rank
     MPI_Comm comm() const
          get the communicator
     void set_dimension (int dim)
          set dimension
          Parameters
                • dim: geometry dimension
     void use_mmls()
          use moving least square, this is the default method
          See use_spline, use_n2n
     void use_spline()
          use spline interpolation method
          See use_mmls, use_n2n
     void use_n2n (bool matching = false)
          use node 2 node project
          See use_mmls, use_spline
          Parameters
```

• matching: are the interfaces mathing?

```
void set basis (int basis)
     set basis function, default is Wendland 4th order
     See BasisFunctions
     Parameters
           • basis: basis function and order
void use_knn_b (int knn)
    use knn for blue mesh
    Parameters
           • knn: number of nearest neighbors
void use_knn_g (int knn)
    use knn for green mesh
    Parameters
           • knn: number of nearest neighbors
void use_radius_b (double r)
    use radius for blue
    See use knn
    Parameters
           • r: physical domain radius support
void use\_radius\_g (double r)
    use radius for green
    See use_knn
     Parameters
           • r: physical domain radius support
int check_method() const
    check method
int check_basis() const
    check basis
int knn b() const
    check blue knn
    Note if blue does not use knn, then negative value returned
int knn_g() const
    check green knn
double radius_b() const
    check blue radius
```

Note if blue does not use radius, then -1.0 is returned

```
double radius q() const
    check green radius
int dimension() const
     get the dimension
std::shared_ptr</br>std::shared_ptrIMeshDB blue_mesh() const
     get blue mesh
std::shared_ptr</ri>
     get green mesh
void begin_initialization()
    begin initialization
void register_coupling_fields (const std::string &bf, const std::string &gf, bool direct)
     register coupling fields
     Parameters
           • bf: blue meshdb field data
           • gf: green meshdb field data
           • direct: true for b->g, false for g->b
bool has_coupling_fields (const std::string &bf, const std::string &gf, bool direct)
     check if a coupling data fields exists
     Parameters
           • bf: blue meshdb field data
           • qf: green meshdb field data
           • direct: true for b->g, false for g->b
void end initialization()
    end initialization
void begin_transfer()
     begin to transfer data
void transfer_data (const std::string &bf, const std::string &gf, bool direct)
     transfer data
     Parameters
           • bf: blue meshdb field data
           • qf: green meshdb field data
           • direct: true for b->g, false for g->b
void end_transfer()
```

end transfer

Public Functions

Parameters

- B: input blue mesh
- G: input green mesh
- version: passed from Python inteface
- date: passed from Python interface
- profiling: whether do simple profiling, i.e. wtime

Protected Attributes

```
std::shared ptr<IMeshDB> B
     blue mesh
std::shared_ptr<IMeshDB> G_
     green mesh
int dim
     dimension
bool ready
     flag to indicate the mapper is ready for transfering
bool profiling_
     whether do simple profiling
double timer_
     a simple timer buffer
std::unique_ptr<Teuchos::ParameterList> opts_[2]
     parameter list
std::map<std::pair<std::string, std::string>, Teuchos::RCP<DataTransferKit::MapOperator>> operators_[2]
     transfer operators
```

Protected Static Attributes

```
DataTransferKit::MapOperatorFactory factory_ map factory
```

Private Functions

```
void init_parlist_()
    initialize parameter list

template <bool _Dir, typename _V>
void set_search (const std::string &type, const std::string &value, const _V &v)
    helper for set local search
```

Template Parameters

- _Dir: direction
- _V: value type

Parameters

- type: search type
- value: tag for value
- v: actual value

```
template <bool _Dir, typename _V>
_V get_search (const std::string &type, const std::string &value, const _V &dft) const
helper for get search info
```

Template Parameters

- _Dir: direction
- _V: value type

Parameters

- type: search type
- value: tag for value
- dft: default value

Private Static Functions

```
static std::string parse_list_ (Teuchos::ParameterList &list)
parse and formatting a parameter list
```

Parameters

• list: parameter list

CHAPTER

SIX

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

р

parpydtk2,11 parpydtk2.error_handle,12

INDEX

A assign_field() (parpydtk2.IMeshDB method), 13	get_include() (in module parpydtk2), 11 green_mesh (parpydtk2.Mapper attribute), 17, 19
assign_gids() (parpydtk2.IMeshDB method), 13	Н
B2G (in module parpydtk2), 11 basis (parpydtk2.Mapper attribute), 17, 18 bbox (parpydtk2.IMeshDB attribute), 12, 13 begin_create() (parpydtk2.IMeshDB method), 13 begin_initialization() (parpydtk2.Mapper method), 18 begin_transfer() (parpydtk2.Mapper method), 18 blue_mesh (parpydtk2.Mapper attribute), 17, 18 BUHMANN3 (in module parpydtk2), 11	handle_moab_error (C macro), 21 has_coupling_fields() (parpydtk2.Mapper method), 19 has_empty() (parpydtk2.IMeshDB method), 16 has_field() (parpydtk2.IMeshDB method), 16 IMeshDB (class in parpydtk2), 12
С	knn_b (parpydtk2.Mapper attribute), 17, 19 knn_g (parpydtk2.Mapper attribute), 17, 19
comm (parpydtk2.IMeshDB attribute), 12, 14 comm (parpydtk2.Mapper attribute), 17, 18 common::anonymous0 (C++ type), 22 common::root_set (C++ enumerator), 22 create_field() (parpydtk2.IMeshDB method), 14 create_vertices() (parpydtk2.IMeshDB method), 14	M Mapper (class in parpydtk2), 17 method (parpydtk2.Mapper attribute), 17, 19 MMLS (in module parpydtk2), 11
D	NON (in second language Max), 11
dimension (parpydtk2.Mapper attribute), 17, 19	N2N (in module parpydtk2), 11 P
empty() (parpydtk2.IMeshDB method), 15 end_initialization() (parpydtk2.Mapper method), 19 end_transfer() (parpydtk2.Mapper method), 19 ERROR_CODE (in module parpydtk2.error_handle), 12 extract_field() (parpydtk2.IMeshDB method), 15 extract_gids() (parpydtk2.IMeshDB method), 15 extract_vertices() (parpydtk2.IMeshDB method), 15	parpydtk2 (module), 11 parpydtk2::error_handle (module), 12 parpydtk2::entity_t (C++ type), 22 parpydtk2::FieldData (C++ class), 22 parpydtk2::FieldData::assign (C++ function), 22 parpydtk2::FieldData::assign_1st (C++ function), 23 parpydtk2::FieldData::dim (C++ function), 23 parpydtk2::FieldData::dim_(C++ member), 23 parpydtk2::FieldData::extract (C++ function), 23 parpydtk2::FieldData::extract (C++ function), 23
field_dim() (parpydtk2.IMeshDB method), 15	parpydtk2::FieldData::FieldData (C++ function), 22
finish_create() (parpydtk2.IMeshDB method), 15	parpydtk2::FieldData::fn_ (C++ member), 23 parpydtk2::FieldData::mdb_ (C++ member), 23
G	parpydtk2::FieldData::mdo_ (C++ member), 23 parpydtk2::FieldData::operator const std::string& (C++
G2B (in module parpydtk2), 11 gbbox (parpydtk2.IMeshDB attribute), 12, 16	function), 23 parpydtk2::FieldData::set (C++ function), 23

parpydtk2::FieldData::set_ (C++ member), 23	parpydtk2::IMeshDB::m2s_(C++ member), 29
parpydtk2::FieldData::tag (C++ function), 23	parpydtk2::IMeshDB::mangers (C++ function), 28
parpydtk2::FieldData::tag_ (C++ member), 24	parpydtk2::IMeshDB::mdb_ (C++ member), 29
parpydtk2::FieldDataSet (C++ class), 24	parpydtk2::IMeshDB::mngrs_ (C++ member), 29
parpydtk2::FieldDataSet::~FieldDataSet (C++ function),	parpydtk2::IMeshDB::par_ (C++ member), 29
24	parpydtk2::IMeshDB::parttag_(C++ member), 29
parpydtk2::FieldDataSet::base_t (C++ type), 25	parpydtk2::IMeshDB::pcomm (C++ function), 28
parpydtk2::FieldDataSet::begin (C++ function), 25	parpydtk2::IMeshDB::rank (C++ function), 28
parpydtk2::FieldDataSet::cbegin (C++ function), 25	parpydtk2::IMeshDB::ranks (C++ function), 28
parpydtk2::FieldDataSet::cend (C++ function), 25	parpydtk2::IMeshDB::ready (C++ function), 28
parpydtk2::FieldDataSet::const_iterator (C++ type), 24	parpydtk2::IMeshDB::reset_vecs_ (C++ function), 29
parpydtk2::FieldDataSet::create (C++ function), 24	parpydtk2::IMeshDB::set_dimension (C++ function), 28
parpydtk2::FieldDataSet::end (C++ function), 25	parpydtk2::IMeshDB::size (C++ function), 26
parpydtk2::FieldDataSet::fs_ (C++ member), 25	parpydtk2::IMeshDB::usergid_ (C++ member), 29
parpydtk2::FieldDataSet::has_field (C++ function), 24	parpydtk2::IMeshDB::vsets_ (C++ member), 29
parpydtk2::FieldDataSet::iterator (C++ type), 24	parpydtk2::Mapper (C++ class), 30
parpydtk2::FieldDataSet::operator[] (C++ function), 24	parpydtk2::Mapper::B_ (C++ member), 33
parpydtk2::IMeshDB (C++ class), 25	parpydtk2::Mapper::begin_initialization (C++ function),
parpydtk2::IMeshDB::_assign_1st (C++ function), 27	32
parpydtk2::IMeshDB::_extract_1st (C++ function), 27	parpydtk2::Mapper::begin_transfer (C++ function), 32
parpydtk2::IMeshDB::_m2s (C++ function), 26	parpydtk2::Mapper::blue_mesh (C++ function), 32
parpydtk2::IMeshDB::assign_field (C++ function), 27	parpydtk2::Mapper::check_basis (C++ function), 31
parpydtk2::IMeshDB::assign_gids (C++ function), 26	parpydtk2::Mapper::check_method (C++ function), 31
parpydtk2::IMeshDB::bboxes_ (C++ member), 29	parpydtk2::Mapper::comm (C++ function), 30
parpydtk2::IMeshDB::begin_create (C++ function), 25	parpydtk2::Mapper::dim_ (C++ member), 33
parpydtk2::IMeshDB::cmpt_bboxes_ (C++ function), 30	parpydtk2::Mapper::dimension (C++ function), 32
parpydtk2::IMeshDB::comm (C++ function), 28	parpydtk2::Mapper::end_initialization (C++ function), 32
parpydtk2::IMeshDB::create_field (C++ function), 27	parpydtk2::Mapper::end_transfer (C++ function), 32
parpydtk2::IMeshDB::create_vertices (C++ function), 25	parpydtk2::Mapper::factory_ (C++ member), 33
parpydtk2::IMeshDB::create_vset (C++ function), 25	parpydtk2::Mapper::G_ (C++ member), 33
parpydtk2::IMeshDB::created_ (C++ member), 29	parpydtk2::Mapper::get_search (C++ function), 34
parpydtk2::IMeshDB::dtk_field_t (C++ type), 28	parpydtk2::Mapper::green_mesh (C++ function), 32
parpydtk2::IMeshDB::dtk_fields (C++ function), 28	parpydtk2::Mapper::has_coupling_fields (C++ function),
parpydtk2::IMeshDB::dtkfields_(C++ member), 29	32
parpydtk2::IMeshDB::empty (C++ function), 26	parpydtk2::Mapper::init_parlist_ (C++ function), 33
parpydtk2::IMeshDB::empty_(C++ member), 29	parpydtk2::Mapper::knn_b (C++ function), 31
parpydtk2::IMeshDB::extract_field (C++ function), 27	parpydtk2::Mapper::knn_g (C++ function), 31
parpydtk2::IMeshDB::extract_gids (C++ function), 26	parpydtk2::Mapper::Mapper (C++ function), 33
parpydtk2::IMeshDB::extract_vertices (C++ function),	parpydtk2::Mapper::operators_ (C++ member), 33
25	parpydtk2::Mapper::opts_ (C++ member), 33
parpydtk2::IMeshDB::field_dim (C++ function), 27	parpydtk2::Mapper::parse_list_ (C++ function), 34
parpydtk2::IMeshDB::fields_(C++ member), 29	parpydtk2::Mapper::profiling_ (C++ member), 33
parpydtk2::IMeshDB::finish_create (C++ function), 26	parpydtk2::Mapper::radius_b (C++ function), 31
parpydtk2::IMeshDB::gbboxes_ (C++ member), 29	parpydtk2::Mapper::radius_g (C++ function), 32
parpydtk2::IMeshDB::get_bbox (C++ function), 26	parpydtk2::Mapper::rank (C++ function), 30
parpydtk2::IMeshDB::get_gbbox (C++ function), 26	parpydtk2::Mapper::ranks (C++ function), 30
parpydtk2::IMeshDB::gidtag_(C++ member), 29	parpydtk2::Mapper::ready_ (C++ member), 33
parpydtk2::IMeshDB::has_empty (C++ function), 26	parpydtk2::Mapper::register_coupling_fields (C++ func-
parpydtk2::IMeshDB::has_empty_ (C++ member), 29	tion), 32
parpydtk2::IMeshDB::has_field (C++ function), 27	parpydtk2::Mapper::set_basis (C++ function), 31
parpydtk2::IMeshDB::IMeshDB (C++ function), 28	parpydtk2::Mapper::set_dimension (C++ function), 30
parpydtk2::IMeshDB::init_ (C++ function), 29	parpydtk2::Mapper::set_search (C++ function), 33
parpydtk2::IMeshDB::init_bbox_ (C++ function), 30	parpydtk2::Mapper::timer_ (C++ member), 33
parpydtk2::IMeshDB::locals (C++ member), 29	parpydtk2::Mapper::transfer data (C++ function), 32

Index 38

```
parpydtk2::Mapper::use knn b (C++ function), 31
parpydtk2::Mapper::use_knn_g (C++ function), 31
parpydtk2::Mapper::use mmls (C++ function), 30
parpydtk2::Mapper::use_n2n (C++ function), 30
parpydtk2::Mapper::use radius b (C++ function), 31
parpydtk2::Mapper::use radius g (C++ function), 31
parpydtk2::Mapper::use spline (C++ function), 30
R
radius b (parpydtk2.Mapper attribute), 17, 20
radius g (parpydtk2.Mapper attribute), 18, 20
rank (parpydtk2.IMeshDB attribute), 12, 16
rank (parpydtk2.Mapper attribute), 17, 20
ranks (parpydtk2.IMeshDB attribute), 12, 16
ranks (parpydtk2.Mapper attribute), 17, 20
register_coupling_fields() (parpydtk2.Mapper method),
resolve_empty_partitions()
                                 (parpydtk2.IMeshDB
         method), 16
S
set_matching_flag_n2n() (parpydtk2.Mapper method), 21
show experimental (C macro), 21
show_experimental_if (C macro), 22
show info (C macro), 22
show info master (C macro), 22
show_warning (C macro), 21
show_warning_if (C macro), 21
size (parpydtk2.IMeshDB attribute), 12, 17
SPLINE (in module parpydtk2), 11
streamer (C macro), 22
streamer_master (C macro), 22
Т
throw_error (C macro), 21
throw_error_if (C macro), 21
throw_noimpl (C macro), 21
throw_noimpl_if (C macro), 21
transfer_data() (parpydtk2.Mapper method), 21
W
WENDLAND2 (in module parpydtk2), 11
WENDLAND4 (in module parpydtk2), 11
WENDLAND6 (in module parpydtk2), 11
WU2 (in module parpydtk2), 11
WU4 (in module parpydtk2), 11
WU6 (in module parpydtk2), 11
```

Index 39