IP sample processing

This document describes processing of eluted IP samples.

Quick links

- Reagents and materials
- Solution recipes
- Protocol
- Notes

Reagents and materials

- 1M HEPES pH 7.3 (Thermo Scientific, CAT#BP299)
- Dithiothreitol (Bio-Rad, CAT#1610611)
- Ethanol, absolute (whatever vendor sells this to your lab)
- SP3 beads (Thermo Scientific, CAT#65152105050250, CAT#45152105050250) (see **Note 1**)
- LysargiNase (Millipore, CAT#EMS0008)
- 1.5mL or 2.0mL Safe-Lock tubes (Fisher Scientific, CAT#05-402-25 or CAT#05-402-7)
- Thermomixer capable of holding 1.5mL or 2.0mL tubes
- Benchtop centrifuge (capable of holding 1.5mL or 2mL microfuge tubes)
- Magnetic rack for 1.5mL or 2.0mL tubes (I like this rack: Promega, CAT#Z5342)

Solution recipes

- 100mM HEPES, pH 7.3 (100uL of 1M stock combined with 900uL of water)
- 0.2M of dithiothreitol (DTT) 15mg in 500uL of 1M HEPES, pH 7.3, prepare fresh and keep on ice
- 80% (v/v) ethanol (prepare fresh)

Protocol

- 1. Adjust the volume of the IP elution samples to 90uL in a fresh 2mL tube using 100mM HEPES pH 7.3.
- 2. Add 10uL of the 0.2M DTT stock and pipette mix. Incubate at +65C for 30-minutes in a Thermomixer at 1,000rpm.
- 3. During this incubation, prepare the SP3 beads stock (see **Note 2**):
 - 1. Vortex the bead stock to re-suspend the material.
 - Take 500uL of each of the bead stocks and combine in a fresh 2mL tube.
 - 3. Place on a magnetic rack and wait for beads to settle. Discard the supernatant.

- 4. Reconstitute the beads in 1mL of water with pipetting and place back on the magnetic rack. After the beads settle, discard the supernatant.
- 5. Repeat the above rinse one additional time for a total of 2 rinses.
- 6. Reconstitute the beads in 500uL of water. The bead stock can be stored at +4C indefinitely.
- 4. Add 10uL of SP3 beads to the sample and pipette mix.
- 5. Add 150uL of ethanol to the sample and gently shake the tube with your hand to mix the phases. Do not vortex.
- 6. Place in a shaking incubator at room temperature for 5-minutes.
- 7. While this is incubating, prepare your digestion solution by combining 0.5ug of lysNarginase in 100uL of 100mM HEPES, pH 7.3 per sample and keep on ice (see **Note 3**). The original enzyme stock should be 0.1ug/uL.
- 8. Centrifuge the tube at 250g for 30-seconds to bring any liquid down from the top of the tube.
- 9. Place the tube on a magnetic rack and wait for the beads to settle. Discard the supernatant.
- 10. Remove the tube from the rack and reconstitute the beads in 800uL of 80% ethanol. Gently rinse the beads by pipetting.
- 11. Place the tube on a magnetic rack and wait for the beads to settle. Discard the supernatant.
- 12. Repeat Steps 9 11 two additional times for a total of 3 rinses.
- 13. Place the tube back on the magnetic rack an wait for the beads to settle.
- 14. Discard the supernatant taking care to remove any residual ethanol remaining. It is not necessary to air dry the tubes.
- 15. Now digest your samples into peptides:
 - 1. Add 100uL of the digestion solution to the sample and pipette mix.
 - 2. Incubate at +37C in a shaking incubator or ThermoMixer overnight (around 14-hours).
 - 3. After digestion, gently shake the tube to reconstitute the beads.
 - 4. Centrifuge the tube at 20,000g for 2-minutes.
 - 5. Place on the magnetic rack and wait for the beads to settle.
 - 6. Transfer the supernatant to a fresh 1.5mL tube.
 - 7. The peptide sample can be stored at -80C indefinitely.

Notes

Note 1 - Other beads can be substituted here, such as BangsLabs Magnefy beads (CAT#MFY0001), or other carboxylate modified particles. Other companies, such as MagReSyn also offer HILIC beads which are also compatible.

Note 2 - The bead stock from the vendor is 50mg/mL. We recommend using the beads at a 10:1 (ug of beads : ug of protein) ratio. This is far in excess of what is necessary, but will improve rinsing and elution efficiency by reducing the amount of 'clumping' that happens during binding.

Note 3 - I generally aim to have a trypsin:protein, ug:ug ratio of around 1:100, depending on the volume. For a larger volume I would likely scale this down to

a 1:25 ratio. But these are personal preferences and digestion should be efficient at the values you would typically use in your lab.