

1st Slide Set Computer Networks

Prof. Dr. Christian Baun

Frankfurt University of Applied Sciences
(1971–2014: Fachhochschule Frankfurt am Main)
Faculty of Computer Science and Engineering
christianbaun@fb2.fra-uas.de

Learning Objectives of this Slide Set

- Organizational Information
- Fundamentals of computer networks
 - Network services, roles, transmission media and network protocols
 - Classification of networks
 - Parallel/ serial data, synchronous/asynchronous data transmission
 - Directional dependence (anisotropy) of data transmission
 - Topologies
 - Frequency, data signal and fourier series
 - Bitrate, baud rate, bandwidth and latency
- Protocols
 - TCP/IP reference model
 - Hybrid reference model
 - OSI reference model

Organizational Information

- E-Mail: christianbaun@fb2.fra-uas.de

!!! Tell me when problems exist at an early stage !!!

- **Homepage:** <http://www.christianbaun.de>



!!! Check the course page regularly !!!

- The homepage contains among others
 - **Presentation slides** in English and German language
 - **(Lab) Exercise sheets** in English and German language
 - **Exams**
 - **Sample solutions**
 - Participating the exercises and the lab is not a precondition for exam participation
 - But it is recommended to participate the exercises

The content of the English and German slides is identical, but please use the English slides for the exam preparation to become familiar with the technical terms



Situation today and Objective for this Semester



Topics of this Course

Image source: unknown


- Organisational information, introduction
 - Fundamentals of computer networks
 - Reference models
 - Line codes, protocols and services
 - Wired and wireless networks



The course includes > 500 slides. But you do not need to memorize them all in detail for the exam...

The Way a good Course works. . .

Image source: Google



- 
 - Active participation please!
 - Mr. Miyagi says:
“Not only the student learns from his master, also the master learns from his student.”

Things, which are bad in a Course. . .

Attending late (regularly!)



⇒ annoying and disrespectful

Noisy eating in the course



⇒ annoying

Offensive-smelling food in the course



⇒ disgusting

Noisy greeting of/by people attending late



⇒ embarrassing and disrespectful

Teamwork at the laptop in the course



⇒ annoying for the rows behind

Filming or photographing the course



⇒ embarrassing and disrespectful

Computer Networks in Computer Science (1/2)

**Practical
Computer
Science**

**Technical
Computer
Science**

**Theoretical
Computer
Science**

Mathematics

**Minor
Subject**

Where would you place the computer networks?

Computer Networks in Computer Science (2/2)

Practical Computer Science		Technical Computer Science		Minor Subject
Programming (SW-Engineering, Modelling)		Robotics	Sensor Technology	
Distributed Systems	Operating Systems	Real-Time Systems		
Databases	Computer Architecture	Hardware Design		
Compiler Construction	Computer Networks	Embedded Systems		
Formal Languages	Analysis	Stochastics		
Computability Theory	Algebra	Optimization		
Automata Theory	Logic			
Theoretical Computer Science		Mathematics		

Computer networks belong to practical computer science and technical computer science

Required Components to set up a Computer Network

- For setting up and running a computer network, these components are required:
 - 1 ≥ 2 **terminal devices with network services running**
 - The devices are intended to communicate with each other or access shared resources
 - A network service provides a service for communication or shared resources usage
 - 2 **Transmission medium** to send and receive data (see slide set 2)
 - Common used transmission media are based of copper wires (e.g. twisted pair cables or coaxial cables) and fiber-optic cables
 - Wireless data transmission is also possible
 - 3 **Network protocols** (see slides 33)
 - Rules that specify, how computers can communicate

The rules (network protocols) are mandatory. Without them, the communication partners cannot understand each other. Just imagine a phone call to a foreign country. The connection is established, but no participant understands the other's language. Only if all participants speak the same language, communication becomes possible

Parallel Data Transmission

Image source: <http://www.elektron-bbs.de> and Google

- Communication between computers is possible via **parallel** and **serial** data transmission
- With **parallel data transmission**, in addition to the control lines, multiple data lines exist
- Example: Parallel port which was the standard interface to connect printers until it was replaced by USB
 - Via this interface, a complete byte of data can be transferred per time unit
- Benefit: Higher throughput
- Drawback: Lots of lines are necessary
 - This is cost-intensive for long distances
- Usage: Local bus systems

The image shows the parallel port (25 pins)


GND - Ground	15	SLCT - Select
GND - Ground	12	PE - Paper End
GND - Ground	11	BUSY
GND - Ground	10	ACK - Acknowledge
GND - Ground	22	D7 - Databit 7
GND - Ground	21	D6 - Databit 6
GND - Ground	20	D5 - Databit 5
GND - Ground	19	D4 - Databit 4
GND - Ground	18	D3 - Databit 3
SHIELD	17	D2 - Databit 2
INIT	16	D1 - Databit 1
ERROR	15	D0 - Databit 0
ALF - Auto Line Feed	14	STB - Strobe
SUB-D 25-polig weiblich Ansicht auf Buchseseite	13	




Serial Data Transmission

Image source: <http://www.elektron-bbs.de>


- When **serial data transmission** is used, the bits are transmitted one after another via the bus
- Transferring a byte takes 8 times longer compared to parallel data transmission
- Benefit: Can be used for long range distances, because only few wires are required
- Drawback: Lesser throughput
- Usage: Local bus systems and **computer networks**



The image shows the serial port (25 pins)



The image shows the serial port (9 pins)



Directional Dependence (Anisotropy) of Data Transmission

- **Simplex**

- The information transfer only works in one direction
- After the end of a transmission, the communication channel can be used by another sender
- Examples: Radio, TV, Pager

- **Duplex (Full-duplex)**





- The information transfer works in both directions simultaneously
- Examples: Phone, Networks with twisted pair cables because they provide separate wires to send and receive

- **Half-duplex**

- The information transfer works in both directions, but not simultaneously
 - Only one direction at a time
- Examples:
 - Networks with fiber-optic cables or coaxial cables, because there exists just a single line to sending and receiving
 - Wireless networks with just a single channel


Topologies of Computer Networks

- The topology of a computer network...
 - determines how the communication partners are connected with each other
 - affects its reliability a lot
- The structure of large-scale networks is often a combination of different topologies
- Physical and logical topology can be different
 - **Physical topology:** Describes the wiring
 - **Logical topology:** Describes the flow of data between the terminal devices
- Topologies are graphically represented with nodes and edges



Bus Network


- All terminal devices are connected via a shared communication cable – the bus




- No active components between the terminal devices and the shared communication cable
 - If a participant fails, it does not affect the network itself
- Advantage: Cheap to implement
 - In the past, Hubs and Switches have been expensive
- Shared communication cable fails
 - ⇒ complete network fails
- Only one participant can send data at each point in time ⇒ otherwise, collisions will occur
 - A media access control method like CSMA/CD is required (see slide set 6)

- Examples:
 - 10BASE2 (Thin Ethernet) and 10BASE5 (Thick Ethernet): 10 Mbps

10BASE2 (A Journey into the Past)




Ring Network



- Connects participant to participant
- All data is transferred from participant to participant until the destination is reached
- Disruption of a single link \Rightarrow network failure
- Each participant is also a repeater, which amplifies the signal
 - For that reason, large-sized rings (transmission medium dependent) are possible
 - Maximum ring length for Token Ring: 800 m
- Examples:
 - Token Ring (logical): 4-16 Mbps
 - Fiber Distributed Data Interface (FDDI): 100-1000 Mbps
 - FDDI implements 2 rings
 - One is a secondary backup, in case the primary ring fails

Star Network



- All participants are connected directly with a central component (Hub or Switch)
 - Outage of the central component leads to an outage of the network itself
 - The central component can be implemented in a redundant way
 - Outage of a participant do not cause an outage of the network itself
 - Advantages: Expandability and stability
-
- Examples:
 - Ethernet: 10 Mbps, 100 Mbps, 1 Gbps, 10 Gbps
 - Token Ring (physical): 4-16 Mbps
 - Fibre Channel (storage networks): 2-16 Gbps
 - InfiniBand (cluster): 10-40 Gbps

Media Access Unit


Image source: Google Image Search

- Token Ring demonstrates that the physical and logical topology of a network can be different
 - Token Ring implements a logical ring network
 - Wiring is mostly done equal to a star network
- Using a Media Access Unit (MAU) is common
 - Each device is connected with just a single cable with the MAU
 - Realizes a star network from a technical point of few
 - Still a ring network from a logical point of view
 - A MAU is a *ring in a box*
 - If a participant is not connected or does its connection fail, then the MAU bypasses this participant and the ring is still properly functioning



Mesh Network

- Each participant is connected with one or more other participants
 - In a **fully connected mesh network**, the participants are all connected to each other
- If participants or connections fail, the communication is typically still possible because the frames are redirected



- Benefit: Failure safe (depends on the cabling effort)
- Drawbacks: Cabling effort and energy consumption
- Furthermore, in not fully connected meshed networks, it is complex to identify the best way from sender to receiver during packet forwarding
- Examples:
 - Logical topology between Routers
 - Ad-hoc (wireless) networks

Tree Network

Image source: Google Image Search


- One or more edges are connected with the root
 - Every edge leads to a leaf node or to the root of another tree
- Several star topology networks are hierarchically connected
- Benefits:
 - Failure of a terminal device (leaf node) has no consequences
 - Good expandability and long distances are possible
 - Well suited for searching and sorting algorithms
- Drawbacks:
 - When a node fails, the complete (sub-)tree behind is no longer accessible
 - In a large tree, the root can be a bottleneck because the communication from one half of the tree to the other half always needs to pass the root



- Example:
 - Connecting Hubs or Switches via uplink

Cellular Network

- Implemented mainly by wireless networks
- **Cell:** Area where the participants can communicate with the base station
- Advantage: Outage of participants do not affect the network itself
- Drawback: Maximum dimension is limited by the number of base stations and their positions
 - Only one participant can send data at each point in time \Rightarrow otherwise, collisions will occur
 - A media access control method like CSMA/CA is required (see slide set 6)
 - Examples:
 - Wireless LAN (IEEE 802.11)
 - Global System for Mobile Communications (GSM)
 - Bluetooth hotspots




Current Situation

- Today, Ethernet (1-10 Gbit/s) with Switches (\Rightarrow **star topology**) is the standard for wired LAN
- Connecting Hubs and Switches implements a **tree topology**, if there are no loops in the cabling
- **Cell topology** is the standard for wireless networks
- **Mesh topology** is one possible use case of wireless networks and it is the logical topology between routers
- **Bus** and **ring topologies** are no longer used for new computer network infrastructures
 - 10BASE2 (Thin Ethernet) and 10BASE5 (Thick Ethernet) are outdated since the mid/end-1990s
 - May 2004: IBM sells his complete Token Ring product lineup

Frequency


Image source: <http://www.dj4uf.de>

- Electrical engineering distinguishes between 2 types of voltage:
 - 1 Direct current voltage:** Polarity of voltage and voltage level remain constant
 - 2 Alternating current voltage:** Polarity of voltage and voltage level change periodically



- Fig. A: *Rectangular shaped alternating current voltage in theory*
- Fig. B: *Sinus shaped alternating current voltage in practice*

- Period:** The time it takes for the periodic voltage curve
- Frequency:** Number of oscillations per second
- The lower the period, the higher is the frequency



$$\text{Frequency [Hz]} = \frac{1}{\text{Period [s]}}$$



- The unit for frequency is the hertz (Hz)
- 1 Hz means = 1 event (oscillation) per second
- Example: Alternating current voltage in Europe with 50 Hz

Data Signal

- Data exchange takes place through the exchange of **binary data**
 - But the transmission media always transmit **analog signals**
- The signals are subject to physical laws
 - This includes the **attenuation** (signal weakening)
 - Attenuation causes the weakening of the amplitude of a signal with increasing distance on all transmission media
 - If the amplitude of a data signal has dropped below a certain value, it can no longer be clearly detected
 - Thus, the attenuation limits the maximum bridgeable distance for all transmission media
 - The **higher the frequency**, the **higher** is the **attenuation**

Fourier Series

Image source: Jörg Rech. Ethernet. Heise




- According to the **fourier series**, which is named in honour of Jean Baptiste Joseph Fourier (1768-1830), a square-wave signal (e.g. a binary signal), consists of the sum of a set of oscillating functions
 - A square wave signal consists of a fundamental frequency and harmonics
 - Harmonics are integer multiples of the fundamental frequency
 - They are often referred to as harmonics of the 3rd, 5th, 7th, etc. order
 - The more harmonics are taken into account, the closer to get a perfect square wave

Fourier Series and Bandwidth

Image Source: Wikipedia

- To transmit a **square-wave signal** clearly via the transmission medium, at least the **fundamental frequency** and the **harmonics of the 3rd and 5th order** need to be transmitted bug-free
 - The harmonics of the 3rd and 5th order are necessary for keeping the square wave its rectangular shape and preventing that it looks rounded (see next slide)
 - In practice, the harmonics are more attenuated than the fundamental frequency
- The **bandwidth**, from the viewpoint of the transmission medium, is the range of frequencies which can be transmitted via the transmission medium without interferences




We already know...

The attenuation of the signal increases with the frequency

Fourier Synthesis of a square-wave Signal

Source: Wikipedia



- The graphs in the 1st column show the oscillation, which is added in the respective row. The graphs in the 2nd column show all so far recognized oscillations, which are then added to the diagrams of the 3rd column, to reach as close as possible the signal which shall be generated. The more harmonics (multiples of the fundamental frequency) are taken into account, the more we get an ideal square-wave signal. The 4th column shows the amplitude spectrum, normalized to the fundamental frequency

Bitrate and Baud Rate

Image source: <http://maggiesfarm.anotherdotcom.com>

- **Bitrate:** Transferred payload bits per time unit
 - Typically measured as bits per second (bit/s or bps)
- **Baud Rate:** Transferred symbols per second
 - Unit of the symbol rate
 - 1 baud means 1 symbol is transferred per second
 - Originally the baud rate described the number of distinct symbol changes (signaling events) when using the telegraph
 - Number of morse characters per second
- The ratio between bitrate and baud rate depends of the line encoding scheme used



The line code...

- The line code specifies in computer networks the maximum number of signals that can be transmitted via the transmission media used
- The line code of a network technology is specified by the layer protocol protocol used
- More information about line codes provides slide set 3

Bandwidth and Latency (1/2)

- Main factors, influencing the performance of a computer network:
 - **Bandwidth (throughput)**
 - **Latency (delay)**
- The **bandwidth** specifies how many bits can be transmitted within a period via the network
 - In a network has a bandwidth (throughput) of 1 Mbit/s, one million bits can be transmitted per second
 - Thus, a bit has a *width* of $1 \mu\text{s}$
 - If the bandwidth is doubled, the number of bits that can be transmitted per second doubles too

Bandwidth and Latency (2/2)

- The **latency** of a network is the time, a message needs to travel from one end of the network to the most distant end

$$\text{Latency} = \text{Propagation delay} + \text{Transmission delay} + \text{Waiting time}$$

$$\text{Propagation delay} = \frac{\text{Distance}}{\text{Speed of light} * \text{Velocity factor}}$$

- Distance: Length of the network connection
- Speed of light: 299, 792, 458 m/s
- Velocity factor: Vacuum = 1, twisted pair cables = 0,6, optical fiber = 0,67, coaxial cables = 0,77

$$\text{Transmission delay} = \frac{\text{Message size}}{\text{Bandwidth}}$$

Transmission delay = 0, if the message consists only of a single bit

- Waiting times are caused by network devices (e.g. Switches)
 - They need to cache received data first before forwarding it

Waiting time = 0, if the network connection between sender and destination is just a single line or a single channel

Source: Larry L. Peterson, Bruce S. Davie. Computernetzwerke. dpunkt (2008)

Bandwidth-Delay Product

- Calculates the **volume of a network connection**
 - Signals cannot be transmitted with infinite speed via the transmission media
 - The propagation speed is in any event limited by the speed of light and it depends on the velocity factor of the transmission medium
 - The product of bandwidth and delay (latency) corresponds to the maximum number of bits that can reside inside the line between sender and receiver
- Example: A network with 100 Mbit/s bandwidth, and 10 ms latency

$$100,000,000 \text{ Bits/s} \times 0.01 \text{ s} = 1,000,000 \text{ Bits}$$

- There are a maximum number of 1,000,000 Bits inside the network line
 - This is equivalent to 125,000 Bytes (approx. 123 kB)

Protocols

- A **protocol** is the set of all previously made **agreements** between communication partners
 - These agreements include:
 - Rules for connection establishment and clearing
 - Method of synchronization between sender and receiver
 - Measures for the detection and treatment of transmission errors
 - Definition of valid messages (vocabulary)
 - Format and encoding of messages
- Protocols specify...
 - the **syntax** (= format of valid messages)
 - the **semantics** (= vocabulary and meaning of valid messages)

Reference Models


- Communication in computer networks is subdivided into **reference models**
- Each **layer** of a reference model handles a particular aspect of communication and offers **interfaces** to the overlying layer and underlying layer
- Each interface consists of a set of **operations**, which together define a **service**
- In the layers, the data is encapsulated (⇒ **encapsulation**)
- Because each layer is complete in itself, single protocols can be modified or replaced without affecting all aspects of communication
- The most popular reference models are...
 - the **TCP/IP reference model**,
 - the **OSI reference model**
 - and the **hybrid reference model**

TCP/IP Reference Model or DoD Model


- Developed from 1970 onwards by the Department of Defense (DoD) in the Arpanet project
- Divides the required functionality to realize communication into 4 layers
- For each layer, it is specified, what functionality it has to provide
 - These requirements are implemented by communication protocols
 - Concrete implementation is not specified and can be realized in different ways
 - Therefore, for each of the 4 layers, multiple protocols exist

Number	Layer	Protocols (Examples)
4	Application Layer	HTTP, FTP, SMTP, POP3, DNS, SSH, Telnet
3	Transport Layer	TCP, UDP
2	Internet Layer	IP (IPv4, IPv6), ICMP, IPsec, IPX
1	Link Layer	Ethernet, WLAN, ATM, FDDI, PPP, Token Ring

TCP/IP Reference Model – Message Structure




- Each layer adds additional information as **header** to the message
 - Some protocols (e.g. Ethernet) add in the link layer not only a header but also a **trailer** at the end of the message
 - The receiver analyzes the header (and trailer) on the same layer



Hybrid Reference Model

- The TCP/IP reference model is represented frequently in the literature (e.g. by Andrew S. Tanenbaum) as a 5-layer model
 - Reason: It makes sense to split the **link layer** into 2 layers, because they cover completely different responsibilities
- This model is an extension of the TCP/IP model and is called **hybrid reference model**




The objects of the individual layers will be discussed on the basis of the hybrid reference model

Physical Layer

(see Slide Sets 2+3)

- Transmits the ones and zeros
 - Physical connection to the network
 - Conversion of data in signals
- Protocol and transmission medium specify among others:
 - How many bits can be transmitted per second?
 - Can transmission take place simultaneously in both directions?
- Devices: **Repeater**, **Hub** (Multiport Repeater)


Hybrid Reference Model



Data Link Layer

(see Slide Sets 4+5+6)

- Ensures error-free data exchange of **frames** between devices in physical networks
 - Detects transmission errors with **checksums**
 - Controls the access to the transmission medium (e.g. via CSMA/CD or CSMA/CA)
- Specifies physical network addresses (**MAC addresses**)
- At sender site: Packs the Network Layer packets into frames and transmits them with the desired reliability via a physical network from one device to another
- At receiver site: Identifies frames in the bit stream from the Physical Layer
- Devices: **Bridges**, **Layer-2-Switches** (multiport Bridges) and **Modems** connect physical networks




Network Layer

(see Slide Sets 7+8)

- Forwards (*routes*) **packets** between logical networks (over physical networks)
 - For this *internetworking*, the network layer defines **logical addresses (IP address)**
 - Each IP packet is *routed* independently to its destination and the path is not recorded
- At sender site: Packs the segments of the Transport Layer in packets
- At receiver site: Unpacks the packets in the frames from the Data Link Layer
- **Routers and Layer-3-Switches** connect logical networks
- Usually the connectionless Internet Protocol (IP) is used
 - Other protocols (e.g. IPX) have been replaced by IP

Hybrid Reference Model




Transport Layer

(see Slide Set 9)

- Transports **segments** between processes on different devices via so-called end-to-end protocols
- At sender site: Packs the data of the Application Layer into segments
- At receiver site: Unpacks the segments in the packets from the network link layer
- Addresses processes with **port numbers**
 - Data Link Layer and Network Layer implement physical and logical addressing of the network devices
- Different transport protocols implement different ways to communicate
 - UDP (User Datagram Protocol): Connectionless communication
 - TCP (Transport Control Protocol): Connection-oriented communication
 - Combination of TCP/IP = de facto standard for computer networks

Hybrid Reference Model



Different Forms of Communication

• Connectionless communication

- Analogous to a mailbox
- Sender transmits messages without prior connection establishment
- Disadvantage: No validation that a segment arrives at the destination
 - If validation is wanted, it must be implemented in the Application Layer
- Benefit: Better throughput, because of lesser overhead

• Connection-oriented communication


- Analogous to a telephone
- Prior data exchange, a connection is established between sender and receiver
 - The connection is not terminated, even if no data is transmitted
- After all data is exchanged, the connection becomes terminated
- Implements flow control and congestion control
 - Ensures lossless segment delivery in the correct order
⇒ Successful delivery is guaranteed

Application Layer

(see Slide Set 10)

- Contains all protocols that work together with the application programs (e.g. browser or email program)
- Here are the messages (e.g. HTML pages or emails), formated according to the used application protocol
- Some Application Layer protocols: HTTP, FTP, SMTP, POP3, DNS, SSH, Telnet


Hybrid Reference Model



How Communication works (1/2)

• Vertical communication


- Messages are packed from top to bottom layer by layer and extracted at the receiver in the reverse layer sequence
- **Data encapsulation and de-encapsulation**



How Communication works (2/2)


• Horizontal communication

- Equal protocol functions are used in the equivalent layers by sender and receiver



OSI Reference Model

- Some years after the TCP/IP reference model (1970s), the OSI reference model was developed from 1979 onwards
 - 1983: Standardized by the Intern. Organization for Standardization (ISO)
 - OSI = Open Systems Interconnection
- The structure is similar to the TCP/IP reference model
 - The OSI model implements 7 layers
- In contrast to the hybrid reference model, the Application Layer functionality is distributed across 3 layers in the OSI reference model



Session Layer

- **Controls the dialogues** (connections) between processes
 - Controls which participant is allowed to send next
- Provides checkpointing which is useful for longer data transmissions to enable **synchronization**
 - If the connection fails, returning to a checkpoint avoids starting the transmission from the beginning
- Protocols that meet the required capabilities of the Session Layer are **Telnet** for remote controlling computers and **FTP** for files transmission
 - These protocols can be assigned to the Application Layer too
 - The Application Layer includes the protocols, used by the users' applications
 - FTP and Telnet are used directly by the relevant programs and not by abstract protocols of upper levels
 - Thus, it makes sense to assign these Session Layer protocols to the Application Layer

The Session Layer is seldom used in practice, because all tasks intended to this layer are fulfilled by Application Layer protocols today

Presentation Layer

- Contains rules for changing the **format (presentation) of messages**
 - The sender can notify the receiver that a message has a specific **format** (e.g. ASCII) to make a perhaps necessary conversion possible
 - Data records can be defined here with fields (e.g. name, student ID number...)
 - **Data types and their length** can be defined here
 - **Compression and encryption** could be covered by this layer

The Presentation Layer is seldom used in practice, because all tasks intended to this layer are fulfilled by Application Layer protocols today

Reference Models – Summary

- Conclusion: The hybrid reference model illustrates the functioning of computer networks in a realistic way
 - It distinguishes between the Physical Layer and Data Link Layer
 - This is useful, because the objectives differ a lot
 - It does not subdivide the Application Layer
 - This is not useful and does not take place in practice
 - Functionalities, which are intended for Session Layer and Presentation Layer, are provided by Application Layer protocols and services
 - It combines the advantages of the TCP/IP reference model and the OSI reference model, without taking over their drawbacks

