
Delivery

Berlin Delivery can be staffed as soon as there is Berlin Tower and Berlin Apron online. To open more than three stations on the ground Berlin Delivery is always required to be online.

Runway Assignment

The runway assignment is depending on the parking positions of departing aircraft. It might be necessary to deviate from this rule due to traffic. The task of Delivery is to assign the departure runways to the aircraft as efficient as possible at any time.



Departure Routes

• All SIDs are RNAV only (excl. ROKMU1P)

 All aircraft via SUKIP 2Q and LOGDO 2Q are required an RFL (Requested Flight Level) of least FL120

vSID Plugin Commands

The following plugin commands for vSID are available at EDDB:

Command	Explanation
.vsid area eddb north	This will disable the area where all aircraft will be assigned to runway 06L/24R.
.vsid area eddb south	This will disable the area where all aircraft will be assigned to runway 06R/24L.

Datalink Clearance (PDC/DCL)

The service of Datalink clearances shall be provided at any time.

Airport collaborative decision-making (A-CDM)

The A-CDM process will be simulated at EDDB during (weekly) events and any other high-traffic situations. Further information here: https://dms.vatsim-germany.org/s/odw629qZk5WezPi

Invalid Routes / Old AIRAC

Invalid Route + old AIRAC installed

- Assign old SID
- Only applicable for flights via SOGMA, ODLUN, MAXAN, POVEL, HLZ

Invalid Route + new AIRAC installed

- re-routing required
- Only applicable for flights via SOGMA, ODLUN, MAXAN, POVEL, HLZ
- Available re-routings:
 - SOGMA → SUKIP M748 SOGMA
 - HLZ → SUKIP Y206 BUREL P203 HLZ
 - POVEL → LOGDO Z20 MAG L986 POVEL

- MAXAN → LOGDO Z20 MAG Z115 MAXAN
- ODLUN → LOGDO Z117 ODLUN

All other invalid routes


Either complete re-routing or vectored / visual departure

VFR Traffic

- VFR pilots are required to do their initial call on Berlin Delivery
- Berlin Delivery provides pilots with information such as active runways and QNH
- Berlin Delivery should create a F-Plan if not already done by the pilot (".am" command)
- Coordinate every VFR aircraft with Tower (release by Tower required prior handoff to Ground)

Quicksheet

EDDB Quicksheet



06L	300011	3B		3B <i>⁴</i> ″			
06R			2Q ; £				
UUK	FL 80*			2	Q٢		
If Unable	CLB	GERGA	ARSAP	LUROS	SUKIP	LOGDO	ROKMU
24L							2P**
24R			2M				
06L	4000 ft				3	K	
06R			2Z				
UOK					3	Z	
Climb vi	ia SID 🧨	*Minimum RFL 120			**Non-R	NAV only	

ID	Freq	Callsign
ADB	123.780	Berlin ATIS
DBC	121.605	Berlin Delivery
DBGA	121.855	Berlin Apron
DBGE	129.605	Berlin Apron
DBGN	129.505	Berlin Ground
DBGS	121.705	Berlin Ground
DBTN	120.030	Berlin Tower
DBTS	118.805	Berlin Tower
DBAS	126.425	Bremen Radar
DBAN	119.630	Bremen Radar
DBAST	121.130	Berlin Arrival
DBANT	136.105	Berlin Arrival
DBDS	120.630	Bremen Radar
DBDN	120.340	Bremen Radar
BOR	123.225	Bremen Radar
MRZ	124.175	Bremen Radar
FLG	136.450	Bremen Radar
MAR	136.050	Bremen Radar

VA	T SIM	Germany
•	• •	\

	Intersection Departure											
	2	4L	24R	North	24R South 06R		06L North		06L South			
Heavy	M8	4000 m	K6	3600 m	L8	3600 m	M2	4000 m	K1	3300 m	L1	3600 m
Medium	M7	2715 m	K6	3600 m	L7	3300 m	M3	2475 m	K1	3300 m	L2	3500 m
Light	M6	2265 m	K5	3385 m	L6	2515 m	M3	2475 m	K2	2150 m	L3	2470 m

Holdings Approach								
Fix	OGBER	OGBER***	KETAP	KETAP***	KLF	ATGUP	NUKRO	
MHA	5000ft	FL080	5000ft	FL080	4000ft	4000ft	4000ft	
Max								
lbd track	L 117°	L 117°	L 147°	L 147°	R 018°	R 018°	R 329°	

*Missed Approach as published

Approach Procedures									
	24L 24R 06L 06R								
APP	ILS	ILS	ILS	ILS					
ID	IBSW	IBNW	IBNE	IBSE					
FREQ	109.50	109.90	110.70	109.70					
CRS	244°	244°	064°	064°					
FAP	XANIM	UBURU	ODIDO	TEBGO					
ALT	3000 ft	4000 ft	4000 ft	3000 ft					

Version #6

Erstellt: 29 August 2024 12:42:04 von 1395737

Zuletzt aktualisiert: 20 Januar 2025 21:20:31 von 1497525