# Dissipation and dispersion in finite difference solutions of hyperbolic PDEs Numerical solutions of PDEs

Gabriele Cimador

Data Science and Scientific computing at Università di Trieste

February 6, 2023



## Summary

- Hyperbolic problems
  - What is an hyperbolic problem?
  - Some comments
- 2 Finite differences
- Upwind method
- 4 Lax-Wendroff
- 5 Leap-frog

What is an hyperbolic problem?

•00

Usually transport wave-like phenomena with finite speed of propagation. Examples:

- 1d transport/advection eq.  $u_t + au_x = 0$
- Conservation laws  $u_t + (f(u))_x = 0$
- Wave eq.  $u_{tt} + cu_{xx} = 0$

What is an hyperbolic problem?

All of the prevoius can be grouped with the general tranport system of equations:

$$\mathbf{u}_t + A\mathbf{u}_x = 0$$

where A matrix which can depend on t, x, u and has a full set of real eigenvalues.

e.g. for the conservation law equation

$$u_t + (f(u))_x = 0 \Rightarrow u_t + A(u)u_x = 0$$

where 
$$A(u) = \frac{\partial f}{\partial u}$$
.

Some comments

- There is no dissipation:  $||u(t,\cdot)||_{L_2} = ||u_0||_{L_2}$
- Information propagates at finite speed
- Discontinuites in initial data is propagated ⇒ discontinue solution
- CFL condition necessary for convergence of a finite difference scheme

#### Finite differences

If the PDE is defined in a domain  $I \times \Omega$  where I is the time interval  $[0, T_f]$  and  $\Omega$  is the space domain of one variable [a, b], we can discretize the PDE domain with  $N_t \times N_x$  points. We can than define a general explicit difference scheme at time  $t = t_n$  as

$$v_j^{n+1} = \sum_{i=-1}^r \beta_i v_{j+i}^n$$

where  $j = 1, ..., N_x - r - 1$ ,  $n = 0, ..., N_t$  and  $v_j^n$  is a mesh function over the discretised domain.

#### If:

- PDE has constant coefficients
- Problem is defined on infinte mesh or has periodic boundary conditions

Can perform a Fourier analysis of how the difference scheme acts on the initial condition.

If  $\hat{v}(t,\xi)$  is Fourier transform of the solution and  $\iota=\sqrt{-1}$ , we have

$$v(t,x) = \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{\infty} e^{\iota \xi x} \hat{v}(t,\xi) d\xi$$

#### The difference scheme gives

$$\int_{-\infty}^{\infty} e^{\iota \xi x} \hat{v}(t+\tau,\xi) d\xi = \sum_{i=-l}^{r} \beta_{i} \int_{-\infty}^{\infty} e^{\iota \xi(x+ih)} \hat{v}(t,\xi) d\xi$$

$$= \int_{-\infty}^{\infty} \left( \sum_{i=-l}^{r} \beta_{i} e^{\iota \xi ih} \right) e^{\iota \xi x} \hat{v}(t,\xi) d\xi$$

$$\sum_{i=-l}^{r} \beta_{i} e^{\iota \xi ih} = g(\zeta) \implies \hat{v}(t+\tau,\xi) = g(\zeta) \hat{v}(t,\xi)$$

$$\zeta = \xi h, \ \tau = \frac{T_{f}}{M}, \ h = \frac{b-a}{M}$$

$$g(\zeta)$$
 is the **amplification factor** and  $\hat{v}(t,\xi) = g(\zeta)^n \hat{v}(0,\xi)$ 

- $||g|| \Rightarrow$  analysis of dissipation of wave numbers
- $Arg(g) \Rightarrow$  analysis of dispersion of wave numbers
- If the PDE has s components than g is an  $s \times s$  amplification matrix G. Dissipation and dispersion studied via the eigenvalues of G.

Dissipation and dispersion in the finite difference scheme can occur even if the PDE has not these characteristics.

## Advection equation

Consider the advection equation equipped with initial and boundary condition:

$$\begin{cases} u_t + au_x = 0, & x, t \in [a, b] \times [0, T_f] \\ u(0, x) = u_0, & x \in [a, b] \end{cases}$$

Boundary condition depends on the sign of a. e.g. if a>0 the boundary condition reads  $u(a,t)=f(t) \ \forall \ t \in [0,T_f]$ 

# Upwind method

Considering a discretization of  $[0, T_f] \times [a, b]$  and that  $U_j^n$  is mesh function approximating u solution of PDE we can discretize the operators as follows:

$$\begin{cases} \frac{U_j^{n+1} - U_j^n}{\tau} = \frac{U_j^n - U_{j-1}^n}{h}, & \text{if } a > 0\\ \frac{U_j^{n+1} - U_j^n}{\tau} = \frac{U_{j+1}^n - U_j^n}{h}, & \text{if } a < 0 \end{cases}$$

$$n = 0, ..., N_t - 1$$

## Upwind method

Can be rewritten as:

$$U_j^{n+1} = \begin{cases} (1-\nu)U_j^n + \nu U_{j-1}^n & \text{if } a > 0\\ (1+\nu)U_j^n - \nu U_{j+1}^n & \text{if } a < 0 \end{cases}$$

where 
$$\nu = a \frac{\tau}{h}, \ n = 0, ..., N_t - 1$$

Amplification factor for a > 0 is  $g(\zeta) = (1 - \nu) + \nu e^{-\iota \xi h}$ :

- $\|g\| \le 1 \ \forall \ \xi \iff 0 \le |\nu| \le 1$
- Dissipative scheme
- Monotone scheme: if  $\nu \leq 1 \Rightarrow \max_{j} |v_{j}^{n+1}| \leq \max_{j} |v_{j}^{n}|$   $\Rightarrow$  stability even if  $a = a(x, t) \iff |a_{j}^{n} \frac{\tau}{h}| \leq 1$
- $Arg(g) = -\tan^{-1}\left(\frac{\nu\sin\xi h}{(1-\nu) + \nu\cos\xi h}\right)$


PDE admits plane-wave solutions of the form

$$u(t,x)=e^{\iota(\xi x+\omega t)}$$

where  $\xi =$  wave number,  $\omega =$  frequency.

PDE imposes the dispersion relation  $\omega = \omega(\xi)$  and phase velocity  $c = \frac{\omega}{\xi}$ . e.g. Advection eq. imposes  $\omega = -a\xi$  and c = -a independent on wave number.

To study dispersion, we can study the ratio  $\phi_e = \frac{Arg(g)}{\omega}$ 



Dissipation can be explained also as follows:

$$0 = \frac{U_j^{n+1} - U_j^n}{\tau} + a \frac{U_j^n - U_{j-1}^n}{h} =$$

$$= \frac{U_j^{n+1} - U_j^n}{\tau} + a \frac{U_{j+1}^n - U_{j-1}^n}{2h} - \frac{a * h}{2} \frac{U_{j+1}^n - 2U_j^n + U_{j-1}^n}{h^2}$$

i.e. it is a difference scheme for the parabolic PDE

$$u_t + au_x - \frac{ah}{2}u_{xx} = 0$$

So upwind scheme pollutes PDE with artificial diffusion.

#### Lax-Wendroff

It takes the form

$$U_j^{n+1} = \frac{1}{2}\nu(1+\nu)U_{j-1}^n + (1-\nu^2)U_j^n - \frac{1}{2}\nu(1-\nu)U_{j+1}^n$$

Can be rewritten as

$$\frac{U_i^{n+1} - U_i^n}{\tau} + a \frac{U_{i+1}^n - U_{i-1}^n}{2h} - \frac{\tau a^2}{2} \frac{U_{i+1}^n - 2U_i^n + U_{i-1}^n}{h^2} = 0$$

So it approximates the PDE  $u_t + au_x = \frac{\tau a^2}{2}u_{xx}$ . Comparing with upwind:


$$\frac{|a|}{2} = \frac{|a|\tau}{2\nu} = \frac{a^2\tau}{2|a|\nu} \ge \frac{a^2\tau}{2}$$

So LW expected to be less dissipative.

#### Amplification factor

$$g(\zeta) = 1 - 2\eta^2 \sin^2 \frac{1}{2} \zeta - \iota \eta \sin \zeta$$

- $|g|^2 = 1 4\nu^2(1 \nu^2)\sin^4\frac{1}{2}\zeta \le 1 \iff |\nu| \le 1$ Order of amplitude error  $\zeta^4$  when  $\zeta = h\xi$  small
- $Arg(g) = -\tan^{-1} \frac{\nu \sin \zeta}{1 2\nu^2 \sin^2 \frac{1}{2}\zeta}$





### Lax-Wendroff with variable coefficient

Now 
$$a = a(x, t)$$

# Leap-frog scheme

$$\frac{U_j^{n+1} - U_j^{n-1}}{2\tau} + a \frac{U_{j+1}^n - U_{j-1}^n}{2h} = 0$$

Oss.: need special procedure to obtain  $U_1$ , e.g. with Lax-Wendroff Fourier analysis gives

$$g(\zeta) = -\iota\nu\sin\zeta \pm \sqrt{1 - \nu^2\sin^2\zeta}$$

conservation law - burgers

bibliography