页码,1/4 Lazy Foo' Productions

Lazy Foo' Productions

News **FAQs** Games **Tutorials Donations** Articles Contact

SDL Real Time

Combine SDL graphical abstraction and C Detect memory leaks and runtime errors. Language precision

C++ Debugging

Debug C/C++ code w/Insure++

Ads by Google

Setting up SDL Extension Libraries in Dev C++

Last Updated 12/09/07

In this tutorial you're going to learn to set up SDL image. If you know how to set up this extension, you can set any of them up.

SDL_image is located on this page.

Also, always make sure that when you get an SDL extension (SDL_image, SDL_ttf, SDL_mixer, etc) that you also get the newest version of SDL. New versions of the SDL extensions don't like old versions of SDL. If you don't, Dev C++ will compile the program but the program will complain at run time (it's typically something about an entry point).

development library Binary: Linux SDL image-1.2.4-1.i386.rpm SDL image-1.2.4-1.ppc.rpm SDL image-devel-1.2.4-1.i386.rpm SDL image-devel-1.2.4-1.ppc.rpm Win32 SDL image-1.2.4-win32.zip SDL image-devel-1.2.4-VC6.zip \angle MacOS X

1)Scroll down to the Binary section and download the Windows

SDL image-1.2.4.pkg.tar.gz

Every extension libary has 3 essential parts:


- 1. The header file.
- 2. The lib file.
- 3. The *.dll file(s)

They're all set up pretty much the same way no matter which extension you're setting up.

Open up the zip archive and there should be a folder inside. Open the folder and it'll contain 2 subfolders.

- 2)First, open the include subfolder in the archive and extract the header file inside to the SDL subfolder inside of the Dev C++ include folder. It should be at C:\Dev-Cpp\include\SDL.
- 3)Next extract the lib file that's inside of lib subfolder of the archive to the Dev C++ lib folder. The Dev C++ lib folder should be at C:\Dev-Cpp\lib.
- 4) Next extract the *.dll file(s) located in the lib subfolder of the archive to the Dev C++ bin folder. It should be at C:\Dev-Cpp\bin.
- 5)Now extract the *.dll file(s) to C:\WINDOWS\SYSTEM32. This is so whenever you make an SDL extension app, the program will be able to find the *.dll file(s) even if they're not in the same directory as the *.exe


6) Now open up your SDL project and go to the project options.



7) Under the Parameters tab, paste:

-ISDL_image

in the linker after "-Imingw32 -ISDLmain -ISDL".



#include "SDL/SDL_image.h"

```
If you were setting up SDL_ttf you'd put

#include "SDL/SDL_ttf.h"

If you were setting up SDL_mixer you'd put

#include "SDL/SDL_mixer.h"

etc, etc.

Now the extension library is all set up.
```

Now you can use SDL_image functions.

The main one you want to know about is IMG_Load().

SDL_Surface *load_image(std::string filename)

```
//The image that's loaded
SDL_Surface* loadedImage = NULL;

//The optimized image that will be used
SDL_Surface* optimizedImage = NULL;

//Load the image using SDL_image
loadedImage = IMG_Load( filename.c_str() );

//If the image loaded
if( loadedImage != NULL )
{
    //Create an optimized image
    optimizedImage = SDL_DisplayFormat( loadedImage );

    //Free the old image
    SDL_FreeSurface( loadedImage );
}

//Return the optimized image
return optimizedImage;
}
```

Here is a revised version of the image loading function from the previous tutorial. As you can see IMG_Load() functions exactly the same as SDL_LoadBMP(), but there's one big exception: IMG_Load() can load BMP, PNM, XPM, LBM, PCX, GIF, JPEG, TGA and PNG files.

From this tutorial on, PNG image files will be the primary image format used. PNGs have excellent lossless compression.

Download the media and source code for this tutorial here.

I highly recommend that you download the documentation for SDL image and keep it handy.

It can be found here.

```
SlickEdit Code Editor
Code Faster and more Efficiently Download a Free Trial Today! <a href="www.slickedit.com">www.slickedit.com</a>
Ads by Google

News FAQs Games Tutorials Articles Contact Donations
```

Copyright Lazy Foo' Productions 2004-2008