


# Double-Diffusive Convection: An Extensional Module of Channelflow



Salinity behavior of 2D finger regime



Salinity and temperature behaviors of 2D diffusive regime in Couette flow configuration. ChannelFlow-DoubleDiffusiveConvection is an extensional module of Channelflow 2.0 for wall-bounded double-component problems like Double-Diffusive Convection and Binary Fluid Convection. To use this code, pls read following instruction to install Channelflow (this also contains setup on a HPC)

After knowing how to install the standard Channelflow, you can clone them to your local machine and add present ddc module inside by

```
git clone https://github.com/epf1-ecps/channelflow.git

cp ./CMakeLists.txt ./channelflow/CMakeLists.txt

mkdir -p ./channelflow/modules/
rm -rf ./channelflow/modules/ddc
cp -r ./ddc ./channelflow/modules/ddc
```

And build them, for example

```
mkdir -p build
cd build
cmake ../channelflow -DCMAKE_CXX_COMPILER=/usr/bin/mpicxx -DWITH_DDC=ON -DWITH_NSOLVER=ON -DCMAKE_
make -j16
```

## **Building DNS**

First of all, you need to define governing equations of problem. In this code, we offer nondimensional governing equations, which have form:

ParseError: KaTeX parse error: {align} can be used only in display mode.

where  ${\pmb u}, \theta,$  and s are perturbations of the velocity, first scalar (temperature), and second scalar (salinity) fields. If you can not see equations, let read pdf file instead. Because this code offers a general form of governing equations, so first you need to define the problem you want to use in this code. This is perfored by modifying controlling parameters  $(p_i)$  via a header file ddc/macros.h . Here, we suggest some governing equations which are nondimensionalized for specific problems:

Parameters	Double- diffusive convection (Singh & Srinivasan 2014)	Double- diffusive convection (normalized by free-fall velocity) (Yang et al. JFM 2021)	Binary fluid convection (Mercader et al. JFM 2013)	Stratified plane Couette flow (Langham et al. JFM 2019)	Description
$p_1$	$Pr_T$	$\sqrt{rac{Pr_T}{Ra_T}}$	Pr	1/Re	$Pr_T = rac{ u}{\kappa_T}$ is Prandtl number
$p_2$	$Pr_TRa_T$	$rac{RiR_{ ho}}{1-R_{ ho}}$	$Pr_TRa_T$	Re	$Ra_T=rac{glpha\Delta_TH^3}{ u\kappa_T}$ is Thermal Rayleigh

Parameters	Double- diffusive convection (Singh & Srinivasan 2014)	Double- diffusive convection (normalized by free-fall velocity) (Yang et al. JFM 2021)	Binary fluid convection (Mercader et al. JFM 2013)	Stratified plane Couette flow (Langham et al. JFM 2019)	Description
					number
$p_3$	1	1	$1+R_{sep}$	-Ri	$R_{sep}$ is Separation ratio
$p_4$	$rac{1}{R_{ ho}}$	$rac{1}{R_{ ho}}$	$R_{sep}$		$R_ ho = rac{lpha \Delta_T}{eta \Delta_S}$ is Density stability ratio
$p_5$	1	$\frac{1}{\sqrt{Pr_TRa_T}}$	1	$\frac{1}{RePr}$	$Re=rac{Uh}{ u}$ is Raynolds number
$p_6$	$\frac{1}{Le}$	$rac{1}{Le\sqrt{Pr_TRa_T}}$	$\frac{1}{Le}$		$Le=rac{\kappa_T}{\kappa_S}$ is Lewis number
$p_7$			1		Ri is Richardson number

Notes that if you don't define  $p_5$  or  $p_6$ , corresponding scalar's governing equations and buoyancy components  $(p_3,\,p_4)$  in momentum equations will be removed. You can create a new your own governing equations.

A correct defination looks like this

```
// Example 1: Stationary-wall bounded double-diffusive convection [Yang2016PNAS]
// Boundary velocity is not normalized into unit velocity, don't know exact U0
// Only use this form for stationary walls
// #define P1 Pr
// #define P2 Pr*Ra
// #define P3 1.0
// #define P4 1.0/Rrho
// #define P5 1.0
// #define P6 1.0/Le
// Example 2: Moving-wall bounded double-diffusive convection [Yang2021JFM]
// Velocity is normalized by free-fall velocity into unit velocity, U0=1.0
// For example, Ua=-0.5 Ub=0.5 or Ua=0 Ub=1
#define P1 sqrt(Pr/Ra)
#define P2 1.0
#define P3 1.0
#define P4 (1.0/Rrho)
#define P5 (1.0/sqrt(Pr*Ra))
#define P6 (1.0/(Le*sqrt(Pr*Ra)))
// Example 3: Binary fluid convection [Mercader2013JFM]
// #define P1 Pr
// #define P2 Pr*Ra
// #define P3 (1.0+Rsep)
// #define P4 Rsep
// #define P5 1.0
// #define P6 1.0/Le
// #define P7 1.0
// Example 4: Couette flow
// #define P1 1.0/Rey
// Example 5: Stratified plane Couette flow [Langham2019JFM]
// #define P1 1.0/Rey
// #define P2 Rey
// #define P3 (-Ri)
// #define P5 1.0/(Rey*Pr)
```

# Running executable files

A exact executable command likes this:

```
mpiexec -n <ncpu> ./<exename> <option1> <option2> ...
```

#### with controling parameters

Option	Default	Description
-Nx <value></value>	200	Number of points along x-direction
-Ny <value></value>	101	Number of points along y-direction, notes that $N_y$ is odd number
-Nz <value></value>	6	Number of points along z-direction, minimal number is 6 ( can be used for 2D setup)
-Lx <value></value>	2	Streamwise length
-Lz <value></value>	0.004	Spanwise length, default setup is a small length representing 2D domain
-Pr <value></value>	10	Prandtl number $Pr=rac{ u}{\kappa_T}$
-Ra <value></value>	$10^{3}$	Thermal Rayleigh number $Ra_T=rac{glpha\Delta TH^3}{ u\kappa_T}$
-Le <value></value>	100	Lewis number $Le=rac{\kappa_T}{\kappa_S}$
-Rr <value></value>	2	Density stability ratio $R_ ho = rac{lpha \Delta T}{eta \Delta S}$
-Ua <value></value>	0	X-velocity at lower wall, U(y=a)
-Ub <value></value>	0	X-velocity at upper wall, U(y=b)
-Wa <value></value>	0	Z-velocity at lower wall, W(y=a)
-Wb <value></value>	0	Z-velocity at upper wall, W(y=b)
-Ta <value></value>	0	Temperature at lower wall, T(y=a)
-Tb <value></value>	1	Temperature at upper wall, T(y=b)

Option	Default	Description
-Sa <value></value>	0	Salinity at lower wall, S(y=a)
-Sb <value></value>	1	Salinity at upper wall, S(y=b)
-T0 <value></value>	0	Start time of DNS
-T <value></value>	20	Final time of DNS
-dt <value></value>	0.03125	Timestep
-dT <value></value>	1	Save interval
-nl <value></value>	"rot"	Method of calculating nonlinearity, one of [rot conv div skew alt linear]

### Examples:

```
mpiexec -n 16 ./ddc_simulateflow -Pr 10 -Ra 1000 -Le 100 -Rr 2 -dt 0.02 -dT 1 -T 100 -Nx 200 -Ny 8
```