User Guide for SLIP LU, A Sparse Left-Looking Integer Preserving LU Factorization

Version 1.0.0, March 2020

Christopher Lourenco, Jinhao Chen, Erick Moreno-Centeno, Timothy A. Davis Texas A&M University

Contact Information: Contact Chris Lourenco, chrisjlourenco@gmail.com, or Tim Davis, timdavis@aldenmath.com, davis@tamu.edu, DrTimothyAldenDavis@gmail.com

Contents

1	Summary				
2	Availability				
3	3 Installation				
4	Ove	rview	of User Data Structures	8	
	4.1	SLIP_:	info: status code returned by SLIP LU	9	
	4.2	SLIP_]	pivot: enum for pivoting schemes	9	
	4.3	SLIP_	col_order: enum for column ordering schemes	10	
	4.4	SLIP_	options structure	10	
	4.5	The SI	LIP_sparse structure	12	
	4.6	The SI	LIP_dense structure	13	
	4.7	SLIP_	LU_analysis structure	14	
5	Ove	rview	of SLIP LU User-Callable Routines	15	
	5.1	Memo	ry Management Routines	15	
		5.1.1	SLIP_calloc: allocate initialized memory	15	
		5.1.2	SLIP_malloc: allocate uninitialized memory	15	
		5.1.3	SLIP_realloc: resize allocated memory	15	
		5.1.4	SLIP_free: free allocated memory	16	
		5.1.5	SLIP_initialize: initialize the working environment	16	
		5.1.6	SLIP_initialize_expert: initialize the working environment (ex-		
			pert version)	17	
		5.1.7	SLIP_finalize: free the working environment	18	
		5.1.8	SLIP_create_default_options: create default SLIP_option object	18	
		5.1.9	SLIP_create_sparse: create empty sparse matrix	19	
		5.1.10	SLIP_delete_sparse: delete sparse matrix	19	
		5.1.11	SLIP_create_dense: create empty dense matrix	19	
		5.1.12	SLIP_delete_dense: delete dense matrix	19	
		5.1.13	SLIP_create_LU_analysis: create SLIP_LU_analysis structure	20	
		5.1.14	${\tt SLIP_delete_LU_analysis: \ delete\ SLIP_LU_analysis\ structure\ .\ .}$	20	
	5.2	Matrix	Building Routines	20	
		5.2.1	SLIP_build_sparse_csc_double: build sparse matrix using CSC		
			with double entries	21	
		5.2.2	SLIP_build_sparse_csc_int: build sparse matrix using CSC with		
			int32_t entries	21	
		5.2.3	SLIP_build_sparse_csc_mpq: build sparse matrix using CSC with		
			mpq_t entries	22	

	5.2.4	SLIP_build_sparse_csc_mpfr: build sparse matrix using CSC with mpfr_t entries	22
	5.2.5	SLIP_build_sparse_csc_mpz: build sparse matrix using CSC with	42
	0.2.0	mpz_t entries	23
	5.2.6	SLIP_build_sparse_trip_double: build sparse matrix using triplet	20
	0.2.0	with double entries	23
	5.2.7	SLIP_build_sparse_trip_int: build sparse matrix using triplet	20
	0.2.1	with int32_t entries	24
	5.2.8	SLIP_build_sparse_trip_mpq: build sparse matrix using triplet	
	0.2.0	with mpq_t entries	24
	5.2.9	SLIP_build_sparse_trip_mpfr: build sparse matrix using triplet	
	0.2.0	with mpfr_t entries	25
	5.2.10	•	
		with mpz_t entries	25
	5.2.11	SLIP_build_dense_double: build dense matrix using 2D double	
		array	26
	5.2.12	SLIP_build_dense_int: build dense matrix using 2D int32_t array	26
	5.2.13	SLIP_build_dense_mpq: build dense matrix using 2D mpq_t array .	27
	5.2.14	SLIP_build_dense_mpfr: build dense matrix using 2D mpfr_t array	27
	5.2.15	SLIP_build_dense_mpz: build dense matrix using 2D mpz_t array .	27
5.3	Utility	Routines	28
	5.3.1	SLIP_LU_analyze: perform symbolic analysis	28
	5.3.2	SLIP_LU_factorize: perform LU factorization	28
	5.3.3	SLIP_LU_solve: solve the scaled linear system $LDUx = b$	29
	5.3.4	SLIP_permute_x: permute solution back to original form	30
	5.3.5	SLIP_check_solution: check if $A_{scaled}x = b_{scaled}$	30
	5.3.6	${\tt SLIP_scale_x:}$ scale solution with scaling factors of A and b	31
	5.3.7	SLIP_get_double_soln: obtain solution in double type	31
	5.3.8	SLIP_get_mpfr_soln: obtain solution in mpfr_t type	31
	5.3.9	SLIP_solve_double: solve $Ax = b$ and return x in double type	32
		SLIP_solve_mpq: solve $Ax = b$ and return x in mpq_t type	32
		SLIP_solve_mpfr: solve $Ax = b$ and return x in mpfr_t type	33
5.4		laneous Routines	34
	5.4.1	·	34
	5.4.2	SLIP_delete_double_mat: delete a m-by-n double matrix	35
	5.4.3	SLIP_create_int_mat: create a m-by-n int32_t matrix	35
	5.4.4	SLIP_delete_int_mat: delete a m-by-n int32_t matrix	35
	5.4.5	SLIP_create_mpfr_mat: create a m-by-n mpfr_t matrix	35
	5.4.6	SLIP_delete_mpfr_mat: delete a m-by-n mpfr_t matrix	36
	5.4.7	SLIP_create_mpq_mat: create a m-by-n mpq_t matrix	36
	5.4.8	SLIP_delete_mpq_mat: delete a m-by-n mpq_t matrix	36

		5.4.9 SLIP_create_mpz_mat: create a m-by-n mpz_t matrix
		5.4.10 SLIP_delete_mpz_mat: delete a m-by-n mpz_t matrix
		$5.4.11$ SLIP_create_mpfr_array: create a mpfr_t of length n
		$5.4.12$ SLIP_delete_mpfr_array: delete a mpfr_t of length n
		$5.4.13$ SLIP_create_mpq_array: create a mpq_t of length n
		$5.4.14$ SLIP_delete_mpq_array: delete a mpq_t of length n
		$5.4.15$ SLIP_create_mpz_array: create a mpz_t of length n
		$5.4.16$ SLIP_delete_mpz_array: delete a mpz_t of length n
		5.4.17 SLIP_spok: check and print a SLIP_sparse matrix
	5.5	Miscellaneous Routines2
		5.5.1 SLIP_read_matrix
		5.5.2 SLIP_read_rhs 40
	5.6	SLIP LU GMP and MPFR Wrappers
6	Usi	ng SLIP LU in C
	6.1	SLIP LU Initialization and Population of Data Structures
		6.1.1 Initializing the Environment
		6.1.2 Initializing Data Structures
		6.1.3 Populating Data Structures
	6.2	SLIP LU Symbolic Analysis
	6.3	Easy SLIP LU for Solving Linear Systems (no L and U) 50
	6.4	Complex SLIP LU for Solving Linear Systems (with L and U) 51
		6.4.1 Allocating New Memory
		6.4.2 Computing the Factorization
		6.4.3 Solving the Linear System
		6.4.4 Permuting the Solution Vectors
		6.4.5 Scaling the Solution Vectors
		6.4.6 Converting the Solution Vector to the User's Desired Form 53
	6.5	SLIP LU Freeing all Used Memory
	6.6	Examples of Using SLIP LU in a C Program
7	Usi	ng SLIP LU in MATLAB 55
	7.1	SLIP_get_options.m 55
	7 2	CITD III m

1 Summary

SLIP LU is a software package designed to exactly solve unsymmetric sparse linear systems, $A\mathbf{x} = \mathbf{b}$, where $A \in \mathbb{Q}^{n \times n}$, $b \in \mathbb{Q}^{n \times m}$, and $\mathbf{x} \in \mathbb{Q}^{n \times m}$. This package performs a left-looking, roundoff-error-free (REF) LU factorization PAQ = LDU, where L and U are integral, D is diagonal, and P and Q are row and column permutations, respectively. It is important to note that the matrix D is never explicitly computed nor needed; thus the functional form of the factorization requires only the matrices L and U. The theory associated with this code is the Sparse Left-looking Integer-Preserving (SLIP) LU factorization [8]. Aside from solving sparse linear systems exactly, one of the key goals of this package is to provide a framework for other solvers to benchmark the reliability and stability of their linear solvers, as our final solution vector \mathbf{x} is guaranteed to be exact. In addition, SLIP LU provides a wrapper class for the GNU Multiple Precision Arithmetic (GMP) [7] and GNU Multiple Precision Floating Point Reliable (MPFR) [6] libraries in order to prevent memory leaks and improve the overall stability of these external libraries. SLIP LU is written in ANSI C and is accompanied by a MATLAB interface.

The user's input matrix A and right hand side vectors \mathbf{b} are read from either double, int, mpq_t, mpz_t, or mpfr_t data types. A must be stored in either sparse compressed column form or sparse triplet form while \mathbf{b} must be stored as a dense matrix. A discussion of building each of these types of input is given in Section 5.2.

The matrices L and U are computed using internal, integer-preserving routines with the big integer (mpz_t) data types from the GMP Library [7]. The matrices L and U are computed one column at a time, where each column is computed via the sparse REF triangular solve detailed in [8]. All divisions performed in the algorithm are guaranteed to be exact (i.e., integral); therefore, no greatest common divisor algorithms are needed to reduce the size of entries.

The matrices P and Q are either user specified or determined dynamically during the factorization. For the matrix P, the default option is to use a partial pivoting scheme in which the diagonal entry in column k is selected if it is the same magnitude as the smallest entry of k-th column, otherwise the smallest entry is selected as the k-th pivot. In addition to this approach, the code allows diagonal pivoting, partial pivoting which selects the largest pivot, or various tolerance based diagonal pivoting schemes. For the matrix Q, the default ordering is the Column Approximate Minimum Degree (COLAMD) algorithm [4, 5]. Other approaches include using the Approximate Minimum Degree (AMD) ordering [1, 2], a user specified column ordering (i.e., the default column ordering applied to the input matrix). A discussion of how to select these matrices prior to factorization is given in Section 5.

Once the factorization LDU = PAQ is computed, the vector \mathbf{x} is computed via sparse REF forward and backward substitution. The forward substitution is a variant of the sparse REF triangular solve discussed above. The backward substitution is a typical column oriented sparse backward substitution. Both of these routines assume that the right hand side vector(s) \mathbf{b} are dense. At the conclusion of the forward and backward substitution routines, the final solution vector(s) \mathbf{x} are guaranteed to be exact and is stored using the GMP mpq_t data structure.

The final phase of SLIP LU comprises output routines. If the user desires it, their final solution vector(s) can be output in the aforementioned mpq_t data type. Alternatively, the solution vector(s) can be output in double precision or to any user desired precision via the $mpfr_t$ data type. One key advantage of utilizing SLIP LU with floating-point output is that the solution is guaranteed to be exact until this final conversion; meaning that roundoff errors are only introduced in the final conversion from rational numbers. Thus, the solution vector(s) output in double precision are accurate to machine roundoff (approximately 10^{-16}) and SLIP LU utilizes higher precision for the MPFR output; thus it is also accurate to user specified precision.

All left-hand side matrices (referred to as A henceforth) within this package are stored in compressed sparse column form (CSC). This data structure stores the matrix A as a sequence of three arrays:

- A->p: Column pointers; an array of size n+1. The row indices of column j are located in positions A->p[j] to A->p[j+1]-1 of the array A->i. Data type: int32_t.
- A->i: Row indices; an array of size equal to the number of entries in the matrix. The entry A->i[k] is the row index of the kth nonzero in the matrix. Data type: int32_t.
- A->x: Numeric entries. The entry A->x[k] is the numeric value of the kth nonzero in the matrix. Data type: mpz_t.

An example matrix A is stored as follows (notice that via C convention, the indexing is zero based).

$$A = \begin{bmatrix} 1 & 0 & 0 & 1 \\ 2 & 0 & 4 & 12 \\ 7 & 1 & 1 & 1 \\ 0 & 2 & 3 & 0 \end{bmatrix}$$

$$A \rightarrow p = [0, 3, 5, 8, 11]$$

 $A \rightarrow i = [0, 1, 2, 2, 3, 1, 2, 3, 0, 1, 2]$
 $A \rightarrow x = [1, 2, 7, 1, 2, 4, 1, 3, 1, 12, 1]$

For example, the last column appears in positions 8 to 10 of A->i and A->x, with row indices 0, 1, and 2, and values $a_{03} = 1$, $a_{13} = 12$, and $a_{23} = 1$.

2 Availability

Copyright: This software is copyright by Christopher Lourenco, Jinhao Chen, Erick Moreno-Centeno, and Timothy Davis.

Contact Info: Contact Chris Lourenco, chrisjlourenco@gmail.com, or Tim Davis, timdavis@aldenmath.com, davis@tamu.edu, or DrTimothyAldenDavis@gmail.com

Licence: This software package is dual licensed under the GNU General Public License version 2 or the GNU Lesser General Public License version 3. Details of this license can be seen in the directory SLIP_LU/License/license.txt. In short, SLIP LU is free to use for research purposes. For a commercial license, please contact the authors.

Location: https://github.com/clouren/SLIP_LU and www.suitesparse.com
Required Packages: SLIP LU requires the installation of AMD [1, 2], COLAMD [5, 4], SuiteSparse_config [3], the GNU GMP [7] and GNU MPFR [6] libraries. AMD and COLAMD are available under a BSD 3-clause license, and no license restrictions apply to SuiteSparse_config. Notice that AMD, COLAMD, and SuiteSparse_config are included in this distribution for users' convenience. The GNU GMP and GNU MPFR library can be acquired and installed from https://gmplib.org/ and http://www.mpfr.org/ respectively.

If a user is running Unix that is Debian/Ubuntu based, a compatible version of GMP and MPFR can be installed with the following terminal commands:

```
sudo apt-get install libgmp3-dev
sudo apt-get install libmpfr-dev libmpfr-doc libmpfr4 libmpfr4-dbg
```

3 Installation

Installation of SLIP LU requires the make utility in Linux or Cygwin make in Windows. With the proper compiler, typing make under the main directory will compile AMD, COLAMD and SLIP LU to the respective SLIP_LU/Lib folder. To further install the libraries onto your computer, simply type make install. Thereafter, to use the code inside of your program, precede your code with #include "SLIP_LU.h".

If you want to use SLIP LU within MATLAB, from your installation of MATLAB, cd to the folder SLIP_LU/SLIP_LU/MATLAB then type SLIP_install. This

should compile the necessary code so that you can use SLIP LU within MATLAB. Note that this file does not add the correct directory to your path; therefore, if you want SLIP LU as a default function, type pathtool and save your path for future MATLAB sessions. If you cannot save your path because of file permissions, edit your startup.m by adding addpath commands (type doc startup and doc addpath for more information).

4 Overview of User Data Structures

There are four important data structures used throughout the SLIP LU package: SLIP_options, SLIP_sparse, SLIP_dense, and SLIP_LU_analysis. We describe them briefly below and more in detail in this section.

- SLIP_options: Contains numerous command parameters. Default values of these parameters are good for a general user; however, modifying this struct allows a user to control column orderings, pivoting schemes, and other components of the factorization.
- SLIP_sparse: A sparse matrix for SLIP LU. These matrices are stored in the aforementioned sparse CSC form with mpz_t entries.
- SLIP_dense: A dense matrix for SLIP LU. Primarily used for the RHS vector(s) b.
- SLIP_LU_analysis: A symbolic analysis struct. Contains the column permutation and guesses for the number of nonzeros in L and U.

Furthermore, three enumerated types (enum) are defined and used: SLIP_pivot, SLIP_col_order and SLIP_info. Again we briefly describe them below and in more detail later in this section.

- SLIP_pivot: Types of pivoting scheme available for the user.
- SLIP_col_order: Type of column preordering available for the user.
- SLIP_info: Status codes for SLIP LU. Most function return a status indicating success or, in the case of failure, what went wrong.

Lastly, SLIP LU defines the following strings with #define. Refer to SLIP_LU.h file for details.

Macro	purpose
SLIP_LU_VERSION	current version of the code
SLIP_LU_VERSION_MAJOR	major version of the code
SLIP_LU_VERSION_MINOR	minor version of the code
SLIP_LU_VERSION_SUB	sub version of the code
SLIP_PAPER	name of associated paper
SLIP_AUTHOR	authors of the code

The remainder of this section describes each of these data structures and enumerated types.

4.1 SLIP_info: status code returned by SLIP LU

Most of SLIP LU functions return its status to the caller as its return value, an enumerated type called SLIP_info. All possible values for SLIP_info are listed as follows:

0	SLIP_OK	The function was successfully executed.
-1	SLIP_OUT_OF_MEMORY	out of memory
-2	SLIP_SINGULAR	The input matrix A is exactly singular.
-3	SLIP_INCORRECT_INPUT	One or more input arguments are incorrect.
-4	SLIP_INCORRECT	The solution is incorrect.

4.2 SLIP_pivot: enum for pivoting schemes

There are six available pivoting schemes provided in SLIP LU. Users can set the pivoting method through the SLIP_options structure in Section 4.4. Note that the pivot is always nonzero, thus the smallest entry is the nonzero entry with the smallest magnitude. Also, the tolerance is specified by the tol component in SLIP_options. Please refer to Section 4.4 for details of this parameter. The pivoting schemes are described as follows:

0	SLIP_SMALLEST	The k-th pivot is selected as the smallest entry in the kth
		column.
1	SLIP_DIAGONAL	The k-th pivot is selected as the diagonal entry. If the di-
		agonal entry is zero, this method instead selects the smallest
		pivot in the column.
$\overline{2}$	SLIP_FIRST_NONZERO	The k-th pivot is selected as the first eligible nonzero in the
		column.
3	SLIP_TOL_SMALLEST	The k-th pivot is selected as the diagonal entry if the diagonal
		is within a specified tolerance of the smallest entry in the
		column. Otherwise, the smallest entry in the k -th column is
		selected. This is the default pivot selection strategy.
4	SLIP_TOL_LARGEST	The k-th pivot is selected as the diagonal entry if the diago-
		nal is within a specified tolerance of the largest entry in the
		column. Otherwise, the largest entry in the k -th column is
		selected.
5	SLIP_LARGEST	The k -th pivot is selected as the largest entry in the k -th
		column.

4.3 SLIP_col_order: enum for column ordering schemes

The SLIP LU library provides three column ordering schemes: no ordering, CO-LAMD, and AMD. Users can set the column ordering method through order component in the SLIP_option structure described in Section 4.4. In general, it is recommended that the user selects the COLAMD ordering, however, no preordering can be preferable if the user's matrix already has a good preordering.

0	SLIP_NO_ORDERING	No pre-ordering is performed on the matrix A , that is $Q = I$.
1	SLIP_COLAMD	The columns of A are permuted prior to factorization using
		the COLAMD [4] ordering. This is the default ordering.
2	SLIP_AMD	The nonzero pattern of $A + A^T$ is analyzed and the columns
		of A are permuted prior to factorization based on the AMD
		[2] ordering of $A + A^T$. This works well if A has a mostly
		symmetric pattern, but tends to be worse than COLAMD on
		matrices with unsymmetric pattern. [5].

4.4 SLIP_options structure

The SLIP_options struct stores key command parameters for various functions used in the SLIP LU package. The SLIP_options* option struct contains the following components:

- option->pivot: An enum SLIP_pivot type (discussed in Section 4.2) which controls the type of pivoting used. Default value: SLIP_TOL_SMALLEST (3).
- option->order: An enum SLIP_col_order type (discussed in Section 4.3) which controls what column ordering is used. Default value: SLIP_COLAMD (1).
- option->tol: A double which tells the tolerance used if the user selects a tolerance based pivoting scheme, i.e., SLIP_TOL_SMALLEST or SLIP_TOL_LARGEST. option->tol must be in the range of (0, 1]. Default value: 1 meaning that the diagonal entry will be selected if it has the same magnitude as the smallest entry in the k the column.
- option->print_level: An int32_t which controls the amount of output. 0: print nothing, 1: just errors, 2: terse, with basic stats from COLAMD/AMD and SLIP, 3: all, with matrices and results. Default value: 0.
- option->prec: An int64_t which specifies the precision used if the user desires multiple precision floating point numbers, (i.e., MPFR). This can be any integer larger than MPFR_PREC_MIN (value of 1 in MPFR 4.0.2 and 2 in some legacy versions) and smaller than MPFR_PREC_MAX (usually the largest possible int available in your system). Default value: 128 (quad precision).
- option->SLIP_MPFR_ROUND: A mpfr_rnd_t which determines the type of MPFR rounding to be used by SLIP LU. This is a parameter of the MPFR library. The options for this parameter are:
 - MPFR_RNDN: round to nearest (roundTiesToEven in IEEE 754-2008)
 - MPFR_RNDZ: round toward zero (roundTowardZero in IEEE 754-2008)
 - MPFR_RNDU: round toward plus infinity (roundTowardPositive in IEEE 754-2008)
 - MPFR_RNDD: round toward minus infinity (roundTowardNegative in IEEE 754-2008)
 - MPFR_RNDA: round away from zero
 - MPFR_RNDF: faithful rounding. This is not stable.

By default, SLIP LU utilizes MPFR_RNDN. We refer the reader to the MPFR user guide available at https://www.mpfr.org/mpfr-current/mpfr.pdf for details on the MPFR rounding style and any other utilized MPFR convention.

The SLIP LU package uses the following function/macro to create and destroy a SLIP_options object.

function/macro name	description	section
SLIP_create_default_options	create and return SLIP_options pointer with default parameters upon successful allocation	5.1.8
SLIP_FREE	destroy SLIP_options object	5.1.4

4.5 The SLIP_sparse structure

All internal left-hand side matrices are stored in compressed sparse column form (CSC) via the SLIP_sparse structure. A sparse matrix SLIP_sparse *A has the following components:

- A->m: Number of rows in the matrix. It is typically assumed that m = n. Data Type: int32_t
- A->n: Number of columns in the matrix. It is typically assumed that m = n. Data Type: int32_t
- A->nz: The number of nonzeros in the matrix A. Data Type: int32_t
- A->nzmax: The allocated size of the vectors A->x and A->i. Note that A->nzmax
 ≥ A->nz. Internally, this parameter serves as an estimate on the amount of
 memory needed and is used to reduce the number of intermediate reallocations
 performed in the library. Data Type: int32_t
- A->p: An array of size n+1 which contains column pointers of A. Data Type: int32_t*
- A->i: An array of size A->nzmax which contains the row indices of the nonzeros in A. The matrix is zero based therefore indices are in the range of [0, n-1]. Data Type: int32_t*
- A->x: An array of size A->nzmax which contains the numeric values of the matrix. Data Type: mpz_t*
- A->scale: A scaling parameter that ensures integrality if the input sparse matrix is stored as either double, variable precision floating point, or rational. Data Type: mpq_t

The SLIP LU package has a set of functions to create, build and destroy a SLIP LU sparse matrix, SLIP_sparse, as shown in the following table.

function name	description	section
SLIP_create_sparse	create empty sparse matrix	5.1.9
SLIP_build_sparse_csc_double	build sparse matrix from double type CSC matrix	5.2.1
SLIP_build_sparse_csc_int	build sparse matrix from int32_t type CSC matrix	5.2.2
SLIP_build_sparse_csc_mpq	build sparse matrix from mpq_t type CSC matrix	5.2.3
SLIP_build_sparse_csc_mpfr	build sparse matrix from mpfr_t type CSC matrix	5.2.4
SLIP_build_sparse_csc_mpz	build sparse matrix from mpz_t type CSC matrix	5.2.5
SLIP_build_sparse_trip_double	build sparse matrix from double type triplet-format matrix	5.2.6
SLIP_build_sparse_trip_int	build sparse matrix from int32_t type triplet-format matrix	5.2.7
SLIP_build_sparse_trip_mpq	build sparse matrix from mpq_t type triplet-format matrix	5.2.8
SLIP_build_sparse_trip_mpfr	build sparse matrix from mpfr_t type triplet-format matrix	5.2.9
SLIP_build_sparse_trip_mpz	build sparse matrix from mpz_t type triplet-format matrix	5.2.10
SLIP_delete_sparse	destroy sparse matrix	5.1.10

4.6 The SLIP_dense structure

All internal right-hand side matrices are stored as dense matrice, using the SLIP_dense structure. A dense matrix SLIP_dense *b has the following components:

- b->m: Number of rows in the matrix. Data Type: int32_t
- b->n: Number of columns in the matrix. Data Type: int32_t
- b->x: A 2D array of size m-by-n which contains the numeric values of the matrix. Data Type: mpz_t**
- b->scale: A scaling parameters that ensures integrality if the input dense matrix is stored as either double, variable precision floating point, or rational. Data Type: mpq_t

The SLIP LU package has a set of functions to create, build and destroy a SLIP LU dense matrix, SLIP_dense, described in the following table:

function name	description	section
SLIP_create_dense	create empty dense matrix	5.1.11
SLIP_build_dense_double	build dense matrix from double type CSC matrix	5.2.11
SLIP_build_dense_int	build dense matrix from int32_t type CSC matrix	5.2.12
SLIP_build_dense_mpq	build dense matrix from mpq_t type CSC matrix	5.2.13
SLIP_build_dense_mpfr	build dense matrix from mpfr_t type CSC matrix	5.2.14
SLIP_build_dense_mpz	build dense matrix from mpz_t type CSC matrix	5.2.15
SLIP_delete_dense	destroy dense matrix	5.1.12

4.7 SLIP_LU_analysis structure

The SLIP_LU_analysis data structure is used for storing the column permutation for LU and the guess on nonzeros for L and U. Users do not need to modify this struct, just pass it into the functions. A SLIP_LU_analysis structure has the following components:

- S->q: The column permutation stored as a dense int32_t vector of size n+1, where n is the number of rows of the analyzed matrix. Currently this vector is obtained via COLAMD, AMD, or is set to no ordering (i.e., [0, 1, ..., n-1]).
- S->lnz: An int32_t which is a guess for the number of nonzeros in L. S->lnz must be greater than or equal to n and less than or equal to n^2 . If S->lnz is too small, the program may waste time performing extra memory reallocations. This is set during the symbolic analysis.
- S->unz: An int32_t which is a guess for the number of nonzeros in U. S->unz must be greater than or equal to n and less than or equal to n^2 . If S->unz is too small, the program may waste time performing extra memory reallocations. This is set during the symbolic analysis.

The SLIP LU package provides the following functions to create and destroy a SLIP_LU_analysis object:

function/macro name	description	section
SLIP_create_LU_analysis	${ m create}$ SLIP_LU_analysis ${ m object}$	5.1.13
SLIP_delete_LU_analysis	destroy SLIP_LU_analysis object	5.1.14

5 Overview of SLIP LU User-Callable Routines

This section provides a brief overview of the user callable routines in SLIP LU. A comprehensive list of these routines is located in the SLIP_LU.h file. For each of these functions, this section briefly describes its purpose, syntax, input arguments, and output.

5.1 Memory Management Routines

The routines in this section are used to allocate and free memory for the data structures used in SLIP LU.

5.1.1 SLIP_calloc: allocate initialized memory

SLIP_calloc allocates a block of memory for an array of n elements, each of them size bytes long, and initializes all its bits to zero. If any input is equal to zero, it is treated as if equal to 1. If the function failed to allocate the requested block of memory, then a NULL pointer is returned.

5.1.2 SLIP_malloc: allocate uninitialized memory

```
void * SLIP_malloc
(
    size_t size  // Size to alloc
);
```

SLIP_malloc allocates a block of size bytes of memory, returning a pointer to the beginning of the block. The content of the newly allocated block of memory is not initialized, remaining with indeterminate values. If the size is zero, it is treated as if equal to 1. If the function fails to allocate the requested block of memory, then a NULL pointer is returned.

5.1.3 SLIP_realloc: resize allocated memory

SLIP_realloc attempts to resize the memory block pointed to by p that was previously allocated with a call to SLIP_malloc or SLIP_calloc. In the case when the function fails to allocate new block of memory as required and the newly required memory size is smaller than the old one, then the old block is kept unchanged and SLIP_realloc pretends to succeed. Otherwise, the function returns either NULL when it fails, or the new block of memory when it succeeds.

5.1.4 SLIP_free: free allocated memory

SLIP_free deallocates the memory previously allocated by a call to SLIP_calloc, SLIP_malloc, or SLIP_realloc. Note that the default C free function can cause a segmentation fault if called multiple times on the same pointer or is called via other inappropriate behavior. To remedy this issue, this function frees the input pointer p only when it is not NULL. To further prevent the potential segmentation fault that could be caused by free, the following macro SLIP_FREE is provided, which sets the free'd pointer to NULL.

5.1.5 SLIP_initialize: initialize the working environment

```
void SLIP_initialize
(
     void
);
```

SLIP_initialize initializes the working environment for SLIP LU functions. SLIP LU utilizes a specialized memory management scheme in order to prevent potential memory failures caused by GMP library. This function **must** be called prior to using the library. See the next section SLIP_initialize_expert for more details.

5.1.6 SLIP_initialize_expert: initialize the working environment (expert version)

SLIP_initialize_expert initializes the working environment for SLIP LU with custom memory functions that are used for GMP. If the user passes in their own malloc, realloc, or free function(s), we use those internally to process memory. If a NULL pointer is passed in for any function, then default functions are used.

The three functions are similar to ANSI C malloc, realloc, and free functions, but the calling syntax is not the same. Below are the definitions that **must** be followed, per the GMP specification:

```
void *MyMalloc (size_t size) ; // same as the ANSI C malloc
void *MyRealloc (void *p, size_t oldsize, size_t newsize) ; // differs
void MyFree (void *p, size_t size) ; // differs
```

MyMalloc has identical parameters as the the ANSI C malloc. MyRealloc adds a parameter, oldsize, which is the prior size of the block of memory to be reallocated. MyFree takes a second argument, which is the size of the block that is being free'd.

The default memory management functions used inside of SLIP LU's GMP interface are:

```
MyMalloc slip_gmp_allocate
MyRealloc slip_gmp_reallocate
MyFree slip_gmp_free
```

The slip_gmp_* memory management functions are unique to SLIP LU Library. They provide an elegant workaround for how GMP manages its memory. By default, if GMP attempts to allocate memory, but it fails, then it simply terminates the

user application. This behavior is not suitable for many applications (MATLAB in particular). Fortunately, GMP allows the user application (SLIP LU in this case) to pass in alternative memory manager functions, via mp_set_memory_functions. The slip_gmp_* functions do not return to GMP if the allocation fails, but instead use the longjmp feature of ANSI C to implement a try/catch mechanism. The memory failure can then be safely handled by SLIP LU, without memory leaks and without terminating the user application.

When SLIP LU is used via MATLAB, the following functions are used instead:

```
MyMalloc mxMalloc
MyRealloc slip_gmp_mex_realloc (a wrapper for mxRealloc)
MyFree slip_gmp_mex_free (a wrapper for mxFree)
```

Note that these functions are not used by SLIP LU itself, but only inside GMP. The functions used by SLIP LU itself are SLIP_malloc, SLIP_calloc, SLIP_realloc, and SLIP_free, which are wrappers for the ANSI C malloc, calloc, realloc, and free (see Sections 5.1.1-5.1.4), or (if used inside MATLAB), for the MATLAB mxMalloc, mxCalloc, mxRealloc, and mxFree functions.

5.1.7 SLIP_finalize: free the working environment

```
void SLIP_finalize
(
    void
);
```

SLIP_finalize frees the working environment for SLIP LU library. SLIP LU utilizes a specialized memory management scheme in order to prevent memory failures. Calling the function SLIP_finalize after you are finished using the library ensures all memory is freed.

5.1.8 SLIP_create_default_options: create default SLIP_option object

```
SLIP_options* SLIP_create_default_options
(
     void
);
```

SLIP_create_default_options creates and returns a pointer to a SLIP_options struct with default parameters upon successful allocation, which are discussed in Section 4.4. To safely free the SLIP_options* option structure, simply use SLIP_FREE(option).

5.1.9 SLIP_create_sparse: create empty sparse matrix

```
SLIP_sparse *SLIP_create_sparse
(
    void
);
```

SLIP_create_sparse allocates a new empty sparse matrix and returns a SLIP_sparse pointer to this matrix upon successful allocation. The returned matrix has size of 0-by-0 and scale parameter of 1. For methods to build the created sparse matrix, users can refer to the table in Section 4.5.

5.1.10 SLIP_delete_sparse: delete sparse matrix

```
void SLIP_delete_sparse
(
        SLIP_sparse **A // matrix to be deleted
);
```

SLIP_delete_sparse deletes the sparse matrix A. Note that the input of the function is the pointer to the pointer of a SLIP_sparse structure. This is because this function internally sets the pointer of a SLIP_sparse to be NULL to prevent potential segmentation fault that could be caused by double free.

5.1.11 SLIP_create_dense: create empty dense matrix

```
SLIP_dense *SLIP_create_dense
(
     void
);
```

SLIP_create_dense allocates a new empty dense matrix and returns a SLIP_dense pointer to this matrix upon successful allocation. The returned matrix has size of 0-by-0 and scale parameter of 1. For methods to build the created dense matrix, users can refer to the table in Section 4.6.

5.1.12 SLIP_delete_dense: delete dense matrix

```
void SLIP_delete_dense
(
```

```
SLIP_dense **A
);
```

SLIP_delete_dense deletes the dense matrix A. Note that the input of the function is the pointer to the pointer of a SLIP_dense structure. This is because this function internally sets the pointer of a SLIP_dense to be NULL to prevent potential segmentation fault that could be caused by double free.

5.1.13 SLIP_create_LU_analysis: create SLIP_LU_analysis structure

```
SLIP_LU_analysis *SLIP_create_LU_analysis
(
    int32_t n // length of S->q
);
```

This function allocates an object that will contain a symbolic analysis of an LU factorization, and returns a SLIP_LU_analysis pointer to this newly created object. The object contains an array S->q of length n (which needs to be 1 + number of rows of the analyzed matrix) upon successful allocation, otherwise, return NULL. Both lnz and unz are set to 0. For more information about the SLIP_LU_analysis structure, users can refer to Section 4.7.

5.1.14 SLIP_delete_LU_analysis: delete SLIP_LU_analysis structure

```
void SLIP_delete_LU_analysis
(
        SLIP_LU_analysis **S // Structure to be deleted
);
```

SLIP_delete_LU_analysis deletes a SLIP_LU_analysis structure. Note that the input of the function is the pointer to the pointer of a SLIP_LU_analysis structure. This is because this function internally sets the pointer of a SLIP_LU_analysis to be NULL to prevent potential segmentation fault that could be caused by double free.

5.2 Matrix Building Routines

The routines in this section are used to build either the sparse matrix or the dense matrix.

5.2.1 SLIP_build_sparse_csc_double: build sparse matrix using CSC with double entries

```
SLIP_info SLIP_build_sparse_csc_double

(

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *p, // The set of column pointers int32_t *I, // set of row indices

double *x, // Set of values as doubles int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x and I vect);
```

SLIP_build_sparse_csc_double builds a sparse matrix using compressed column form inputs, where the entry values are double type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.2 SLIP_build_sparse_csc_int: build sparse matrix using CSC with int32_t entries

```
SLIP_info SLIP_build_sparse_csc_int

(

SLIP_sparse *A_output,// It should be initialized but unused yet int32_t *p, // The set of column pointers int32_t *I, // set of row indices int32_t *x, // Set of values as doubles int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x and I vect);
```

SLIP_build_sparse_csc_int builds a sparse matrix using compressed column form inputs, where the entry values are int32_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.3 SLIP_build_sparse_csc_mpq: build sparse matrix using CSC with mpq_t entries

```
SLIP_info SLIP_build_sparse_csc_mpq

(

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *p, // The set of column pointers int32_t *I, // set of row indices mpq_t *x, // Set of values as mpq_t rational numbers int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x and I vect);
```

SLIP_build_sparse_csc_mpq builds a sparse matrix using compressed column form inputs, where the entry values are mpq_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.4 SLIP_build_sparse_csc_mpfr: build sparse matrix using CSC with mpfr_t entries

SLIP_build_sparse_csc_mpfr builds a sparse matrix using compressed column form inputs, where the entry values are mpfr_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse

matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.5 SLIP_build_sparse_csc_mpz: build sparse matrix using CSC with mpz_t entries

```
SLIP_info SLIP_build_sparse_csc_mpz

(

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *p, // The set of column pointers int32_t *I, // set of row indices mpz_t *x, // Set of values in full precision int. int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x and I vect);
```

SLIP_build_sparse_csc_mpz builds a sparse matrix using compressed column form inputs, where the entry values are mpz_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.6 SLIP_build_sparse_trip_double: build sparse matrix using triplet with double entries

```
SLIP_info SLIP_build_sparse_trip_double

(

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *I, // set of row indices int32_t *J, // set of column indices double *x, // Set of values in double int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x, I, // and J vectors)
);
```

SLIP_build_sparse_trip_double builds a sparse matrix using triplet form inputs, where the entry values are double type. The input sparse matrix A_output

should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.7 SLIP_build_sparse_trip_int: build sparse matrix using triplet with int32_t entries

```
SLIP_info SLIP_build_sparse_trip_int

(

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *I, // set of row indices int32_t *J, // set of column indices int32_t *x, // Set of values in int int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x, I, // and J vectors)

);
```

SLIP_build_sparse_trip_int builds a sparse matrix using triplet form inputs, where the entry values are int32_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.8 SLIP_build_sparse_trip_mpq: build sparse matrix using triplet with mpq_t entries

```
SLIP_info SLIP_build_sparse_trip_mpq (

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *I, // set of row indices int32_t *J, // set of column indices mpq_t *x, // Set of values as rational numbers int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x, I // and J vectors)
);
```

SLIP_build_sparse_trip_mpq builds a sparse matrix using triplet form inputs, where the entry values are mpq_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.9 SLIP_build_sparse_trip_mpfr: build sparse matrix using triplet with mpfr_t entries

SLIP_build_sparse_trip_mpfr builds a sparse matrix using triplet form inputs, where the entry values are mpfr_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.10 SLIP_build_sparse_trip_mpz: build sparse matrix using triplet with mpz_t entries

```
SLIP_info SLIP_build_sparse_trip_mpz

(

SLIP_sparse *A_output, // It should be initialized but unused yet int32_t *I, // set of row indices int32_t *J, // set of column indices mpz_t *x, // Set of values in full precision int int32_t n, // dimension of the matrix int32_t nz // number of nonzeros in A (size of x, I,
```

```
);  /\!/ \ and \ J \ vectors)
```

SLIP_build_sparse_trip_mpz builds a sparse matrix using triplet form inputs, where the entry values are mpz_t type. The input sparse matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_sparse (in Section 5.1.9). WARNING: Using sparse matrix that has been built with SLIP_build_sparse_* as input would cause memory leak.

5.2.11 SLIP_build_dense_double: build dense matrix using 2D double array

```
SLIP_info SLIP_build_dense_double
(
SLIP_dense *A_output, // Dense matrix, allocated but unused
double **b, // Set of values as doubles
int32_t m, // number of rows
int32_t n // number of columns
);
```

SLIP_build_dense_double builds a dense matrix using 2D double array. The input dense matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_dense (in Section 5.1.11). WARNING: Using dense matrix that has been built with SLIP_build_dense_* as input would cause memory leak.

5.2.12 SLIP_build_dense_int: build dense matrix using 2D int32_t array

```
SLIP_info SLIP_build_dense_int
(

SLIP_dense *A_output, // Dense matrix, allocated but unused int32_t **b, // Set of values as ints int32_t m, // number of rows int32_t n // number of columns
);
```

SLIP_build_dense_int builds a dense matrix using 2D int32_t array. The input dense matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_dense (in Section 5.1.11). WARNING:

Using dense matrix that has been built with SLIP_build_dense_* as input would cause memory leak.

5.2.13 SLIP_build_dense_mpq: build dense matrix using 2D mpq_t array

```
SLIP_info SLIP_build_dense_mpq

(
SLIP_dense *A_output, // dense matrix, allocated but unused mpq_t **b, // set of values as mpq_t int32_t m, // number of rows int32_t n // number of columns
);
```

SLIP_build_dense_mpq builds a dense matrix using 2D mpq_t array. The input dense matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_dense (in Section 5.1.11). WARNING: Using dense matrix that has been built with SLIP_build_dense_* as input would cause memory leak.

5.2.14 SLIP_build_dense_mpfr: build dense matrix using 2D mpfr_t array

```
SLIP_info SLIP_build_dense_mpfr (

SLIP_dense *A_output, // Dense matrix, allocated but unused mpfr_t **b, // Set of values as mpfr_t int32_t m, // number of rows int32_t n, // number of columns SLIP_options *option // command options containing the prec for mpfr );
```

SLIP_build_dense_mpfr builds a dense matrix using 2D mpfr_t array. The input dense matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_dense (in Section 5.1.11). WARNING: Using dense matrix that has been built with SLIP_build_dense_* as input would cause memory leak.

5.2.15 SLIP_build_dense_mpz: build dense matrix using 2D mpz_t array

```
SLIP_info SLIP_build_dense_mpz

(

SLIP_dense *A_output, // Dense matrix, allocated but unused mpz_t **b, // Set of values in full precision int. int32_t m, // number of rows int32_t n // number of columns
);
```

SLIP_build_dense_mpz builds a dense matrix using 2D mpz_t array. The input dense matrix A_output should be a created empty matrix. The best practice is to use the one returned from SLIP_create_dense (in Section 5.1.11). WARNING: Using dense matrix that has been built with SLIP_build_dense_* as input would cause memory leak.

5.3 Utility Routines

These routines perform symbolic analysis, compute the factorization of the matrix A and solve Ax = B.

5.3.1 SLIP_LU_analyze: perform symbolic analysis

```
SLIP_info SLIP_LU_analyze
(
SLIP_LU_analysis *S, // symbolic analysis (column permutation and nnz
SLIP_sparse *A, // Input matrix
SLIP_options *option // Control parameters
);
```

SLIP_LU_analyze performs the symbolic ordering for SLIP LU. Currently, there are three options: user-defined order, COLAMD, or AMD, which are passed in by SLIP_option *option. For more details, users can refer to Section 4.4.

5.3.2 SLIP_LU_factorize: perform LU factorization

```
SLIP_info SLIP_LU_factorize
(
SLIP_sparse *L, // lower triangular matrix
SLIP_sparse *U, // upper triangular matrix
```

SLIP_LU_factorize performs the SLIP LU factorization. This factorization is done via n (number of rows in A) iterations of the sparse REF triangular solve function. The overall factorization is PAQ = LDU. This routine allows the user to separate factorization and solve. For example codes, please refer to either Demos/S-LIPLU.c or Section 6.4.

On input, both L and U should be created using SLIP_create_sparse (see Section 5.1.9), and both mpz_t *rhos and int32_t *pinv should be allocated as arrays of size n using SLIP_create_mpz_array (see Section 5.4.15) and SLIP_malloc (see Section 5.1.2), respectively.

On output, L and U are the lower and upper triangular matrices, **rhos** contains the sequence of pivots. The determinant of A can be obtained as **rhos**[n-1]. pinv contains the inverse row permutation (that is, the row index in the permuted matrix PA. For the *i*th row in A, p[i] gives the row index in PA).

5.3.3 SLIP_LU_solve: solve the scaled linear system LDUx = b

SLIP_LU_solve obtains the solution to the scaled linear system LDUx = b upon a successful factorization.

On input, mpq_t **x should be allocated as a 2D array of same size as b using SLIP_create_mpq_mat (see Section 5.4.7). The function is called upon successful return from SLIP_LU_factorize.

Upon completion, **x** contains the solution to the *scaled* linear system. Like some of the other routines discussed in this section, this function is primarily internal; thus for usage information please refer to either Demos/SLIPLU.c or Section 6.4.

5.3.4 SLIP_permute_x: permute solution back to original form

SLIP_permute_x permutes the solution vector(s) \mathbf{x} so that they are with respect to the chosen column permutation (that is, this function computes $Q\mathbf{x}$). The function is called upon successful return from SLIP_LU_solve.

Like some of the other routines discussed in this section, thus function is primarily internal; thus for usage information please refer to either Demos/SLIPLU.c or Section 6.4.

5.3.5 SLIP_check_solution: check if $A_{scaled}x = b_{scaled}$

```
SLIP_info SLIP_check_solution
(
SLIP_sparse *A,  // input matrix
mpq_t **x,  // solution vector
SLIP_dense *b  // right hand side
);
```

SLIP_check_solution checks the solution of the linear system. This function returns either SLIP_CORRECT or SLIP_INCORRECT.

This function is provided simply for integrity or as troubleshoot code. It is mostly not needed since the algorithm is designed to be exact. To use it correctly, SLIP_check_solution must be called before SLIP_scale_x. WARNING: SLIP_check_solution could return SLIP_INCORRECT if it is called after SLIP_solve_double (in Section 5.3.9), SLIP_solve_mpq (in Section 5.3.10) or SLIP_solve_mpfr (in Section 5.3.11).

5.3.6 SLIP_scale_x: scale solution with scaling factors of A and b

SLIP_scale_x scales solution vector with scaling factors of A and b. SLIP LU will scale the user's input matrix to ensure everything is integral; thus, once the rational solution vector x is obtained, it must be properly scaled so that it is accurate. Again, this is mainly an internal function, thus for usage, please refer to either Demos/SLIPLU.c or Section 6.4.

5.3.7 SLIP_get_double_soln: obtain solution in double type

SLIP_get_double_soln converts the mpq_t** solution vector obtained from SLIP_LU_solve and SLIP_permute_x to double**. This process introduces round-off error.

On input, double **x_doub should be allocated using SLIP_create_double_mat in Section 5.4.1.

5.3.8 SLIP_get_mpfr_soln: obtain solution in mpfr_t type

SLIP_get_mpfr_soln converts the mpq_t** solution vector obtained from SLIP_LU_solve and SLIP_permute_x to mpfr_t**. This process introduces round-off error.

On input, mpfr_t **x_mpfr should be allocated using SLIP_create_mpfr_mat in Section 5.4.5.

5.3.9 SLIP_solve_double: solve Ax = b and return x in double type

SLIP_solve_double solves the linear system $A\mathbf{x} = \mathbf{b}$ and returns the solution as a matrix accurate to double precision. This is a "all-in-one" function that performs factorization, solving, permutation and scaling. However, symbolic analysis SLIP_LU_analysis should be performed before calling this function.

On output, this x_doub contains the solution to the linear system in double precision and the function returns $SLIP_OK$.

For the full example, users can refer to Demos/example3.c. Here is an brief example of how to use this code:

```
/* Create and populate A, b, and option */
/* A has size of nrows-by-nrows, b has size of nrows-by-numRHS */
SLIP_LU_analysis* S = SLIP_create_LU_analysis(nrows+1);
SLIP_LU_analyze(S, A, option);
double** x = SLIP_create_double_mat(nrows, numRHS);
SLIP_solve_double(x, A, S, b, option);
```

5.3.10 SLIP_solve_mpq: solve Ax = b and return x in mpq_t type

SLIP_solve_mpq solves the linear system $A\mathbf{x} = \mathbf{b}$ and returns the solution as a matrix of mpq_t numbers. This is a "all-in-one" function that performs factorization, solving, permutation and scaling. However, symbolic analysis SLIP_LU_analysis should be performed before calling this function.

On output, this x_mpq contains the exact solution to the linear system as mpq_t numbers and the function returns $SLIP_0K$

For the full example, users can refer to Demos/example2.c. Here is an brief example of how to use this code:

```
/* Create and populate A, b, and option */
/* A has size of nrows-by-nrows, b has size of nrows-by-numRHS */
SLIP_LU_analysis* S = SLIP_create_LU_analysis(nrows+1);
SLIP_LU_analyze(S, A, option);
mpq_t** x = SLIP_initialize_mpq_mat(nrows, numRHS);
SLIP_solve_mpq(x, A, S, b, option);
```

5.3.11 SLIP_solve_mpfr: solve Ax = b and return x in mpfr_t type

```
SLIP_options *option // Control parameters
);
```

SLIP_solve_mpq solves the linear system $A\mathbf{x} = \mathbf{b}$ and returns the solution as a matrix of mpfr_t numbers. This is a "all-in-one" function that performs factorization, solving, permutation and scaling. However, symbolic analysis SLIP_LU_analysis should be performed before calling this function.

On output, this x_mpfr contains the exact solution to the linear system as $mpfr_t$ numbers and the function returns $SLIP_OK$

Here is an brief example of how to use this code:

```
/* Create and populate A, b, and option */
/* A has size of nrows-by-nrows, b has size of nrows-by-numRHS */
SLIP_LU_analysis* S = SLIP_create_LU_analysis(nrows+1);
SLIP_LU_analyze(S, A, option);
option->prec = 128; // Quad
mpfr_t** x = SLIP_create_mpfr_mat(nrows, numRHS, option);
SLIP_solve_mpfr(x, A, S, b, option);
```

5.4 Miscellaneous Routines

This section contains miscellaneous routines that may be of interest to the user.

5.4.1 SLIP_create_double_mat: create a *m*-by-*n* double matrix

SLIP_create_double_mat allocates a double matrix of size $m \times n$ and sets each entry equal to zero, where A[i][j] is the (i,j)th entry. A[i] is a pointer to row i, of size n.

5.4.2 SLIP_delete_double_mat: delete a m-by-n double matrix

```
void SLIP_delete_double_mat
(
    double*** A,  // dense matrix
    int32_t m,  // number of rows of A
    int32_t n  // number of columns of A
);
```

SLIP_delete_double_mat frees the memory associated with a double matrix of size $m \times n$, and set **A=NULL.

5.4.3 SLIP_create_int_mat: create a m-by-n int32_t matrix

SLIP_create_int_mat allocates a int32_t matrix of size $m \times n$ and sets each entry equal to zero, where A[i][j] is the (i,j)th entry. A[i] is a pointer to row i, of size n.

5.4.4 SLIP_delete_int_mat: delete a m-by-n int32_t matrix

```
void SLIP_delete_int_mat
(
    int32_t*** A, // dense matrix
    int32_t m, // number of rows
    int32_t n // number of columns
);
```

SLIP_delete_int_mat frees the memory associated with a int32_t matrix of size $m \times n$, and set **A=NULL.

5.4.5 SLIP_create_mpfr_mat: create a m-by-n mpfr_t matrix

SLIP_create_mpfr_mat allocates a mpfr_t matrix of size $m \times n$ and sets each entry equal to zero, where A[i][j] is the (i, j)th entry. A[i] is a pointer to row i, of size n. The floating point precision associated with each entry is given by option->prec.

5.4.6 SLIP_delete_mpfr_mat: delete a m-by-n mpfr_t matrix

```
void SLIP_delete_mpfr_mat
(
    mpfr_t ***A,  // Dense mpfr matrix
    int32_t m,  // number of rows of A
    int32_t n  // number of columns of A
);
```

SLIP_delete_mpfr_mat frees the memory associated with a mpfr_t matrix of size $m \times n$, and set **A=NULL. When using the GMP library for SLIP LU, it is highly recommended that the user uses the defined SLIP_delete* functions in order to avoid memory leaks or potential segmentation faults.

5.4.7 SLIP_create_mpq_mat: create a m-by-n mpq_t matrix

SLIP_create_mpq_mat allocates a mpq_t matrix of size $m \times n$ and sets each entry equal to zero, where A[i][j] is the (i, j)th entry. A[i] is a pointer to row i, of size n.

5.4.8 SLIP_delete_mpq_mat: delete a m-by-n mpq_t matrix

SLIP_delete_mpq_mat frees the memory associated with a mpq_t matrix of size $m \times n$, and set **A=NULL. When using the GMP library for SLIP LU, it is highly recommended that the user uses the defined SLIP_delete* functions in order to avoid memory leaks or potential segmentation faults.

5.4.9 SLIP_create_mpz_mat: create a m-by-n mpz_t matrix

SLIP_create_mpz_mat allocates a mpz_t matrix of size $m \times n$ and sets each entry equal to zero, where A[i][j] is the (i, j)th entry. A[i] is a pointer to row i, of size n.

5.4.10 SLIP_delete_mpz_mat: delete a m-by-n mpz_t matrix

SLIP_delete_mpz_mat frees the memory associated with a mpz_t matrix of size $m \times n$, and set **A=NULL. When using the GMP library for SLIP LU, it is highly recommended that the user uses the defined SLIP_delete* functions in order to avoid memory leaks or potential segmentation faults.

5.4.11 SLIP_create_mpfr_array: create a mpfr_t of length n

SLIP_create_mpfr_array allocates a mpfr_t matrix of length n and sets each entry equal to zero, where A[i] is an entry of type mpfr_t. The floating point precision associated with each entry is given by option->prec.

5.4.12 SLIP_delete_mpfr_array: delete a mpfr_t of length n

```
void SLIP_delete_mpfr_array
(
    mpfr_t** x, // mpfr array to be deleted
    int32_t n // size of x
);
```

SLIP_delete_mpfr_array frees the memory associated with a mpfr_t array of size n, and set *x=NULL. When using the GMP library for SLIP LU, it is highly recommended that the user uses the defined SLIP_delete* functions in order to avoid memory leaks or potential segmentation faults.

5.4.13 SLIP_create_mpq_array: create a mpq_t of length n

```
mpq_t* SLIP_create_mpq_array
(
    int32_t n // size of the array
);
```

SLIP_create_mpq_array allocates a mpq_t matrix of length n and sets each entry equal to zero, where A[i] is an entry of type mpq_t.

5.4.14 SLIP_delete_mpq_array: delete a mpq_t of length n

```
void SLIP_delete_mpq_array
(
```

SLIP_delete_mpq_array frees the memory associated with a mpq_t array of size n, and set *x=NULL. When using the GMP library for SLIP LU, it is highly recommended that the user uses the defined SLIP_delete* functions in order to avoid memory leaks or potential segmentation faults.

5.4.15 SLIP_create_mpz_array: create a mpz_t of length n

```
mpz_t* SLIP_create_mpz_array
(
   int32_t n // Size of x
);
```

SLIP_create_mpz_array allocates a mpz_t matrix of length n and sets each entry equal to zero, where A[i] is an entry of type mpz_t.

5.4.16 SLIP_delete_mpz_array: delete a mpz_t of length n

SLIP_delete_mpz_array frees the memory associated with a mpz_t array of size n, and set *x=NULL. When using the GMP library for SLIP LU, it is highly recommended that the user uses the defined SLIP_delete* functions in order to avoid memory leaks or potential segmentation faults.

5.4.17 SLIP_spok: check and print a SLIP_sparse matrix

SLIP_spok check the validity of a SLIP_sparse matrix in compressed-sparse column form. Derived from SuiteSparse/MATLAB_TOOLS/spok.

5.5 Miscellaneous Routines2

5.5.1 SLIP_read_matrix

```
int SLIP_read_matrix
(
    SLIP_mat* A,
    char* filename
);
```

This function reads in an integral matrix stored in matrix market format from the file filename. On success, the value SLIP_OK is returned. The following code snippet shows how to use this function.

```
SLIP_mat* A = SLIP_initialize_mat();
char* myfile = "myfile.txt";
SLIP_read_matrix(A, myfile);
```

5.5.2 SLIP_read_rhs

Thus function's syntax is:

```
int SLIP_read_rhs
(
    mpz_t** b,
    int n,
    char* filename
);
```

This function assumes **b** is $n \times 1$ and reads in the integral right hand side vector from the file filename.

5.6 SLIP LU GMP and MPFR Wrappers

As discussed previously, SLIP LU provides a wrapper class for all utilized GMP and MPFR functions which are used to eliminate potential memory leaks and segmentation fault. Each wrapped function has the same name as its corresponding GMP/MPFR function with the added prefix SLIP_. For example, the default GMP function mpz_mul is changed to SLIP_mpz_mul. Each SLIP GMP/MPFR function returns SLIP_OK if successful or the correct error code if not. The following table gives a brief list of each currently covered SLIP GMP/MPFR function. For a detailed description of each function, please refer to SLIP_LU/Source/SLIP_gmp.c.

Given a GMP function void MY_GMP_FUNCTION(TYPEa a, TYPEb b, ...), where TYPEa and TYPEb can be GMP type data (e.g., mpz_t, mpq_t and mpfr_t) or non-GMP type data (e.g., int, double), and they need not to be the same. In order to apply our wrapper to a new function, one can create it as follows:

```
SLIP_info SLIP_MY_GMP_FUNCTION
   TYPEa a,
    TYPEb b,
{
    // Start the GMP Wrappter
    // uncomment one of the followings that meets the needs
    // If this function is not modifying any GMP type variable, then use
    //SLIP\_GMP\_WRAPPER\_START;
    // If this function is modifying mpz_{-}t type (say TYPEa = mpz_{-}t), then
    //SLIP\_GMPZ\_WRAPPER\_START(a);
    // If this function is modifying mpq_{-}t type (say TYPEa = mpq_{-}t), then
    //SLIP\_GMPQ\_WRAPPER\_START(a);
    // If this function is modifying mpz_{-}t type (say TYPEa = mpz_{-}t), then
    //SLIP\_GMPFR\_WRAPPER\_START(a);
    // Call my gmp function
    MY_GMP_FUNCTION(a,b,...);
    //Finish the wrapper and return ok if successful.
    SLIP_GMP_WRAPPER_FINISH;
    return SLIP_OK;
```

}

Note that, most of the wrapped GMP/MPFR functions (other than the print functions) should always return SLIP_info to the caller. Therefore, for some GM-P/MPFR functions that have their own return value, e.g., int mpq_cmp (const mpq_t a, const mpq the return value need to be added into wrapped function. In general, a GMP/MPFR function in the form of TYPEr MY_GMP_FUNCTION(TYPEa a, TYPEb b, ...), user can create the wrapped function as follows:

```
SLIP_info SLIP_MY_GMP_FUNCTION
                // return value of the GMP/MPFR function
   TYPEr *r,
   TYPEa a,
   TYPEb b,
{
   // Start the GMP Wrappter
   // uncomment one of the followings that meets the needs
    //SLIP_GMP_WRAPPER_START;
   //SLIP\_GMPZ\_WRAPPER\_START(a);
   //SLIP_GMPQ_WRAPPER_START(a);
    //SLIP\_GMPFR\_WRAPPER\_START(a);
    // Call my gmp function
    *r = MY\_GMP\_FUNCTION(a, b, ...);
   //Finish the wrapper and return ok if successful.
   SLIP_GMP_WRAPPER_FINISH;
   return SLIP_OK;
```

MPFR Function	SLIP_MPFR Function	Description
<pre>n = mpfr_fprintf(fp, format,)</pre>	<pre>n = SLIP_mpfr_fprintf(fp, format,)</pre>	Print form
<pre>mpfr_init2(x, size)</pre>	SLIP_mpfr_init2(x, size)	Initialize x
<pre>mpfr_set(x, y, rnd)</pre>	SLIP_mpfr_set(x, y, rnd)	x = y
<pre>mpfr_set_d(x, y, rnd)</pre>	SLIP_mpfr_set_d(x, y, rnd)	x = y (dov)
<pre>mpfr_set_q(x, y, rnd)</pre>	SLIP_mpfr_set_q(x, y, rnd)	x = y (mp)
<pre>mpfr_set_z(x, y, rnd)</pre>	SLIP_mpfr_set_z(x, y, rnd)	x = y (mp)
<pre>mpfr_get_z(x, y, rnd)</pre>	SLIP_mpfr_get_z(x, y, rnd)	(mpz) x =
x = mpfr_get_d(y, rnd)	<pre>SLIP_mpfr_get_d(x, y, rnd)</pre>	(double) x
<pre>mpfr_mul(x, y, z, rnd)</pre>	SLIP_mpfr_mul(x, y, z, rnd)	x = y * z
<pre>mpfr_mul_d(x, y, z, rnd)</pre>	SLIP_mpfr_mul_d(x, y, z, rnd)	x = y * z
<pre>mpfr_div_d(x, y, z, rnd)</pre>	SLIP_mpfr_div_d(x, y, z, rnd)	x = y/z
<pre>mpfr_ui_pow_ui(x, y, z, rnd)</pre>	SLIP_mpfr_ui_pow_ui(x, y, z, rnd)	$x = y^z$
<pre>mpfr_log2(x, y, rnd)</pre>	SLIP_mpfr_log2(x, y, rnd)	$x = \log_2(y)$
<pre>mpfr_free_cache()</pre>	SLIP_mpfr_free_cache()	Free cache

6 Using SLIP LU in C

Using SLIP LU in C has four steps: 1) initialize and populate data structures, 2) perform symbolic analysis, 3) factorize the matrix A and solve the linear system for each \mathbf{b} vector, and 4) free all used memory and finalize. Steps 1 and 2 are discussed in Subsections 6.1 and 6.2. Factorizing A and solving the linear $A\mathbf{x} = \mathbf{b}$ can be done in one of two ways. If the user is only interested in obtaining the solution vector \mathbf{x} , SLIP LU provides a simple interface for this purpose which is discussed in Section 6.3. Alternatively, if the user wants the actual L and U factors, please refer to Section 6.4. Finally, step 4 is discussed in Section 6.5. For the remainder of this section, \mathbf{n} will indicate the dimension of A (that is, $A \in \mathbb{Z}^{n \times n}$) and numRHS will indicate the number of right hand side vectors being solved (that is, if numRHS=r, then $\mathbf{b} \in \mathbb{Z}^{n \times r}$).

6.1 SLIP LU Initialization and Population of Data Structures

This section discusses how to initialize and populate the global data structures required for SLIP LU.

GMP Function	SLIP_GMP Function	Description
n = gmp_fprintf(fp, format,)	n = SLIP_gmp_fprintf(fp, format,)	Print format
n = gmp_printf(format,)	n = SLIP_gmp_printf(format,)	Print to scre
n = gmp_fscanf(fp, format,)	n = SLIP_gmp_fscanf(fp, format,)	Read from fi
mpz_init(x)	SLIP_mpz_init(x)	Initialize x
mpz_init2(x, size)	SLIP_info SLIP_mpz_init2(x, size)	Initialize x t
mpz_set(x, y)	SLIP_mpz_set(x, y)	x = y (mpz)
mpz_set_ui(x, y)	SLIP_mpz_set_ui(x, y)	x = y (signed
mpz_set_si(x, y)	SLIP_mpz_set_si(x, y)	x = y (unsig
mpz_set_d(x, y)	SLIP_mpz_set_d(x, y)	x = y (doub)
$x = mpz_get_d(y)$	SLIP_mpz_get_d(x, y)	x = y (doub)
mpz_set_q(x, y)	SLIP_mpz_set_q(x, y)	x = y (mpq)
mpz_mul(x, y, z)	SLIP_mpz_mul(x, y, z)	x = y * z
mpz_add(x, y, z)	SLIP_mpz_add(x, y, z)	x = y + z
mpz_addmul(x, y, z)	SLIP_mpz_addmul(x, y, z)	x = x + y * z
mpz_submul(x, y, z)	SLIP_mpz_submul(x, y, z)	x = x + y + z $x = x - y * z$
mpz_divexact(x, y, z)	SLIP_mpz_divexact(x, y, z)	x = y/z
gcd = mpz_gcd(x, y)	SLIP_mpz_gcd(gcd, x, y)	gcd = gcd(x,
$1cm = mpz_1cm(x, y)$	SLIP_mpz_lcm(lcm, x, y)	lcm = lcm(x)
mpz_abs(x, y)	SLIP_mpz_abs(x, y)	x = y
$r = mpz_cmp(x, y)$	SLIP_mpz_cmp(r, x, y)	r = 0 if x = 0
i mpz_omp(x, y)	bull_mpz_omp(r, x, y)	$r \neq 0$ o.w.
r = mpz_cmpabs(x, y)	SLIP_mpz_cmpabs(r, x, y)	r = 0 if $ x =$
i mpz_empass(x, y)	BHI _mp2_cmpdbb(I, X, y)	$r \neq 0$ o.w.
r = mpz_cmp_ui(x, y)	SLIP_mpz_cmp_ui(r, x, y)	r = 0 if $x =$
mp2_emp_u1(n, y)		$r \neq 0$ o.w.
sgn = mpz_sgn(x)	SLIP_mpz_sgn(sgn, x)	sgn = 0 if x
size = mpz_sizeinbase(x, base)	SLIP_mpz_sizeinbase(size, x, base)	size of x in b
mpq_init(x)	SLIP_mpq_init(x)	Initialize x
mpq_set(x, y)	SLIP_mpq_set(x, y)	x = y
mpq_set_z(x, y)	SLIP_mpq_set_z(x, y)	x = y (mpz)
mpq_set_d(x, y)	SLIP_mpq_set_d(x, y)	x = y (doub)
mpq_set_ui(x, y, z)	SLIP_mpq_set_ui(x, y, z)	x = y/z (uns
mpq_set_num(x, y)	SLIP_mpq_set_num(x, y)	num(x) = y
mpq_set_den(x, y)	SLIP_mpq_set_den(x, y)	den(x) = y
mpq_get_den(x, y)	SLIP_mpq_get_den(x, y)	x = den(y)
$x = mpq_get_d(y)$	SLIP_mpq_get_d(x, y)	(double) $x =$
mpq_abs(x, y)	SLIP_mpq_abs(x, y)	x = y
mpq_add(x, y, z)	SLIP_mpq_add(x, y, z)	x = y + z
mpq_mul(x, y, z)	SLIP_mpq_mul(x, y, z)	x = y * z
mpq_div(x, y, z)	SLIP_mpq_div(x, y, z)	x = y/z
$r = mpq_cmp(x, y)$	SLIP_mpq_cmp(r, x, y)	r = 0 if x = 0
		$r \neq 0$ o.w.
r = mpq_cmp_ui(x, n, d)	SLIP_mpq_cmp_ui(r, x, n, d)	r = 0 if x =
		$r \neq 0$ o.w.
r = mpq_equal(x, y)	SLIP_mpq_equal(r, x, y)	r = 0 if $x =$
		$r \neq 0$ o.w.

6.1.1 Initializing the Environment

SLIP LU is built upon the GNU GMP library [7] and provides wrappers to all GMP functions in order to regulate memory management and ensure that the user does not have to directly interface with the GMP library. Moreover, SLIP LU strives to not cause out of memory errors. To ensure all of these precautions, SLIP LU requires initialization. This can be done by beginning your code with the statement:

SLIP_initialize();

6.1.2 Initializing Data Structures

SLIP LU assumes four specific input options for all functions. These are:

- SLIP_sparse* A: A contains the user's input matrix. If the input matrix was already an integral matrix, A is the user's input and A->scale=1. Otherwise, the input matrix is not integral and A contains the user's scaled input matrix.
- SLIP_LU_analysis* S: S contains the column permutation used for A as well as guesses for the number of nonzeros in L and U.
- SLIP_options* option: option contains various control options for the factorization including column ordering used, pivot selection scheme, and others. For a full list of the contents of the SLIP_options structure, please refer to Section 4.4.
- SLIP_dense* b: b contains the user's right hand side vector(s). If the input right hand side vectors were already integral, b contains them directly and b->scale=1. Otherwise, b is the scaled input right hand side vector(s).

SLIP LU provides four separate functions to allocate memory for and initialize each of these data structures. For more details, users can refer to Sections 4.4-4.7. Thus, after calling SLIP_initialize();, the user should call the following:

6.1.3 Populating Data Structures

Of the four aforementioned data structures, S is populated during symbolic analysis (Section 6.2), option is initialized to default values and can be modified if the user desires (please refer to Section 4.4 for the contents of option) and A and b are populated by the user. SLIP LU allows the input numerical data for A and b to come in one of 5 options: int32_t, double, mpfr_t, mpq_t, and mpz_t. Moreover, A can be stored in either triplet form or compressed column form. Compressed column form is discussed in Section 1. Conversely, triplet form stores the contents of the matrix A in three arrays i, j, and x where the kth nonzero entry is stored as A(i[k], j[k]) = x[k].

If the input matrix is stored in compressed column form, the functions SLIP_build_sparse_csc_* can be used. Details of these functions are described in Sections 5.2.1-5.2.5.

The user should use the function that matches the data type of their available x. The following code snippet will show how to use these functions. Note that this snippet serves as partially working code (i.e., select the one you'd want to use and delete the surrounding if statements).

```
/* Assume everything has been declared and initialized */
/* Get the matrix A. Assume that everything is stored in
   compressed column form. This means that int* I is the
   set of row indices, int* p are the column pointers, x
   is the array of values, n is the size of the matrix and
  nz is the number of nonzeros in the matrix. We will show
  how to obtain for each possible data type of x (again,
   to have working code, select the one that fits your code
   and delete the rest) */
if(X IS mpz_t)
{
    SLIP_build_sparse_csc_mpz(A, p, I, x, n, nz);
else if (X IS double)
{
    SLIP_build_sparse_csc_double(A, p, I, x, n, nz);
}
else if (X IS int32_t)
{
    SLIP_build_sparse_csc_int(A, p, I, x, n, nz);
```

```
}
else if (X IS mpq_t)
{
    SLIP_build_sparse_csc_mpq(A, p, I, x, n, nz);
}
else if (X IS mpfr_t)
{
    SLIP_build_sparse_csc_mpfr(A, p, I, x, n, nz, option);
}
```

Conversely, if the input matrix is stored in triplet form, the functions SLIP_build_sparse_trip_* are used. Details of these functions are described in Sections 5.2.6-5.2.10.

The user should use the function that matches the data type of their available x. The following code snippet will show how to use these functions. Note that this snippet serves as partially working code (i.e., select the one you'd want to use and delete the surrounding if statements).

```
/* Assume everything has been declared and initialized */
```

/* Get the matrix A. Assume that everything is stored in
 compressed column form. This means that int* I is the
 set of row indices, int* J is the set of column indices,
 x is the array of values, n is the size of the matrix and
 nz is the number of nonzeros in the matrix. We will show
 how to obtain for each possible data type of x (again,
 to have working code, select the one that fits your code
 and delete the rest) */

```
if(X IS mpz_t)
{
    SLIP_build_sparse_trip_mpz(A, I, J, x, n, nz);
}
else if (X IS double)
{
    SLIP_build_sparse_trip_double(A, I, J, x, n, nz);
}
else if (X IS int32_t)
{
```

```
SLIP_build_sparse_trip_int(A, I, J, x, n, nz);
}
else if (X IS mpq_t)
{
    SLIP_build_sparse_trip_mpq(A, I, J, x, n, nz);
}
else if (X IS mpfr_t)
{
    SLIP_build_sparse_trip_mpfr(A, I, J, x, n, nz, option);
}
```

Lastly, the right hand side vectors **b** are populated via the SLIP_build_dense_* functions. Details of these functions are described in Sections 5.2.11-5.2.14.

The user should use the function that matches the data type of their available b. The following code snippet will show how to use this function. Note that this snippet serves as partially working code (i.e., select the one you'd want to use and delete the surrounding if statements).

```
if (b2 IS mpz_t)
{
    SLIP_build_dense_mpz(b, b2, n, numRHS);
}
else if (b2 IS double)
{
    SLIP_build_dense_double(b, b2, n, numRHS);
}
else if (b2 IS int32_t)
{
    SLIP_build_dense_int(b, b2, n, numRHS);
else if (b2 IS mpq_t)
    SLIP_build_dense_mpq(b, b2, n, numRHS);
else if (b2 IS mpfr_t)
{
    SLIP_build_dense_mpfr(b, b2, n, numRHS, option);
}
```

6.2 SLIP LU Symbolic Analysis

The symbolic analysis phase of SLIP LU computes the column permutation and guesses for the number of nonzeros in L and U. This function is called as:

```
/* Assume A has been populated, and option and S have been initialized. */
SLIP_LU_analyze(S, A, option);
```

6.3 Easy SLIP LU for Solving Linear Systems (no L and U)

After initializing the necessary data structures and performing symbolic analysis, SLIP LU obtains the solution to $A\mathbf{x} = \mathbf{b}$. Using the "easy" interface of SLIP LU requires only that the user decides what data type that he/she wants \mathbf{x} to be stored as. SLIP LU allows \mathbf{x} to be returned as either double, mpq_t, or mpfr_t with an associated precision. This is done by using one of the following functions: SLIP_solve_double (Section 5.3.9), SLIP_solve_mpq (Section 5.3.10) or SLIP_solve_mpfr (Section 5.3.11).

Below, we show sample syntax to use each of these functions. As above, this code snippet contains all of the potential options, thus a user can merely copy the one they desire and paste into their code.

```
/* Assume that A, S, option, and b have been properly declared and populated. */
if (USER WANTS MPQ)
{
    // The solution is a dense matrix of size n*numRHS
    mpq_t** soln = SLIP_create_mpq_mat(n, numRHS);
    int ok = SLIP_solve_mpq(soln, A, S, b, option);
}
else if (USER WANTS DOUBLE)
{
    // The solution is a dense matrix of size n*numRHS
    double** soln = SLIP_create_double_mat(n, numRHS);
    int ok = SLIP_solve_double(soln, A, S, b, option);
}
```

```
else if (USER WANTS MPFR)
{
    // The solution is a dense matrix of size n*numRHS
    mpfr_t** soln = SLIP_create_mpfr_mat(n, numRHS, option);
    int ok = SLIP_solve_mpfr(soln, A, S, b, option);
}
```

On success, each of these functions return SLIP_OK (see Section 4.1).

6.4 Complex SLIP LU for Solving Linear Systems (with L and U)

If a user wishes to perform the SLIP LU factorization of the matrix A while capturing information about the factorization itself and solving the linear system, extra steps must be performed that are all done internally in the methods described in the previous subsection. Particularly, the following steps must be performed: 1) allocate memory for L, U, the solution vector(s) (stored as mpq_t) \mathbf{x} , and others, 2) compute the factorization PAQ = LDU, 3) solve the linear system $P^{-1}LDUQ^{-1}\mathbf{x} = \mathbf{b}$, 4) permute the solution vector(s), 5) scale the solution vector if the scaling factors of A and b are not zero, and 6) convert the final solution into the user's desired form. Below, we discuss each of these steps followed by an example of putting it all together.

6.4.1 Allocating New Memory

Using SLIP LU in this form requires that memory be allocated for L, U, and the solution vector(s). The solution vectors are **required** to be stored as a mpq_t** array. Additionally, SLIP LU utilizes a mpz_t array which stores the pivot elements (referred to as rhos) and the inverse row permutation (referred to as pinv). The following code snippet shows how to allocate these entries.

```
/* Purpose: Allocate memory for L, U, and x */
SLIP_sparse* L = SLIP_create_sparse();
SLIP_sparse* U = SLIP_create_sparse();
// x is of size n * numRHS
mpq_t** x = SLIP_create_mpq_mat(n, numRHS);
```

```
// rhos is the sequence of pivots
mpz_t* rhos = SLIP_create_mpz_array(n);

// pinv is the inverse row permutation
int32_t* pinv = (int32_t*) SLIP_malloc(n*sizeof(int32_t));
```

6.4.2 Computing the Factorization

The matrices L and U are computed via the SLIP_LU_factorize function (Section 5.3.2).

Upon successful completion, this function returns SLIP_OK.

6.4.3 Solving the Linear System

After factorization, the next step is to solve the linear system and store the solution as a set of rational number mpq_t in the previously allocated x data structure. This solution is done via the SLIP_LU_solve function (Section 5.3.3).

Upon successful completion, this function returns SLIP_OK.

Note: The solution vector given here is NOT the solution to $A\mathbf{x} = \mathbf{b}$ because it has not been properly permuted and scaled. Recall that when solving a system via the SLIP LU factorization, two systems are solved: $LD\mathbf{y} = P\mathbf{b}$ and $U\mathbf{x} = \mathbf{y}$. The solution here is the solution to $Y\mathbf{x} = \mathbf{y}$ and must still be permuted by the column permutation Q which is discussed in the next subsection.

6.4.4 Permuting the Solution Vectors

Permuting the solution vector(s) is done via the function SLIP_permute_x (Section 5.3.4).

Upon successful completion, this function returns SLIP_OK. At the conclusion of this routine, \mathbf{x} contains the solution to the scaled system $A_{int}\mathbf{x} = \mathbf{b}_{int}$.

6.4.5 Scaling the Solution Vectors

Scaling the solution vector(s) is done via the function SLIP_scale_x (Section 5.3.6). Upon successful completion, this function returns SLIP_OK. At the conclusion of this routine, x contains the solution to the system $A\mathbf{x} = \mathbf{b}$.

6.4.6 Converting the Solution Vector to the User's Desired Form

Upon completion of the above routines, the solution to the linear system is given by the mpq_t** x. SLIP LU allows this to be converted into either a double precision matrix or a mpfr_t precision matrix via the functions SLIP_get_double_soln (Section 5.3.7) or SLIP_get_mpfr_soln (Section 5.3.8). Below, we show how to call these functions.

```
if (USER WANTS DOUBLE)
{
    double** x2 = SLIP_create_double_mat(n, numRHS);
    SLIP_get_double_soln(x2, x, n, numRHS);
}
else if (USER WANTS MPFR)
{
    mpfr_t** x2 = SLIP_create_mpfr_mat(n, numRHS, option);
    SLIP_get_mpfr_soln(x2, x, n, numRHS);
}
```

6.5 SLIP LU Freeing all Used Memory

Upon finishing using SLIP LU all memory must be freed. As described in Sections 5.1 and 5.4, SLIP LU provides a number of functions to handle this for the user. Below, we briefly summarize which memory freeing routine should be used for specific data types:

- SLIP_sparse*: A SLIP_sparse* A data structure can be freed with a call to SLIP_delete_sparse(&A);
- SLIP_LU_analysis*: A SLIP_LU_analysis* S data structure can be freed with a call to SLIP_delete_LU_analysis(&S);
- SLIP_dense*: The SLIP_dense* b of dimension n * numRHS can be cleared with a call to SLIP_delete_dense(&b).
- 2D array created via SLIP_create_*_mat: The 2D array **x of dimension n * numRHS can be cleared with a call to SLIP_delete_*_mat(&x, n, numRHS).

- 1D array of GMP data type created via SLIP_create_*_array: The 1D array *x of size n can be cleared with a call to SLIP_delete_*_array(&x, n).
- All others including SLIP_options*: These data structures can be freed with a call to the macro SLIP_FREE(), e.g., SLIP_FREE(option) for SLIP_options* option.

Note: after usage of the SLIP LU routines are finished, one must call SLIP_finalize() (Section 5.1.7) to finalize usage of the library.

6.6 Examples of Using SLIP LU in a C Program

The "Demo" folder contains six sample C codes which utilize SLIP LU. These files demonstrate the usage of SLIP LU as follows:

- **example.c** This example generates a random dense 50×50 matrix and a random dense 50×1 right hand side vector **b** and solves the linear system. In this function, the SLIP_solve_double function is used; thus the output is given as a double matrix.
- **example2.c** This example reads in a matrix stored in integral matrix market format from the ExampleMats folder. Additionally, it reads in a right hand side vector from this folder and solves the associated linear system via the SLIP_solve_mpq function. Thus, the solution is given as a set of rational numbers.
- **example3.c** This example creates an input matrix and right hand side vector stored as mpfr_t numbers. Then, it shows how to create the input matrix A and right hand side vector **b** and solves the linear system using the SLIP_solve_double function, outputting the solution in double precision.
- **example4.c** This example is nearly identical to example3 except that the input has multiple right hand side vectors and all input numbers are stored as double precision numbers.
- **example 5.c** This example creates a random set of right hand side vectors, reads in a matrix from a file, and solves the associated linear system outputting the solution as a double matrix.
- **SLIPLU.c** This example reads in a matrix and right hand side vector from a file and solves the linear system $A\mathbf{x} = \mathbf{b}$ using the techniques discussed in Section 6.4. This file also allows command line arguments (discussed in README.txt) and can be used to replicate the results from [8].

7 Using SLIP LU in MATLAB

After following the installation steps discussed in Section 3, using the SLIP LU factorization within MATLAB can be done via the SLIP_LU.m and the SLIP_get_options functions. First, this section will describe the SLIP_get_options struct in Section 7.1 then we describe how to use the factorization in Section 7.2. Again, recall that by default the SLIP LU MATLAB routines are not natively installed into your MATLAB installation; thus if you want to use them in a different directory please add the "SLIP_LU/MATLAB" folder to your path.

7.1 SLIP_get_options.m

Much like the C routines described throughout, the SLIP LU MATLAB interface has various parameters that the user can modify to control the factorization. In MATLAB, these are stored in a struct (hereafter referred to as the "options" struct) which contains 9 elements. Notice that this struct is optional for the user to use and can be avoided if one wishes to use only default options. The options struct can be accessed by typing the following into the MATLAB command window:

option = SLIP_get_options;

The elements of the options struct are as follows:

option.column: This parameter controls the column ordering used. 0 (default): COLAMD, 1: AMD, 2: no column ordering. It is usually recommended that the user keep this at COLAMD unless they already have a good column permutation.

option.pivot: This parameter controls the pivoting scheme used. The factorization selects a pivot element in each column as follows: 0: smallest pivot, 1: diagonal pivot if possible, o.w., smallest pivot, 2: first nonzero pivot in each column, 3 (default): diagonal pivot with a tolerance for the smallest pivot, 4: diagonal pivot with a tolerance for the largest pivot, 5: largest pivot. It is recommended that the user always selects either 3 or 1 for this parameter UNLESS they are trying to extract the Doolittle factors, then 5 may be appropriate (due to the size of numbers in Doolittle).

option.int: Set this parameter equal to 1 if the input matrix is already integral. Otherwise, if the input matrix has any decimal entries, scaling must be performed to obtain an integral input matrix. **IMPORTANT**If the input matrix is not integral and this parameter is set equal to 1, the values will be truncated.

option.intb: Set this parameter equal to 1 if the input right hand side vector(s) are already integral. Like the input matrix, if **b** contains any fractional entries, scaling must be performed to ensure integrality.

option.tol: This parameter determines the tolerance used if one of the threshold

pivoting schemes is chosen. The default value is 0.1 and this parameter can take any value in the range (0,1).

7.2 SLIP_LU.m

The SLIP_LU.m function solves the linear system $A\mathbf{x} = \mathbf{b}$ where $A \in \mathbb{R}^{n \times n}$, $\mathbf{x} \in \mathbb{R}^{n \times m}$ and $\mathbf{b} \in \mathbb{R}^{n \times m}$. The final solution vector(s) obtained via this function are exact prior to their conversion to double precision.

The SLIP LU function expects as input a sparse matrix A and dense set of right hand side vectors \mathbf{b} . Optionally, the user can also pass in the options struct. Currently, there are 2 ways to use this function outlined below:

- $x = SLIP_LU(A,b)$ returns the solution to Ax = b using default settings. The solution vectors are more accurate than the solution obtained via $x = A \setminus b$.
- $x = SLIP_LU(A,b,option)$ returns the solution to Ax = b using user specified settings from the options struct.

References

- [1] P. R. AMESTOY, T. A. DAVIS, AND I. S. DUFF, An approximate minimum degree ordering algorithm, SIAM Journal on Matrix Analysis and Applications, 17 (1996), pp. 886–905.
- [2] —, Algorithm 837: Amd, an approximate minimum degree ordering algorithm, ACM Transactions on Mathematical Software (TOMS), 30 (2004), pp. 381–388.
- [3] T. Davis, W. Hager, and I. Duff, *Suitesparse*, htt p://faculty.cse.tamu.edu/davis/suitesparse.html, (2014).
- [4] T. A. DAVIS, J. R. GILBERT, S. I. LARIMORE, AND E. G. NG, Algorithm 836: Colamd, a column approximate minimum degree ordering algorithm, ACM Transactions on Mathematical Software (TOMS), 30 (2004), pp. 377–380.
- [5] —, A column approximate minimum degree ordering algorithm, ACM Transactions on Mathematical Software (TOMS), 30 (2004), pp. 353–376.
- [6] L. Fousse, G. Hanrot, V. Lefèvre, P. Pélissier, and P. Zimmermann, *Mpfr: A multiple-precision binary floating-point library with correct rounding*, ACM Transactions on Mathematical Software (TOMS), 33 (2007), p. 13.
- [7] T. Granlund et al., GNU MP 6.0 Multiple Precision Arithmetic Library, Samurai Media Limited, 2015.
- [8] C. Lourenco, A. R. Escobedo, E. Moreno-Centeno, and T. A. Davis, Exact solution of sparse linear systems via left-looking roundoff-error-free lu factorization in time proportional to arithmetic work, SIAM Journal on Matrix Analysis and Applications, 40 (2019), pp. 609–638.