Differential form

Yi-Fan Wang

May 3, 2019

Contents

	3.1 Lorenz gauge	2
3	Maxwell-Klein-Fock-Gordon theory	1
2	Covariant codifferential	1
L	Covariant differential	1

1 Covariant differential

 ϕ a C-valued 0-form

$$\mathbb{D}\phi \coloneqq (\mathbf{d} - ieA) \wedge \phi, \qquad \mathbb{D}\phi^* \coloneqq (\mathbf{d} + ieA) \wedge \phi^*, \tag{1.0.1}$$

A the $\mathfrak{u}(1)$ -valued connection form.

2 Covariant codifferential

Define the covariant codifferential of a $\mathbb C$ -valued k-form ζ as follows. Let η be an arbitrary $\mathbb C$ -valued (k-1)-form.

$$\begin{split} \int \mathrm{d}(\eta^* \wedge \star \zeta) &\equiv \int \mathrm{d}\eta^* \wedge \star \zeta - (-)^k \eta^* \wedge \mathrm{d} \star \zeta =: \int \mathbb{D}\eta^* \wedge \star \zeta - \eta^* \wedge \star \mathbb{D}^\dagger \zeta \ \ (2.0.1) \\ &= \int \mathbb{D}\eta^* \wedge \star \zeta - \mathrm{i}eA \wedge \eta^* \wedge \star \zeta - (-)^k \eta^* \wedge \mathrm{d} \star \zeta \\ &= \int \mathbb{D}\eta^* \wedge \star \zeta + \eta^* \wedge (-)^k \mathrm{i}eA \wedge \star \zeta - (-)^k \eta^* \wedge \mathrm{d} \star \zeta \\ &= \int \mathbb{D}\eta^* \wedge \star \zeta - \eta^* \wedge \star (-)^k \star^{-1} \left(\mathrm{d} - \mathrm{i}eA \right) \wedge \star \zeta \,. \end{split} \tag{2.0.2}$$

$$\mathbb{D}^\dagger \zeta = (-)^k \star^{-1} \left(\mathrm{d} - \mathrm{i}eA \right) \wedge \star \zeta \,. \tag{2.0.3}$$

3 Maxwell-Klein-Fock-Gordon theory

$$S = \int -\mathbb{D}\phi^* \wedge \star \mathbb{D}\phi - m^2 \phi^* \wedge \star \phi - \frac{1}{2} F \wedge \star F. \tag{3.0.1}$$

$$\delta \mathbb{D} \phi = -ie\delta A \phi + \mathbb{D} \delta \phi. \tag{3.0.2}$$

$$\begin{split} \delta(\mathbb{D}\phi^* \wedge \star \mathbb{D}\phi) &= \mathbb{d}(\delta\phi^* \wedge \star \mathbb{D}\phi + \delta\phi \wedge \star \mathbb{D}\phi^*) \\ &+ \delta\phi^* \wedge \star \mathbb{D}^\dagger \mathbb{D}\phi + \delta\phi \wedge \star \mathbb{D}^\dagger \mathbb{D}\phi^* \\ &+ \delta A \wedge \left(\mathrm{i}e(\phi^* \star \mathbb{D}\phi - \phi \star \mathbb{D}\phi^*) \right), \end{split} \tag{3.0.3}$$

$$\delta(F \wedge \star F) = 2d(\delta A \wedge \star F) - 2\delta A \wedge d \star F. \tag{3.0.4}$$

$$\begin{split} \delta S &= \int -\mathrm{d}(\delta \phi^* \wedge \star \mathbb{D} \phi + \delta \phi \wedge \star \mathbb{D} \phi^* + \delta A \wedge \star F) \\ &+ \delta \phi^* \wedge \star (\mathbb{D}^\dagger \mathbb{D} - m^2) \phi + \delta \phi \wedge \star (\mathbb{D}^\dagger \mathbb{D} - m^2) \phi^* + \\ &+ \delta A \wedge (-\mathrm{d} \star F + \mathrm{i} e(\phi^* \star \mathbb{D} \phi - \phi \star \mathbb{D} \phi^*)). \end{split} \tag{3.0.5}$$

3.1 Lorenz gauge

$$\Box^2 := \left(\mathbf{d} + \mathbf{d}^{\dagger} \right)^2 = \mathbf{d} \mathbf{d}^{\dagger} + \mathbf{d}^{\dagger} \mathbf{d}. \tag{3.1.1}$$

$$d \star F = d \star dA = \star (-)^2 \star^{-1} d \star dA = \star d^{\dagger} dA = \star (\Box^2 - dd^{\dagger}) A. \tag{3.1.2}$$

One would like to have $dd^{\dagger}A = 0$, or $d^{\dagger}A = \text{const.}$ This would be fulfilled if

$$\mathbf{d}^{\dagger} A = 0 \,, \tag{3.1.3}$$

which is the Lorenz gauge [1–3].