Virtual Memory

Operating System

Background

- Code needs to be in memory to execute, but entire program rarely used
 - Unusual routines, large data structures
- □ Entire program code not needed at same time
- □ Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Each program takes less memory while running -> more programs run at the same time
 - Increased CPU utilization and throughput with no increase in response time or turnaround time
 - Less I/O needed to load or swap programs into memory -> each user program runs faster

Operating System

2

Virtual memory

- Virtual memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - More programs running concurrently
 - Less I/O needed to load or swap processes

Operating System

Virtual memory (Cont.)


- Virtual address space logical view of how process is stored in memory
 - Usually start at address 0, contiguous addresses until end of space
 - Meanwhile, physical memory organized in page frames
 - MMU must map logical to physical
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation

Operating System

Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when
 - Less I/O needed, no unnecessary
 - Less memory needed
 - □ Faster response
 - More users
- Similar to paging system with swapping (diagram on right)
- □ Page is needed ⇒ reference to it
 - ${\color{red} \bullet} \quad \text{invalid reference} \Rightarrow \text{abort}$
 - lacksquare not-in-memory \Rightarrow bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager

Operating System



5

Basic Concepts

- With swapping, pager guesses which pages will be used before swapping out again
- □ Instead, pager brings in only those pages into memory
- □ How to determine that set of pages?
 - □ Need new MMU functionality to implement demand paging
- ☐ If pages needed are already memory resident
 - □ No difference from non demand-paging
- ☐ If page needed and not memory resident
 - $\hfill \square$ Need to detect and load the page into memory from storage
 - > Without changing program behavior
 - ▶ Without programmer needing to change code

Operating System

.




- $\begin{tabular}{ll} \hline U & With each page table entry a valid-invalid bit is associated \\ ({\bf v} \Rightarrow in-memory memory resident, i \Rightarrow not-in-memory) \\ \hline \end{tabular}$
- □ Initially valid–invalid bit is set to i on all entries
- Example of a page table snapshot:



 \blacksquare During MMU address translation, if valid–invalid bit in page table entry is $\stackrel{.}{\textbf{i}}\Rightarrow$ page fault

Operating System


7



Steps in Handling Page Fault

- If there is a reference to a page, first reference to that page will trap to operating system
 - Page fault
- 2. Operating system looks at another table to decide:
 - ${\color{red} \blacksquare} \quad \text{Invalid reference} \Rightarrow \text{abort}$
 - Just not in memory
- 3. Find free frame
- 4. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory Set validation bit = v
- 6. Restart the instruction that caused the page fault

Operating System



Aspects of Demand Paging

- □ Extreme case start process with *no* pages in memory
 - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
 - And for every other process pages on first access
 - Pure demand paging
- □ Actually, a given instruction could access multiple pages -> multiple page faults
- □ Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart

Operating System

11

Free-Frame List

- ☐ When a page fault occurs, the operating system must bring the desired page from secondary storage into main memory.
- Most operating systems maintain a free-frame list -- a pool of free frames for satisfying such requests.

head
$$\longrightarrow$$
 7 \longrightarrow 97 \longrightarrow 15 \longrightarrow 126 \cdots \longrightarrow 75

- Operating system typically allocate free frames using a technique known as zero-fill-on-demand -- the content of the frames zeroed-out before being allocated.
- □ When a system starts up, all available memory is placed on the free-frame list.

Operating System

Stages in Demand Paging - Worse Case

- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - 1. Wait in a queue for this device until the read request is serviced
 - 2. Wait for the device seek and/or latency time
 - 3. Begin the transfer of the page to a free frame

Operating System

3

Stages in Demand Paging (Cont.)

- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

Operating System

14

Performance of Demand Paging

- □ Page Fault Rate $0 \le p \le 1$

 - \square if p = 1, every reference is a fault
- □ Effective Access Time (EAT)

 $EAT = (1 - p) \times memory access$

- + p (page fault overhead
- + swap page out
- + swap page in)

Operating System

Demand Paging Example

- ☐ Memory access time = 200 nanoseconds
- ☐ Average page-fault service time = 8 milliseconds
- \square EAT = $(1 p) \times 200 + p$ (8 milliseconds)
 - $= (1 p) \times 200 + p \times 8,000,000$ (nanosec)
 - = 200 + p x 7,999,800 (nanosec)

Operating System

.

What Happens if There is no Free Frame?

- Used up by process pages
- Page replacement find some page in memory, but not really in use, page it out
 - □ Algorithm terminate? swap out? replace the page?
 - Performance want an algorithm which will result in minimum number of page faults
- ☐ Same page may be brought into memory several times


Operating System

17

Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- ☐ Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory

Operating System




Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select
 - a victim frame
 - Write victim frame to disk if dirty
- Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap

Note now potentially 2 page transfers for page fault – increasing EAT

Operating System





Page and Frame Replacement Algorithms


- □ Frame-allocation algorithm determines
 - How many frames to give each process
 - Which frames to replace
- □ Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- □ Page-replacement algorithms: OPT(MIN), LRU, FIFO, CLOCK


Operating System

5









LRU Algorithm (Cont.)


- Counter implementation
 - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - When a page needs to be changed, look at the counters to find smallest value
 - > Search through table needed
- Stack implementation
 - □ Keep a stack of page numbers in a double link form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - But each update more expensive
 - No search for replacement
- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly

Operating System

1

Use Of A Stack to Record Most Recent Page References

reference string



Operating System

2

LRU Approximation Algorithms

- LRU needs special hardware and still slow
- □ Reference bit / use bit
 - □ With each page associate a bit, initially = 0
 - $\hfill\Box$ When page is referenced bit set to 1
 - □ Replace any with reference bit = 0 (if one exists)
 - We do not know the order, however
- Second-chance algorithm
 - Generally FIFO, plus hardware-provided reference bit
 - Clock replacement
 - If page to be replaced has
 - Reference bit = 0 -> replace it
 - reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules

Operating System


second chance (CLOCK) algorithm

- ☐ The frames for the process are treated as a circular buffer.
- When a page is changed, the pointer will point to the next frame in the buffer.
- ☐ Each frame has a use bit. This bit is set to 1 when
 - A page is first loaded into the frame
 - ☐ The page in the frame is referenced
- \Box The page is only replaced at the frame with use bit = 0
 - □ While trying to find the page to replace, all use bits are reset to 0

Operating System

4

second chance (CLOCK) algorithm



NOTE: Asterisk (*) indicates reference/use bit = 1

Operating System

5

Enhanced Second-Chance Algorithm

- Improve algorithm by using reference bit and modify bit (if available) in concert
- □ Take ordered pair (reference, modify):
 - (0, 0) neither recently used not modified best page to replace
 - (0, 1) not recently used but modified not quite as good, must write out before replacement
 - (1, 0) recently used but clean probably will be used again soon
 - (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
 - ☐ Might need to search circular queue several times

Operating System


Thrashing

- ☐ If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - ▶ Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system

Operating System

Thrashing (Cont.)

☐ Thrashing. A process is busy swapping pages in and out



Operating System

Demand Paging and Thrashing

■ Why does demand paging work?

Locality model

- $\hfill\Box$ Process migrates from one locality to another
- Localities may overlap
- Why does thrashing occur?

 Σ size of locality > total memory size

□ Limit effects by using local or priority page replacement

Operating System

Working-Set Model

- $\begin{tabular}{ll} \square $$ $\Delta \equiv $ working-set window $\equiv $ a fixed number of page references \\ Example: 10,000 instructions \\ \end{tabular}$
- □ WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - $\ \square$ if Δ too small will not encompass entire locality
 - $\ \square$ if Δ too large will encompass several localities
 - □ if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \Sigma WSS_i = \text{total demand frames}$
 - Approximation of locality

Working-Set Model (Cont.)


- □ if $D > m \Rightarrow$ Thrashing
- \square Policy if D > m, then suspend or swap out one of the processes

page reference table ...2615777751623412344434441323444344... $WS(t_1) = \{1,2,5,6,7\}$

Operating System

Page-Fault Frequency

- More direct approach than WSS
- ☐ Establish "acceptable" page-fault frequency (PFF) rate and use local replacement policy
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame



Buddy System

- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - ▶ Continue until appropriate sized chunk available
- ☐ For example, assume 256KB chunk available, kernel requests 21KB
 - □ Split into A_{L and} A_R of 128KB each
 - $\,\blacktriangleright\,$ One further divided into ${\rm B_L}$ and ${\rm B_R}$ of 64KB
 - One further into \mathbf{C}_{L} and \mathbf{C}_{R} of 32KB each one used to satisfy request
- ☐ Advantage quickly coalesce unused chunks into larger chunk
- □ Disadvantage fragmentation

Operating System

