

ADVANCED DATA FLOW







LEARNING OBJECTIVES

- Learn about ways to use initial data and pinned memory
- Learn about uninitialized buffers and when to use them





SYCL

PRECURSOR

Parts of this lecture will focus primarily on the buffer/accessor model.







INITIAL DATA

• Often when writing SYCL kernel functions there is initial data which has been allocated somewhere else in the application.







INITIAL DATA (USM)

```
auto devicePtr = sycl::malloc_device(sizeInBytes, gpuQueue);
gpuQueue.memcpy(devicePtr, initialData, sizeInBytes).wait();
```

- When using the USM model (unless using system USM) pointers passed to kernel functions must be allocated by the SYCL runtime.
- This means you have to copy the initial data to the USM memory allocation using memcpy.







INITIAL DATA (USM)

```
auto sharedData = sycl::malloc_shared(sizeInBytes, gpuQueue);
```

- Alternatively if your device supports shared USM allocations you can allocate memory which is shared across the host and device.
- Then there is no need to copy the data to the device.







INITIAL DATA (BUFFER/ACCESSOR)

```
auto buf = sycl::buffer{initialData, sycl::range{size}};
```

- When using the buffer/accessor model a buffer can manage already allocated memory or have the SYCL runtime allocate it.
- To do this simply provide an initial pointer when constructing a buffer.
- Note that the SYCL runtime is free to allocate memory and copy this into it, which can introduce an overhead.







USE_HOST_POINTER PROPERTY

```
auto buf = sycl::buffer{initialData, sycl::range{size},
   {sycl::property::buffer::use_host_ptr{}}};
```

- To prevent the runtime allocation memory you can provide the property::buffer::use_host_ptr property when constructing the buffer.
- This instructs the SYCL runtime that it may not allocate any additional memory.
- Though note that the backend (such as OpenCL) may still allocate memory.







COPY BACK

• A buffer will synchronize the latest modified copy of the data it manages back to the initial pointer on destruction.







SET_FINAL_DATA

```
auto buf = sycl::buffer{initialData, sycl::range{size}};
buf.set_final_data(finalData);
```

- To change the destination that a buffer will synchronize to on destruction you can call set final data with another.
- The address provided must be capable of holding the size of the data the buffer manages.







SET_FINAL_DATA

```
auto buf = sycl::buffer{initialData, sycl::range{size}};
buf.set_final_data(nullptr);
```

- Alternatively to prevent the buffer from synchronizing back to the initial data entirely you can call set_final_data with nullptr.
- A buffer with no final data address is useful because the data can left on a device and not copied back to the host from the device.







UNINITIALIZED BUFFERS (BUFFER/ACCESSOR)

```
auto buf = sycl::buffer<T>{sycl::range{size}};
```


- As we've seen in the USM model all memory is allocated initialized, but buffers can be constructed without initial data.
- A buffer like this is called uninitialized.
- To do this simply construct a buffer without initial data. Just remember to explicitly specify the buffers data type as it can't be inferred from the initial data anymore.
- Uninitialized buffers are useful for a couple of reasons because they can be allocated directly on a device and don't require moving data from the host.







USING INITIAL DATA AND UNINITIALIZED BUFFERS



- Here we have an example of using these techniques:
 - Input data is initialized with initial data but doesn't need to be copied back so it can use set_final_data(nullptr).
 - Temporary is only used on the device so can be an uninitialized buffer.
 - Output data is initialized on the device and needs to be copied back so it can be an uninitialized buffer and use set_final_data to provide the final data address.







PINNED MEMORY (BUFFER/ACCESSOR)

- Pinned memory is a feature supported by most SYCL backends and devices.
- It allows you to allocate memory which can be mapped between the host and device more efficiently, providing similar benefits to USM.
- Though the requirements can vary from one device to another.
- It's always best to check the vendor's programming guide.







PINNED MEMORY (BUFFER/ACCESSOR)

- The SYCL runtime will always aim to manage the memory for you in the most efficient way for the target device.
- Generally there are two approaches to facilitate pinned memory:
 - Allocate memory according to the vendor's programming guide, usually involved allocating a size of a particular multiple and aligned to a particular size, and then use the property::buffer::use_host_ptr property.
 - Create an uninitialized buffer and allow the runtime to allocate the memory the appropriate way.





QUESTIONS









EXERCISE

Code_Exercises/Exercise_12_Temporary_Data/source

Write a SYCL application which uses uninitialized buffers and disabling write back.

