

USING USM







LEARNING OBJECTIVES

- Learn how to allocate memory using USM
- Learn how to copy data to and from USM allocated memory
- Learn how to access data from USM allocated memory in a kernel function
- Learn how to free USM memory allocations





FOCUS ON EXPLICIT USM

- Remember that there are different variants of USM; explicit, restricted, concurrent and system.
- Remember also that there are different ways USM memory can be allocated; host, device and shared.
- We're going to focus explicit USM and device allocations this is the minimum required variant.





USM ALLOCATION TYPES

Туре	Description	Accessible on host?	Accessible on device?	Located on
device	Allocations in device memory	×	✓	device
host	Allocations in host memory	√	>	host
shared	Allocations shared between host and device	√	√	Can migrate between host and device

Figure 6-1. USM allocation types

(from book)





MALLOC_DEVICE

```
void* malloc_device(size_t numBytes, const queue& syclQueue, const property_list &propList = {});
template <typename T>
T* malloc_device(size_t count, const queue& syclQueue, const property_list &propList = {});
```

- A USM device allocation is performed by calling one of the malloc_device functions.
- Both of these functions allocate the specified region of memory on the device associated with the specified queue.
- The pointer returned is only accessible in a kernel function running on that device.
- Synchronous exception if the device does not have aspect::usm_device_allocations
- This is a blocking operation.







```
void free(void* ptr, queue& syclQueue);
```

- In order to prevent memory leaks USM device allocations must be free by calling the free function.
- The queue must be the same as was used to allocate the memory.
- This is a blocking operation.







event queue::memcpy(void* dest, const void* src, size_t numBytes, const std::vector &depEvents);

- Data can be copied to and from a USM device allocation by calling the queue's memcpy member function.
- The source and destination can be either a host application pointer or a USM device allocation.
- This is an asynchronous operation enqueued to the queue.
- An event is returned which can be used to synchronize with the completion of copy operation.
- May depend on other events via depEvents





MEMSET & FILL

```
event queue::memset(void* ptr, int value, size_t numBytes, const std::vector &depEvents);
event queue::fill(void* ptr, const T& pattern, size_t count, const std::vector &depEvents);
```

- The additional queue member functions memset and fill provide operations for initializing the data of a USM device allocation.
- The member function memset initializes each byte of the data with the value interpreted as an unsigned char.
- The member function fill initializes the data with a recurring pattern.
- These are also asynchronous operations.





```
int square_number(int x) {
  auto myQueue = queue{};

myQueue.submit([&](handler &cgh) {
    cgh.single_task<square_number>([=]() {
        /* square some number */
    });
  }).wait();

return x;
}
```

We start with a basic SYCL application which invokes a kernel function with single_task.





```
int square_number(int x) {
  auto myQueue = queue{usm_selector{}};

myQueue.submit([&](handler &cgh) {
    cgh.single_task<square_number>([=]() {
        /* square some number */
    });
  }).wait();

return x;
}
```

We initialize the queue with the usm_selector we wrote in the last exercise, which will choose a device which supports USM device allocations.





```
int square_number(int x) {
  auto myQueue = queue{usm_selector{}};
  auto devicePtr = malloc_device<int>(1, myQueue);

  myQueue.submit([&](handler &cgh) {
    cgh.single_task<square_number>([=]() {
        /* square some number */
    });
  }).wait();
  return x;
}
```

We allocate USM device memory by calling malloc_device. Here we use the template variant and specify type int.





```
int square_number(int x) {
   auto myQueue = queue{usm_selector{}};
   auto devicePtr = malloc_device<int>(1, myQueue);
   myQueue.memcpy(devicePtr, &x, sizeof(int)).wait();

myQueue.submit([&] (handler &cgh) {
    cgh.single_task<square>([=](){
        /* square some number */
    });
   }).wait();
   return x;
}
```

We copy the value of x in the host application to the USM device memory by calling memcpy on myQueue. We immediately call wait on the returned event to synchronize with the completion of the copy operation.





```
int square_number(int x) {
   auto myQueue = queue{usm_selector{}};
   auto devicePtr = malloc_device<int>(1, myQueue);
   myQueue.memcpy(devicePtr, &x, sizeof(int)).wait();

myQueue.submit([&] (handler &cgh) {
    cgh.single_task<square>([=]() {
        *devicePtr = (*devicePtr) * (*devicePtr);
    });
   }).wait();
   return x;
}
```

We then pass the devicePtr directly to the kernel function and access it can then be deferenced and the data written to.





```
int square_number(int x) {
  auto myQueue = queue{usm_selector{}};
  auto devicePtr = malloc_device<int>(1, myQueue);
  myQueue.memcpy(devicePtr, &x, sizeof(int)).wait();
  myQueue.submit([&](handler &cgh){
    cgh.single_task<square>([=](){
      *devicePtr = (*devicePtr) * (*devicePtr);
    });
  }).wait();
  myQueue.memcpy(&x, devicePtr, sizeof(int)).wait();
  return x;
```

We then copy the result from USM device memory back to the variable x in the host application by calling memcpy on myQueue.





```
int square_number(int x) {
  auto myQueue = queue{usm_selector{}};
  auto devicePtr = malloc_device<int>(1, myQueue);
  myQueue.memcpy(devicePtr, &x, sizeof(int)).wait();
  myQueue.submit([&](handler &cgh){
    cgh.single_task<square>([=](){
      *devicePtr = (*devicePtr) * (*devicePtr);
    });
  }).wait();
  myQueue.memcpy(&x, devicePtr, sizeof(int)).wait();
  free(devicePtr, myQueue);
  return x;
```

Finally, we free the USM device memory that we allocated.





QUEUE SHORTCUTS

```
template <typename KernelName, typename KernelType>
event queue::single_task(const KernelType &KernelFunc);

template <typename KernelName, typename KernelType, int Dims>
event queue::parallel_for(range GlobalRange, const KernelType &KernelFunc);
```

- The queue provides shortcut member functions which allow you to invoke a single_task or a parallel_for without defining a command group.
- These can only be used when using the USM data management model.





WITH THE QUEUE SHORTCUT

```
int square_number(int x) {
  auto myQueue = queue{usm_selector{}};
  auto devicePtr = malloc_device<int>(1, myQueue);
  myQueue.memcpy(devicePtr, &x, sizeof(int)).wait();
  myQueue.single_task<square>([=](){
    *devicePtr = (*devicePtr) * (*devicePtr);
  }).wait();
  myQueue.memcpy(&x, devicePtr, sizeof(int)).wait();
  free(devicePtr, myQueue);
  return x;
```

If we use the queue shortcut here it reduces the complexity of the code.



QUESTIONS









Code_Exercises/Exercise_8_USM_Vector_Add/source

Implement the vector add from lesson 6 using the USM data management model.