# Common Lisp Webdriver Client

# Table of Contents

1	Introduction	1
<b>2</b>	Usage	2
	2.1 Actions	2
3	Installation	4
4	Utils	5
	4.1 Interactive session	
	4.2 Utils API conventions	
	4.3 Waiting for the reaction	6
	4.4 Running tests	6
5	API	7
	5.1 WEBDRIVER-CLIENT package	7
	5.2 WEBDRIVER-CLIENT-UTILS package	
6	Index	7

# 1 Introduction

CL Webdriver Client is client library for WebDriver.

WebDriver is a remote control interface that enables introspection and control of user agents. It provides a platform- and language-neutral wire protocol as a way for out-of-process programs to remotely instruct the behavior of web browsers.

Provided is a set of interfaces to discover and manipulate DOM elements in web documents and to control the behavior of a user agent. It is primarily intended to allow web authors to write tests that automate a user agent from a separate controlling process, but may also be used in such a way as to allow in-browser scripts to control a — possibly separate — browser.

See W3C Webdriver spec (https://www.w3.org/TR/webdriver).

# 2 Usage

```
;; see examples/*.lisp and t/*.lisp
(in-package :cl-user)
(eval-when (:compile-toplevel :load-toplevel :execute)
  (ql:quickload :cl-webdriver-client))
(defpackage go-test
  (:use :cl :webdriver-client))
(in-package :go-test)
(defparameter *code* "
package main
import \"fmt\"
func main() {
    fmt.Print(\"Hello WebDriver!\")
}")
(with-session ()
  (setf (url) "http://play.golang.org/?simple=1")
  (let ((elem (find-element "#code" :by :css-selector)))
    (element-clear elem)
    (element-send-keys elem *code*))
  (let ((btn (find-element "#run")))
    (element-click btn))
  (loop
     with div = (find-element "#output")
     for ouput = (element-text div)
     while (equal ouput "Waiting for remote server...")
     do (sleep 0.1)
     finally (print ouput)))
```

#### 2.1 Actions

The Actions API provides a low-level interface for providing virtualised device input to the web browser. Conceptually, the Actions commands divide time into a series of ticks. The local end sends a series of actions which correspond to the change in state, if any, of each input device during each tick. For example, pressing a key is represented by an action sequence consisting of a single key input device and two ticks, the first containing a keyDown action, and the second a keyUp action, whereas a pinch-zoom input is represented by an action sequence consisting of three ticks and two pointer input devices of type touch, each performing a sequence of actions pointerDown, followed by pointerMove, and then pointerUp.

Chapter 2: Usage 3

See https://www.w3.org/TR/webdriver/#actions for the whole explanation.

To perform actions in *cl-webdriver-client* use [PERFORM-ACTIONS], page 15. That function implements a little language, with the following syntax:

### **Syntax:**

```
actions ::= ({actions-input-source}*)
actions-input-source ::= (input-source-type {action}*)
input-source-type ::= :none | :pointer | :mouse | :pen | :touch | :key
action ::= pause | pointer-move | pointer-down | pointer-up | key-down | key-up
pause ::= (:pause duration)
pointer-move ::= (:pointer-move x y)
pointer-down ::= (:pointer-down button-number)
pointer-up ::= (:pointer-up button-number)
key-down ::= (:key-down key)
key-up ::= (:key-up key)
```

### Arguments and values:

- actions—a list of actions-input-sources. One list for each type of input source that wants to be used.
- actions-input-source—a list. Specifies the list of actions to perform for a particular input source.
- duration—an integer. The time to pause in milliseconds.
- key—a string. A string with the character (e.g. "a"). Use [KEY], page 15 for entering special characters.
- button-number—an integer greater than or equal to 0.
- x—an integer. Horizontal screen coordinate.
- y—an integer. Vertical screen coordinate.

## Examples:

# 3 Installation

```
git clone https://github.com/copyleft/cl-webdriver-client ~/quicklisp/local-projects/(ql:quickload :cl-webdriver-client)

You need a running instance of selenium-server-standalone.

[Download](http://www.seleniumhq.org/download/) it and run:

curl -LO https://goo.gl/SP94ZB -o selenium-server-standalone.jar
java -jar selenium-server-standalone.jar
```

# 4 Utils

There is a :webdriver-client-utils package which should reduce boilerplate. For example:

#### 4.1 Interactive session

You can just start the session and control it from your repl:

```
(in-package :my-test)
(start-interactive-session)
(setf (url) "http://google.com")
(send-keys "cl-webdriver-client")
(send-keys (key :enter))
(classlist "#slim_appbar") ; prints ("ab_tnav_wrp")
(stop-interactive-session)
```

## 4.2 Utils API conventions

```
If utility function needs an element to work on it defaults to '(active-element)'.

(click); click on the current active element.

You can also pass a css selector as a last parameter.

(print (id "#submit")); print id the of matched element

(assert (= (first (classlist "div")) "first-div-ever"))

To change default element you can:

(setf webdriver-client-utils:*default-element-func* (lambda () (find-element "input[ty
```

Chapter 4: Utils 6

# 4.3 Waiting for the reaction

Often you need to wait for some action to be done. For example if you do a (click) on the button to load search results, you need to wait them to load.

```
(wait-for ".search-result" :timeout 10) ; wait 10 seconds
Timeout defaults to 30 seconds. You can globally change it:
    (setf webdriver-client-utils:*timeout* 3)
```

# 4.4 Running tests

## REPL

```
(ql:quickload '(:cl-selenium :prove))
(setf prove:*enable-colors* nil)
(prove:run :cl-webdriver-client-test)
```

## Shell

sh
./test.sh

## 5 API

## 5.1 WEBDRIVER-CLIENT package

WEBDRIVER-CLIENT [PACKAGE]

This package exports functions for working with Selenium WebDriver.

For documentation see:

- https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol
- https://www.w3.org/TR/webdriver1

#### External definitions

## Uncategorized

ELEMENT-ID (sb-pcl::object)

[WEBDRIVER-CLIENT]

NO-SUCH-ELEMENT-ERROR

[WEBDRIVER-CLIENT]

Error signaled when no such element is found.

Class precedence list: no-such-element-error, find-error, error, serious-condition, condition, t

LOG-TYPES (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Return the types of logs supported by the WebDriver.

- browser: Javascript console logs from the browser.
- client: Logs from the client side implementation of the WebDriver protocol (e.g. the Java bindings).
- driver: Logs from the internals of the driver (e.g. FirefoxDriver internals).
- performance: Logs relating to the performance characteristics of the page under test (e.g. resource load timings).
- server: Logs from within the selenium server.

See: https://github.com/SeleniumHQ/selenium/wiki/Logging.

 ${\tt MOUSE-CLICK}~(button~\&key~(session~*session*))$ 

[WEBDRIVER-CLIENT]

Click any mouse button (at the coordinates set by the last moveto command). Note that calling this command after calling buttondown and before calling button up (or any out-of-order interactions sequence) will yield undefined behaviour).

See: https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol#sessionsessionidclick

MOUSE-MOVE-TO (x y & key element (session \*session\*)) [WEBDRIVER-CLIENT] Move the mouse by an offset of the specificed element. If no element is specified, the move is relative to the current mouse cursor. If an element is provided but no offset, the mouse will be moved to the center of the element. If the element is not visible, it

will be scrolled into view.

See: https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol#sessionsessionidmoveto

LOGS (type & key (session \*session\*))

[WEBDRIVER-CLIENT]

Return the logs of a particular TYPE.

See: [LOG-TYPES], page 7.

#### Elements

ELEMENT-TEXT (element & key (session \*session\*)) [WEBD

[WEBDRIVER-CLIENT]

The Get *Element* Text command intends to return an *element*'s text "as rendered". An *element*'s rendered text is also used for locating a elements by their link text and partial link text.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#get-element-text.

ELEMENT-ENABLED (element &key (session \*session\*)) [WEBDRIVER-CLIENT]

Returns if ELEMENT is enabled.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#is-element-enabled.

ELEMENT-RECT (element & key (session \*session\*))

[WEBDRIVER-CLIENT]

The Get *Element* Rect command returns the dimensions and coordinates of the given web *element*. The returned value is a dictionary with the following members:

X

X axis position of the top-left corner of the web *element* relative to the current browsing context's document *element* in CSS pixels.

у

Y axis position of the top-left corner of the web *element* relative to the current browsing context's document *element* in CSS pixels.

height

Height of the web element's bounding rectangle in CSS pixels.

width

Width of the web *element*'s bounding rectangle in CSS pixels.

Category: Elements

Return the ELEMENT's tag name.

Category: Elements

## ACTIVE-ELEMENT (&key (session \*session\*)) [WEBDRIVER-CLIENT]

Return the active element of the current browsing context's document.

The active element is the Element within the DOM that currently has focus.

If there's no active element, an error is signaled.

Category: Elements

See: https://www.w3.org/TR/webdriver2/#get-active-element.

See: https://developer.mozilla.org/en-US/docs/Web/API/Document/

activeElement.

# FIND-ELEMENT (value & key (by :css-selector) (session [WEBDRIVER-CLIENT] \*session\*))

The Find Element command is used to find an element in the current browsing context that can be used as the web element context for future element-centric commands.

For example, consider this pseudo code which retrieves an element with the #tore-move ID and uses this as the argument for a script it injects to remove it from the HTML document:

let body (undefined) [=], page (undefined) session.find.css("#toremove"); session.execute("arguments[0].remove()", [body]);

The BY parameter represents the element location strategy.

It can be one of:

- :id : Finds element by id.
- :class-name : Finds element by class name.
- :css-selector : Returns element that matches css selector.
- -: link-text: Returns element that matches <a> element text.
- :partial-link-text: Returns element that matches <a> element text partially.
- :tag-name: Returns element that matches tag name.
- :xpath: Returns element that matches the XPath expression.

If result is empty, a  $\langle$ undefined $\rangle$  [HANDLE-FIND-ERROR], page  $\langle$ undefined $\rangle$  is signaled.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#dfn-find-element.

# FIND-ELEMENTS (value & key (by :css-selector) (session [WEBDRIVER-CLIENT] \*session\*))

Find elements that match VALUE using location strategy in BY.

Category: Elements

See [FIND-ELEMENT], page 9.

See https://www.w3.org/TR/webdriver1/#find-elements.

ELEMENT-DISPLAYED (element & key (session \*session\*)) [WEBDRIVER-CLIENT]

Returns if *ELEMENT* is visible.

Category: Elements

See: https://www.w3.org/TR/webdriver1/#element-displayedness.

ELEMENT-ATTRIBUTE (element name & key (session [WEBDRIVER-CLIENT]

\*session\*))

Return the *ELEMENT*'s attribute named *NAME*.

Category: Elements

Session

DELETE-SESSION (session) [WEBDRIVER-CLIENT]

Delete the WebDriver SESSION.

Category: Session

START-INTERACTIVE-SESSION (&rest capabilities) [WEBDRIVER-CLIENT]

Start an interactive session. Use this to interact with Selenium driver from a REPL.

Category: Session

See: [MAKE-SESSION], page 10

STOP-INTERACTIVE-SESSION nil [WEBDRIVER-CLIENT]

Stop an interactive session.

Category: Session

USE-SESSION (session) [WEBDRIVER-CLIENT]

Make SESSION the current session.

Category: Session

WITH-SESSION ((&rest capabilities) &body body) [WEBDRIVER-CLIENT]

Execute BODY inside a Selenium session.

Category: Session

See: [MAKE-SESSION], page 10

MAKE-SESSION (&key (browser-name :chrome) [WEBDRIVER-CLIENT]

browser-version (platform-name "Linux") platform-version

accept-ssl-certs additional-capabilities)

Creates a new WebDriver session with the endpoint node. If the creation fails, a

session not created error is returned.

Category: Session

See: https://www.w3.org/TR/webdriver1/#new-session. See: https://www.w3.org/TR/webdriver1/#capabilities.

#### Element interaction

ELEMENT-SEND-KEYS (element keys & key (session [WEBDRIVER-CLIENT] \*session\*))

The *Element Send Keys* command scrolls into view the form control *element* and then sends the provided *keys* to the *element*. In case the *element* is not keyboard-interactable, an *element* not interactable error is returned.

KEYS should be a string.

Category: *Element* interaction

See: https://www.w3.org/TR/webdriver1/#element-send-keys.

ELEMENT-CLICK (element & key (session \*session\*)) [WEBDRIVER-CLIENT]

The Element Click command scrolls into view the element if it is not already pointerinteractable, and clicks its in-view center point.

If the *element*'s center point is obscured by another *element*, an *element* click intercepted error is returned. If the *element* is outside the viewport, an *element* not interactable error is returned.

Category: Element interaction

See: https://www.w3.org/TR/webdriver1/#element-click.

ELEMENT-CLEAR (element & key (session \*session\*)) [WEBDRIVER-CLIENT] Clear the contents of ELEMENT (for example, a form field element).

Category: Element interaction

See: https://www.w3.org/TR/webdriver1/#dfn-element-clear.

### Navigation

PAGE-TITLE (&key (session \*session\*)) [WEBDRIVER-CLIENT]

This command returns the document title of the current top-level browsing context, equivalent to calling document.title.

Category: Navigation

See: https://www.w3.org/TR/webdriver2/#get-title.

PAGE-SOURCE (&key (session \*session\*)) [WEBDRIVER-CLIENT]

Returns a string serialization of the DOM of the current browsing context active document.

Category: Navigation

See: https://www.w3.org/TR/webdriver1/#get-page-source

 ${\tt SWITCH-TO-FRAME} \ (id \ \& {\tt key} \ (session \ *session*)) \\ {\tt [WEBDRIVER-CLIENT]}$ 

Change focus to another frame on the page. If the frame *id* is null, the server should switch to the page's default content.

In the context of a web browser, a frame is a part of a web page or browser window which displays content independent of its container, with the ability to load content independently.

Category: Navigation

See: https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol#

sessionsessionidframe.

See: https://en.wikipedia.org/wiki/Frame\_(World\_Wide\_Web) .

## BACK (&key (session \*session\*))

[WEBDRIVER-CLIENT]

This command causes the browser to traverse one step backward in the joint session history of the current top-level browsing context. This is equivalent to pressing the back button in the browser chrome or invoking window.history.back.

Category: Navigation

See: https://www.w3.org/TR/webdriver1/#dfn-back.

## REFRESH (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Refresh the current page.

Category: Navigation

### URL (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Get the current url in session.

Category: Navigation

See: https://www.w3.org/TR/webdriver1/#dfn-get-current-url.

#### Cookies

#### COOKIE

[WEBDRIVER-CLIENT]

A cookie is described in [RFC6265] by a name-value pair holding the cookie's data, followed by zero or more attribute-value pairs describing its characteristics.

Category: Cookies

Class precedence list: cookie, standard-object, t

Slots:

ullet name — initarg: :name

The name of the cookie

• value — initarg: :value

The cookie value

• path — initarg: :path

The cookie path. Defaults to '/' if omitted when adding a cookie.

• domain — initarg: :domain

The domain the cookie is visible to. Defaults to the current browsing context's active document's URL domain if omitted when adding a cookie.

• secure — initarg: :secure

Whether the cookie is a secure cookie. Defaults to false if omitted when adding a cookie.

• http-only — initarg: :http-only

Whether the cookie is an HTTP only cookie. Defaults to false if omitted when adding a cookie.

• expiry — initarg: :expiry

When the cookie expires, specified in seconds since Unix Epoch. Must not be set if omitted when adding a cookie.

### COOKIE (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Retrieve all cookies visible to the current page.

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#get-all-cookies.

See: https://github.com/SeleniumHQ/selenium/wiki/JsonWireProtocol#

sessionsessionidcookie.

DELETE-COOKIE (cookie-name & key (session \*session\*)) [WEBDRIVER-CLIENT]

Delete the cookie with name COOKIE-NAME.

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#delete-cookie

#### DELETE-ALL-COOKIES (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Deletes all cookies

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#delete-all-cookies

# MAKE-COOKIE (name value & key path domain secure

[WEBDRIVER-CLIENT]

expiry)

Create a cookie object.

Category: Cookies

# FIND-COOKIE (cookie-name & key (session \*session\*))

[WEBDRIVER-CLIENT]

Retrieve the cookie with name COOKIE-NAME.

Category: Cookies

See: https://www.w3.org/TR/webdriver1/#get-named-cookie

## Document handling

EXECUTE-SCRIPT (script args &key (session \*session\*)) [WEBDRIVER-CLIENT] Inject a snippet of JavaScript into the page for execution in the context of the currently selected frame. The executed script is assumed to be synchronous and the result of evaluating the script is returned to the client.

The *script* argument defines the *script* to execute in the form of a function body. The value returned by that function will be returned to the client. The function will be invoked with the provided *args* array and the values may be accessed via the arguments object in the order specified.

Arguments may be any JSON-primitive, array, or JSON object. JSON objects that define a WebElement reference will be converted to the corresponding DOM element. Likewise, any WebElements in the *script* result will be returned to the client as WebElement JSON objects.

Category: Document handling

See: https://www.w3.org/TR/webdriver1/#executing-script.

### Screen capture

## SCREENSHOT (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Screenshots are a mechanism for providing additional visual diagnostic information. They work by dumping a snapshot of the initial viewport's framebuffer as a lossless PNG image. It is returned to the local end as a Base64 encoded string.

Category: Screen capture

See: https://www.w3.org/TR/webdriver2/#screen-capture.

# ${\tt ELEMENT-SCREENSHOT} \ (element \ \& key \ (session$

[WEBDRIVER-CLIENT]

\*session\*))

The Take *Element* Screenshot command takes a screenshot of the visible region encompassed by the bounding rectangle of an *element*. If given a parameter argument scroll that evaluates to false, the *element* will not be scrolled into view.

Category: Screen capture

See: https://www.w3.org/TR/webdriver1/#take-element-screenshot.

#### User prompts

#### DISMISS-ALERT (&key (session \*session\*))

[WEBDRIVER-CLIENT]

The Dismiss Alert command dismisses a simple dialog if present. A request to dismiss an alert user prompt, which may not necessarily have a dismiss button, has the same effect as accepting it.

Category: User prompts

See: https://www.w3.org/TR/webdriver1/#dismiss-alert

### ACCEPT-ALERT (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Accept Alert.

Category: User prompts

See: https://www.w3.org/TR/webdriver1/#dfn-accept-alert

ALERT-TEXT (&key (session \*session\*))

[WEBDRIVER-CLIENT]

Get Alert Text.

Category: User prompts

See: https://www.w3.org/TR/webdriver1/#get-alert-text

#### Actions

KEY (key)

[WEBDRIVER-CLIENT]

Returns a string with KEY's codepoint.

Category: Actions

See: https://www.w3.org/TR/webdriver/#keyboard-actions

PERFORM-ACTIONS (actions & optional (session

[WEBDRIVER-CLIENT]

\*session\*))

The Actions API provides a low-level interface for providing virtualised device input to the web browser.

Conceptually, the Actions commands divide time into a series of ticks. The local end sends a series of actions which correspond to the change in state, if any, of each input device during each tick. For example, pressing a key is represented by an action sequence consisting of a single key input device and two ticks, the first containing a keyDown action, and the second a keyUp action, whereas a pinch-zoom input is represented by an action sequence consisting of three ticks and two pointer input devices of type touch, each performing a sequence of actions pointerDown, followed by pointerMove, and then pointerUp.

Category: Actions

See: https://www.w3.org/TR/webdriver/#actions

#### Windows

CLOSE-CURRENT-WINDOW (&key (session \*session\*)) [WEBDRIVER-CLIENT]

Close the current window.

Category: Windows

# 5.2 WEBDRIVER-CLIENT-UTILS package

#### WEBDRIVER-CLIENT-UTILS

[PACKAGE]

Package with the purpose of reducing boilerplate.

The exported definitions work with an implicit element. The default implicit element is the current active element. So, it is not necessary to pass the element you are working with around most of the time.

#### External definitions

#### Variables

\*TIMEOUT\*

[WEBDRIVER-CLIENT-UTILS]

Default timeout value to use in selenium-utils functions.

\*DEFAULT-ELEMENT-FUNC\*

[WEBDRIVER-CLIENT-UTILS]

Function used to get the 'default element' by selenium-utils functions. It is [ACTIVE-ELEMENT], page 9 function by default.

Functions

ID (&optional selector)

[WEBDRIVER-CLIENT-UTILS]

Get active element id.

GET-COOKIE (cookie name)

[WEBDRIVER-CLIENT-UTILS]

Get value of COOKIE at NAME.

FIND-ELEM (selector & key (by :css-selector))

[WEBDRIVER-CLIENT-UTILS]

Find element by SELECTOR. Returns NIL if the element is not found.

WAIT-FOR (selector & key (timeout \*timeout\*))

[WEBDRIVER-CLIENT-UTILS]

Wait for an element that matches *SELECTOR* to appear on the screen. *TIMEOUT* indicates how much time to wait (default is \*TIMEOUT\*).

CLASSNAME (&optional selector)

[WEBDRIVER-CLIENT-UTILS]

Get active element classname.

TEXT (&optional selector)

[WEBDRIVER-CLIENT-UTILS]

Get active element's text.

SEND-KEY (key &optional selector)

[WEBDRIVER-CLIENT-UTILS]

Send a key to active element.

CLASSLIST (&optional selector)

[WEBDRIVER-CLIENT-UTILS]

Get active element class list.

ATTR (name &optional selector)

[WEBDRIVER-CLIENT-UTILS]

Get acttive element attribute.

SEND-KEYS (keys &optional selector)

[WEBDRIVER-CLIENT-UTILS]

Send keys to active element.

ELEM (&optional selector)

[WEBDRIVER-CLIENT-UTILS]

If SELECTOR is given, wait for an element that matches the selector to appear. Otherwise, call [\*DEFAULT-ELEMENT-FUNC\*], page 16 (the active element is returned by default).

CLICK (&optional selector)

[WEBDRIVER-CLIENT-UTILS]

Click on active element.

# 6 Index

 $({\rm Index}\ is\ nonexistent})$ 

*	$\mathbf{W}$
*DEFAULT-ELEMENT-FUNC*	WEBDRIVER-CLIENT- UTILS:*DEFAULT-ELEMENT-FUNC*
$\mathbf{A}$	$\mathbf{F}$
ACCEPT-ALERT       14         ACTIVE-ELEMENT       9         ALERT-TEXT       15         ATTR       16	FIND-COOKIE       13         FIND-ELEM       16         FIND-ELEMENT       9         FIND-ELEMENTS       9
В	G
BACK	GET-COOKIE
$\mathbf{C}$	I
CLASSLIST       16         CLASSNAME       16	ID
CLICK       16         CLOSE-CURRENT-WINDOW       15         COOKIE       13	<b>K</b> KEY
	KEI 19
D	L
DELETE-ALL-COOKIES       13         DELETE-COOKIE       13         DELETE-SESSION       10         DISMISS-ALERT       14	LOG-TYPES 7 LOGS 8
DISPLISS ALERT	$\mathbf{M}$
$\mathbf{E}$	MAKE-COOKIE
ELEM	MOUSE-CLICK
ELEMENT-CLICK         11           ELEMENT-DISPLAYED         10	P
ELEMENT-ENABLED 8	-
ELEMENT-ID	PAGE-SOURCE
ELEMENT-RECT8	PAGE-TITLE
ELEMENT-SCREENSHOT	TEM OWT ROTTONS
ELEMENT-SEND-KEYS       11         ELEMENT-TAGNAME       8	
ELEMENT-TEXT	R
EXECUTE-SCRIPT	REFRESH

Chapter 6: Index 18

$\mathbf{S}$	WEBDRIVER-CLIENT:DELETE-COOKIE
SCREENSHOT 14	WEBDRIVER-CLIENT: DELETE-SESSION
SEND-KEY	WEBDRIVER-CLIENT:DISMISS-ALERT
SEND-KEYS	${\tt WEBDRIVER-CLIENT:ELEMENT-ATTRIBUTE} \dots \dots 10$
START-INTERACTIVE-SESSION	WEBDRIVER-CLIENT: ELEMENT-CLEAR
STOP-INTERACTIVE-SESSION	WEBDRIVER-CLIENT:ELEMENT-CLICK
SWITCH-TO-FRAME	WEBDRIVER-CLIENT: ELEMENT-DISPLAYED 10
	WEBDRIVER-CLIENT: ELEMENT-ENABLED
m	WEBDRIVER-CLIENT:ELEMENT-ID 7
$\mathbf{T}$	WEBDRIVER-CLIENT:ELEMENT-RECT8
TEXT	WEBDRIVER-CLIENT:ELEMENT-SCREENSHOT 14
	WEBDRIVER-CLIENT: ELEMENT-SEND-KEYS 11
$\mathbf{U}$	WEBDRIVER-CLIENT: ELEMENT-TAGNAME
U	WEBDRIVER-CLIENT:ELEMENT-TEXT8
URL	WEBDRIVER-CLIENT: EXECUTE-SCRIPT
USE-SESSION	WEBDRIVER-CLIENT:FIND-COOKIE
	WEBDRIVER-CLIENT:FIND-ELEMENT
$\mathbf{W}$	WEBDRIVER-CLIENT:FIND-ELEMENTS9
• •	WEBDRIVER-CLIENT:KEY
WAIT-FOR	WEBDRIVER-CLIENT:LOG-TYPES
WEBDRIVER-CLIENT-UTILS:ATTR	WEBDRIVER-CLIENT:LOGS 8
WEBDRIVER-CLIENT-UTILS:CLASSLIST	WEBDRIVER-CLIENT: MAKE-COOKIE
WEBDRIVER-CLIENT-UTILS:CLASSNAME	WEBDRIVER-CLIENT: MAKE-SESSION
WEBDRIVER-CLIENT-UTILS:CLICK	WEBDRIVER-CLIENT: MOUSE-CLICK
WEBDRIVER-CLIENT-UTILS:ELEM	WEBDRIVER-CLIENT: MOUSE-MOVE-TO
WEBDRIVER-CLIENT-UTILS:FIND-ELEM	WEBDRIVER-CLIENT: PAGE-SOURCE
WEBDRIVER-CLIENT-UTILS:GET-COOKIE 16	WEBDRIVER-CLIENT:PAGE-TITLE
WEBDRIVER-CLIENT-UTILS: ID	WEBDRIVER-CLIENT: PERFORM-ACTIONS
WEBDRIVER-CLIENT-UTILS:SEND-KEY	WEBDRIVER-CLIENT: REFRESH
WEBDRIVER-CLIENT-UTILS:SEND-KEYS	WEBDRIVER-CLIENT: SCREENSHOT
WEBDRIVER-CLIENT-UTILS: TEXT	WEBDRIVER-CLIENT:START-
WEBDRIVER-CLIENT-UTILS:WAIT-FOR	INTERACTIVE-SESSION
WEBDRIVER-CLIENT: ACCEPT-ALERT	WEBDRIVER-CLIENT:STOP-
WEBDRIVER-CLIENT: ACTIVE-ELEMENT9	INTERACTIVE-SESSION
WEBDRIVER-CLIENT: ALERT-TEXT	WEBDRIVER-CLIENT:SWITCH-TO-FRAME
WEBDRIVER-CLIENT: BACK	WEBDRIVER-CLIENT:URL
WEBDRIVER-CLIENT: CLOSE-CURRENT-WINDOW 15	WEBDRIVER-CLIENT: USE-SESSION
WEBDRIVER-CLIENT:COOKIE	WEBDRIVER-CLIENT: WITH-SESSION
WEBDRIVER-CLIENT: DELETE-ALL-COOKIES 13	WITH-SESSION