
Resource Allocation: Congestion Control



COS 316: Principles of Computer System Design
Lecture 13


Amit Levy & Jennifer Rexford

1



Resource Contention and Resource Allocation


- System resources are shared by multiple users
 - Resource contention: conflict over an oversubscribed resource
 - Resource allocation: assigning resources to various users
- Application process
 - Use of the CPU for processing
 - Use of physical memory for virtual memory
- Network sockets
 - · Use of the network bandwidth




2

Internet Congestion

- Best-effort networks do not "block" calls
 - So, they can easily become overloaded
 - Congestion == "Load higher than capacity"
- Examples of congestion
 - Link layer: Ethernet frame collisions
 - Network layer: full IP packet buffers
- Excess packets are simply dropped
 - And the sender can simply retransmit








TCP Congestion Collapse

- Easily leads to congestion collapse
 - Senders retransmit the lost packets
 - Leading to even greater load
 - ... and even *more* packet loss



Increase in load that results in a *decrease* in useful work done.

Detect and Respond to Congestion



- What does the end host see?
- What can the end host change?

7

Detecting Congestion

- Link layer
 - Carrier sense multiple access
 - Seeing your own frame collide with others
- Network layer
 - Observing end-to-end performance
 - Packet delay or loss over the path












TCP Congestion Control

9


Congestion in a Drop-Tail FIFO Queue

- Access to the bandwidth: first-in first-out queue
 - Packets transmitted in the order they arrive



- · Access to the buffer space: drop-tail queuing
 - If the queue is full, drop the incoming packet





How it Looks to the End Host

- Delay: Packet experiences high delay
- Loss: Packet gets dropped along path
- How does TCP sender learn this?
 - Delay: Round-trip time estimate
 - Loss: Timeout and/or duplicate acknowledgments






11

TCP Congestion Window

- Each TCP sender maintains a congestion window
 - Max number of bytes to have in transit (not yet ACK'd)



• Limits the sending rate of traffic

Receiver Window vs. Congestion Window

- Flow control
 - Keep a fast sender from overwhelming a slow receiver
- Congestion control
 - Keep a set of senders from overloading the network
- Different concepts, but similar mechanisms
 - TCP flow control: receiver window
 - TCP congestion control: congestion window
 - Sender TCP window = min { congestion window, receiver window }

13

13

TCP Sender Adjusts the Congestion Window


- Packet loss (fail!)
 - Suspect an overutilized network (congestion)
 - Pessimistically decrease the congestion window
- Packet delivery (succeed!)
 - Suspect an underutilized network
 - Optimistically *increase* the sending rate
- Always struggling to find the right rate
 - Pro: avoids the need for explicit feedback
 - Con: continually under-shooting and over-shooting

How Much Should the Sender Adapt?

- Additive increase (AI)
 - · Cautious to avoid triggering congestion
 - On success of last window of data, increase congestion window by 1 Max Segment Size (MSS)
- Multiplicative decrease (MD)
 - · Aggressive to respond quickly to congestion
 - On the loss of packet, divide congestion window in half
- Much quicker to slow down than speed up?
 - Over-sized windows (causing loss) are much worse than under-sized windows (causing lower throughput)

16

Leads to the TCP "Sawtooth" Behavior



Sources of Poor TCP Performance

- The below conditions may primarily result in:
- (A) Higher packet latency (B) Greater loss (C) Lower throughput
- 1.Larger buffers in routers
- 2.Smaller buffers in routers
- 3.Smaller buffers on end-hosts
- 4. Slow application receivers

18

Sources of Poor TCP Performance

- The below conditions may primarily result in:
- (A) Higher packet latency (B) Greater loss (C) Lower thruput
- 1.Larger buffers in routers (A) Higher latency
- 2.Smaller buffers in routers (B) Greater Loss
- 3.Smaller buffers on end-hosts (C) Lower Throughput
- 4. Slow application receivers (C) Lower Throughput

TCP Seeks "Fairness"



20

Fair and Efficient Use of a Resource

- Suppose *n* users share a single resource
 - Like the bandwidth on a single link
 - E.g., 3 users sharing a 30 Gbps link
- What is a fair allocation of bandwidth?
 - Suppose user demand is "elastic" (i.e., unlimited)
 - Allocate each a 1/n share (e.g., 10 Gbps each)
- But, "equality" is not enough
 - Which allocation is best: [5, 5, 5] or [18, 6, 6]?
 - [5, 5, 5] is more "fair", but [18, 6, 6] more efficient
 - What about [5, 5, 5] vs. [22, 4, 4]?

Fair Use of a Single Resource


- What if some users have inelastic demand?
 - E.g., 3 users where 1 user only wants 6 Gbps
 - And the total link capacity is 30 Gbps
- Should we still do an "equal" allocation?
 - E.g., [6, 6, 6]
 - · But that leaves 12 Gbps unused
- Should we allocate in proportion to demand?
 - E.g., 1 user wants 6 Gbps, and 2 each want 20 Gbps
 - Allocate [4, 13, 13]?
- Or, give the least demanding user all he wants?
 - E.g., allocate [6, 12, 12]?

22

Max-Min Fairness

- The allocation must be "feasible"
 - Total allocation should not exceed link capacity
- Protect the less fortunate
 - Any attempt to *increase* the allocation of one user
 - ... necessarily decreases for another user with equal or lower allocation
- Fully utilize a "bottlenecked" resource
 - If demand exceeds capacity, the link is fully used
- Progressive filling algorithm
 - · Grow all rates until some users stop having demand
 - Continue increasing all remaining rates till link is full

Resource Allocation Over Paths




Three users A, B, and C Two 30 Gbps links

- Maximum throughput: [30, 30, 0]
 - Total throughput of 60, but user C starves
- Max-min fairness: [15, 15, 15]
 - Equal allocation, but throughput of just 45
- Proportional fairness: [20, 20, 10]
 - Balance trade-off between throughput and equality
 - Throughput of 50, and penalize C for using 2 busy links

24

TCP Achieves a Notion of Fairness

- Effective utilization is not only goal
 - We also want to be fair to various flows
- Simple definition: equal bandwidth shares
 - N flows that each get 1/N of the bandwidth?
- But, what if flows traverse different paths?
 - Result: bandwidth shared in proportion to RTT




Conclusions

- Congestion is inevitable
 - Internet does not reserve resources in advance
 - TCP actively tries to push the envelope
- Congestion can be handled
 - TCP sender limits traffic to a congestion window
 - Additive increase, multiplicative decrease of congestion window size
- Fairness
 - TCP congestion control is a distributed algorithm that achieves "fairness"
 - ... well, as long as TCP end-points don't cheat!

26

Starting a New Flow




"Slow Start" Phase

- Start with a small congestion window
 - Initially, CWND is 1 MSS
 - So, initial sending rate is MSS / RTT
- Could be pretty wasteful
 - Might be much less than actual bandwidth
 - Linear increase takes a long time to accelerate
- Slow-start phase (really "fast start")
 - Sender starts at a slow rate (hence the name)
 - ... but increases rate exponentially until the first loss


Slow Start in Action

Double CWND per round-trip time



30

Slow Start and the TCP Sawtooth





- TCP originally had no congestion control
 - Source would start by sending entire receiver window
 - Led to congestion collapse!
 - "Slow start" is, comparatively, slower

Two Kinds of Loss in TCP

- Timeout vs. Triple Duplicate ACK
 - Which suggests network is in worse shape?
- Timeout
 - If entire window was lost, buffers may be full
 - ...blasting entire CWND would cause another burst
 - ...be aggressive: start over with a low CWND
- Triple duplicate ACK
 - Might be do to bit errors, or "micro" congestion
 - ...react less aggressively (halve CWND)

32





Repeating Slow Start After Idle Period

- Suppose a TCP connection goes idle for a while
- Eventually, the network conditions change
 - Maybe many more flows are traversing the link
- Dangerous to start transmitting at the old rate
 - Previously-idle TCP sender might blast network
 - ... causing excessive congestion and packet loss
- So, some TCP implementations repeat slow start
 - Slow-start restart after an idle period