# **Elementary Signals**

The preparatory reading for this section is <u>Chapter 1 (https://ebookcentral.proquest.com/lib/swansea-ebooks/reader.action?docID=3384197&ppg=75#ppg=17)</u> of {cite} karris which


- · begins with a discussion of the elementary signals that may be applied to electrical circuits
- introduces the unit step, unit ramp and dirac delta functions
- presents the sampling and sifting properties of the delta function and
- concludes with examples of how other useful signals can be synthesised from these elementary signals.

# Colophon

An annotatable worksheet for this presentation is available as <u>Worksheet 3</u> (/elementary\_signals/worksheet3).

- The source code for this page is <u>elementary signals/index.ipynb (https://github.com/cpjobling/eg-247-textbook/blob/master/elementary signals/index.ipynb)</u>.
- You can view the notes for this presentation as a webpage (<u>HTML (https://cpjobling.github.io/eg-247-textbook/elementary\_signals/index.html)</u>).
- This page is downloadable as a <u>PDF (https://cpjobling.github.io/eg-247-textbook/elementary\_signals/elementary\_signals.pdf)</u> file.

Consider the network shown in below where the switch is closed at time t=T and all components are ideal.



Express the output voltage  $V_{\mathrm{out}}$  as a function of the unit step function, and sketch the appropriate waveform.

#### **Solution**


Before the switch is closed at t < T:

$$V_{\text{out}} = 0.$$

After the switch is closed for t > T:

$$V_{\rm out} = V_s$$
.


We imagine that the voltage jumps instantaneously from 0 to  $V_{\scriptscriptstyle S}$  volts at t=T seconds as shown below.



We call this type of signal a step function.

# **The Unit Step Function**

$$u_0(t) = \begin{cases} 0 & t < 0 \\ 1 & t > 0 \end{cases}$$




### In Matlab

In Matlab, we use the heaviside function (named after Oliver Heaviside (http://en.wikipedia.org/wiki/Oliver\_Heaviside)).

```
In [2]: %%file plot_heaviside.m
    syms t
    ezplot(heaviside(t),[-1,1])
    heaviside(0)
```

Created file '/Users/eechris/dev/eg-247-textbook/content/elementary\_signals/plot\_heaviside.m'.



Note that, so that it can be plotted, Matlab defines the *heaviside function* slightly differently from the mathematically ideal unit step:


heaviside(t) = 
$$\begin{cases} 0 & t < 0 \\ 1/2 & t = 0 \\ 1 & t > 0 \end{cases}$$

# **Simple Signal Operations**

# **Amplitude Scaling**


Sketch  $Au_0(t)$  and  $-Au_0(t)$ 

```
In [4]: syms t;
u0(t) = heaviside(t); % rename heaviside function for ease of use
A = 2; % so signal can be plotted
ezplot(A*u0(t),[-1,1]),grid,title('Applitude scaling $$Au_0(t)$$','
interpreter','latex')
```



Note that the signal is scaled in the y direction.

```
In [5]: ezplot(-A*u0(t),[-1,1]),grid,title('Amplitude scaling and mirroring
$$-Au_0(t)$$','interpreter','latex')
```




Note that, because of the sign, the signal is mirrored about the x axis as well as being scaled by 2.

### **Time Reversal**

Sketch  $u_0(-t)$ 

```
In [6]: ezplot(A*u0(-t),[-1,1]),grid,title('Time reversal $$Au_0(-t)$$','in
terpreter','latex')
```




The sign on the function argument -t causes the whole signal to be reversed in time. Note that another way of looking at this is that the signal is mirrored about the y axis.

## **Time Delay and Advance**


Sketch  $u_0(t-T)$  and  $u_0(t+T)$ 

```
In [7]: T = 1; % again to make the signal plottable.
    ezplot(u0(t - T),[-1,2]),grid,title('Time delay $$u_0(t - T)$$','in
    terpreter','latex')
```



This is a *time delay* ... note for  $u_0(t-T)$  the step change occurs T seconds **later** than it does for  $u_0(t)$ .

```
In [8]: ezplot(u0(t + T),[-2,1]),grid,title('Time advance $$u_0(t + T)$$','
    interpreter','latex')
```



This is a *time advance* ... note for  $u_0(t+T)$  the step change occurs T seconds **earlier** than it does for  $u_0(t)$ .


## **Examples**

We will work through some examples in class. See Worksheet 3 (worksheet3).

# Synthesis of Signals from the Unit Step

Unit step functions can be used to represent other time-varying functions such as rectangular pulses, square waves and triangular pulses. See <u>Worksheet 3 (worksheet 3)</u> for the examples that we will look at in class.

## **The Ramp Function**



In the circuit shown above  $i_s$  is a constant current source and the switch is closed at time t=0.

When the current through the capacitor  $i_c(t) = i_s$  is a constant and the voltage across the capacitor is

$$v_c(t) = \frac{1}{C} \int_{-\infty}^{t} i_c(\tau) \ d\tau$$

where  $\tau$  is a dummy variable.

Since the switch closes at t = 0, we can express the current  $i_c(t)$  as

$$i_c(t) = i_s u_0(t)$$

and if  $v_c(t) = 0$  for t < 0 we have


$$v_c(t) = \frac{i_s}{C} \int_{-\infty}^t u_0(\tau) \ d\tau = \underbrace{\frac{i_s}{C} \int_{-\infty}^0 0 \ d\tau + \frac{i_s}{C} \int_0^t 1 \ d\tau}_{0}$$

So, the voltage across the capacitor can be represented as

$$v_C(t) = \frac{i_s}{C} t u_0(t)$$

**Note** that in this as in other examples throughout these notes, and in published tables of transforms, the inclusion of  $u_0(t)$  in  $v_c(t)$  acts as a "gating function" that limits the definition of the signal to the causal range  $0 \le t < \infty$ .

To sketch the wave form, let's arbitrarily let C and  $i_s$  be one and then plot with MATLAB.



This type of signal is called a **ramp function**. Note that it is the *integral* of the step function (the resistor-capacitor circuit implements a simple integrator circuit).

The unit ramp function is defined as

$$u_1(t) = \int_{-\infty}^{t} u_0(\tau) d\tau$$

so

$$u_1(t) = \begin{cases} 0 & t < 0 \\ t & t \ge 0 \end{cases}$$

and

$$u_0(t) = \frac{d}{dt}u_1(t)$$

#### **Note**


Higher order functions of t can be generated by the repeated integration of the unit step function.

For future reference, you should determine  $u_2(t)$ ,  $u_3(t)$  and  $u_n(t)$  for yourself and make a note of the general rule:

$$u_{n-1} = \frac{1}{n} \frac{d}{dt} u_n(t)$$

Details are given in equations 1.26—1.29 in Karris.

## The Dirac Delta Function



In the circuit shown above, the switch is closed at time t=0 and  $i_L(t)=0$  for t<0. Express the inductor current  $i_L(t)$  in terms of the unit step function and hence derive an expression for  $v_L(t)$ .

#### **Solution**

$$v_L(t) = L \frac{di_L}{dt}$$

Because the switch closes instantaneously at t = 0

$$i_L(t) = i_s u_0(t)$$

Thus

$$v_L(t) = i_s L \frac{d}{dt} u_0(t).$$

To solve this problem we need to invent a function that represents the derivative of the unit step function. This function is called  $\delta(t)$  or the *dirac delta* function (named after Paul Dirac (http://en.wikipedia.org/wiki/Paul\_Dirac)).

#### The delta function

The unit impulse or the delta function, denoted as  $\delta(t)$ , is the derivative of the unit step.

This function is tricky because  $u_0(t)$  is discontinuous at t=0 but it must have the properties

$$\int_{-\infty}^{t} \delta(\tau) d\tau = u_0(t)$$

and

$$\delta(t) = 0 \ \forall \ t \neq 0.$$

#### Sketch of the delta function



### **MATLAB Confirmation**

```
In [11]: syms is L;
vL(t) = is * L * diff(u0(t))

vL(t) =
    L*is*dirac(t)
```

Note that we can't plot dirac(t) in MATLAB with ezplot.

## Important properties of the delta function

## **Sampling Property**

The sampling property of the delta function states that

$$f(t)\delta(t-a) = f(a)\delta(t-a)$$

or, when a=0,

$$f(t)\delta(t) = f(0)\delta(t)$$

Multiplication of any function f(t) by the delta function  $\delta(t)$  results in sampling the function at the time instants for which the delta function is not zero.

The study of descrete-time (sampled) systems is based on this property.

You should work through the proof for youself.

## **Sifting Property**

The sifting property of the delta function states that

$$\int_{-\infty}^{\infty} f(t)\delta(t-\alpha)dt = f(\alpha)$$

That is, if multiply any function f(t) by  $\delta(t-\alpha)$ , and integrate from  $-\infty$  to  $+\infty$ , we will get the value of f(t) evaluated at  $t=\alpha$ .

You should also work through the proof for yourself.

## **Higher Order Delta Fuctions**

the nth-order delta function is defined as the nth derivative of  $u_0(t)$ , that is

$$\delta^n(t) = \frac{d^n}{dt^n} [u_0(t)]$$

The function  $\delta'(t)$  is called the *doublet*,  $\delta''(t)$  is called the *triplet* and so on.

By a procedure similar to the derivation of the sampling property we can show that

$$f(t)\delta'(t-a) = f(a)\delta'(t-a) - f'(t)\delta(t-a)$$

Also, derivation of the sifting property can be extended to show that

$$\int_{-\infty}^{\infty} f(t)\delta^{n}(t-\alpha)dt = (-1)^{n} \frac{d^{n}}{dt^{n}} [f(t)]\Big|_{t=\alpha}$$

# **Summary**

In this chapter we have looked at some elementary signals and the theoretical circuits that can be used to generate them.

### **Takeaways**

- You should note that the unit step is the *heaviside function*  $u_0(t)$ .
- Many useful signals can be synthesized by use of the unit step as a "gating function" in combination with other signals
- That unit ramp function  $u_1(t)$  is the integral of the step function.
- The *Dirac delta* function  $\delta(t)$  is the derivative of the unit step function. We sometimes refer to it as the *unit impulse function*.
- The delta function has sampling and sifting properties that will be useful in the development of *time* convolution and sampling theory.

## **Examples**

We will do some of these in class. See Worksheet 3 (worksheet3).

#### **Homework**

These are for you to do later for further practice. See <a href="Homework1">Homework 1</a> (../homework/hw1).

## References

See Bibliography (/zbib)