Package 'amapGeocode'

September 29, 2020						
Type Package						
Title An Interface to the 'AutoNavi Maps' API Geocoding Services						
Version 0.3.1						
Description Getting and parsing data of location geocode/reverse-geocode and administrative regions from 'AutoNavi Maps' https://lbs.amap.com/api/webservice/summary API.						
License MIT + file LICENSE						
<pre>URL https://github.com/womeimingzi11/amapGeocode</pre>						
Imports dplyr, httr, jsonlite, magrittr, sjmisc, stats, stringr, tibble, xml2, purrr, lifecycle						
Suggests knitr, rmarkdown, testthat						
VignetteBuilder knitr						
Encoding UTF-8						
LazyData true						
RoxygenNote 7.1.1						
RdMacros lifecycle						
R topics documented:						
convertCoord 2 convertCoord.individual 3 extractAdmin 4 extractConvertCoord 5 extractCoord 6 extractLocation 7						

2 convertCoord

conv	ertCoord	Conver tem	t coo	ordin	iate j	fron	n d	iffe	ren	et c	001	rdi	na	te i	sys	ter	ns	to	Ai	uto	Na	ıvi	sy.	S-
Index																								18
	str_loc_to_num_co	oord			• •					•			•				•	•				•		17
	num_coord_to_str																							
	getLocation.indivi																							
	getLocation																							
	getCoord.individua																							
	getAdmin.individu																							
	getAdmin																							7

Description

Experimental This function is a wrap of coordinate convert API of AutoNavi Map Service. While how to input the origin coordinate is sill unstable and 95% sure that it will have a breaking change in the future. Please consider carefully if introduced this function in product environment.

Usage

```
convertCoord(
  locations,
  key = NULL,
  coordsys = NULL,
  sig = NULL,
  output = NULL,
  to_table = TRUE
)
```

Arguments

locations	Required. String coordinate point from other coordinate system
key	Optional. Amap Key. Applied from AutoNavi Map API official websitehttps://lbs.amap.com/dev/
coordsys	Optional. Coordinate System. Support: 'gps', 'mapbar', 'baidu' and 'autonavi'-not convert
sig	Optional. Digital Signature. How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72
output	Optional. Output Data Structure. Support JSON and XML. The default value is JSON.
to_table	Optional. Transform response content to tibble.

convertCoord.individual 3

Value

Returns a JSON, XML or Tibble of results containing detailed geocode information. See https://lbs.amap.com/api/webservice/guide/api/convert for more information.

See Also

convertCoord

Examples

```
## Not run:
library(amapGeocode)

# Before the `convertCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `convertCoord()`

# get result of converted coordinate system as a tibble
convertCoord('116.481499,39.990475',coordsys = 'gps')
# get result of converted coordinate system as a XML
convertCoord('116.481499,39.990475',coordsys = 'gps', to_table = FALSE)

## End(Not run)
```

convertCoord.individual

Convert an individual coordinate from different coordinate systems to AutoNavi system

Description

Convert an individual coordinate from different coordinate systems to AutoNavi system

Usage

```
convertCoord.individual(
  locations,
  key = NULL,
  coordsys = NULL,
  sig = NULL,
  output = NULL,
  to_table = TRUE
)
```

Arguments

locations Required.

String coordinate point from other coordinate system

key Optional.

Amap Key.

Applied from AutoNavi Map API official websitehttps://lbs.amap.com/dev/

4 extractAdmin

coordsys Optional.

Coordinate System.

Support: 'gps', 'mapbar', 'baidu' and 'autonavi'-not convert

sig Optional.

Digital Signature.

How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

to_table Optional.

Transform response content to tibble.

#'

Value

Returns a JSON, XML or Tibble of results containing detailed geocode information. See https://lbs.amap.com/api/webservice/guide/api/convert for more information.

extractAdmin Get Subordinate Administrative Region from getAdmin request Now, it

 $only\ support\ extract\ the\ first\ layer\ of\ subordinate\ administrative\ region$

information.

Description

Get Subordinate Administrative Region from getAdmin request Now, it only support extract the first layer of subordinate administrative region information.

Usage

extractAdmin(res)

Arguments

res Response from getAdmin.

Value

Returns a tibble which extracts detailed subordinate administrative region information from results of getCoord. See https://lbs.amap.com/api/webservice/guide/api/district for more information.

See Also

getAdmin

extractConvertCoord 5

Examples

extractConvertCoord

Extract converted coordinate points from convertCoord request

Description

Extract converted coordinate points from convertCoord request

Usage

```
extractConvertCoord(res)
```

Arguments

res

Required.

Response from convertCoord.

Value

Returns a tibble which extracts converted coordinate points from request of convertCoord. See https://lbs.amap.com/api/webservice/guide/api/convert for more information.

See Also

convertCoord

Examples

```
## Not run:
library(dplyr)
library(amapGeocode)

# Before the `convertCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `convertCoord()`

# get result of converted coordinate system as a XML
```

6 extractCoord

```
convertCoord('116.481499,39.990475',coordsys = 'gps', to_table = FALSE) %>%
  # extract result of converted coordinate system as a tibble
  extractConvertCoord()

## End(Not run)
```

extractCoord

Extract coordinate from location request

Description

Extract coordinate from location request

Usage

```
extractCoord(res)
```

Arguments

res

Required.

Response from getCoord.

Value

Returns a tibble which extracts detailed coordinate information from results of getCoord. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

getCoord

Examples

extractLocation 7

extractLocation

Extract location from coordinate request

Description

Extract location from coordinate request

Usage

```
extractLocation(res)
```

Arguments

res

Required.

Response from getLocation.

Value

Returns a tibble which extracts detailed location information from results of getLocation. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

```
getLocation
```

Examples

getAdmin

Get Subordinate Administrative Regions from location

Description

Get Subordinate Administrative Regions from location

8 getAdmin

Usage

```
getAdmin(
  keywords,
  key = NULL,
  subdistrict = NULL,
  page = NULL,
  offset = NULL,
  extensions = NULL,
  filter = NULL,
  callback = NULL,
  output = NULL,
  to_table = TRUE
)
```

Arguments

keywords Required.

Search keywords.

Rules: Country/Region, Province/State, City, County/District, Town, Country,

Road, Number, Room, Building.

key Optional.

Amap Key.

Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/

dev/

subdistrict Optional.

Subordinate Administrative Level.

Display level of subordinate administrative regions. Available value: 0,1,2,3.

'0' do not return subordinate administrative regions.

'1' return first one subordinate administrative regions.

'2' return first two subordinate administrative regions.

'3' return first three subordinate administrative regions.

page Optional.

Which page to return.

Each time the outmost layer will return a maximum of 20 records. If the limit is exceeded, please request the next page of records with the page argument.

offset Optional.

Maximum records per page. Maximum value is 20.

extensions Optional.

Return results controller.

'base': does not return the coordinates of the administrative district boundary. 'all': returns only the boundary value of the current query district, not the bound-

ary value of the child node.

filter Optional.

Filter administrative regions.

Filtering by designated administrative divisions, which returns information only

for the province/municipality.

It is strongly recommended to fill in this parameter in order to ensure the correct

records.

getAdmin.individual 9

callback Optional.

Callback Function.

The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

to_table Optional.

Transform response content to tibble.

Value

Returns a JSON or XML of results containing detailed subordinate administrative region information. See https://lbs.amap.com/api/webservice/guide/api/district for more information.

See Also

extractAdmin

Examples

```
## Not run:
library(amapGeocode)

# Before the `getAdmin()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getAdmin()`

# Get subordinate administrative regions as a tibble getAdmin('Sichuan Province')
# Get subordinate administrative regions as a XML getCoord('Sichuan Province', output = 'XML')

## End(Not run)
```

getAdmin.individual

Get an individual tibble of Subordinate Administrative Regions from location

Description

Get an individual tibble of Subordinate Administrative Regions from location

```
getAdmin.individual(
  keywords,
  key = NULL,
  subdistrict = NULL,
```

10 getAdmin.individual

```
page = NULL,
offset = NULL,
extensions = NULL,
filter = NULL,
callback = NULL,
output = NULL,
to_table = TRUE
)
```

Arguments

keywords Required.

Search keywords.

Rules: Country/Region, Province/State, City, County/District, Town, Country,

Road, Number, Room, Building.

key Optional.

Amap Key.

Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/

dev/

subdistrict Optional.

Subordinate Administrative Level.

Display level of subordinate administrative regions. Available value: 0,1,2,3.

'0' do not return subordinate administrative regions.
'1' return first one subordinate administrative regions.
'2' return first two subordinate administrative regions.

'3' return first three subordinate administrative regions.

page Optional.

Which page to return.

Each time the outmost layer will return a maximum of 20 records. If the limit is exceeded, please request the next page of records with the page argument.

offset Optional.

Maximum records per page. Maximum value is 20.

extensions Optional.

Return results controller.

'base': does not return the coordinates of the administrative district boundary. 'all': returns only the boundary value of the current query district, not the bound-

ary value of the child node.

filter Optional.

Filter administrative regions.

Filtering by designated administrative divisions, which returns information only

for the province/municipality.

It is strongly recommended to fill in this parameter in order to ensure the correct

records.

callback Optional.

Callback Function.

The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

getCoord 11

```
to_table Optional.
```

Transform response content to tibble.

Value

Returns a JSON or XML of results containing detailed subordinate administrative region information. See https://lbs.amap.com/api/webservice/guide/api/district for more information.

getCoord

Get coordinate from location

Description

Get coordinate from location

Usage

```
getCoord(
  address,
  key = NULL,
  city = NULL,
  sig = NULL,
  output = NULL,
  callback = NULL,
  to_table = TRUE
)
```

Arguments

address Required.

Structured address information.

Rules: Country/Region, Province/State, City, County/District, Town, Country,

Road, Number, Room, Building.

key Optional.

Amap Key.

Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/

dev/

city Optional.

Specify the City.

Support: city in Chinese, full pinyin, citycode, adcodehttps://lbs.amap.

com/api/webservice/download.

The default value is NULL which will search country-wide. The default value

is NULL

sig Optional.

Digital Signature.

How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

12 getCoord.individual

callback Optional.

Callback Function.

The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.

to_table Optional.

Transform response content to tibble.

#'

Value

Returns a JSON, XML or Tibble of results containing detailed geocode information. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

```
extractCoord
```

Examples

```
## Not run:
library(amapGeocode)

# Before the `getCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getCoord()`

# Get geocode as a tibble
getCoord('IFS Chengdu')
# Get geocode as a XML
getCoord('IFS Chengdu', output = 'XML')

## End(Not run)
```

getCoord.individual

Get an individual coordinate from location

Description

Get an individual coordinate from location

```
getCoord.individual(
  address,
  key = NULL,
  city = NULL,
  sig = NULL,
  output = NULL,
  callback = NULL,
  to_table = TRUE
)
```

getLocation 13

Arguments

address Required.

Structured address information.

Rules: Country/Region, Province/State, City, County/District, Town, Country,

Road, Number, Room, Building.

key Optional.

Amap Key.

Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/

dev/

city Optional.

Specify the City.

Support: city in Chinese, full pinyin, citycode, adcodehttps://lbs.amap.

com/api/webservice/download.

The default value is NULL which will search country-wide. The default value

is NULL

sig Optional.

Digital Signature.

How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

callback Optional.

Callback Function.

The value of callback is the customized function. Only available with JSON

output. If you don't understand, it means you don't need it, just like me.

to_table Optional.

Transform response content to tibble.

#'

Value

Returns a JSON, XML or Tibble of results containing detailed geocode information. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

getLocation

Get location from coordinate

Description

Get location from coordinate

```
getLocation(
  lng,
  lat,
  key = NULL,
  poitype = NULL,
  radius = NULL,
```

14 getLocation

```
extensions = NULL,
roadlevel = NULL,
sig = NULL,
output = NULL,
callback = NULL,
homeorcorp = 0,
to_table = TRUE
)
```

Arguments

lng Required.

Longitude in decimal

lat Required.

Latitude in decimal

key Optional.

Amap Key.

Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/

dev/

poitype Optional.

Return nearby POI types.

When 'extensions = all', this argument makes sense. For detailed poitype type,

please referhttps://lbs.amap.com/api/webservice/download

radius Optional.

Searching radius.

radius ranges from 0 to 3000, the default value is 1000, unit: meter.

extensions Optional.

Return results controller.

'base': the default value, it only return base information about coordinate. 'all': it will return nearby POI, road information and cross information.

roadlevel Optional.

Road levels.

When 'extensions = all', this argument makes sense.

'roadlevel=0', return all roads.

'roadlevel=1', only return main roads.

sig Optional.

Digital Signature.

How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

callback Optional.

Callback Function.

The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.

homeorcorp Optional.

Optimize the order of returned POI or not.

When 'extensions = all', this argument makes sense.

'homeorcorp=0', do not optimize, by default.

'homeorcorp=1', home related POIs are first, by default.

getLocation.individual 15

'homeorcorp=2', corporation related POIs are first, by default.

to_table Optional.

Transform response content to tibble.

Value

Returns a JSON, XML or Tibble of results containing detailed reverse geocode information. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

extractCoord

Examples

```
## Not run:
library(amapGeocode)

# Before the `getLocation()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getLocation()`

# Get reverse-geocode as a tibble
getLocation(104.043284, 30.666864)
# Get reverse-geocode as a XML
getLocation('104.043284, 30.666864', output = 'XML')

## End(Not run)
```

getLocation.individual

Get an individual location from coordinate

Description

Get an individual location from coordinate

```
getLocation.individual(
  lng,
  lat,
  key = NULL,
  poitype = NULL,
  radius = NULL,
  extensions = NULL,
  roadlevel = NULL,
  sig = NULL,
```

```
output = NULL,
  callback = NULL,
  homeorcorp = 0,
  to_table = TRUE
)
```

Arguments

lng Required.

Longitude in decimal

lat Required.

Latitude in decimal

key Optional.

Amap Key.

Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/

dev/

poitype Optional.

Return nearby POI types.

When 'extensions = all', this argument makes sense. For detailed poitype type,

please referhttps://lbs.amap.com/api/webservice/download

radius Optional.

Searching radius.

radius ranges from 0 to 3000, the default value is 1000, unit: meter.

extensions Optional.

Return results controller.

'base': the default value, it only return base information about coordinate. 'all': it will return nearby POI, road information and cross information.

roadlevel Optional.

Road levels.

When 'extensions = all', this argument makes sense.

'roadlevel=0', return all roads.

'roadlevel=1', only return main roads.

sig Optional.

Digital Signature.

How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72

output Optional.

Output Data Structure.

Support JSON and XML. The default value is JSON.

callback Optional.

Callback Function.

The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.

homeorcorp Optional.

Optimize the order of returned POI or not.

When 'extensions = all', this argument makes sense.

'homeorcorp=0', do not optimize, by default.

'homeorcorp=1', home related POIs are first, by default. 'homeorcorp=2', corporation related POIs are first, by default.

num_coord_to_str_loc 17

to_table Optional.

Transform response content to tibble.

Value

Returns a JSON, XML or Tibble of results containing detailed reverse geocode information. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

num_coord_to_str_loc Take longitude and latitude from location string out.

Description

Take longitude and latitude from location string out.

Usage

```
num_coord_to_str_loc(lng, lat)
```

Arguments

lng Required.

Longitude in decimal

lat Required.

Latitude in decimal

Value

Comma binded coordinate string

Description

Take longitude and latitude from location string out.

Usage

```
str_loc_to_num_coord(str_location)
```

Arguments

str_location Required.

Location string from response

Value

vector contains Longitude and Latitude in numeric

Index

```
convertCoord, 2, 3, 5
convertCoord.individual, 3

extractAdmin, 4, 9
extractConvertCoord, 5
extractCoord, 6, 12, 15
extractLocation, 7

getAdmin, 4, 7
getAdmin.individual, 9
getCoord, 6, 11
getCoord.individual, 12
getLocation, 7, 13
getLocation.individual, 15

num_coord_to_str_loc, 17

str_loc_to_num_coord, 17
```