CS 33

Data Representation (Part 2)

Why Should I Use Unsigned?

- Don't use just because number nonnegative
 - easy to make mistakes

```
unsigned i;
for (i = cnt-2; i >= 0; i--)
   a[i] += a[i+1];
```

can be very subtle

```
#define DELTA sizeof(int)
int i;
for (i = CNT; i-DELTA >= 0; i-= DELTA)
. . .
```

- Do use when using bits to represent sets
 - logical right shift, no sign extension

Word Size

- (Mostly) obsolete term
 - old computers had items of one size: the word size
- Now used to express the number of bits necessary to hold an address
 - 16 bits (really old computers)
 - 32 bits (old computers)
 - 64 bits (most current computers)

Byte Ordering

- Four-byte integer
 - -0x76543210
- Stored at location 0x100
 - which byte is at 0x100?
 - which byte is at 0x103?


2	L

10	32	54	76
0x100	0x101	0x102	0x103


Little-endian

76 54 32 10 0x100 0x101 0x102 0x103

Big-endian



Byte Ordering (2)



Quiz 1

```
int main() {
  long x=1;
  func((int *)&x);
  return 0;
}

void func(int *arg) {
  printf("%d\n", *arg);
}
```

What value is printed on a big-endian 64-bit computer?

- a) 1
- b) 0
- c) 2^{32}
- d) 2³²-1

Which Byte Ordering Do We Use?

```
int main() {
    unsigned int x = 0x03020100;
    unsigned char *xarray = (unsigned char *) &x;
    for (int i=0; i<4; i++) {
            printf("%02x", xarray[i]);
    printf("\n");
    return 0;
```


Possible results:

00010203 03020100

Fractional binary numbers

• What is 1011.101₂?

Fractional Binary Numbers



- bits to right of "binary point" represent fractional powers of 2
- represents rational number: $\sum_{k=0}^{\infty} b_k \times 2^k$

Representable Numbers

Limitation #1

- can exactly represent only numbers of the form n/2^k
 - » other rational numbers have repeating bit representations

```
value representation
1/3 0.0101010101[01]...2
1/5 0.001100110011[0011]...2
1/10 0.0001100110011[0011]...2
```

Limitation #2

- just one setting of decimal point within the w bits
 - » limited range of numbers (very small values? very large?)

IEEE Floating Point

IEEE Standard 754

- established in 1985 as uniform standard for floating point arithmetic
 - » before that, many idiosyncratic formats
- supported on all major CPUs

Driven by numerical concerns

- nice standards for rounding, overflow, underflow
- hard to make fast in hardware
 - » numerical analysts predominated over hardware designers in defining standard

Floating-Point Representation

Numerical Form:

$$(-1)^{s} M 2^{E}$$

- sign bit s determines whether number is negative or positive
- significand M normally a fractional value in range [1.0,2.0)
- exponent E weights value by power of two
- Encoding
 - MSB s is sign bit s
 - exp field encodes E (but is not equal to E)
 - frac field encodes M (but is not equal to M)

S	ехр	frac
---	-----	------

Precision options

Single precision: 32 bits

S	ехр	frac
1	8-bits	23-bits

Double precision: 64 bits

S	exp	frac
1	11-bits	52-bits

Extended precision: 80 bits (Intel only)

S	ехр	frac
1	15-bits	64-bits

"Normalized" Values

- When: exp ≠ 000...0 and exp ≠ 111...1
- Exponent coded as biased value: E = Exp Bias
 - exp: unsigned value exp
 - bias = 2^{k-1} 1, where k is number of exponent bits
 - » single precision: 127 (Exp: 1...254, E: -126...127)
 - » double precision: 1023 (Exp: 1...2046, E: -1022...1023)
- Significand coded with implied leading 1: M = 1.xxx...x2
 - xxx...x: bits of frac
 - minimum when frac=000...0 (M = 1.0)
 - maximum when frac=111...1 (M = 2.0ϵ)
 - get extra leading bit for "free"

Normalized Encoding Example

```
• Value: float F = 15213.0;

- 15213<sub>10</sub> = 11101101101101<sub>2</sub>

= 1.1101101101101<sub>2</sub> x 2<sup>13</sup>
```

Significand

```
M = 1.101101101_2
frac = 11011011011010000000000_2
```

Exponent

$$E = 13$$
bias = 127
exp = 140 = 10001100₂

Result:

0 10001100 1101101101101000000000 s exp frac

Denormalized Values

- Condition: exp = 000...0
- Exponent value: E = -Bias + 1 (instead of E = 0 Bias)
- Significand coded with implied leading 0:
 M = 0.xxx...x₂
 - xxx...x: bits of frac


Cases

- $\exp = 000...0$, frac = 000...0
 - » represents zero value
 - » note distinct values: +0 and -0 (why?)
- $-\exp = 000...0$, frac $\neq 000...0$
 - » numbers closest to 0.0
 - » equispaced


Special Values

- Condition: exp = 111...1
- Case: exp = 111...1, frac = 000...0
 - represents value ∞ (infinity)
 - operation that overflows
 - both positive and negative
 - e.g., $1.0/0.0 = -1.0/-0.0 = +\infty$, $1.0/-0.0 = -\infty$
- Case: exp = 111...1, $frac \neq 000...0$
 - not-a-number (NaN)
 - represents case when no numeric value can be determined
 - e.g., sqrt(-1), ∞ ∞ , $\infty \times 0$

Visualization: Floating-Point Encodings



Tiny Floating-Point Example



8-bit Floating Point Representation

- the sign bit is in the most significant bit
- the next four bits are the exponent, with a bias of 7
- the last three bits are the frac

Same general form as IEEE Format

- normalized, denormalized
- representation of 0, NaN, infinity

Dynamic Range (Positive Only)

	s	exp	frac	E	Value
	0	0000	000	-6	0
	0	0000	001	-6	1/8*1/64 = 1/512 closest to zero
Denormalized	0	0000	010	-6	2/8*1/64 = 2/512
numbers	•••				
	0	0000	110	-6	6/8*1/64 = 6/512
	0	0000	111	-6	7/8*1/64 = 7/512 largest denorm
	0	0001	000	-6	8/8*1/64 = 8/512 smallest norm
	0	0001	001	-6	9/8*1/64 = 9/512
	•••				
	0	0110	110	-1	14/8*1/2 = 14/16
	0	0110	111	-1	15/8*1/2 = 15/16 closest to 1 below
Normalized	0	0111	000	0	8/8*1 = 1
numbers	0	0111	001	0	9/8*1 = 9/8 closest to 1 above
	0	0111	010	0	10/8*1 = 10/8
	•••				
	0	1110	110	7	14/8*128 = 224
	0	1110	111	7	15/8*128 = 240 largest norm
	0	1111	000	n/a	inf


Distribution of Values

6-bit IEEE-like format

- e = 3 exponent bits
- f = 2 fraction bits
- bias is $2^{3-1}-1=3$

S	exp	frac
1	3-bits	2-bits

Notice how the distribution gets denser toward zero.




Distribution of Values (close-up view)

6-bit IEEE-like format

- e = 3 exponent bits
- f = 2 fraction bits
- bias is 3

S	exp	frac			
1	3-bits	2-bits			



Quiz 1

- 6-bit IEEE-like format
 - -e = 3 exponent bits
 - f = 2 fraction bits
 - bias is 3


S	exp	frac
1	3-bits	2-bits

What number is represented by 0 010 10?

- a) 3
- b) 1.5
- c) .75
- d) none of the above

Mapping Real Numbers to Float

- The real number 3 is represented as 0 100 10
- The real number 3.5 is represented as 0 100 11
- How is the real number 3.4 represented?
 0 100 11
- How is the real number π represented?
 0 100 10




Mapping Real Numbers to Float

- If R is a real number, it's mapped to the floating-point number whose value is closest to R
- What if it's midway between two values?
 - rounding rules coming up soon!

Floats are Sets of Values

- If A, B, and C are successive floating-point numbers
 - e.g., 010001, 010010, and 010011
- B represents all real numbers from midway between A and B through midway between B and C



Significance

Normalized numbers

- for a particular exponent value E and an S-bit significand, the range from 2^E up to 2^{E+1} is divided into 2^S equi-spaced floating-point values
 - » thus each floating-point value represents 1/2^s of the range of values with that exponent
 - » all bits of the significand are important
 - » we say that there are S significant bits for reasonably large S, each floating-point value covers a rather small part of the range
 - high accuracy
 - for S=23 (32-bit float), accurate to one in 2²³ (.0000119% accuracy)

Significance

Unnormalized numbers

- high-order zero bits of the significand aren't important
- in 8-bit floating point, 0 0000 001 represents 2-9
 - » it is the only value with that exponent: 1 significant bit (either 2⁻⁹ or 0)
- 0 0000 010 represents 2-8
 0 0000 011 represents 1.5*2-8
 - » only two values with exponent -8: 2 significant bits (encoding those two values, as well as 2⁻⁹ and 0)
- fewer significant bits mean less accuracy
- 0 0000 001 represents a range of values from .5*2-9
 to 1.5*2-9
- 50% accuracy

Floating-Point Operations: Basic Idea

•
$$x +_f y = Round(x + y)$$

•
$$x \times_f y = Round(x \times y)$$

Basic idea

- first compute exact result
- make it fit into desired precision
 - » possibly overflow if exponent too large
 - » possibly round to fit into frac

Rounding

Rounding modes (illustrated with \$ rounding)

	\$1.40	\$1.60	\$1.50	\$2.50	- \$1.50
towards zero	\$1	\$1	\$1	\$2	- \$1
round down (−∞)	\$1	\$1	\$1	\$2	-\$2
round up (+∞)	\$2	\$2	\$2	\$3	- \$1
nearest integer	\$1	\$2	?	?	?
nearest even (default)	\$1	\$2	\$2	\$2	- \$2

Floating-Point Multiplication

- $(-1)^{s1}$ M1 2^{E1} x $(-1)^{s2}$ M2 2^{E2}
- Exact result: (-1)^s M 2^E
 - sign s: s1 ^ s2
 - significand M: M1 x M2
 - exponent E: E1 + E2

Fixing


- if M ≥ 2, shift M right, increment E
- if E out of range, overflow (or underflow)
- round M to fit frac precision
- Implementation
 - biggest chore is multiplying significands

Floating-Point Addition

• $(-1)^{s1}$ M1 2^{E1} + $(-1)^{s2}$ M2 2^{E2}

-assume E1 > E2

- Exact result: (-1)^s M 2^E
 - -sign s, significand M:
 - » result of signed align & add
 - -exponent E: E1



Fixing

- —if M ≥ 2, shift M right, increment E
- -if M < 1, shift M left k positions, decrement E by k
- -overflow if E out of range
- —round M to fit frac precision