

CS 423 Operating System Design

https://cs423-uiuc.github.io

Tianyin Xu tyxu@illinois.edu

* Thanks Adam Bates for the slides.

Implementing Synchronization



- Take I: using memory load/store
 - See too much milk solution/Peterson's algorithm
- Take 2: (corrected from last class!)

```
Lock::acquire() {
    disableInterrupts();
}
Lock::release() {
    enableInterrupts();
}
```

Above solution "works" on single processor...

Queueing Lock Implementation (1 Proc)



```
Lock::acquire() {
                                     Lock::release() {
                                         disableInterrupts();
    disableInterrupts();
    if (value == BUSY) {
                                         if (!waiting.Empty()) {
        waiting.add(myTCB);
                                             next = waiting.remove();
                                             next->state = READY;
        myTCB->state = WAITING;
        next = readyList.remove();
                                             readyList.add(next);
        switch(myTCB, next);
                                         } else {
        myTCB->state = RUNNING;
                                         value = FREE;
    } else {
        value = BUSY;
                                         enableInterrupts();
    enableInterrupts();
```

Question



Why won't this work for multiprocessing?

Multiprocessor Sync Tool!



- Read-modify-write (RMW) instructions
 - Atomically read a value from memory, operate on it, and then write it back to memory
 - Intervening instructions prevented in hardware
- Examples
 - Test and set
 - Intel: xchgb, lock prefix
 - Compare and swap
- Any of these can be used for implementing locks and condition variables!

Test-and-set



- The **test-and-set** instruction is an instruction used to write I (set) to a memory location and return its old value as a single **atomic** (i.e., non-interruptible) operation. If multiple processes may access the same memory location, and if a process is currently performing a test-and-set, no other process may begin another test-and-set until the first process's test-and-set is finished.
- Please implement a lock using test-and-set (5 minutes)

```
lock:acquire() {
}
lock:release() {
}
```

Spinlocks



- A spinlock is a lock where the processor waits in a loop for the lock to become free
 - Assumes lock will be held for a short time
 - Used to protect the CPU scheduler and to implement locks

```
Spinlock::acquire() {
    while (testAndSet(&lockValue) == BUSY)
    ;
}
Spinlock::release() {
    lockValue = FREE;
    memorybarrier();
}
```

Question



Neat. So how many spinlocks do we need?

What thread is currently running?



- Thread scheduler needs to find the TCB of the currently running thread
 - To suspend and switch to a new thread
 - To check if the current thread holds a lock before acquiring or releasing it
- On a uniprocessor, easy: just use a global
- On a multiprocessor, various methods:
 - Compiler dedicates a register (e.g., r31 points to TCB running on the this CPU; each CPU has its own r31)
 - If hardware has a special per-processor register, use it
 - Fixed-size stacks: put a pointer to the TCB at the bottom of its stack



Lock implementation —

```
Lock::acquire() {
                                Lock::release() {
    disableInterrupts();
                                    TCB *next;
    spinLock.acquire();
    if (value == BUSY) {
                                    disableInterrupts();
        waiting.add(myTCB);
                                     spinLock.acquire();
        scheduler->
                                     if (!waiting.Empty()) {
                                         next = waiting.remove();
          suspend(&spinlock);
    } else {
                                         scheduler->makeReady(next);
        value = BUSY;
                                     } else {
                                         value = FREE;
    spinLock.release();
    enableInterrupts();
                                     spinLock.release();
                                    enableInterrupts();
```



Scheduler implementation (7.5 minutes)

```
Sched::suspend(SpinLock *lock) { Sched::makeReady(TCB *thread) {
```

CS423: Operating Systems Design



Lock implementation (7.5 minutes)

```
Lock::acquire() {
                                Lock::release() {
    disableInterrupts();
                                    TCB *next;
    spinLock.acquire();
    if (value == BUSY) {
                                    disableInterrupts();
        waiting.add(myTCB);
                                     spinLock.acquire();
        scheduler->
                                     if (!waiting.Empty()) {
          suspend(&spinlock);
                                         next = waiting.remove();
    } else {
                                         scheduler->makeReady(next);
        value = BUSY;
                                     } else {
                                        value = FREE;
    spinLock.release();
    enableInterrupts();
                                     spinLock.release();
                                    enableInterrupts();
```



Scheduler implementation —

```
Sched::suspend(SpinLock *lock) {
                                    Sched::makeReady(TCB *thread) {
    TCB *next;
    disableInterrupts();
                                        disableInterrupts ();
    schedSpinLock.acquire();
                                        schedSpinLock.acquire();
    lock->release();
                                        readyList.add(thread);
   myTCB->state = WAITING;
                                        thread->state = READY;
    next = readyList.remove();
                                        schedSpinLock.release();
    thread switch(myTCB, next);
                                        enableInterrupts();
   myTCB->state = RUNNING;
    schedSpinLock.release();
    enableInterrupts();
```

Locks for user space??



- Kernel-managed threads
 - Manage data structures in kernel space
 - System calls to communicate w/ scheduler
- User-managed threads
 - Implement functionality in thread library
 - Can't disable interrupts, but can temporarily disable upcalls to avoid preemption in library scheduler, etc.

Spinning vs Context Switch



What's the tradeoff?

Locks in Linux



 Most locks are free most of the time. Linux implementation takes advantage of this fact!

• Fast path:

- If lock is FREE, and no one is waiting, two instructions to acquire the lock
- If no one is waiting, two instructions to release the lock

Slow path

- If lock is BUSY or someone is waiting, use multiproc impl.
- User-level locks also optimized:
 - Fast path: count is mapped to proc address space, no sys call needed when count is 0.
 - Slow path: system call to kernel, use kernel lock when waiting

Locks in Linux



Lock struct contains 3 (not two) states...

```
struct mutex {
   /* 1: unlocked;
     0: locked;
     negative : locked, possible waiters */
   atomic_t count;
   spinlock_t wait_lock;
   struct list_head wait_list;
};
```

Lock acquire code is a macro (to avoid proc call)...

```
lock decl (%eax)
jns 1f
call slowpath_acquire
1: ...
```

```
// atomic decrement
// %eax is pointer to count
// jump if not signed
// (i.e., if value is now 0)
```

Synchronization: Semaphores



- Semaphore has a non-negative integer value
 - P() atomically waits for value to become > 0, then decrements
 - V() atomically increments value (waking up waiter if needed)
- Semaphores are like integers except:
 - Only operations are P and V
 - Operations are atomic
 - If value is 1, two P's will result in value 0 and one waiter

Compare Implementations



Lock implementation —

```
Lock::acquire() {
                                  Lock::release() {
    disableInterrupts();
    spinLock.acquire();
    if (value == BUSY) {
        waiting.add(myTCB);
        suspend(&spinlock);
    } else {
                                      } else {
                                       value = FREE;
        value = BUSY;
    spinLock.release();
   enableInterrupts();
```

Compare Implementations



Semaphore implementation —

```
Semaphore::V() {
Semaphore::P() {
    disableInterrupts();
                                      disableInterrupts();
    spinLock.acquire();
                                      spinLock.acquire();
                                      if (!waiting.Empty()) {
    if (value == 0) {
                                          next = waiting.remove();
        waiting.add(myTCB);
                                          scheduler->makeReady(next);
        suspend(&spinlock);
    } else {
                                      } else {
                                       value++;
        value--;
    spinLock.release();
                                      spinLock.release();
   enableInterrupts();
                                      enableInterrupts();
```

Semaphores Harmful?



- Semaphores conflate the roles of locks and condition variables (mutual exclusion, shared data).
 - Simpler code verification w/o: prove every lock is eventually unlocked.
- Semaphores have state!
 - What does value=3 mean? Programmer must carefully map object state to semaphore value.
 - CVs, in contrast, allows us to wait on arbitrary state/predicate, and are thus a better abstraction.
- However, semaphores have good uses, including...
 - Unlocked waits, e.g., interrupt handler that synchronizes communication between I/O device and waiting threads.

Semaphore Bounded Queue



```
get() {
    fullSlots.P();
    mutex.P();
    item = buf[front % MAX];
    front++;
    mutex.V();
    emptySlots.V();
    return item;
}

put(item) {
    emptySlots.P();
    mutex.P();
    mutex.P();
    mutex.P();
    mutex.V();
    fullSlots.V();
}
```

```
Initially: front = last = 0; MAX is buffer capacity mutex = 1; emptySlots = MAX; fullSlots = 0;
```



How can we implement Condition Variables using semaphore

Take 1:

```
wait(lock) {
    lock.release();
    semaphore.P();
    lock.acquire();
}
signal() {
    semaphore.V();
}
```

Problems?



How can we implement Condition Variables using semaphore

Take 2:

```
wait(lock) {
    lock.release();
    semaphore.P();
    lock.acquire();
}
signal() {
    if (semaphore is not empty)
        semaphore.V();
}
```

Problems?



How can we implement Condition Variables using semaphore

Take 3:

```
wait(lock) {
    semaphore = new Semaphore;
    queue.Append(semaphore); // queue of waiting threads
    lock.release();
    semaphore.P();
    lock.acquire();
}
signal() {
    if (!queue.Empty()) {
        semaphore = queue.Remove();
        semaphore.V(); // wake up waiter
    }
}
Problems?
```



Implementation used for Microsoft Windows before native support was offered:

Take 4:

```
//Put thread on queue of waiting threads...
void CV::wait(Lock *lock){
   semaphore = new Semaphore(0);
   waitQueue.Append(semaphore)
        lock.release();
   semaphore.P();
   lock.acquire();
}

//Wake up one waiter if any.
void CV::signal() {
   if(!waitQueue.isEmpty()) {
        semaphore = queue.Remove();
        semaphore.V();
   }
}
```