
#### CSC4200/5200 - COMPUTER NETWORKING

#### **CONNECTING MACHINES TO A NETWORK**

Instructor: Susmit Shannigrahi sshannigrahi@tntech.edu



# Recap - Propagation and Transmission delay



# **Performance - Example**

 Calculate the total time required to transfer a 1000-KB file in the following case, assuming bandwidth is 1.5 Mbps, an RTT of 50 ms, a packet size of 1 KB data, and an initial 2 × RTT of "handshaking" before data is sent. (Peterson-Davie Exercise 3, Chapter 1)

Delay = Handshake + Transmission + Propagation + Queuing

Delay = 2\*50ms + (1000\*1024\*8)/(1.5\*1000\*1000) second + 50/2ms + 0 = 5.586seconds

Propagation delay = First bit from sender to receiver


# **Performance - Example**


Calculate the total time required to transfer a 1.5-MB file in the following cases, assuming an RTT of 80 ms, bandwidth= 10Mbps, a packet size of 1 KB data, and an initial 2 × RTT of "handshaking" before data is sent:


Delay = Handshake + Transmission + Propagation + Queuing

Propagation delay = First bit from sender to receiver


# Recap - Network = Graph (Nodes + Links)








#### What does it take to create a link?



- Common abstractions
  - Why?


## **Packet to Low level Signals**

- Bit pattern 0101001
  - Must encode it into electrical signals and then decode it on the other end!




#### One easy way - NRZ


- 0 = low, 1 = low
- Problem if you have too many 0s or 1s in a row
  - Baseline wander (read it in the book)




## Other ways - NRZI/ Manchester Encoding

- NRZI 1=transition, 0= Don't
- Machester encoding XOR of clock + NRZ data






# Frames - bag of bits



- Bits between adaptors
- Frames between hosts (two computers)
  - The job of adaptors is to find frames in a bit sequence
- Frames are link layer protocols


# Frames - bag of bits



Bits flow between adaptors, frames between hosts

Let's see it in wireshark!

# Frames - bag of bits



- Sending side encapsulation, add error check bits, flow control
- Receiving side extract frames, check for error, flow control

## **Framing**

- Point-to-point
  - Special start of text character denoted as Flag
    - 01111110
  - Address, control : default numbers
  - Protocol for demux : IP / IPX
  - Payload : negotiated (1500 bytes)
  - Checksum: for error detection




#### **Point to Point Links**

- Requirements:
  - Packet framing: encapsulation of network-layer datagram in data link frame
  - Bit transparency: Does not care about what its carrying
  - Error Detection: Correction is on upper layers
  - Connection liveness
  - Network layer address negotiation



#### **Point to Point Links**

- Flag: 01111110
  - Address: Does nothing
  - Control; Does nothing
  - Protocol: IP/ATM
  - Payload: Whatever
  - Checksum: Discussing later
- Flag: 01111110



## **Point to Point Links - Byte stuffing**

- Flag: 01111110
  - Data transparency means it can also carry 01111110
  - How do you differentiate between data and flag?
    - Two back to back sequences of 011111110
    - Two sequences = Data, discard first
    - One sequence = Flag



#### **Error Detection**


- Bit errors are introduced into frames
  - Because of electrical interference and thermal noises
- Detecting Error
- Correction Error
- Two approaches when the recipient detects an error
  - Notify the sender that the message was corrupted, so the sender can send again.
    - If the error is rare, then the retransmitted message will be error-free
  - Using some error correct detection and correction algorithm, the receiver reconstructs the message

#### **Error Detection**

- Common technique for detecting transmission error
  - CRC (Cyclic Redundancy Check)
    - Used in HDLC, DDCMP, CSMA/CD, Token Ring
  - Other approaches
    - Two Dimensional Parity (BISYNC)
    - Checksum (IP)

#### **Error Detection**

- Basic Idea of Error Detection
  - To add redundant information to a frame that can be used to determine if errors have been introduced




Number of 1s

- Odd 1s = Parity bit 0
- Even 1s = Parity bit 1

# **Two-dimensional parity**

- Two-dimensional parity does a similar calculation
- Extra parity byte for the entire frame, in addition to a parity bit for each byte
- Two-dimensional parity catches all 1-, 2-, and 3-bit errors and most 4-bit errors

# **Two-dimensional parity**



Two Dimensional Parity

# **Internet Checksum Algorithm**

- Not used at the link level
- Add up all the words that are transmitted and then transmit the result of that sum
  - The result is called the checksum
- The receiver performs the same calculation on the received data and compares the result with the received checksum

# **Internet Checksum Algorithm**

#### **Server Side**

- 1. It treats segment contents as sequence of 16-bit integers.
- 2. All segments are added. Let's call it sum.
- 3. Checksum: 1's complement of sum.(In 1's complement all 0s are converted into 1s and all 1s are converted into 0s).
- 4. Sender puts this checksum value in UDP checksum field.

#### **Client Side:**

- 1. Calculate checksum
- 2. All segments are added and then sum is added with sender's checksum.
- 3. Check that any 0 bit is presented in checksum. If receiver side checksum contains any 0 then error is detected. So the packet is discarded by receiver.


25

#### **Internet Checksum Algorithm (RFC 1071)**

```
• A = 0110011001100110
• B = 0101010101010101
 A+B = 1011101110111011
• C = 0000111100001111
      1100101011001010 (sum of all segments)
      00110101010101 (1's complement, 1 \rightarrow 0, 0 \rightarrow 1) <= this is the checksum
 At receiver:
 Add sum of all segments and checksum
  - If correct, all 1s
```

# Others - Cyclic Redundancy Check (CRC)

- Reduce the number of extra bits and maximize protection
- Very interesting but we will skip it for now.



#### All these for what?

- Handles bit transmission errors that might occur
- Link access who can access the link at a given time?
- Flow control control the pace that does not overwhelm sending and receiving devices
- Reliable delivery next topic
- It permits the transmission of data to Layer 3, the network layer, where it is addressed and routed.

# **Next Steps**

• Read Chapter 2

• Next lecture - Reliable Delivery