



#### **Accessing Pointers (argv) in ARM assembly**

```
argv[0] = ./cipher
    .extern printf
                                                                           argv[1] = -e
    .extern stderr
                                                                           argv[2] = -b
    .section .rodata
.Lstr: .string "argv[%d] = %s\n"
                                                                           argv[3] = in/B00K
                                                need to save r1 as
    .text
    .qlobal main
                 // main(r0=argc, r1=argv)
                                                we are calling a
                                                                               r0-r3 lost due to fprintf call
           main, %function
    .type
                                                function - fprintf
           FP_OFF,
                       20
    •equ
main:
           {r4-r7, fp, lr}
                                                                                       "argv[%d] = %s\n"
    push
           fp, sp, FP_OFF
    add
                                                                 Registers
            r7, r1
                            // save ardv!
    mov
                                                           r7
            r4, =stderr
                            // get the address of stderr
    ldr
                                                                                       NULL
           r4, [r4]
                            // get the contents of stderr
                                                           r6
   ldr
                                                                   indx
                                                                                     argv[3]
            r5, =.Lstr
                           // get the address of .Lstr
                                                                                                   in/book
    ldr
                                                                                     argv[2]
            r6, 0
                            // set indx = 0;
    mov
                                                                                     argv[1]
                                                                                                      -b
                                                                file * stderr
// see next slide
                                                                                     argv[0]
                                                           r3
                                                                                                      -e
.Ldone:
            r0, 0
                                                           r2
    mov
                                                                                                   ./cipher
    sub
           sp, fp, FP_OFF
                                                                  **argv
            {r4-r7, fp, lr}
    pop
            lr
    bx
                                                            r0
                                                                   argc
```

fprintf(stderr, "argv[%d] = %s\n", indx, \*argv);

3

% \*/cipher -e -b in/B00K

#### Accessing Pointers (argv) in ARM assembly

```
% ./cipher -e -b in/B00K
                                                             argv[0] = ./cipher
                                                             argv[1] = -e
.Lloop:
                                                             argv[2] = -b
   // fprintf(stderr, "argv[%d] = %s\n", indx, *argv)
                                                             argv[3] = in/B00K
   ldr
           r3, [r7] // arg 4: *argv
           r3, 0
                          // check *argv == NULL
   cmp
                                                                 r0-r3 lost due to fprintf call
           Ldone
                          // if so done
   beq
                        // arg 3: indx
           r2, r6
   mov
                  // arg 2: "argv[%d] = %s\n"
           r1, r5
   mov
                                                                            "arqv[%d] = %s\n"
           r0, r4
                          // arg 1: stderr
   mov
                                                          Registers
   bl
           fprintf
                                                    r7
                                                                             NULL
           r6, r6, 1
                           // indx++ for printing
   add
                                                    r6
                                                            indx
   add
                           // argv++ pointer
           r7, r7, 4
                                                                            argv[3]
                                                                                       in/book
           .Lloop
                                                    r5
   h
                                                                            argv[2]
.Ldone:
                                                                            argv[1]
                                                                                          -b
                                                    r4
                                                         file * stderr
                            observe the
                                                                           argv[0]
                                                    r3
                                                                                          -e
                             different
                                                    r2
                             increment sizes
                                                                                       ./cipher
                                                    r1
                                                           **argv
                                                    r0
                                                            argc
```

#### **Allocating Space For Locals on the Stack**


- Space for local variables is allocated on the stack right below the lowest pushed register
  - Move the sp towards low memory by the total size of all local variables in bytes plus padding

FRMADD = total local var space (bytes) + padding


· Allocate the space after the register push by

Requirement: on function entry, sp is always 8-byte aligned
 sp % 8 == 0

- Padding (as required):
  - 1. Additional space between variables on the stack to meet memory alignment requirements
  - 2. Additional space so the frame size is evenly divisible by 8
- fp (frame pointer) is used as a pointer (base register) to access all stack variables — later slides



#### **Local Variables on the stack**



```
.text
              main, %function
      .tvpe
      .global main
      .equ
              FP OFF,
                          12
              FRMADD,
                           8
      .equ
   main:
               {r4, r5, fp, lr}
       push
               fp, sp, FP OFF
       add
       add
               sp, sp, -FRMADD
   // but we are not done yet!
// when FRMADD values fail to assemble
```


ldr r3, =-FRMADD
add sp, sp, r3

- In this example we are allocating two variables on the stack
- When writing assembly functions, in many situations you may choose allocate these to registers instead

- Add space on the stack for each local
  - we will allocate space in same order the locals are listed the C function shown from high to low stack address
  - gcc compiler allocates from low to high stack addresses
  - · Order does not matter for our use

**Accessing Stack Variables: Introduction** 

```
int main(void)
{
    int c;
    int count = 0;
    // rest of code
}
```



low memory 4-byte words


- To Access data stored in the stack
  - use the ldr/str instructions
- Use register fp with offset (distance in bytes)
   addressing (use either register offset or immediate offset)
- No matter what address the stack frame is at, fp always points at saved lr, so you can find a local stack variable by using an offset address from the contents of fp

Variable	distance from fp	Read variable	Write Variable
int c	-16	ldr r0, [fp, -16]	str r0, [fp, -16]
int count	-20	ldr r0, [fp, -20]	str r0, [fp, -20]


```
.text
    .type
            main, %function
    .global main
           FP OFF,
   .equ
                      12
           FRMADD,
                       8
   .equ
main:
            {r4, r5, fp, lr}
    push
            fp, sp, FP_OFF
    add
            sp, sp, -FRMADD
    add
// but we are not done yet!
```

## **Stack Frame Design – Local Variables**

- When writing an ARM equivalent for a C program, for CSE30 we will not re-arrange the order of the variables to optimize space (covered in the compiler course)
- Arrays start at a 4-byte boundary (even arrays with only 1 element)
  - Exception: double arrays [] start at an 8-byte boundary
  - struct arrays are aligned to the requirements of largest member
- Single chars (and shorts) can be grouped together in same 4-byte word (following the alignment for the short)
- Padding may be required (see next slide)




Rule: When the function is entered the stack is already 8-byte aligned




#### **Stack Variables: Padding**

 Variable padding – start arrays at 4byte boundary and leave unused space at end (high side address) before the variable higher on the stack



 Frame padding – add space below the last local variable to keep 8-byte alignment



}

```
Ir to caller
                                      callers fp
                                                      FP_OFF
        8-byte aligned
                                      saved r5
                                12
      32 bytes
    Total frame
                                      saved r4
               ξр
                                 4
                                        count
                             1 + 3 pad
                                            buf
                                       frame pad
                                                         sp
                                   .text
                                                main, %function
                                       .type
int main(void)
                                       .global main
                                               FP OFF.
                                      .equ
                                                            12
    int c;
                                                            16
                                               FRMADD,
                                      .equ
    int count = 0;
                                  main:
    char buf[] = "hi";
                                                {r4, r5, fp, lr}
                                       push
    // rest of code
                                                fp, sp, FP_OFF
                                       add
```

add

sp, sp, -FRMADD


X

// but we are not done yet!

Accessing Stack Variables, the hard way.


```
int main(void)
{
    int c;
    int count = 0;
    char buf[] = "hi";
    // rest of code
}
```

```
.text
    .tvpe
            main, %function
    .global main
   .equ
           FP OFF,
                      12
           FRMADD,
                      16
   .equ
main:
            {r4, r5, fp, lr}
    push
    add
            fp, sp, FP OFF
            sp, sp, -FRMADD
    add
// but we are not done yet!
```




char buf[] by usage with ASCII chars we will use strb (or make it unsigned char)


Variable	distance from fp	Read variable	Write Variable
int c	16	ldr r0, [fp, -16]	str r0, [fp, -16]
int count	20	ldr r0, [fp, -20]	str r0, [fp, -20]
char buf[0]	24	ldrb r0, [fp, -24]	strb r0, [fp, -24]
char buf[1]	23	ldrb r0, [fp, -23]	strb r0, [fp, -23]
char buf[2]	22	ldrb r0, [fp, -22]	strb r0, [fp, -22]




- Calculating offsets is a lot of work to get it correct
- · It is also hard to debug
- There is a better way!

#### **Best Practice: Assembler Generated FP Distance Table**






- 1. For each stack variable create a .equ symbol whose value is the distance in bytes from the FP after the prologue
- 2. After the last variable add a name PAD for the size of the frame padding (if any). if no padding, PAD will be set to the same value as the variable above it
- 3. The value of the symbol is an expression that calculates the distance from the FP based on the distance of the variable above it on the stack. The first variable will use SP\_OFF as the starting distance
  - .equ VAR, size of var + variable padding + previous var symbol // previous var symbol distance of the var above
- Calculate the size of the local variable area that needs to be added to the sp in bytes
   FRMADD = distance PAD minus distance of the SP to the FP (FP OFF) after the prologue push



Variable	distance from fp	Address on Stack	Read variable	Write Variable
int c	С	add r0, fp, -C	ldr r0, [fp, -C]	str r0, [fp, -C]
int count	COUNT	add r0, fp, -COUNT	ldr r0, [fp, -COUNT]	str r0, [fp, -COUNT]
char buf[0]	BUF	add r0, fp, -BUF	ldrb r0, [fp, -BUF]	strb r0, [fp, -BUF]
char buf[1]	BUF-1	add r0, fp, -BUF+1	ldrb r0, [fp, -BUF+1]	strb r0, [fp, -BUF+1]
char buf[2]	BUF-2	add r0, fp, -BUF+2	ldrb r0, [fp, -BUF+2]	strb r0, [fp, -BUF+2]



passes address of a stack variable buf

## **Stack Frame Design Practice**

```
void func(void)
  signed char c;
  signed short s;
  unsigned char b[] = "Stack";
  unsigned char *ptr = &b;
   // rest of code
```

- 1. Write the variables in C
- Draw a picture of the stack frame
- Write the code to generate the offsets
- 4. create the distance table to the variables

12


2 + C

8 + S

4 + B

0 + PTR

2 + FP OFF



Variable	distance from fp	Address on Stack	Read variable	Write Variable	
signed char c	С	add r0, fp, -C	ldrsb r0, [fp, -C]	strsb r0, [fp, -C]	
signed short s	S	add r0, fp, -S	ldrsh r0, [fp, -S]	strsh r0, [fp, -S]	
unsigned char b[0]	В	add r0, fp, -B	ldrb r0, [fp, -B]	strb r0, [fp, -B]	
unsigned char *ptr	PTR	add r0, fp, -PTR	ldr r0, [fp, -PTR]	str r0, [fp, -PTR]	

Ir to caller

```
int sum(int j, int k)
    return j + k;
void testp(int j, int k, int (*func)(int, int), int *i)
    *i = func(j,k);
    return;
int main()
                            // NOTICE: i must be on stack as you pass the address!
    int i;
    int (*pf)(int, int) = sum; // pf could be in a register
    testp(1, 2, pf, &i); Output Parameters (like i) you
    printf("%d\n", i);
                             pass a pointer to them, must be
    return EXIT_SUCCESS;
                             on the stack!
```

```
int main()
{
   int i; // NOTICE: i must be on stack as you pass the address!
   int (*pf)(int, int) = sum; // pf could be in a register

   testp(1, 2, pf, &i);
   printf("%d\n", i);
   return EXIT_SUCCESS;
}
```

```
Ir to caller

callers fp

4

fp

4

fp

4

(pf)()

frame pad

sp
```


	<pre>.section .rodata .Lmess: .string "%d\n"</pre>				
.extern	_	•			
	рітіісі				
.text					
.global	main				
.type	main, %	function			
<b>.</b> equ	FP_OFF,				
<b>.</b> equ	•	4 + FP_0FF			
•equ	PF,	4 + I			
• equ	PAD,	0 + PF			
<b>.</b> equ	FRMADD,	PAD-FP_OFF			
// FRMADD =	12 - 4 =	8			

Variable	distance from fp	Address on Stack	Read variable	Write Variable
int i	I	add r0, fp, -I	ldr r0, [fp, -I]	str r0, [fp, -I]
int (*pf)()	PF	add r0, fp, -PF	ldr r0, [fp, -PF]	str r0, [fp, -PF]

```
main:
Working with Pointers on the stack
                                                                   {fp, lr}
                                                           push
                                                                   fp, sp, FP OFF
                                                           add
int main()
                                                           add
                                                                    sp, sp,-FRMADD
   int i:
                                                           ldr
                                                                    r2, =sum
                                                                                    // func address
   int (*pf)(int, int) = sum;
                                                                                    // PF address
                                                           add
                                                                    r1, fp, –PF
   testp(1, 2, pf, &i); lis Output
                                                                    r2, [r1]
                                                                                    // store in pf
                                                           str
                                     Ir to caller
   printf("%d\n", i);
                         Parameter
   return EXIT_SUCCESS;
                                                                    r0, 1
                                                                               // arg 1: 1
                                                           mov
                                                  4
                                      callers fp
                                                                    r1, 2 // arg 2: 2
r2, [fp, -PF] // arg 3: (*pf)()
                                                           mov
     .section .rodata
                                                           ldr
                                                  4
 .Lmess: .string "%d\n"
                                                                    r3, fp, -I
                                                                                    // arg 4: &I
                                                           add
                                  FRMADD
     .extern printf
                                        *(pf)()
                                                           bl
                                                                    testp
                                                  4
     .text
    .global main
                                                 0
                                                                    r0, =.Lmess // arg 1: "%d\n"
                                       frame pad
                                                      sp
                                                           ldr
            main, %function
    .type
                                                                    r1, [fp, -I] // arg 2: I
                                                           ldr
            FP_OFF, 4
    .equ
                   4 + FP_0FF
                                                                    printf
            I,
                                                           bl
    •equ
            PF,
    . equ
                   4 + I
                   0 + PF
     •equ
            PAD,
                                                                    sp, fp, FP_OFF
                                                           sub
            FRMADD, PAD-FP_OFF
     •equ
                                                                    {fp, lr}
                                                           pop
 // FRMADD = 12 - 4 = 8
                                                                    lr
                                                           bx
```

Variable	distance from fp	Address on Stack	Read variable	Write Variable
int i	I	add r0, fp, -I	ldr r0, [fp, -I]	str r0, [fp, -I]
int (*pf)()	PF	add r0, fp, -PF	ldr r0, [fp, -PF]	str r0, [fp, -PF]


```
void
testp(int j, int k, int (*func)(int, int), int *i)
{
    *i = func(j,k);
    return;
}
```



```
int
sum(int j, int k)
{
    return j + k;
}
```

```
.global sum
.type sum, %function
.equ FP_OFF, 4
sum:
   push {fp, lr}
   add fp, sp, FP_OFF
   add r0, r0, r1

   sub sp, fp, FP_OFF
   pop {fp, lr}
   bx lr
.size sum, (. - sum)
```




Passing More Than Four Arguments – At the point of Call

r0 = function(r0, r1, r2, r3, arg5, arg6, ... argn)

arg1, arg2, arg3, arg4, ...


- Approach: Increase stack frame size to include space for args# > 4
  - Arg5 and above are in <u>caller's stack frame</u> at the bottom of the stack
- Arg5 is always at the bottom (at sp), arg6 and greater are above it
- One arg value per slot! NO arrays across multiple slots
  - · chars, shorts and ints are directly stored
  - Structs (not always), and arrays (always) are passed via a pointer
- Output parameters contain an address that points at the stack, BSS, data, or heap
- Prior to any function call (and obviously at the start of the called function):
  - 1. sp must point at arg5
  - 2. sp and therefore arg5 must be at an 8-byte boundary,
  - 3. Add padding to force arg5 alignment if needed is placed above the last argument the called function is expecting



#### **Passing More Than Four Arguments – At the point of Call**

r0 = function(r0, r1, r2, r3, arg5, arg6, ... argn)arg1, arg2, arg3, arg4, ...

- Called functions have the right to change stack args just like they can change the register args!
  - Caller must always assume all args including ones on the stack are changed by the caller
- Calling function prior to making the call you must
  - 1. Evaluate first four args: place the resulting values in r0-r3
  - 2. Evaluate Arg 5 and greater and place the resulting values on the stack




#### Passing More Than Four Arguments – At the point of Call

```
r0 = function(r0, r1, r2, r3, arg5, arg6, ... argn)

arg1, arg2, arg3, arg4, ...
```

- Approach: Extend the stack frame to include enough space for stack arguments for the called function that has the greatest number of args
  - 1. Examine every function call in the body of a function
  - 2. Find the function call with greatest arg count, this determines space needed for outgoing args
  - 3. Add the greatest arg count space as needed to the frame layout
  - 4. Adjust PAD as required to keep the sp 8-byte aligned



22

# **Determining Size of the Passed Parameter Area on The Stack**

- Find the function called by main with the largest number of parameters
- That function determines the size of the Passed Parameter allocation on the stack

```
int main(void)
{
    /* code not shown */
    a(g, h);

    /* code not shown */
    sixsum(a1, a2, a3, a4, a5, a6);

    /* code not shown */

    b(q, w, e, r);
    /* code not shown */
}
```


largest arg count is 6 allocate space for 6 - 4 = 2 arg slots

#### **<u>Calling Function Stack Frame:</u>** Pass ARG 5 and higher

#### **Rules: At point of call**

- 1. OARG5 must be pointed at by sp
- 2. SP must be 8-byte aligned at function call

```
int cnt;
r0 = func(r0, r1, r2, r3, OARG5, OARG6);
```



Variable	distance from fp	Address on Stack	Read variable	Write Variable
int cnt	CNT	add r0, fp, -CNT	ldr r0, [fp, -CNT]	str r0, [fp, -CNT]
int oarg6	OARG6	add r0, fp, -OARG6	ldr r0, [fp, -OARG6]	str r0, [fp, -OARG6]
int oarg5	OARG5	add r0, fp, -OARG5	ldr r0, [fp, -OARG5]	str r0, [fp, -OARG5]


# **Called Function: Retrieving Args From the Stack**

r0 = func(r0, r1, r2, r3, r4, ARG5, ARG6);

- At function start and before the push{} the sp is at an 8-byte boundary
- Args > 4 in <u>caller's stack frame</u> and arg 5 always starts at fp+4
  - Additional args are higher up the stack, with one "slot" every 4bytes

.equ ARGN, 
$$(N-4)*4$$
 // where n must be > 4

- This "algorithm" for finding args was designed to enable variable arg count functions like printf("conversion list", arg0, ... argn);
- No limit to the number of args (except running out of stack space)



#### Rule:

**Called functions** always access stack args using a **positive offset to the fp** 




```
FP OFF,
.equ
       C, 4 + FP_OFF
.equ
       INDX,
               4 + C
.equ
       PAD,
                 4 + INDX
.equ
              PAD - FP OFF
.equ
       FRMADD,
// below are distances into the caller's stack frame
.equ
       ARG6,
.equ
       ARG5,
```

r0 = func(r0, r1, r2, r3, r4, ARG5, ARG6);

#### Rule:

**Called functions** always access stack args using a **positive offset to the fp** 

Variable or Argument	distance from fp	Address on Stack	Read variable	Write Variable	
int arg6	ARG6	add r0, fp, ARG6	ldr r0, [fp, ARG6]	str r0, [fp, ARG6]	Obse positi
int arg5	ARG5	add r0, fp, ARG5	ldr r0, [fp, ARG5]	str r0, [fp, ARG5] 🗲	offset
int c	С	add r0, fp, -C	ldr r0, [fp, -C]	str r0, [fp, -C]	
int count	INDX	add r0, fp, -INDX	ldr r0, [fp, -INDX]	str r0, [fp, -INDX]	




Previous

## **Example: Passing Stack Args, Calling Function**

```
int sum(int j, int k)
    return j + k;
      arg1
                      arg3
                             arg4
                                         arg5
              arg2
                                                           arg6
void
testp(int j, int k, int l, int m, int (*func)(int, int), int *i)
    *i = func(j,k) + func(l, m); // notice two func() calls
    return;
}
int main()
    int i; // NOTICE: i must be on stack as you pass the address!
    int (*pf)(int, int) = sum; // pf could be in a register
    testp(1, 2, 3, 4, pf, &i);
    printf("%d\n", i);
    return EXIT_SUCCESS;
```

**Example: Passing Stack Args, Calling Function** 

```
int main()
{
    int i; // NOTICE: i must be on stack as you pass the address!
    int (*pf)(int, int) = Sum; // pf could be in a register
   testp(1, 2, 3, 4, pf, &i);
    printf("%d\n", i);
   return EXIT SUCCESS;
                                    FP OFF, 4
                            •equ
                                             4 + FP OFF
                                    I,
                            •equ
                                  PF, \qquad 4 + I
                            •equ
                                  PAD, 0 + PF
                            •equ
                                  OARG6, 4 + PAD
                            •equ
                                             4 + 0ARG6
                                    0ARG5
                            •equ
                                    FRMADD, OARG5 - FP OFF
                            •equ
                        // FRMADD = 20 - 4 = 16
```



Variable or Argument	distance from fp	Address on Stack	Read variable	Write Variable
int i	I	add r0, fp, -I	ldr r0, [fp, -I]	str r0, [fp, -I]
int (*pf)()	PF	add r0, fp, -PF	ldr r0, [fp, -PF]	str r0, [fp, -PF]
int oarg6	OARG6	add r0, fp, -OARG6	ldr r0, [fp, -OARG6]	str r0, [fp, -OARG6]
int oarg5	OARG5	add r0, fp, -OARG5	ldr r0, [fp, -OARG5]	str r0, [fp, -OARG5]

Example: Passing Stack Args, Calling Function

```
int main()
{
    int i;
    int (*pf)(int, int) = sum;

    testp(1, 2, 3, 4, pf, &i);
    printf("%d\n", i);
    return EXIT_SUCCESS;
}
```

```
4 Ir to caller
4 callers fp
4 i
4 *(pf)()
6 frame pad
4 oarg6
4 oarg5
```

```
FP_0FF, 4
    •equ
                    4 + FP 0FF
    •equ
            PF,
                    4 + T
   •equ
            PAD.
                    0 + PF
   •equ
                    4 + PAD
            OARG6,
   •equ
            0ARG5
                    4 + 0ARG6
   •equ
            FRMADD, OARG5 - FP_OFF
    .equ
// FRMADD = 20 - 4 = 16
```

```
main:
            {fp, lr}
    push
    add
            fp, sp, FP_OFF
    add
            sp, sp,-FRMADD
                            // get func address
    ldr
            r0, =sum
            r1, fp, -PF
                            // PF address on stack
    add
            r0, [r1]
                            // store sum in var pf
    str
            r0, fp, −I
                           // get address of I
    add
            r1, fp, -OARG6 // address of OARG6
    add
    str
            r0, [r1]
                           // arg 6: store address of I
    ldr
            r0, [fp, -PF] // get PF from stack
            r1, fp, -OARG5 // address of OARG5
    add
            r0, [r1]
                            // arg 5: store sum() address
    str
            r0, 1
                            // arg 1: 1
    mov
            r1, 2
                           // arg 2: 2
    mov
            r2, 3
                            // arg 3: 3
    mov
            r3, 4
                            // arg 4: 4
    mov
    bl
            testp
    ldr
            r0, =.Lmess
                           // arg 1: "%d\n"
            r1, [fp, -I]
                           // arg 2: i
    ldr
    bl
            printf
    sub
            sp, fp, FP_OFF
    pop
            {fp, lr}
```

Variable or	distance			
Argument	from fp	Address on Stack	Read variable	Write Variable
int i	I	add r0, fp, -I	ldr r0, [fp, -I]	str r0, [fp, -I]
int (*pf)()	PF	add r0, fp, -PF	ldr r0, [fp, -PF]	str r0, [fp, -PF]
int oarg6	OARG6	add r0, fp, -OARG6	ldr r0, [fp, -OARG6]	str r0, [fp, -OARG6]
int oarg5	OARG5	add r0, fp, -OARG5	ldr r0, [fp, -OARG5]	str r0, [fp, -OARG5]

```
Example: Passing Stack Args, Called Function
                                                                        FP_0FF, 20
                                                                •equ
            arg2 arg3
                         arg4
                                    arg5
                                                                        ARG6, 8
                                                   arg6
                                                                equ
void
                                                                        ARG5,
                                                                . equ
testp(int j, int k, int l, int m, int (*func)(int, int), int *i)
                                                           testp:
                                                                        {r4-r7, fp, lr}
                                                               push
   *i = func(j, k) + func(l, m);
                                                                        fp, sp, FP_OFF
                                                               add
   return;
            short circuit: make this call first
                                                                        r4, r2
                                                                                       // save l
                                                               mov
                                                                                        // save m
                                                                        r5, r3
                                                               mov
                       Ir to caller
                                                                        r6, [fp, ARG5] // load func
                                                               ldr
                                                                        r7, [fp, ARG6] // load i
                                                               ldr
                        callers fp
                                                                                        // r0 = func(j, k)
                                                                        r6
                                                               blx
                                                                                       // arg 2 saved m
                                                                        r1, r5
                                                               mov
     main()
                          *(pf)()
                                                                                       // save func return value
                                                                        r5, r0
                                                               mov
     stack
                                                                        r0, r4
                                                                                       // arg 1 saved l
                                                               mov
                         frame pad
                                                               blx
                                                                        r6
                                                                                       // r0 = func(l, m)
                                                                        r0, r0, r5
                                                                                      // func(l,m) + func(j,k)
                                                               add
                          oarg6
                                                                        r0, [r7]
                                                                                      // store sum to *i
                                                               str
                  4
                          oarg5
                                                                        sp, fp, FP_OFF
                                                               sub
                        Ir to main
     testp()
                                                                        {r4-r7, fp, lr}
                                                               pop
     stack
                        main's fp
                                                               bx
                                                                        lr
```

	Argument	distance	Address on Stack	Read variable	Write Variable
	int *i	ARG6	add r0, fp, ARG6	ldr r0, [fp, ARG6]	str r0, [fp, ARG6]
30	int (*fp)()	ARG5	add r0, fp, ARG5	ldr r0, [fp, ARG5]	str r0, [fp, ARG5]

# **Extra Slides**

## By following the saved fp, you can find each stack frame

